CAPPA Miner License Guide

Buying renewing and activating a license

All screenshots use fictional wallets and an example invoice. Do not pay the illustrated 979.42 NACKL. Pay only the amount in your own active invoice.

1 Open the license screen

A license is required for mining. You may save up to 100 wallets and read their public information without a license.

Load the intended wallets


Before buying, leave only the wallets you want to license in the miner. The payment covers every loaded wallet, not a selection inside the payment panel. Back up wallets before removing any.

Wait for levels

Every loaded wallet must have valid identity and level information. If any level is missing, wait for the public data to load; no payable amount should be shown yet.

Open the menu

Open the application menu and click Enter / Renew License. Subscription / payment opens by default. License code is the manual alternative.



The menu entry keeps the English wording Enter / Renew License in every language.

- An existing license does not automatically license unrelated newly added wallets. Saving a wallet does not give it mining permission.
- Automatic renewal currently requires the same wallet addresses and count. For a changed set or wallet replacement, contact the license issuer before paying.
- If a manual license record already exists, even an expired one, automatic purchase is blocked. Continue with the manual-code alternative or contact the issuer; do not delete license records yourself.

2 Prepare your payment

Choose your options first. Preparing the payment creates an invoice; it does not send funds from your wallet.

Choose currency and duration


Select NACKL or SHELL and 30, 60 or 90 days. Total remaining automatic-license time cannot exceed 90 days, including early renewal. Options that exceed the limit are disabled.

Click Prepare payment

The service verifies the wallet information and prepares the invoice. Once it is ready, check Amount to pay, CAPPA recipient address and Time left to pay. Currency and duration stay fixed while that invoice is unresolved.

Use the current invoice

The five-minute payment window begins when the invoice is created. Use the amount and address displayed in your own miner, not a screenshot or an old invoice.



Example only: two fictional wallets, 30 days, 979.42 NACKL and a 05:00 payment window.

- Send exactly both decimal places. For example, an active invoice for 979.42 needs 979.42, not 979 or 980. The pictured invoice is only an example.
- Do not create or pay a second invoice to fix a pending payment.

3 Send check and start

Send the payment yourself from your Acki Nacki wallet. The miner does not ask for your seed phrase or private key.

Approve the exact transfer


Use the Acki Nacki network, the selected NACKL or SHELL token, the displayed recipient and the exact invoice amount. Check these in the wallet before approving. This version has no verified payment QR that fills in the amount automatically.

Click Check payment

A payment received within the invoice window remains checkable after the countdown reaches zero. Confirmation requires at least five minutes from receipt plus successful chain-reader checks; congestion or unavailable data can take longer. Do not pay again while waiting.

Start after activation

Wait for License verified and applied. Close the panel and press START ALL. A newly applied entitlement enables licensed AUTO preferences once, but does not start mining for you. Only licensed eligible wallets may run.



Example of a verified and applied license. The zero countdown does not invalidate a payment received in time.

- The five-minute sending window is not a promise of confirmation within five minutes.
- Payment confirmed and license applied are separate steps. If the latter is missing, keep checking the same invoice instead of sending more funds.

4 Problems and manual activation


Keep the original transaction ID and invoice details if a payment needs review. Never send your seed phrase or private key.

Use a manual license code

Choose License code. Copy Device ID for the license issuer, obtain a code for this device, paste it into Activation / license renewal code and click Apply code. This path remains an alternative; an unresolved automatic invoice may temporarily lock it.

After an ordinary reinstall

On the same Windows user profile, preserved device authentication can recover owned invoices and the current license. A different computer, Windows profile, or deleted authentication data is not guaranteed to recover automatically. Do not repurchase merely because recovery is still pending.



Manual activation remains available. This form follows the WebView language: Turkish when that language is Turkish, otherwise English.

- Countdown 00:00: do not send a new payment. If you already paid in time, check the same invoice. If unpaid, wait for the service to finish the unpaid check before preparing another.
- Verification unavailable: retry the check later. The message does not mean that payment failed or that you should pay again.
- Request cancellation: hides the invitation to pay, but is not an instant financial cancellation or refund. A payment already sent can still be detected; wait for resolution.
- A disabled duration means that renewal would exceed 90 remaining days. Choose an allowed duration or renew later.