Type C1 (chirp plane streak 211), 3.56 kHz @ chirps 3.1 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature




Figure S7-C1. Type C1 (chirp plane streak 211): 3.56 kHz @ chirps 3.1 Hz at 25 °C, 62 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 1 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale; a cell whose singer had no syllable rate in that window is folded at its chirp rate. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type C2 (chirp plane streak 21), 3.94 kHz @ chirps 4.2 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature




Figure S7-C2. Type C2 (chirp plane streak 21): 3.94 kHz @ chirps 4.2 Hz at 25 °C, 351 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 1 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale; a cell whose singer had no syllable rate in that window is folded at its chirp rate. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type C3 (chirp plane streak 10), 5.75 kHz @ chirps 3.4 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature




Figure S7-C3. Type C3 (chirp plane streak 10): 5.75 kHz @ chirps 3.4 Hz at 25 °C, 55 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 1 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale; a cell whose singer had no syllable rate in that window is folded at its chirp rate. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type C4 (chirp plane streak 9), 6.16 kHz @ chirps 3.0 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature




Figure S7-C4. Type C4 (chirp plane streak 9): 6.16 kHz @ chirps 3.0 Hz at 25 °C, 90 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 1 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale; a cell whose singer had no syllable rate in that window is folded at its chirp rate. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.




Figure S7-C5. Type C5 (chirp plane streak 91): 6.44 kHz @ chirps 3.2 Hz at 25 °C, 48 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 1 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale; a cell whose singer had no syllable rate in that window is folded at its chirp rate. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type C6 (chirp plane streak 5), 6.84 kHz @ chirps 2.9 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature




Figure S7-C6. Type C6 (chirp plane streak 5): 6.84 kHz @ chirps 2.9 Hz at 25 °C, 365 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 1 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale; a cell whose singer had no syllable rate in that window is folded at its chirp rate. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type C7 (chirp plane streak 4), 8.07 kHz @ chirps 3.4 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature






Figure S7-C7. Type C7 (chirp plane streak 4): 8.07 kHz @ chirps 3.4 Hz at 25 °C, 2659 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 1 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale; a cell whose singer had no syllable rate in that window is folded at its chirp rate. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type C8 (chirp plane streak 7), 8.71 kHz @ chirps 2.7 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature




Figure S7-C8. Type C8 (chirp plane streak 7): 8.71 kHz @ chirps 2.7 Hz at 25 °C, 101 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 1 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale; a cell whose singer had no syllable rate in that window is folded at its chirp rate. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.