

Figure S7-1. Type 1 (streak 4001): 2.21 kHz @ 56 Hz at 25 °C, 132 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-2. Type 2 (streak 45011): 2.38 kHz @ 45 Hz at 25 °C, 109 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-3. Type 3 (streak 4301): 2.59 kHz @ 41 Hz at 25 °C, 1655 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-4. Type 4 (streak 360123): 2.74 kHz @ 22 Hz at 25 °C, 76 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-5. Type 5 (streak 4501): 2.89 kHz @ 63 Hz at 25 °C, 144 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-6. Type 6 (streak 3201): 3.22 kHz @ 47 Hz at 25 °C, 106 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-7. Type 7 (streak 31011): 3.41 kHz @ 44 Hz at 25 °C, 90 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 8 (streak 3601), 3.48 kHz @ 35 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature



Figure S7-8. Type 8 (streak 3601): 3.48 kHz @ 35 Hz at 25 °C, 1834 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-9. Type 9 (streak 31013): 3.94 kHz @ 58 Hz at 25 °C, 167 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 10 (streak 360124), 3.94 kHz @ 40 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature





Figure S7-10. Type 10 (streak 360124): 3.94 kHz @ 40 Hz at 25 °C, 231 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 11 (streak 360125), 3.95 kHz @ 39 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature



Figure S7-11. Type 11 (streak 360125): 3.95 kHz @ 39 Hz at 25 °C, 42 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 12 (streak 5201), 4.05 kHz @ 30 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature



Figure S7-12. Type 12 (streak 5201): 4.05 kHz @ 30 Hz at 25 °C, 630 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-13. Type 13 (streak 31014): 4.23 kHz @ 62 Hz at 25 °C, 44 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 14 (streak 3701), 4.30 kHz @ 58 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature



Figure S7-14. Type 14 (streak 3701): 4.30 kHz @ 58 Hz at 25 °C, 166 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-15. Type 15 (streak 34013): 4.34 kHz @ 43 Hz at 25 °C, 124 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-16. Type 16 (streak 36015): 4.83 kHz @ 65 Hz at 25 °C, 114 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-17. Type 17 (streak 34014): 5.00 kHz @ 55 Hz at 25 °C, 62 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 18 (streak 5501), 5.15 kHz @ 38 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature



Figure S7-18. Type 18 (streak 5501): 5.15 kHz @ 38 Hz at 25 °C, 4213 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 19 (streak 5301), 5.29 kHz @ 54 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature



Figure S7-19. Type 19 (streak 5301): 5.29 kHz @ 54 Hz at 25 °C, 117 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 20 (streak 3301), 5.34 kHz @ 69 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature



Figure S7-20. Type 20 (streak 3301): 5.34 kHz @ 69 Hz at 25 °C, 374 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Figure S7-21. Type 21 (streak 6301): 5.66 kHz @ 20 Hz at 25 °C, 117 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 22 (streak 590116), 5.86 kHz @ 28 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature



Figure S7-22. Type 22 (streak 590116): 5.86 kHz @ 28 Hz at 25 °C, 54 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-23. Type 23 (streak 5401): 6.00 kHz @ 43 Hz at 25 °C, 143 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-24. Type 24 (streak 4601): 6.20 kHz @ 20 Hz at 25 °C, 1908 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 25 (streak 3402), 6.21 kHz @ 81 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature



Figure S7-25. Type 25 (streak 3402): 6.21 kHz @ 81 Hz at 25 °C, 105 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-26. Type 26 (streak 6001): 6.38 kHz @ 29 Hz at 25 °C, 61 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-27. Type 27 (streak 5801): 6.54 kHz @ 39 Hz at 25 °C, 124 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 28 (streak 590117), 6.95 kHz @ 38 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature



Figure S7-28. Type 28 (streak 590117): 6.95 kHz @ 38 Hz at 25 °C, 273 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-29. Type 29 (streak 54012): 6.96 kHz @ 51 Hz at 25 °C, 128 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 30 (streak 4701), 7.01 kHz @ 22 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature



Figure S7-30. Type 30 (streak 4701): 7.01 kHz @ 22 Hz at 25 °C, 2080 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.



Figure S7-31. Type 31 (streak 4801): 7.47 kHz @ 22 Hz at 25 °C, 623 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 32 (streak 5802), 7.66 kHz @ 55 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature



Figure S7-32. Type 32 (streak 5802): 7.66 kHz @ 55 Hz at 25 °C, 375 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 33 (streak 4901), 7.78 kHz @ 20 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature





Figure S7-33. Type 33 (streak 4901): 7.78 kHz @ 20 Hz at 25 °C, 391 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 34 (streak 590118), 7.83 kHz @ 50 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature





Figure S7-34. Type 34 (streak 590118): 7.83 kHz @ 50 Hz at 25 °C, 300 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 35 (streak 5901), 8.55 kHz @ 58 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature



Figure S7-35. Type 35 (streak 5901): 8.55 kHz @ 58 Hz at 25 °C, 826 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 36 (streak 5101), 8.95 kHz @ 21 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature



Figure S7-36. Type 36 (streak 5101): 8.95 kHz @ 21 Hz at 25 °C, 69 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.

Type 37 (streak 6102), 9.46 kHz @ 58 Hz at 25 °C

rows: positions along the line, cold and slow at the top, warm and fast at the bottom
columns: singers at that position, distinct recorder-nights, by air temperature



Figure S7-37. Type 37 (streak 6102): 9.46 kHz @ 58 Hz at 25 °C, 64 singer-nights. Rows are positions along the line from the cold, slow end at the top to the warm, fast end at the bottom; columns are singers at that position from distinct recorder-nights, ordered by air temperature. Each cell is 0.5 s of the loudest 30 s of the singer's deepest window on one shared log-frequency axis, the detected band in color (dB above the row's quiet level, 0 to 30) and the rest in grayscale. The cell head gives the night, recorder, site, air temperature and rate (c: chirp rate). Top right: the type on the plane, and the row positions on the streak, in order.