# Software through Pictures® Structured Environment

**Millennium Edition 8** 

**Quick Reference** 

UD/REF/ST0000-10138/001



### Software through Pictures Structured Environment Quick Reference Millennium Edition 8 April 2001

Aonix® reserves the right to make changes in the specifications and other information contained in this publication without prior notice. In case of doubt, the reader should consult Aonix to determine whether any such changes have been made. The software described in this document is furnished under a license and may be used or copied only in accordance with the terms of such license.

## **Copyright** © 2001 by Aonix® Corporation. All rights reserved.

This publication is protected by Federal Copyright Law, with all rights reserved. Unless you are a licensed user, no part of this publication may be reproduced, stored in a retrieval system, translated, transcribed, or transmitted, in any form, by any means, without prior written permission from Aonix. Licensed users may make copies of this document as needed solely for their internal use—as long as this copyright notice is also reproduced.

#### **Trademarks**

Aonix and its logo, Software through Pictures, and StP are registered trademarks of Aonix Corporation. ACD, Architecture Component Development, and ObjectAda are trademarks of Aonix. All rights reserved.

HP, HP-UX, and SoftBench are trademarks of Hewlett-Packard Company. Sun and Solaris are registered trademarks of Sun Microsystems, Inc. SPARC is a registered trademark of SPARC International, Inc. UNIX is a registered trademark in the United States and other countries, exclusively licensed through X/Open Company, Ltd. Windows, Windows NT, and Windows 2000 are either trademarks or registered trademarks of Microsoft Corporation in the United States and other countries. Adobe, Acrobat, the Acrobat logo, and PostScript are trademarks of Adobe Systems, Inc. Sybase, the Sybase logo, and Sybase products are either trademarks or registered trademarks of Sybase, Inc. DocEXPRESS and DOORS are registered trademarks of Telelogic. Rational Rose and ClearCase are registered trademarks of Rational Software Corporation. Continuus and Continuus products are either trademarks or registered trademarks of Continuus Software Corporation. SNiFF+ and SNiFF products are either trademarks or registered trademarks of Wind River Systems, Inc. Segue is a registered trademarks or registered trademarks of their respective companies.



World Headquarters

5040 Shoreham Place San Diego, CA 92122 Phone: (800) 97-AONIX Fax: (858) 824-0212 E-mail: info@aonix.com http://www.aonix.com

#### **FUNDAMENTALS OF STP**

#### USE SHORTCUT MENUS AND GET HELP

## Access Frequently-Used Commands

Click the right mouse button on a Model category or object on the Desktop or on an object, table cell, row, column or background area in an editor to display a context-sensitive, shortcut menu.

## Access StP's Online Documentation

Choose **Help** > **Online Manuals**.

#### INSERT AND REPLACE SYMBOLS AND ARCS

#### Insert One or More Symbols into a Diagram

- 1. Select a symbol on the Symbols toolbar (or double-click it for multiple entry mode).
- 2. Click the left mouse button in the drawing area to insert the symbol (in multiple entry mode, click multiple times for more instances of the symbol).
- 3. Select Selection or another symbol on the Symbols toolbar to terminate multiple entry mode.

#### **Draw One or More Arcs**

- 1. Select the arc symbol on the Symbols toolbar (or double-click it for drawing multiple arcs).
- 2. Optionally select the arc type on the DefaultArcType toolbar.
- 3. Click the left mouse button on the source and destination objects to draw each link.
- 4. Select Selection or another symbol on the Symbols toolbar to terminate multiple entry mode.

## Draw/Cancel Drawing of Right-Angled Arcs

Click the **Toggle Orthogonal Drawing** toolbar button to set/unset this drawing option.

## Change an Object's Symbol Type

- 1. Select the object in the diagram.
- 2. Select the new symbol on the Symbols toolbar.
- 3. Choose **Replace** on the **Edit** or right-click menu.

#### Change an Arc Type

- 1. Select the arc in the diagram and choose **Replace** from the **Edit** or right-click menu.
- 2. Select an arc type in the dialog box and click **OK**.

#### **FUNDAMENTALS OF STP**

#### SELECT AND REPOSITION SYMBOLS AND ARCS IN A DIAGRAM

Diagram

Select a Single Element in a Single-click the element with the left mouse button.

a Diagram

Select Multiple Elements in Select an element, press SHIFT and click the left mouse button on additional elements.

Select All Elements in One Area of a Diagram

Left-click the mouse in the drawing area and drag a dashed-line "bounding box" around the elements.

Reposition an Element in a Diagram

Drag and drop it with the left mouse button.

Reconnect an Arc

Select one end of the arc and drag and drop it on another object with the left mouse button.

Arcs

Square up Non-Orthogonal From the diagram's right-click menu, choose Align All Links.

#### LABEL AND RENAME OBJECTS

Edit a Name

Double-click a diagram element or table cell to display its label in edit mode; click outside an object label or table cell to terminate label edit mode.

Choose a Name from the **System Repository** 

Select a diagram element or table cell and choose **Choose <object> Names** from the **Edit** or right-click menu; select a name from the list and click OK.

Rename an Object in the **System Repository** 

Select a diagram element or table cell and choose Edit > Rename Object Systemwide.

Rename File or Directory **Objects** 

- Open the Desktop Model Elements category and select File Objects or Directory Objects.
- Select an object in the objects pane and choose 2. Tools > Rename Object System Wide.
- Type the new name in the dialog, and click **OK**.

#### **FUNDAMENTALS OF STP**

#### **EDIT OBJECT PROPERTIES**

- 1. Select an element in the diagram.
- 2. Click **Properties** toolbar button or choose **Properties** on **Edit** or right-click menu.
- 3. Select options and edit or enter values, then click **OK**.

#### **ADD AN ANNOTATION**

- 1. To access the Object Annotation Editor (OAE):
  - From an editor—Select a diagram, object, table or table cell and click the
     Diagram | Object | Table | Cell> Annotation toolbar button or choose the corresponding annotation command on the Edit or right-click menu.
  - From the Desktop—Open the Model Elements category, select File Objects or Directory Objects, select an object from the objects pane, and choose Edit Annotation on the Tools or right-click shortcut menu.
- 2. In the OAE, open the annotation folder and select an annotation, note, or item.
- 3. Add notes or items from the **Edit** menu, as appropriate.
- 4. Type item values and/or a note description in the **Description** field; click **Apply**.
- 5. Choose **File > Save**.

#### ATTACH AN EXTERNAL FILE


- In the editor, select the diagram object or table cell (or none, to attach the file to the diagram or table itself) and click the appropriate Diagram | Object | Table | Cell Annotation toolbar button or choose the corresponding annotation command on the Edit or right-click menu.
- 2. In the Object Annotation Editor, open the annotation folder and select the Object note.
- Choose Edit > Add Item > External File.
- 4. With the External File item still selected in the Annotations list, type the full path to the external file in the **Description** field and click **OK**.

#### **DATA FLOW DIAGRAMS**

#### **DECOMPOSE A PROCESS**

process symbol.

- 1. Select the process symbol.
- From the Go To menu, choose Decomposition and when asked to confirm, click OK.
   The decomposition diagram appears with an unlabeled
- 3. Label the process.
  A process index number appears above the label.
- 4. Add additional processes, stores, and flows as needed.
- 5. From the **File** menu, choose **Save**.



#### **CREATE A PROCESS SPECIFICATION (PSPEC)**

To create a Pspec, first add a Pspec annotation, then generate the Pspec.

- 1. Select the process.
- 2. From the **DFE** menu, choose **Edit Pspec Note**.
- In the **Description** dialog, type a process description and click **OK**.
   A display mark (p) appears next to the process index

A display mark (p) appears next to the process index number in the diagram.

4. With the process still selected, from the **DFE** menu choose **Generate Pspec**.

The Pspec is generated into an ASCII file named <precss\_index>.pspec in the dfe\_files directory.

If no process is selected, a Pspec is generated for each Pspec-annotated process on the diagram.





To generate a pspec for each process in the model that has a Pspec note, from the StP Desktop choose **Code** > **Pspec** > **Generate Pspec for All Diagrams**.

Note: A process can have a decomposition or a process specification, but not both.

#### **DATA FLOW DIAGRAMS**

#### **RENAME A HIERARCHY**

- In the Model pane on the StP Desktop, open the Diagrams category and select the DeMarco/Yourdan or Gane Sarson Data Flow subcategory.
- 2. In the objects pane, select a data flow diagram.
- 3. From the **Tools** menu, choose **Rename Hierarchy**.
- 4. Type the new diagram name in the **New Name** text field and click **OK**.

The diagram and any subdiagrams and associated Cspecs are renamed in the repository.

All process indexes on the affected diagrams are renumbered.

#### **CHANGE A PROCESS INDEX**

- 1. Select the process.
- 2. From the **DFE** menu, choose **Change Process Index**.
- In the dialog box, type the new relative process index (only the last decimal digits) in the New Process Index field.



Ask for Confirmation: 🔽


Show Commands: ▼

Verbose: **⊽** 

- Optionally, select Move Decomposition to change the process indexes throughout the diagram hierarchy.
- 5. Click OK.

#### COLLAPSE MULTIPLE PROCESSES INTO ONE

- 1. Select the processes to be collapsed.
- 2. From the **DFE** menu, choose **Collapse**.
- 3. In the dialog box, type a name for the collapsed process.
- Click **OK**.
   The processes are combined and their decompositions are renumbered.



#### **DATA FLOW DIAGRAMS**

#### **EXPLODE A PROCESS INTO ITS COMPONENTS**

- Select a process that has a decomposition diagram or has been "collapsed."
- From the **DFE** menu, choose **Explode**. The exploded process is replaced with an anchor, and the component processes appear on the diagram.

The decomposition diagram is deleted, and any child diagrams are renumbered to reflect the new levels.

- Move the flows from the anchor to the appropriate component processes.
- 4. Delete the anchor.
- Delete unneeded duplicate stores, processes, and flows.





- 1. Select the flow.
- 2. From the **DFE** menu, choose **Split Flow**.
- Click the left mouse button on the new target process.
   A new flow is drawn from the arc to the process.
- 4. Optionally, label the split flow.


You can draw additional flows from the split flow vertex.

#### **MERGE A FLOW**

- 1. Select the flows to be merged.
- 2. From the **DFE** menu, choose **Merge Flow**. The flows are merged at a vertex.
- Optionally, label the merged section of the flow.







#### **DATA STRUCTURE DIAGRAMS**

#### ADD SUBSTRUCTURE BY CREATING A SCOPED DECOMPOSITION

- Select the object, choose Go To > Scoped
   Decomposition, and click OK to confirm.
   A decomposition diagram appears containing the object and its scope chain.
- 2. Add detail to the structure and save diagram when done.

**Note**: A data object can have either a decomposition or a data type, but not both.




#### ADD SUBSTRUCTURE BY DEFINING AN ABSTRACT DATA TYPE

- Select the object and click the **Properties** toolbar button or choose **Properties** on the **Edit** or rightclick menu.
- 2. Enter an abstract data type name in the **Type** field and click **OK**.
- With the object still selected, choose Go To > Type's Definition.
- In the confirmation box, click **OK**.
   A diagram appears containing a root node labeled with the name of the data type.
- 5. Add detail to diagram and save when done.

# Customer Char Email E\_Address E\_Address Internet Address

#### **DEFINE CONTROL INFORMATION**

- 1. Select a control flow on a data flow diagram.
- Choose Go To > DSE Data Definition and click OK when asked to confirm.
- In the data structure diagram, select the labeled symbol and click the **Object Annotation** toolbar button or choose **Edit** > **Object Annotation**.
- 4. Open the annotation folder and select Data Definition.
- Choose Edit > Add Item > Allowed Value, type a value in the Description field and click Apply (repeat to specify additional allowed values).
- From the OAE File menu, choose Save.






#### **DATA STRUCTURE DIAGRAMS**

#### **SET OBJECT PROPERTIES**

- 1. Select object and click **Properties** toolbar button or choose **Edit** > **Properties**.
- 2. In the dialog box, set object properties, then click **OK**.




#### ANNOTATE DSE OBJECTS FOR CODE GENERATION

Овјест	PROPERTY/ANNOTATION	SETTINGS
All	Data Structure Comment note	String
Sequences Selections Typedefs	Array Size (property)	String specifying array bounds
	Type (property)	Data type of a DSE element (default is int)
	System Type (property)	Selected (True) or unselected
Intermediate nodes (of any type)	Structure Tag (property)	String
SE File Object	SE File Definition note Included File item	String identifying files to be #included in .h file

#### **STRUCTURE CHARTS**

#### **SET OBJECT PROPERTIES**

- 1. Select object and click **Properties** toolbar button or choose **Edit** > **Properties**.
- 2. In the dialog box, set object properties, then click **OK**.



#### ANNOTATE SCE OBJECTS FOR CODE GENERATION

Овјест	PROPERTY/ANNOTATION	SETTINGS
Modules, Globals, Parameters	Туре	Predefined C type (char, double, float, int, long, short, void) or DSE-defined abstract
	Storage Class	Const, static, static const, register, register const (or unset)
Modules	C Code Body note	String specifying code for the module
	Module Comment note	String representing a module comment
	Module Definition note Variable Arguments item	True or False; default is False
Globals	Array Size (property)	String specifying array bounds
	Global Comment	String representing a global comment
SE File Object	SE File Definition note Included File item	String identifying files to be #included in $.c$ file


#### **STRUCTURE CHARTS**

#### CREATE A FORMAL MODULE DEFINITION

- Select the module to be defined. 1.
- From the GoTo menu, choose Definition and click OK when asked to confirm.

A new definition diagram appears with the module connected to a anchor.

Actual parameters from the module's in-link in the original structure chart appear as formal parameters on the anchorto-module link.




- Specify module's return type and formal parameters' data types on module's 3. property sheet (**Properties** toolbar button or **Edit** > **Properties**).
- Define the module's return type and formal parameters' data types in data structure diagrams, as needed:
  - For module's return type, choose **GoTo** > **Return Type**.
  - For formal parameters' data types, choose **GoTo** > **Type Definition**.
- From the structure chart editor's **File** menu, choose **Save** to link the new definition diagram to the parent diagram and save it.

#### **CREATE AND VIEW A MODULE PDL**

- Select a module and choose SCE > Edit PDL Note.
- 2. In the **Description** dialog, type a module description or pseudo code and click **OK**. A display mark (p) appears on the module.
- With the module still selected, choose **SCE** > 3. Generate PDL(s).

A PDL is generated into an ASCII file named <module name>.pdl in the sce files directory. If no module is selected, a PDL file is generated for each PDL-annotated module in the diagram.



Description:

he Finalize Transaction module verifies the transaction and prints a recein

Finalize Transaction


To view the PDL for a selected module, choose SCE > View Generated PDL.

To generate PDLs for every PDL-annotated module in the model, from the StP Desktop, choose Code > PDL > Generate PDL for All Diagrams.

#### REVERSE ENGINEERING

#### PARSE SOURCE CODE


- From the StP Desktop Code menu, choose Reverse Engineering > Parse Source Code.
- In the Filter text field, type the full path for the makefile, project file, directory, or ObjectAda Library containing the files to parse, then click the Filter button to fill the Directory Listing scrolling list.
- 3. Do one of the following:
  - Select individual files to parse in the **Directory Listing** field and click the right arrow button to move them into the **Files to Parse** list.
  - Select a makefile, project file, directory, or ObjectAda Library in the **Directory Listing** scrolling list and click the appropriate button:
    - · Read Selected Makefile
    - · Read Selected DevStudio Project File
    - Parse Directory Tree
    - ObjectAda Library
- 4. Optionally, click **Makefile Options** button, change the options in the **Makefile Options** dialog box and click **OK**.
- Optionally, click Preprocessor Options button, change the options in the Preprocessor Options dialog box and click OK.
- 6. On the **Parse Source Code** dialog box, click **OK**.



#### REVERSE ENGINEERING

#### **EXTRACT COMMENTS**

- From the StP Desktop Code menu, choose Reverse Engineering > Extract Source Code Comments.
- Specify search locations (above, below, and/ or right of definition).
- Specify how many lines (1-4) constitute a legal gap between a comment and the associated code object's line of definition.
- 4. Choose formatting options.
- Click OK.



#### GENERATE THE MODEL

- From the StP Desktop Code menu, choose Reverse Engineering > Generate Model from Parsed Source Code.
- In the dialog box, select the types of diagrams you want to generate: structure charts, data structures, and/or flow charts.
- 3. Select **Backup Existing Diagrams** to copy current diagrams and annotations to a backup directory.
- Click **Options** to invoke a dialog box with drawing options for each type of diagram.
- 5. Database owners can choose **Privileged** Repository Build to speed large builds.
- Click OK.



#### REVERSE ENGINEERING

#### UPDATE THE MODEL

- Parse the modified code with Incremental Mode selected.
- 2. Rerun comment extraction.
- 3. From the **Code** menu, choose **Reverse Engineering** > **Synchronize Model**.



- 4. In the first field on the dialog box, choose Find Differences from the options list.
- 5. Click **Change Diagram Generation Options**, select drawing options in the dialog box that appears and click **OK**.
- 6. To synchronize the model with changes from specified files and directories only, select Synchronize Partial Model and click Choose Files for Partial Model.
  Search for and select files in the dialog box that appears, then click OK.
- In the Synchronize Model dialog box, click OK.
   A dialog box displays the differences between the old and new semantic models.
- 8. Apply all or selected changes to the graphical model using the **Do All Design Updates**, **Do Design Additions**, or **Do Design Deletions** buttons.

#### REMOVE FILES FROM THE SEMANTIC MODEL

- On the StP Desktop, open the Model Elements category and select File Objects or Directory Objects.
- 2. In the objects pane, select one or more file or directory objects.
- 3. From the Code menu, choose Reverse Engineering > Remove File/Directory from RE Semantic Model.

#### C CODE AND SE MODEL BROWSERS

#### **Browse C Code**

- From the StP Desktop Code menu, choose Reverse Engineering > Browse C Code.
- 2. In the dialog box, select a C identifier category. Categories are: user function, global, library function, constant, typedef, literal value, data structure, data member, #define, comment, file, identifier.



- 3. Optionally specify a name (regular expressions are acceptable) and the target's scope.
- 4. Select from among the activated options:
  - Search for Definitions, References, references with Read Access or Write Access; or search for an Exact Match to a text string.
  - · Select desired case sensitivity.
  - Select the Use Focus option and click the Set/Change Focus button to limit the search to specified files.
- Click OK.

#### BROWSE STRUCTURED MODEL

- From the StP Desktop Tools menu, choose Browse Structured Models.
- In the SE Repository Browser, select a Query-By-Example (QBE) row or cell and type an object name or regular expression in one or more columns.
- 3. From the **Query** menu, choose **Execute QBE**. The results appear in the body rows.
- To browse results, select result row(s) (Shiftclick for multiple rows) and choose a target from the **Browse** menu.
  - Additional results appear in the browser.
- To navigate from a result row to the model, select the row and choose a command from the GoTo menu.
  - The target object appears selected in the appropriate diagram editor.

