Package 'poweRlaw'

April 25, 2020

Type Package

Title Analysis of Heavy Tailed Distributions

Version 0.70.6

Maintainer Colin Gillespie <csgillespie@gmail.com>

Description An implementation of maximum likelihood estimators for a variety of heavy tailed distributions, including both the discrete and continuous power law distributions. Additionally, a goodness-of-fit based approach is used to estimate the lower cut-off for the scaling region.

License GPL-2 | GPL-3

URL https://github.com/csgillespie/poweRlaw

BugReports https://github.com/csgillespie/poweRlaw/issues

Depends R (>= 3.4.0)

Imports methods, parallel, pracma, stats, utils

Suggests covr, knitr, testthat

VignetteBuilder knitr

ByteCompile true

Encoding UTF-8

RoxygenNote 7.1.0

Collate 'aaa_all_classes.R' 'all_generics.R' 'bootstrap.R' 'bootstrap_p.R' 'checks.R' 'compare_distributions.R' 'conlnorm.R' 'data_help_files.R' 'def_conexp.R' 'def_conpl.R' 'def_conweibull.R' 'def_disexp.R' 'def_dislnorm.R' 'def_displ.R' 'def_dispois.R' 'def_template.R' 'dist_data_cdf_methods.R' 'estimate_pars.R' 'estimate_xmin.R' 'get_n.R' 'get_ntail.R' 'lines_methods.R' 'plcon.R' 'pldis.R' 'plot_methods.R' 'points_methods.R' 'powerlaw-package.R' 'show_methods.R' 'timer.R'

NeedsCompilation no

Author Colin Gillespie [aut, cre] (https://orcid.org/0000-0003-1787-0275)

2 poweRlaw-package

Repository CRAN

Date/Publication 2020-04-25 07:30:12 UTC

R topics documented:

poweRlaw-package	2
bootstrap_moby	3
compare_distributions	4
conlnorm-class	6
dist_all_cdf	7
dist_cdf	8
dist_ll	10
dist_pdf	12
dist_rand	13
dplcon	14
dpldis	15
estimate_pars	17
get_bootstrap_sims	18
get_KS_statistic	
get_n	21
get_ntail	21
lines, distribution-method	22
moby	23
native_american	23
plot.bs_xmin	24
population	24
show, distribution-method	25
swiss_prot	25
	bootstrap_moby compare_distributions conlnorm-class dist_all_cdf dist_cdf dist_cdf dist_ll dist_pdf dist_rand dplcon dpldis estimate_pars get_bootstrap_sims get_KS_statistic get_n get_nntail lines,distribution-method moby native_american plot.bs_xmin population show,distribution-method

Description

The poweRlaw package aims to make fitting power laws and other heavy-tailed distributions straightforward. This package contains R functions for fitting, comparing and visualising heavy tailed distributions. Overall, it provides a principled approach to fitting power laws to data.

Details

The code developed in this package has been heavily influenced from the python and R code found at: http://tuvalu.santafe.edu/~aaronc/powerlaws/. In particular, the R code of Laurent Dubroca and Cosma Shalizi.

bootstrap_moby 3

Author(s)

```
<colin.gillespie@newcastle.ac.uk>
```

References

A. Clauset, C.R. Shalizi, and M.E.J. Newman, "Power-law distributions in empirical data" SIAM Review 51(4), 661-703 (2009).

See Also

https://github.com/csgillespie/poweRlaw

bootstrap_moby

Example bootstrap results for the full Moby Dick data set

Description

To explore the uncertainity in the model fit, this package provides a bootstrap function.

bootstrap_moby The output from running 5000 bootstraps on the full Moby Dick data set (for a discrete power law) using the bootstrap function.

bootstrap_p_moby The output from running 5000 bootstraps on the full Moby Dick data set (for a discrete power law) using the bootstrap_p function.

The bootstrap_moby values correspond to the first row of table 6.1 in the Clauset et al paper:

bootstrap_moby\$gof the K-S statistic

bootstrap_moby\$bootstraps a data frame for the optimal values from the bootstrapping procedure. Column 1: K-S, Column 2: xmin, Column 3: alpha. So standard deviation of column 2 and 3 is 2.2 and 0.033 (the paper gives 2 and 0.02 respectively).

The bootstrap_p_moby gives the p-value for the hypothesis test of whether the data follows a power-law. For this simulation study, we get a value of 0.43 (the paper gives 0.49).

Format

A list

Source

M. E. J. Newman, "Power laws, Pareto distributions and Zipf's law." Contemporary Physics 46, 323 (2005). See http://tuvalu.santafe.edu/~aaronc/powerlaws/data.htm for further details.

See Also

moby, bootstrap_p

Examples

```
## Generate the bootstrap_moby data set
## Not run:
data(moby)
m = displ$new(moby)
bs = bootstrap(m, no_of_sims=5000, threads=4, seed=1)
## End(Not run)

#' ## Generate the bootstrap_p_moby data set
## Not run:
bs_p = bootstrap_p(m, no_of_sims=5000, threads=4, seed=1)
## End(Not run)
```

compare_distributions Vuong's test for non-nested models

Description

Since it is possible to fit power law models to any data set, it is recommended that alternative distributions are considered. A standard technique is to use Vuong's test. This is a likelihood ratio test for model selection using the Kullback-Leibler criteria. The test statistic, R, is the ratio of the log-likelihoods of the data between the two competing models. The sign of R indicates which model is better. Since the value of R is esimated, we use the method proposed by Vuong, 1989 to select the model.

Usage

```
compare_distributions(d1, d2)
```

Arguments

d1 A distribution object d2 A distribution object

Details

This function compares two models. The null hypothesis is that both classes of distributions are equally far from the true distribution. If this is true, the log-likelihood ratio should (asymptotically) have a Normal distribution with mean zero. The test statistic is the sample average of the log-likelihood ratio, standardized by a consistent estimate of its standard deviation. If the null hypothesis is false, and one class of distributions is closer to the "truth", the test statistic goes to +/-infinity with probability 1, indicating the better-fitting class of distributions.

compare_distributions 5

Value

This function returns

test statistic The test statistic.

p_one_sided A one-sided p-value, which is an upper limit on getting that small a log-likelihood ratio if the first distribution, d1, is actually true.

p_two_sided A two-sided p-value, which is the probability of getting a log-likelihood ratio which deviates that much from zero in either direction, if the two distributions are actually equally good.

ratio A data frame with two columns. The first column is the x value and second column is the difference in log-likelihoods.

Note

Code initially based on R code developed by Cosma Rohilla Shalizi (http://bactra.org/). Also see Appendix C in Clauset et al, 2009.

References

Vuong, Quang H. (1989): "Likelihood Ratio Tests for Model Selection and Non-Nested Hypotheses", Econometrica 57: 307–333.

Examples

```
# Example data
x = rpldis(100, xmin=2, alpha=3)
##Continuous power law
m1 = conpl$new(x)
m1$setXmin(estimate_xmin(m1))
##Exponential
m2 = conexp$new(x)
m2$setXmin(m1$getXmin())
est2 = estimate_pars(m2)
m2$setPars(est2$pars)
comp = compare_distributions(m1, m2)
plot(comp)
```

6 conlnorm-class

conlnorm-class

Heavy-tailed distributions

Description

The **poweRlaw** package supports a number of distributions:

displ Discrete power-law

dislnorm Discrete log-normal

dispois Discrete Poisson

disexp Discrete Exponential

conpl Continuous power-law

conlnorm Continuous log-normal

conexp Continuous exponential

Each object inherits the discrete_distribution or the ctn_distribution class.

Arguments

The object is typically created by passing data using the dat field. Each field has standard setters and getters.

Value

a reference object

Fields

Each distribution object has four fields. However, the object is typically created by passing data, to the dat field. Each field has standard setters and getters. See examples below

dat The data set.

xmin The lower threshold, xmin. Typically set after initialisation. For the continuous power-law, xmin >= 0 for the discrete distributions, xmin >0

pars A parameter vector. Typically set after initialisation. Note the lognormal distribution has two parameters.

internal A list. This list differs between objects and shouldn't be altered.

Copying objects

Distribution objects are reference classes. This means that when we copy objects, we need to use the copy method, i.e. obj\$copy(). See the examples below for further details.

dist_all_cdf 7

Examples

```
#Load data and create distribution object
data(mobv)
m = displnew(moby)
#Xmin is initially the smallest x value
m$getXmin()
m$getPars()
#Set Xmin and parameter
m$setXmin(2)
m$setPars(2)
#Plot the data and fitted distribution
plot(m)
lines(m)
#Copying
## Shallow copy
m_cpy = m
m_cpy$setXmin(5)
m$getXmin()
## Instead
m_{cpy} = mscopy()
```

dist_all_cdf

The data cumulative distribution function

Description

This is generic function for distribution objects. This function calculates the data or empirical cdf.

The functions dist_data_all_cdf and dist_all_cdf are only available for discrete distributions. Their main purpose is to optimise the bootstrap procedure, where generating a vector xmin:xmax is very quick. Also, when bootstrapping very large values can be generated.

Usage

```
dist_all_cdf(m, lower_tail = TRUE, xmax = 1e+05)
```

8 dist_cdf

```
dist_data_cdf(m, lower_tail = TRUE, xmax = 1e+05)
dist_data_all_cdf(m, lower_tail = TRUE, xmax = 1e+05)
## S4 method for signature 'discrete_distribution'
dist_data_cdf(m, lower_tail = TRUE, xmax = 1e+05)
## S4 method for signature 'discrete_distribution'
dist_data_all_cdf(m, lower_tail = TRUE, xmax = 1e+05)
## S4 method for signature 'ctn_distribution'
dist_data_cdf(m, lower_tail = TRUE, xmax = 1e+05)
```

Arguments

m a distribution object.

lower_tail logical; if TRUE (default), probabilities are $P[X \le x]$, otherwise, P[X > x]. xmax default 1e5. The maximum x value calculated when working out the CDF.

Note

This method does *not* alter the internal state of the distribution objects.

Examples

dist_cdf

The cumulative distribution function (cdf)

Description

This is a generic function for calculating the cumulative distribution function (cdf) of distribution objects. This is similar to base R's pnorm for the normal distribution. The dist_cdf function calculates the cumulative probability distribution for the current parameters and xmin value.

dist_cdf 9

Usage

```
dist_cdf(m, q = NULL, lower_tail = FALSE)
## S4 method for signature 'conlnorm'
dist_cdf(m, q = NULL, lower_tail = TRUE)
## S4 method for signature 'conlnorm'
dist_all_cdf(m, lower_tail = TRUE, xmax = 1e+05)
## S4 method for signature 'conexp'
dist_cdf(m, q = NULL, lower_tail = TRUE)
## S4 method for signature 'conexp'
dist_all_cdf(m, lower_tail = TRUE, xmax = 1e+05)
## S4 method for signature 'conpl'
dist_cdf(m, q = NULL, lower_tail = TRUE)
## S4 method for signature 'conpl'
dist_all_cdf(m, lower_tail = TRUE, xmax = 1e+05)
## S4 method for signature 'conweibull'
dist_cdf(m, q = NULL, lower_tail = TRUE)
## S4 method for signature 'conweibull'
dist_all_cdf(m, lower_tail = TRUE, xmax = 1e+05)
## S4 method for signature 'disexp'
dist_cdf(m, q = NULL, lower_tail = TRUE)
## S4 method for signature 'disexp'
dist_all_cdf(m, lower_tail = TRUE, xmax = 1e+05)
## S4 method for signature 'dislnorm'
dist_cdf(m, q = NULL, lower_tail = TRUE)
## S4 method for signature 'dislnorm'
dist_all_cdf(m, lower_tail = TRUE, xmax = 1e+05)
## S4 method for signature 'displ'
dist_cdf(m, q = NULL, lower_tail = TRUE)
## S4 method for signature 'displ'
dist_all_cdf(m, lower_tail = TRUE, xmax = 1e+05)
## S4 method for signature 'dispois'
dist_cdf(m, q = NULL, lower_tail = TRUE)
```

10 dist_ll

```
## S4 method for signature 'dispois'
dist_all_cdf(m, lower_tail = TRUE, xmax = 1e+05)
```

Arguments

Note

This method does *not* alter the internal state of the distribution objects.

Examples

dist_ll

The log-likelihood function

Description

This is generic function for distribution objects. This function calculates the log-likelihood for the current parameters and xmin value.

Usage

```
dist_ll(m)
## S4 method for signature 'conlnorm'
dist_ll(m)
```

dist_ll 11

```
## S4 method for signature 'conexp'
dist_ll(m)

## S4 method for signature 'conpl'
dist_ll(m)

## S4 method for signature 'conweibull'
dist_ll(m)

## S4 method for signature 'disexp'
dist_ll(m)

## S4 method for signature 'dislnorm'
dist_ll(m)

## S4 method for signature 'displ'
dist_ll(m)

## S4 method for signature 'displ'
dist_ll(m)

## S4 method for signature 'dispois'
dist_ll(m)
```

Arguments

m

a distribution object.

Value

The log-likelihood

Note

This method does *not* alter the internal state of the distribution objects.

See Also

```
dist_cdf, dist_pdf and dist_rand
```

Examples

12 dist_pdf

dist_pdf

The probability density function (pdf)

Description

This is generic function for distribution objects. This function calculates the probability density function (pdf) for the current parameters and xmin value.

Usage

```
dist_pdf(m, q = NULL, log = FALSE)
## S4 method for signature 'conlnorm'
dist_pdf(m, q = NULL, log = FALSE)
## S4 method for signature 'conexp'
dist_pdf(m, q = NULL, log = FALSE)
## S4 method for signature 'conpl'
dist_pdf(m, q = NULL, log = FALSE)
## S4 method for signature 'conweibull'
dist_pdf(m, q = NULL, log = FALSE)
## S4 method for signature 'disexp'
dist_pdf(m, q = NULL, log = FALSE)
## S4 method for signature 'dislnorm'
dist_pdf(m, q = NULL, log = FALSE)
## S4 method for signature 'displ'
dist_pdf(m, q = NULL, log = FALSE)
## S4 method for signature 'dispois'
dist_pdf(m, q = NULL, log = FALSE)
```

Arguments

m	a distribution object.
q	a vector values where the function will be evaluated. If ${\bf q}$ is NULL (default), then the data values will be used.
log	default FALSE. If TRUE, probabilities are given as log(p).

Value

The probability density (or mass) function

dist_rand 13

Note

This method does *not* alter the internal state of the distribution objects.

See Also

```
dist_cdf, dist_ll and dist_rand
```

Examples

dist_rand

Random number generation for the distribution objects

Description

This is generic function for generating random numbers from the underlying distribution of the distribution reference objects. This function generates n random numbers using the parameters and xmin values found in the associated reference object.

Usage

```
dist_rand(m, n)

## S4 method for signature 'conlnorm'
dist_rand(m, n = "numeric")

## S4 method for signature 'conexp'
dist_rand(m, n = "numeric")

## S4 method for signature 'conpl'
dist_rand(m, n = "numeric")

## S4 method for signature 'conweibull'
dist_rand(m, n = "numeric")

## S4 method for signature 'disexp'
dist_rand(m, n = "numeric")
```

14 dplcon

```
## S4 method for signature 'dislnorm'
dist_rand(m, n = "numeric")

## S4 method for signature 'displ'
dist_rand(m, n = "numeric")

## S4 method for signature 'dispois'
dist_rand(m, n = "numeric")
```

Arguments

m a distribution object.

n number of observations to be generated.

Value

n random numbers

Note

This method does *not* alter the internal state of the distribution object.

See Also

```
dist_cdf, dist_pdf and dist_ll
```

Examples

dplcon

The continuous power-law distribution

Description

Density and distribution function of the continuous power-law distribution, with parameters xmin and alpha.

dpldis 15

Usage

```
dplcon(x, xmin, alpha, log = FALSE)
pplcon(q, xmin, alpha, lower.tail = TRUE)
rplcon(n, xmin, alpha)
```

Arguments

x, q	vector of quantiles. The discrete power-law distribution is defined for $x > xmin$
xmin	The lower bound of the power-law distribution. For the continuous power-law, $x\min >= 0$. for the discrete distribution, $x\min > 0$.
alpha	The scaling parameter: $alpha > 1$.
log	logical (default FALSE) if TRUE, log values are returned.
lower.tail	logical; if TRUE (default), probabilities are $P[X \leq x]$, otherwise, $P[X > x]$.
n	Number of observations. If $length(n) > 1$, the length is taken to be the number required.

Value

dplcon gives the denisty and pplcon gives the distribution function.

Note

The discrete random number generator is very inefficient

Examples

```
xmin = 1; alpha = 1.5
x = seq(xmin, 10, length.out=1000)
plot(x, dplcon(x, xmin, alpha), type="1")
plot(x, pplcon(x, xmin, alpha), type="1", main="Distribution function")
n = 1000
con_rns = rplcon(n, xmin, alpha)
con_rns = sort(con_rns)
p = rep(1/n, n)
#Zipfs plot
plot(con_rns, rev(cumsum(p)), log="xy", type="1")
```

dpldis

Discrete power-law distribution

Description

Density, distribution function and random number generation for the discrete power law distribution with parameters xmin and alpha.

16 dpldis

Usage

```
dpldis(x, xmin, alpha, log = FALSE)
ppldis(q, xmin, alpha, lower.tail = TRUE)
rpldis(n, xmin, alpha, discrete_max = 10000)
```

imation.

Arguments

x,q	vector of quantiles. The discrete power-law distribution is defined for $x > xmin$.
xmin	The lower bound of the power-law distribution. For the continuous power-law, $x\min >= 0$. for the discrete distribution, $x\min > 0$.
alpha	The scaling parameter: $alpha > 1$.
log	logical (default FALSE) if TRUE, log values are returned.
lower.tail	logical; if TRUE (default), probabilities are $P[X \leq x]$, otherwise, $P[X > x]$.
n	Number of observations. If $length(n) > 1$, the length is taken to be the number required.
discrete_max	The value when we switch from the discrete random numbers to a CTN approx-

Details

The Clauset, 2009 paper provides an algorithm for generating discrete random numbers. However, if this algorithm is implemented in R, it gives terrible performance. This is because the algorithm involves "growing vectors". Another problem is when alpha is close to 1, this can result in very large random number being generated (which means we need to calculate the discrete CDF for very large values).

The algorithm provided in this package generates true discrete random numbers up to 10,000 then switches to using continuous random numbers. This switching point can altered by changing the discrete_max argument.

In order to get a efficient power-law discrete random number generator, the algorithm needs to be implemented in C.

Value

dpldis returns the density, ppldis returns the distribution function and rpldis return random numbers.

Note

The naming of these functions mirrors standard R functions, i.e. dnorm. When alpha is close to one, generating random number can be very slow.

References

Clauset, Aaron, Cosma Rohilla Shalizi, and Mark EJ Newman. "Power-law distributions in empirical data." SIAM review 51.4 (2009): 661-703.

estimate_pars 17

Examples

estimate_pars

Estimates the distributions using mle.

Description

estimate_pars estimates the distribution's parameters using their maximum likelihood estimator. This estimate is conditional on the current xmin value.

Usage

```
estimate_pars(m, pars = NULL)
```

Arguments

m

A reference class object that contains the data.

pars

default NULL. A vector or matrix (number of columns equal to the number of parameters) of parameters used to #' optimise over. Otherwise, for each value of xmin, the mle will be used, i.e. estimate_pars(m). For small samples, the mle may be biased.

Value

returns list.

18 get_bootstrap_sims

Examples

```
data(moby_sample)
m = displ$new(moby_sample)
estimate_xmin(m)
m$setXmin(7)
estimate_pars(m)
```

get_bootstrap_sims

Estimating the lower bound (xmin)

Description

When fitting heavy tailed distributions, sometimes it is necessary to estimate the lower threshold, xmin. The lower bound is estimated by minimising the Kolmogorov-Smirnoff statistic (as described in Clauset, Shalizi, Newman (2009)).

get_KS_statistic Calculates the KS statistic for a particular value of xmin.

estimate_xmin Estimates the optimal lower cutoff using a goodness-of-fit based approach. This function may issue warnings when fitting lognormal, Poisson or Exponential distributions. The warnings occur for large values of xmin. Essentially, we are discarding the bulk of the distribution and cannot calculate the tails to enough accuracy.

bootstrap Estimates the unncertainty in the xmin and parameter values via bootstrapping.

bootstrap_p Performs a bootstrapping hypothesis test to determine whether a suggested (typically power law) distribution is plausible. This is only available for distributions that have dist_rand methods available.

Usage

```
get_bootstrap_sims(m, no_of_sims, seed, threads = 1)
bootstrap(
    m,
    xmins = NULL,
    pars = NULL,
    xmax = 1e+05,
    no_of_sims = 100,
    threads = 1,
    seed = NULL,
    distance = "ks"
)

get_bootstrap_p_sims(m, no_of_sims, seed, threads = 1)
bootstrap_p(
    m,
    xmins = NULL,
```

get_bootstrap_sims 19

```
pars = NULL,
  xmax = 1e+05,
  no_of_sims = 100,
  threads = 1,
  seed = NULL,
  distance = "ks"
)

get_distance_statistic(m, xmax = 1e+05, distance = "ks")

estimate_xmin(m, xmins = NULL, pars = NULL, xmax = 1e+05, distance = "ks")
```

Arguments

m	A reference class object that contains the data.
no_of_sims	number of bootstrap simulations. When no_of_sims is large, this can take a while to run.
seed	default NULL. An integer to be supplied to set.seed, or NULL not to set reproducible seeds. This argument is passed clusterSetRNGStream.
threads	number of concurrent threads used during the bootstrap.
xmins	default 1e5. A vector of possible values of xmin to explore. When a single value is passed, this represents the maximum value to search, i.e. by default we search from (1, 1e5). See details for further information.
pars	default NULL. A vector or matrix (number of columns equal to the number of parameters) of parameters used to #' optimise over. Otherwise, for each value of xmin, the mle will be used, i.e. estimate_pars(m). For small samples, the mle may be biased.
xmax	default 1e5. The maximum x value calculated when working out the CDF. See details for further information.
distance	A string containing the distance measure (or measures) to calculate. Possible

Details

When estimating xmin for discrete distributions, the search space when comparing the data-cdf (empirical cdf) and the distribution_cdf runs from xmin to max(x) where x is the data set. This **can** often be computationally brutal. In particular, when bootstrapping we generate random numbers from the power law distribution, which has a long tail.

values are ks or reweight. See details for further information.

To speed up computations for discrete distributions it is sensible to put an upper bound, i.e. xmax and/or explicitly give values of where to search, i.e. xmin.

Occassionally bootstrapping can generate strange situations. For example, all values in the simulated data set are less then xmin. In this case, the estimated distance measure will be Inf and the parameter values, NA.

There are other possible distance measures that can be calculated. The default is the Kolomogorov Smirnoff statistic (KS). This is equation 3.9 in the CSN paper. The other measure currently available is reweight, which is equation 3.11.

20 get_KS_statistic

Note

Adapted from Laurent Dubroca's code found at http://tuvalu.santafe.edu/~aaronc/powerlaws/plfit.r

Examples

```
# Load the data set and create distribution object#
x = 1:10
m = displ new(x)
# Estimate xmin and pars
est = estimate_xmin(m)
m$setXmin(est)
# Bootstrap examples
## Not run:
bootstrap(m, no_of_sims=1, threads=1)
bootstrap_p(m, no_of_sims=1, threads=1)
## End(Not run)
```

get_KS_statistic

Deprecated function

Description

This function is now deprecated and may be removed in future versions.

Usage

```
get_KS_statistic(m, xmax = 1e+05, distance = "ks")
```

Arguments

m A reference class object that contains the data.

xmax default 1e5. The maximum x value calculated when working out the CDF. See

details for further information.

distance A string containing the distance measure (or measures) to calculate. Possible

values are ks or reweight. See details for further information.

See Also

```
get_distance_statistic
```

get_n 21

get_n

Sample size

Description

Returns the sample size of the data set contained within the distribution object.

Usage

```
get_n(m)
```

Arguments

m

a distribution object.

Examples

get_ntail

Values greater than or equal to xmin

Description

Returns the number of data points greater than or equal to current value of xmin. In the Clauset et al, paper this is called 'ntail'.

Usage

```
get_ntail(m, prop = FALSE, lower = FALSE)
```

Arguments

m a distribution object.

prop default FALSE. Return the value as a proportion of the total sample size

lower default FALSE. If TRUE returns sample size - ntail

Examples

lines, distribution-method

Generic plotting functions

Description

These are generic functions for distribution reference objects. Standard plotting functions, i.e. plot, points, and lines work with all distribution objects.

Usage

```
## S4 method for signature 'distribution'
lines(x, cut = FALSE, draw = TRUE, length.out = 100, ...)
## S4 method for signature 'distribution'
plot(x, cut = FALSE, draw = TRUE, ...)
## S4 method for signature 'distribution'
points(x, cut = FALSE, draw = TRUE, length.out = 100, ...)
```

Arguments

X	a distribution reference object.
cut	logical (default FALSE) - Where should the plot begin. If cut=FALSE, then the plot will start at the minimum data value. Otherwise, the plot will start from xmin
draw	logical (default TRUE). Should the plot/lines/points function plot or return the data (in a data frame object).
length.out	numeric, default 100. How many points should the distribution be evaulated at. This argument is only for plotting the fitted lines.
	Further arguments passed to the lines functions.

Note

This method does *not* alter the internal state of the distribution objects.

moby 23

moby

Moby Dick word count

Description

The frequency of occurrence of unique words in the novel Moby Dick by Herman Melville.

The data set moby_sample is 2000 values sampled from the moby data set.

Format

A vector

Source

M. E. J. Newman, "Power laws, Pareto distributions and Zipf's law." Contemporary Physics 46, 323 (2005). See http://tuvalu.santafe.edu/~aaronc/powerlaws/data.htm for further details.

native_american

Casualties in the American Indian Wars (1776 and 1890)

Description

These data files contain the observed casualties in the American Indian Wars. The data sets native_american and us_american contain the casualties on the Native American and US American sides respectively. Each data set is a data frame, with two columns: the number of casualties and the conflict date.

Format

Data frame

Source

Friedman, Jeffrey A. "Using Power Laws to Estimate Conflict Size." The Journal of conflict resolution (2014).

24 population

plot.bs_xmin

Plot methods for bootstrap objects

Description

A simple wrapper around the plot function to aid with visualising the bootstrap results. The values plotted are returned as an invisible object.

Usage

```
## $3 method for class 'bs_xmin'
plot(x, trim = 0.1, ...)
## $3 method for class 'bs_p_xmin'
plot(x, trim = 0.1, ...)
## $3 method for class 'compare_distributions'
plot(x, ...)
```

Arguments

Х	an object of class bs_xmin or bs_p_xmin
trim	When plotting the cumulative means and standard deviation, the first trim percentage of values are not displayed. default $trim=0.1$
	graphics parameters to be passed to the plotting routines.

population

City boundaries and the universality of scaling laws

Description

This data set contains the population size of cities and towns in England. For further details on the algorithm used to determine city boundries, see the referenced paper.

Format

vector

Source

Arcaute, Elsa, et al. "City boundaries and the universality of scaling laws." arXiv preprint arXiv:1301.1674 (2013).

show, distribution-method 25

show, distribution-method

Generic show method for distribution objects

Description

The distribution objects have an internal structure that is used for caching purposes. Using the default show method gives the illusion of duplicate values. This show method aims to avoid this confusion.

Usage

```
## S4 method for signature 'distribution'
show(object)
```

Arguments

object

A distribution object.

swiss_prot

Word frequency in the Swiss-Prot database

Description

This dataset contains all the words extracted from the Swiss-Prot version 9 data (with the resulting frequency for each word). Other datasets for other database versions can be obtained by contacting Michael Bell (http://homepages.cs.ncl.ac.uk/m.j.bell1/annotationQualityPaper.php)

Full details in http://arxiv.org/abs/arXiv:1208.2175v1

Format

data frame

Source

Bell, MJ, Gillespie, CS, Swan, D, Lord, P. An approach to describing and analysing bulk biological annotation quality: A case study using UniProtKB. Bioinformatics 2012, 28, i562-i568.

Index

*Topic package	dist_cdf, 8, 11, 13, 14
poweRlaw-package, 2	<pre>dist_cdf,conexp-method(dist_cdf), 8</pre>
	<pre>dist_cdf,conlnorm-method(dist_cdf), 8</pre>
bootstrap(get_bootstrap_sims), 18	<pre>dist_cdf,conpl-method(dist_cdf), 8</pre>
bootstrap_moby, 3	<pre>dist_cdf,conweibull-method(dist_cdf), 8</pre>
bootstrap_p(get_bootstrap_sims), 18	dist_cdf, disexp-method (dist_cdf), 8
bootstrap_p_moby(bootstrap_moby), 3	<pre>dist_cdf,dislnorm-method(dist_cdf), 8</pre>
	dist_cdf,displ-method(dist_cdf),8
compare_distributions,4	<pre>dist_cdf,dispois-method(dist_cdf), 8</pre>
conexp (conlnorm-class), 6	dist_data_all_cdf (dist_all_cdf), 7
conexp-class (conlnorm-class), 6	dist_data_all_cdf,discrete_distribution-method
conlnorm(conlnorm-class), 6	(dist_all_cdf), 7
conlnorm-class, 6	dist_data_cdf (dist_all_cdf), 7
conpl (conlnorm-class), 6	dist_data_cdf,ctn_distribution-method
conpl-class (conlnorm-class), 6	(dist_all_cdf), 7
conweibull (conlnorm-class), 6	dist_data_cdf,discrete_distribution-method
conweibull-class (conlnorm-class), 6	(dist_all_cdf), 7
dianum (annlanum alana) 6	dist_11, 10, <i>13</i> , <i>14</i>
disexp (conlnorm-class), 6	dist_ll,conexp-method(dist_ll),10
disexp-class (conlnorm-class), 6	dist_ll,conlnorm-method(dist_ll),10
dislnorm (conlnorm-class), 6	dist_ll,conpl-method(dist_ll), 10
dislnorm-class (conlnorm-class), 6	dist_ll,conweibull-method(dist_ll), 10
<pre>displ(conlnorm-class), 6 displ-class(conlnorm-class), 6</pre>	dist_ll,disexp-method(dist_ll),10
dispois (conlnorm-class), 6	dist_ll,dislnorm-method(dist_ll),10
dispois (confine class), 6	dist_ll,displ-method(dist_ll), 10
dist_all_cdf, 7	dist_ll,dispois-method(dist_ll), 10
dist_all_cdf, conexo-method (dist_cdf), 8	dist_pdf, 11, 12, 14
dist_all_cdf,conexp-method(dist_cdf),8	dist_pdf, conexp-method (dist_pdf), 12
dist_all_cdf,conlnorm-method	dist_pdf,conlnorm-method(dist_pdf), 12
(dist_cdf), 8	dist_pdf, conpl-method (dist_pdf), 12
dist_all_cdf,conpl-method(dist_cdf),8	dist_pdf,conweibull-method(dist_pdf),
dist_all_cdf,conweibull-method	12
(dist_cdf), 8	<pre>dist_pdf,disexp-method(dist_pdf), 12</pre>
dist_all_cdf,disexp-method(dist_cdf),8	dist_pdf, dislnorm-method (dist_pdf), 12
dist_all_cdf,dislnorm-method	dist_pdf, displ-method (dist_pdf), 12
(dist_cdf), 8	dist_pdf,dispois-method(dist_pdf), 12
dist_all_cdf,displ-method(dist_cdf),8	dist_rand, 11, 13, 13
<pre>dist_all_cdf, dispois-method (dist_cdf),</pre>	dist_rand, conexp-method (dist_rand), 13
8	dist rand conlorm-method (dist rand)

INDEX 27

13	rpldis (dpldis), 15
<pre>dist_rand, conpl-method (dist_rand), 13 dist_rand, conweibull-method</pre>	show, distribution-method, 25 Swiss_prot (swiss_prot), 25 swiss_prot, 25 us_american (native_american), 23 USAmerican (native_american), 23
<pre>estimate_pars, 17 estimate_xmin (get_bootstrap_sims), 18</pre>	
<pre>get_bootstrap_p_sims</pre>	
lines, distribution-method, 22	
moby, 23 moby_sample (moby), 23	
native_american, 23 NativeAmerican (native_american), 23	
plot, distribution-method	
rplcon(dplcon), 14	