596K Followers · Editors' Picks Features Deep Dives Grow Contribute About

Understanding AUC - ROC Curve





Understanding AUC - ROC Curve [Image 1] (Image courtesy: My Photoshopped Collection)

In Machine Learning, performance measurement is an essential task. So when it comes to a classification problem, we can count on an AUC - ROC Curve. When we need to check or visualize the performance of the multiclass classification problem, we use the AUC (Area Under The Curve) ROC (Receiver Operating Characteristics) curve. It is one of the most important evaluation metrics for checking any classification model's performance. It is also written as AUROC (Area Under the Receiver Operating Characteristics)

Note: For better understanding, I suggest you read my article about Confusion Matrix.

This blog aims to answer the following questions:


1. What is the AUC - ROC Curve?

- 2. Defining terms used in AUC and ROC Curve.
- 3. How to speculate the performance of the model?
- 4. Relation between Sensitivity, Specificity, FPR, and Threshold.
- 5. How to use AUC ROC curve for the multiclass model?

What is the AUC - ROC Curve?

AUC - ROC curve is a performance measurement for the classification problems at various threshold settings. ROC is a probability curve and AUC represents the degree or measure of separability. It tells how much the model is capable of distinguishing between classes. Higher the AUC, the better the model is at predicting 0 classes as 0 and 1 classes as 1. By analogy, the Higher the AUC, the better the model is at distinguishing between patients with the disease and no disease.

The ROC curve is plotted with TPR against the FPR where TPR is on the y-axis and FPR is on the x-axis.



AUC - ROC Curve [Image 2] (Image courtesy: My Photoshopped Collection)

Defining terms used in AUC and ROC Curve.

TPR (True Positive Rate) / Recall / Sensitivity

TPR /Recall / Sensitivity =
$$\frac{TP}{TP + FN}$$

Image 3

Specificity

FPR


How to speculate about the performance of the model?

An excellent model has AUC near to the 1 which means it has a good measure of separability. A poor model has an AUC near 0 which means it has the worst measure of separability. In fact, it means it is reciprocating the result. It is predicting 0s as 1s and 1s as 0s. And when AUC is 0.5, it means the model has no class separation capacity whatsoever.

Let's interpret the above statements.


As we know, ROC is a curve of probability. So let's plot the distributions of those probabilities:

Note: Red distribution curve is of the positive class (patients with disease) and the green distribution curve is of the negative class (patients with no disease).




[Image 6 and 7] (Image courtesy: My Photoshopped Collection)

This is an ideal situation. When two curves don't overlap at all means model has an ideal measure of separability. It is perfectly able to distinguish between positive class and negative class.




[Image 8 and 9] (Image courtesy: My Photoshopped Collection)

When two distributions overlap, we introduce type 1 and type 2 errors. Depending upon the threshold, we can minimize or maximize them. When AUC is 0.7, it means there is a 70% chance that the model will be able to distinguish between positive class and negative class.



[Image 10 and 11] (Image courtesy: My Photoshopped Collection)

This is the worst situation. When AUC is approximately 0.5, the model has no discrimination capacity to distinguish between positive class and negative class.



[Image 12 and 13] (Image courtesy: My Photoshopped Collection)

classes. It means the model is predicting a negative class as a positive class and vice versa.

The relation between Sensitivity, Specificity, FPR, and Threshold.

Sensitivity and Specificity are inversely proportional to each other. So when we increase Sensitivity, Specificity decreases, and vice versa.

Sensitivity 1, Specificity 1 and Sensitivity 1, Specificity 1

When we decrease the threshold, we get more positive values thus it increases the sensitivity and decreasing the specificity.

Similarly, when we increase the threshold, we get more negative values thus we get higher specificity and lower sensitivity.

As we know FPR is 1 - specificity. So when we increase TPR, FPR also increases and vice versa.

TPR \uparrow , FPR \uparrow and TPR \downarrow , FPR \downarrow

How to use the AUC ROC curve for the multi-class model?

In a multi-class model, we can plot the N number of AUC ROC Curves for N number classes using the One vs ALL methodology. So for example, If you have **three** classes named **X**, **Y**, and **Z**, you will have one ROC for X classified against Y and Z, another ROC for Y classified against X and Z, and the third one of Z classified against Y and X.

Thanks for Reading.

I hope I've given you some understanding of what exactly is the AUC - ROC Curve. If you like this post, a tad of extra motivation will be helpful by giving this post some claps \bigcirc . I am always open to your questions and suggestions. You can share this on Facebook, Twitter, Linkedin, so someone in need might stumble upon this.

You can reach me at:

LinkedIn: https://www.linkedin.com/in/narkhedesarang/

Twitter: https://twitter.com/narkhede-sarang

Sign up for The Variable

By Towards Data Science

Every Thursday, the Variable delivers the very best of Towards Data Science: from hands-on tutorials and cutting-edge research to original features you don't want to miss. <u>Take a look.</u>

Get this newsletter

Machine Learning Auc Roc Curve Data Science Classification Models Data Mining

About Write Help Legal