# Perforce 2010.1 Command Reference

June 2010

This manual copyright 1999-2010 Perforce Software.

All rights reserved.

Perforce software and documentation is available from http://www.perforce.com. You may download and use Perforce programs, but you may not sell or redistribute them. You may download, print, copy, edit, and redistribute the documentation, but you may not sell it, or sell any documentation derived from it. You may not modify or attempt to reverse engineer the programs.

Perforce programs and documents are available from our Web site as is. No warranty or support is provided. Warranties and support, along with higher capacity servers, are sold by Perforce Software.

Perforce Software assumes no responsibility or liability for any errors or inaccuracies that may appear in this book.

By downloading and using our programs and documents you agree to these terms.

Perforce and Inter-File Branching are trademarks of Perforce Software. Perforce software includes software developed by the University of California, Berkeley and its contributors.

All other brands or product names are trademarks or registered trademarks of their respective companies or organizations.

# **Table of Contents**

About This Manual	7
p4 add	9
p4 admin	
p4 annotate	
p4 branch	
p4 branches	
p4 browse	
p4 change	
p4 changelists	
p4 changelist	
p4 changes	
p4 client	
p4 clients	
p4 counter	
p4 counters	
p4 dbschema	
p4 dbstat	
p4 delete	
p4 depot	
p4 depots	
p4 describe	
p4 diff	
p4 diff2	
p4 dirs	
p4 edit	64
p4 export	
p4 filelog	
p4 files	
p4 fix	73
p4 fixes	76
p4 flush	78
p4 fstat	81
p4 grep	88
p4 group	
p4 groups	94

p4 have	
p4 help	98
p4 info	100
p4 integrate	101
p4 integrated	107
p4 job	109
p4 jobs	112
p4 jobspec	117
p4 label	121
p4 labels	124
p4 labelsync	126
p4 license	128
p4 lock	129
p4 lockstat	
p4 logger	131
p4 login	
p4 logout	134
p4 logstat	136
p4 logtail	137
p4 monitor	138
p4 move	141
p4 obliterate	
p4 opened	146
p4 passwd	148
p4 print	
p4 protect	
p4 protects	163
p4 rename	
p4 reopen	
p4 replicate	
p4 resolve	
p4 resolved	
p4 revert	179
p4 review	181
p4 reviews	183
p4 set	185
p4 shelve	
p4 sizes	190
p4 submit	192

p4 sync	197
p4 tag	201
p4 tickets	
p4 triggers	
p4 typemap	
p4 unlock	
p4 unshelve	
p4 user	
p4 users	
p4 verify	
p4 where	
p4 workspace	
p4 workspaces	230
Environment and Donisture Variables	221
Environment and Registry Variables	231
P4AUDIT	233
P4CHARSET	234
P4COMMANDCHARSET	235
P4CLIENT	236
P4CONFIG	237
P4DEBUG	
P4DESCRIPTION	240
P4DIFF	241
P4DIFFUNICODE	242
P4EDITOR	243
P4HOST	244
P4JOURNAL	
P4LANGUAGE	246
P4LOG	247
P4MERGE	248
P4MERGEUNICODE	
P4NAME	250
P4PAGER	251
P4PASSWD	252
P4PCACHE	
P4PFSIZE	254
P4POPTIONS	
	255

P4ROOT	258
P4TARGET	
P4TICKETS	260
P4USER	261
P4ZEROCONF	262
PWD	
TMP, TEMP	264
Additional Information	265
Global Options	267
Global Options	267 271
Global Options	267 271 277

#### **About This Manual**

#### **Synopsis**

This is the *Perforce 2010.1 Command Reference*.

# **Description**

This manual documents every Perforce command and environment variable. This manual is intended for users who prefer to learn by means of UNIX-style man pages, and for users who already understand the basics of Perforce and need to quickly find information on a specific command.

The following table provides an index to the *Command Reference* by functional area:

Function	Where to look
Help	p4 help, p4 info, File Specifications, Views, Global Options, File Types
Client workspace	p4 client,p4 clients,p4 flush,p4 have,p4 sync,p4 where,p4 workspace,p4 workspaces
Files	p4 add,p4 delete,p4 diff,p4 diff2,p4 dirs,p4 edit,p4 files,p4 fstat,p4 grep, p4 move,p4 lock,p4 print,p4 rename,p4 revert,p4 sizes,p4 unlock
Changelists	p4 change, p4 changelist, p4 changes, p4 changelists, p4 describe, p4 filelog, p4 opened, p4 reopen, p4 review, p4 shelve, p4 submit, p4 unshelve
Jobs	p4 fix,p4 fixes,p4 job,p4 jobs,p4 jobspec
Branching and Merging	p4 branch, p4 branches, p4 integrate, p4 integrated, p4 label, p4 labels, p4 labelsync, p4 tag, p4 resolve, p4 resolved
Administration	p4 admin, p4 counter, p4 counters, p4 dbschema, p4 dbstat, p4 depot, p4 depots, p4 license, p4 lockstat, p4 logger, p4 logstat, p4 logtail, p4 monitor, p4 obliterate, p4 replicate, p4 reviews, p4 triggers, p4 typemap, p4 verify

Function	Where to look
Security	p4 group,p4 groups,p4 login,p4 logout,p4 passwd,p4 protect,p4 protects,p4 tickets,p4 user,p4 users
Environment	p4 browse, p4 set, Environment and Registry Variables, P4AUDIT, P4CHARSET, P4COMMANDCHARSET, P4CLIENT, P4CONFIG, P4DEBUG, P4DESCRIPTION, P4DIFF, P4DIFFUNICODE, P4EDITOR, P4HOST, P4JOURNAL, P4LANGUAGE, P4LOG, P4MERGE, P4MERGEUNICODE, P4NAME, P4PAGER, P4PASSWD, P4PCACHE, P4PFSIZE, P4POPTIONS, P4PORT, P4ROOT, P4TARGET, P4TICKETS, P4USER, P4ZEROCONF, PWD, TMP, TEMP

If you'd prefer to learn the concepts on which Perforce is based, or you prefer a style featuring more examples and tutorials than what you find here, see the *P4 User's Guide*, available from our web site at: http://www.perforce.com.

#### **Options**

This manual is available in PDF and HTML.

#### **Usage Notes**

Both the PDF and HTML versions of this manual have been extensively cross-referenced. When viewing the PDF manual online, you can read the description of any particular command by clicking on a reference to that command from any other chapter.

If there's anything we've left out that you think should be included, let us know. Please send your comments to manual@perforce.com.

#### p4 add

#### **Synopsis**

Open file(s) in a client workspace for addition to the depot.

#### **Syntax**

```
p4 [g-opts] add [-c changelist#] [-f -n -d] [-t type] file...
```

#### **Description**

p4 add opens files within the client workspace for addition to the depot. The specified file(s) are linked to a changelist; the files are not actually added to the depot until the changelist is sent to the server with p4 submit. The added files must either not already exist in the depot, or exist in the depot but be marked as deleted at the head revision.

To open a file with p4 add, the file must exist in your client workspace *view*, but does not need to exist in your workspace at the time of p4 add. The file must, however, exist in your workspace when you run p4 submit, or the submission will fail. p4 add does not create or overwrite files in your workspace; if a file does not exist, you must create it yourself.

By default, the specified files are opened in the default changelist. To open the files in a specified changelist, use the -c flag. (To move files from the default changelist to a numbered changelist, use the p4 change command.)

When adding files, Perforce first examines the typemap table (p4 typemap) to see if the system administrator has defined a file type for the file(s) being added. If a match is found, the file's type is set as defined in the typemap table. If a match is not found, Perforce examines the first 8192 bytes of the file to determine whether it is text or binary, and the files are stored in the depot accordingly. By default, text file revisions are stored in reverse delta format; newly-added text files larger than 10MB are assigned filetype text+C and stored in full. Files compressed in the .zip format (including .jar files) are also automatically detected and assigned the type ubinary. Other binary revisions are stored in full, with compression.

The -t *filetype* flag explicitly specifies a file type, overriding both the typemap table and Perforce's default file type detection mechanism.

To add files containing the characters @, #, \*, and %, use the -f flag. This flag forces literal interpretation of characters otherwise used by Perforce as wildcards.

If you open a file for edit or move/add, and another subsequently deletes the file you opened, the operation will fail with an error when you submit the changelist. To ensure that you create the desired target file, specify the -d flag ("downgrade"). More specifically:

- You open a file for edit, then another user submits a changelist that deletes or moves the file. When you submit your edits, the Perforce Server returns an error and the file remains open for edit. To restore the file (including any changes you have made) to the depot location from which you checked it out, open the file for add and specify the -d flag, then submit the file.
- You open a file for move/add and another user submits a changelist that deletes the source file. When you submit the move, the Perforce Server returns an error and the file remains open for add/move. To create the desired target file, issue the p4 add -d command, specifying the target file, and submit the file.

-c changelist	Opens the files for add within the specified <code>changelist</code> . If this flag is not used, the files are linked to the default changelist.
-d	Downgrade file open status to simple add.
-f	Use the -f flag to force inclusion of wildcards in filenames. See the <i>File Specifications</i> chapter for details.
-n	Preview which files would be opened for add, without actually changing any files or metadata.
-t filetype	Adds the file as the specified filetype, overriding any settings in the typemap table.
	Please see the <i>File Types</i> chapter for a list of Perforce file types.
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	open

- Wildcards in file specifications provided to p4 add are expanded by the local operating system, not by the Perforce server. For instance, the . . . wildcard cannot be used with p4 add.
- In Perforce, there is no difference between adding files to an empty depot and adding files to a depot that already contains other files. You can populate new, empty depots by adding files from a client workspace with p4 add.
- Do not use ASCII expansions of special characters with p4 add -f. To add the file status@june.txt, use

```
p4 add -f status@june.txt
```

If you manually expand the @ sign and attempt to add the file status%40june.txt, Perforce interprets the % sign literally, expands it to the hex code %25, resulting in the filename status%2540june.txt.

# **Examples**

•	p	4 add -t binary file.pdf	Assigns a specific file type to a new file, overriding any settings in the typemap table
also opens the README file in the user's current working directory for add. These files are linked to the default changelist.	p	4 add -c 13 *	*
p4 add -f *.c Opens a file named *.c for add.	p	4 add README ~/src/*.c	
	p	4 add -f *.c	Opens a file named *.c for add.
To refer to this file in views, or with other Perforce commands, you must subsequently use the hex expansion \$2A in place of the asterisk.			commands, you must subsequently use the hex
For more information, see "Limitations on characters in filenames and entities" on page 274.			For more information, see "Limitations on characters in filenames and entities" on page 274.

#### **Related Commands**

To open a file for edit	p4 edit
To open a file for deletion	p4 delete
To copy all open files to the depot	p4 submit
To read files from the depot into the client workspace	p4 sync
To create or edit a new changelist	p4 change
To list all opened files	p4 opened
To revert a file to its unopened state	p4 revert
To move an open file to a different pending changelist	p4 reopen
To change an open file's file type	p4 reopen -t filetype

## p4 admin

#### Synopsis

Perform administrative operations on the server.

#### **Syntax**

```
p4 [g-opts] admin checkpoint [ -z ] [ prefix ]
p4 [g-opts] admin journal [ -z ] [ prefix ]
p4 [g-opts] admin stop
p4 [g-opts] admin updatespecdepot [ -a | -s type ]
```

#### Description

The p4 admin command allows Perforce superusers to perform administrative tasks even when working from a different machine than the one running the Perforce Server.

To stop the server, use p4 admin stop. This locks the database to ensure that it is in a consistent state upon server restart, and then shuts down the Perforce background process. (For Windows users, this works whether you are running Perforce as a server or a service.)

To take a checkpoint, use p4 admin checkpoint [prefix]. This is equivalent to logging in to the server machine and taking a checkpoint with p4d -jc [prefix]. A checkpoint is taken and the journal is copied to a numbered file. If a prefix is specified, the files are named prefix.ckp.n or prefix.jnl.n-1 respectively, where n is a sequence number. You can store checkpoints and journals in the directory of your choice by specifying the directory as part of the prefix. (Rotated journals are stored in the P4ROOT directory, regardless of the directory in which the current journal is stored.) If no prefix is specified, the default filenames checkpoint.n and journal.n-1 are used.

The p4 admin journal command is equivalent to p4d -jj. For details, see the *System Administrator's Guide*. The files are created in the server root specified when the Perforce server was started.

The p4 admin updatespecdepot command causes the Perforce Server to archive stored forms (specifically, client, depot, branch, label, typemap, group, user, and job forms) into the spec depot. If the -a flag is used, all of the form specification types are archived. If the -s flag option is used, then only those of the specified *type* are archived. Only those forms that have not yet been archived are created.

- Z	For p4 admin checkpoint and p4 admin journal, save the checkpoint and saved journal file in compressed (gzip) format, appending the .gz suffix to the files.
-a	For p4 admin updatespecdepot, update the spec depot with all current forms.
-s type	For p4 admin updatespecdepot, update the spec depot with forms of the specified type, where type is one of client, depot, branch, label, typemap, group, user, or job.
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	super

- Because p4 admin stop shuts down the Perforce server, you may see an error message
  indicating that the connection between the client and server was closed unexpectedly.
  You can ignore this message.
- $\bullet$  The spec depot must exist before running p4  $\,$  admin  $\,$  updatespecdepot.
- p4 dbstat, p4 lockstat, and p4 logstat are standalone commands; the old p4 admin syntax remains as an alias for backward compatibility.
- For more about administering Perforce, see the *Perforce System Administrator's Guide*.

# **Examples**

p4 admin stop	Stop the Perforce server
p4 admin checkpoint	Create a checkpoint named checkpoint. <i>n</i> , and start a new journal named journal, copying the old journal file to journal. <i>n</i> -1, where <i>n</i> is a sequence number.
p4 admin checkpoint name	Create a checkpoint named name.ckp. $n$ , and start a new journal named journal, copying the old journal file to name.jnl. $n$ -1, where $n$ is a sequence number.

#### p4 annotate

#### **Synopsis**

Print file lines along with their revisions.

#### **Syntax**

```
p4 [g-opts] annotate [ -a -c -i -q -dflag ] file[revRange] ...
```

#### Description

The p4 annotate command displays the revision number for each line of a revision (or range of revisions) of a file (or files). You can then run p4 filelog on the indicated revision(s) to find out who made each change, when, and why.

To display the changelist number associated with each line of the file, use the -c option.

If you specify a revision number, only revisions up to that revision number are displayed. If you specify a revision range, only revisions within that range are displayed.

By default, the first line of output for each file is a header line of the form:

```
filename#rev - action change num (type)
```

where filename#rev is the file's name and revision specifier, action is the operation the file was open for: add, edit, delete, branch, or integrate, num is the number of the submitting changelist, and type of the file at the given revision.

To suppress the header line, use the -q (quiet) option.

To print all lines (including lines from deleted files and/or lines no longer present at the head revision), use the -a (all) option.

#### **Options**

-a	All lines, including deleted lines and lines no longer present at the head revision, are included.
	Each line includes a starting and ending revision.
-c	Display the changelist number, rather than the revision number, associated with each line.
	If you use the -a option and the -c option together, each line includes a starting and ending changelist number.
-dflags	Runs the diff routine with one of a subset of the standard UNIX diff flags. See the <i>Usage Notes</i> below for a listing of these flags.

-i	Follow file history across branches. If a file was created by branching, Perforce includes revisions up to the branch point.
	The use of -i option implies the -c option.
-q	Quiet mode; suppress the one-line header for each file.
g-opts	See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	read

- The output of p4 annotate is highly amenable to scripting or other forms of automated processing.
- The diff flags supported by p4 annotate are:

Flag	Name
-db	ignore changes made within whitespace
-dw	ignore whitespace altogether

# **Examples**

Print all lines of file.c, each line preceded by the revision that introduced that line into the file.
Print all lines of file.c, each line preceded by the changelist number that introduced that line into the file.
Print all lines of file.c, including deleted lines, each line preceded by a revision range.
The starting and ending revision for each line are included.
Print all lines of file.c, including deleted lines, each line preceded by a range of changelists.
The starting and ending changelists for which each line exists in the file are included.

# p4 branch

#### **Synopsis**

Create or edit a branch mapping and its view.

#### **Syntax**

```
p4 [g-opts] branch [ -f ] branchspec
p4 [g-opts] branch -o branchspec
p4 [g-opts] branch -d [ -f ] branchspec
p4 [g-opts] branch -i [ -f ]
```

#### **Description**

p4 branch enables you to construct a mapping between two sets of files for use with p4 integrate. A *branch view* defines the relationship between the files you're integrating from (the *fromFiles*) and the files you're integrating to (the *toFiles*). Both sides of the view are specified in depot syntax.

Once you have named and created a branch mapping, integrate files by typing p4 integrate -b branchname; the branch mapping automatically maps all toFiles to their corresponding fromFiles.

Saving a p4 branch form has no immediate effect on any files in the depot or your client workspace; you must call p4 integrate -b branchspecname to create the branched files in your workspace and to open the files in a changelist.

#### Form Fields

Field Name	Туре	Description
Branch:	read-only	The branch name, as provided on the command line.
Owner:	mandatory	The owner of the branch mapping. By default, this will be set to the user who created the branch. This field is unimportant unless the Option: field value is locked.
Access:	read-only	The date the branch mapping was last accessed.
Update:	read-only	The date the branch mapping was last changed.

Туре	Description
mandatory	Either unlocked (the default) or locked.
	If locked, only the Owner: can modify the branch mapping, and the mapping can't be deleted until it is unlocked.
optional	A short description of the branch's purpose.
mandatory	A set of mappings from one set of files in the depot (the <i>source files</i> ) to another set of files in the depot (the <i>target files</i> ). The view maps from one location in the depot to another; it can't refer to a client workspace.
	For example, the branch view
	//depot/main/ //depot/r2.1/
	<pre>maps all the files under //depot/main to //depot/r2.1.</pre>
	mandatory

-d	Delete the named branch mapping. Files are not affected by this operation; only the stored mapping from one codeline to another is deleted. Normally, only the user who created the branch can use this flag.
-f	Force flag. Combined with -d, allows Perforce administrators to delete branches they don't own. Also allows administrators to change the modification date of the branch mapping (the Update: field is writable when using the -f flag).
-i	Read the branch mapping from standard input without invoking an editor.
-0	Write the branch mapping to standard output without invoking an editor.
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	open

A branch view defines the relationship between two related codelines. For example, if
the development files for a project are stored under //depot/project/dev/..., and
you want to create a related codeline for the 2.0 release of the project under
//depot/project/r2.0/..., specify the branch view as:

```
//depot/project/dev/... //depot/project/r2.0/...
```

Branch views can contain multiple mappings. See the *Views* chapter for more information on specifying views.

• If a path or file name contains spaces, use quotes around the path. For instance:

```
//depot/project/dev/... "//depot/project/release 2.0/..."
```

• Branch views can also be used with p4 diff2 with the syntax p4 diff2 -b branchname fromFiles. This will diff the files that match the pattern fromFiles against their corresponding toFiles as defined in the branch view.

#### **Related Commands**

To view a list of existing branch mappings	p4 branches
To copy changes from one set of files to another	p4 integrate
To view differences between two codelines	p4 diff2

# p4 branches

#### **Synopsis**

List existing branch mappings.

#### **Syntax**

```
p4 [g-opts] [ -u user ] [ -e namefilter -m max ] branches
```

#### **Description**

Print the list of all branch mappings currently known to the system.

Use the -m max option to limit the output to the first max branch mappings.

Use the -e namefilter option to limit the output to branches whose name matches the namefilter pattern.

Use the -u user option to limit the output to branches owned by the named user.

### **Options**

-m max	List only the first max branch mappings.
-e namefilter	List only branches matching namefilter.
-u user	List only branches owned by user.
g-opts	See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	list

#### **Related Commands**

To create or edit a branch mapping	p4 branch
------------------------------------	-----------

# p4 browse

# **Synopsis**

Browse for a list of Zeroconf-registered Perforce servers.

# **Syntax**

p4 [g-opts] browse

## **Description**

Lists all Perforce servers that have registered with Zeroconf.

# **Options**

g-opts See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	none

## p4 change

#### **Synopsis**

Create or edit a changelist specification.

#### **Syntax**

```
p4 [g-opts] change [ -s ] [ -f | -u ] [ changelist# ]
p4 [g-opts] change -d [ -f -s ] changelist#
p4 [g-opts] change -o [ -s ] [ changelist# ]
p4 [g-opts] change -i [ -s ] [ -f | -u ]
```

#### Description

When files are opened with p4 add, p4 delete, p4 edit, or p4 integrate, the files are listed in a *changelist*. Edits to the files are kept in the local client workspace until the changelist is sent to the depot with p4 submit. By default, files are opened within the default changelist, but multiple changelists can be created and edited with the p4 change command.

p4 change brings up a form for editing or viewing in the editor defined by the environment or registry variable P4EDITOR. When no arguments are provided, this command creates a new, numbered changelist. (All files open in the default changelist are moved to the new changelist.)

Changelist numbers are assigned in sequence; Perforce may renumber changelists automatically on submission in order to keep the numeric order of submitted changelists identical to the chronological order.

To edit the description of a pending changelist, or to view the fields of a submitted changelist, use p4 change changelist.

If p4 submit of the default changelist fails, a numbered changelist is created in its place. The changelist must be referred to by number from that point forward.

The command p4 changelist is an alias for p4 change.

#### Form Fields

Field Name	Туре	Description
Change:	Read-only	Contains the changelist number if editing an existing changelist, or new if creating a new changelist.
Client:	Read-only	Name of current client workspace.
Date:	Read-only	Date the changelist was last modified.

Field Name	Туре	Description
User:	Read-only	Name of current Perforce user.
		The owner of an empty pending changelist (that is, a pending changelist without any files in it) can transfer ownership of the changelist to another existing user.
Status:	Read-only	pending, submitted, or new. Not editable by the user. The status is new when the changelist is created, pending when it has been created but has not yet been submitted to the depot with p4 submit, and submitted when its contents have been stored in the depot with p4 submit.
Description:	Writable, mandatory	Textual description of changelist. This value <i>must</i> be changed before submission.
Jobs:	List	A list of jobs that are fixed by this changelist. The list of jobs that appears when the form is first displayed is controlled by the p4 user form's JobView: setting. Jobs can be deleted from or added to this list.
Files:	List	The list of files being submitted in this changelist. Files can be deleted from this list, and files that are found in the default changelist can be added.

Delete the changelist. This is usually allowed only with pending changelists that contain no files or pending fixes, but the superuser can delete changelists under other circumstances with the addition of the -f flag.  Force flag. Allows the description, modification date, or user of a submitted changelist to be edited. Editing a submitted changelist requires admin or super access. Superusers and administrators can also overwrite read-only fields when using the -f flag.  Forcibly delete a previously submitted changelist. Only a Perforce administrator or superuser can use this command, and the changelist must have had all of its files removed from the system with p4 obliterate.		
submitted changelist to be edited. Editing a submitted changelist requires admin or super access. Superusers and administrators can also overwrite read-only fields when using the -f flag.  -f -d Forcibly delete a previously submitted changelist. Only a Perforce administrator or superuser can use this command, and the changelist must have had all of its files removed from the system with p4 obliterate.	-d	changelists that contain no files or pending fixes, but the superuser can delete changelists under other circumstances with the addition of
administrator or superuser can use this command, and the changelist must have had all of its files removed from the system with p4 obliterate.	-f	submitted changelist to be edited. Editing a submitted changelist requires admin or super access. Superusers and administrators can
TAT 1: 1 1: 1 1: 1 1 1 1 1 1 1 1 1 1 1 1 1	-f -d	administrator or superuser can use this command, and the changelist must have had all of its files removed from the system with p4
-o Write a changelist description to standard output.	-0	Write a changelist description to standard output.

-i	Read a changelist description from standard input. Input must be in the same format used by the p4 change form.
-s	Allows jobs to be assigned arbitrary status values on submission of the changelist, rather than the default status of closed. To leave a job unchanged, use the special status of same.
	On new changelists, the fix status is displayed as the special status ignore. (If the status is left unchanged, the job is not fixed by the submission of the changelist.)
	This option works in conjunction with the -s option to p4 fix, and is intended for use in conjunction with defect tracking systems.
-u	Update a submitted changelist. Only the Jobs: and Description: fields can be updated, and only the submitter of the changelist can update the changelist. The -u and the -f flags are mutually exclusive.
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	open

- You should create multiple changelists when editing files corresponding to different logical tasks. For example, if edits to files file1.c and file2.c fix a particular bug, and edits to file other.c add a new feature, file1.c and file2.c should be opened in one changelist, and other.c should be opened in a different changelist.
- p4 change changelist# edits the specification of an existing changelist, but does not display the files or jobs that are linked to the changelist. Use p4 opened -c changelist# to see a list of files linked to a particular changelist and p4 fixes -c changelist# to see a list of jobs linked to a particular changelist
- To move a file from one changelist to another, use p4 reopen, or use p4 revert to remove a file from all pending changelists.

#### **Examples**

p4 change	Create a new changelist.
p4 change -f 25	Edit previously submitted changelist 25. Administrator or superuser access is required.
p4 change -d 29	Delete changelist 29. This succeeds only if changelist 29 is pending and contains no files.

# **Related Commands**

To submit a changelist to the depot	p4 submit
To move a file from one changelist to another	p4 reopen
To remove a file from all pending changelists	p4 revert
To list changelists meeting particular criteria	p4 changes
To list opened files	p4 opened
To list fixes linked to particular changelists	p4 fixes
To link a job to a particular changelist	p4 fix
To remove a job from a particular changelist	p4 fix -d
To list all the files listed in a changelist	p4 opened -c changelist#
To obtain a description of files changed in a changelist	p4 describe <i>changelist#</i>

# p4 changelists

# **Synopsis**

List submitted and pending changelists.

### **Syntax**

```
p4 [g-opts] changelists [-i -t -l -L -c client -m max -s status -u user] [file[RevRange]...]
```

#### **Description**

The command p4 changelists is an alias for p4 changes.

# p4 changelist

#### **Synopsis**

Create or edit a changelist specification.

# **Syntax**

```
p4 [g-opts] changelist [ -f -s ] [changelist#]
p4 [g-opts] changelist -d [ -f -s ] changelist#
p4 [g-opts] changelist -o [ -s ] [changelist#]
p4 [g-opts] changelist -i [ -f -s ]
```

# **Description**

The command p4 changelist is an alias for p4 change.

#### p4 changes

#### **Synopsis**

List submitted and pending changelists.

#### **Syntax**

```
p4 [g-opts] changes [-i -t -l -L -c client -m max -s status -u user] [file[RevRange]...]
```

#### **Description**

Use p4 changes to view a list of submitted and pending changelists. When you use p4 changes without any arguments, all numbered changelists are listed. (The default changelist is never listed.)

By default, the format of each line is:

Change num on date by user@client [status] description

If you use the -t option to display the time of each changelist, the format is:

Change num on date hh:mm:ss by user@client [status] description

The status value appears only if the changelist is pending or shelved. The description is limited to the first 31 characters unless you provide the -L flag for the first 250 characters, or the -l flag for the full description.

If you provide file patterns as arguments, the changelists listed are those that affect files matching the patterns, whether submitted or pending.

Revision specifications and revision ranges can be included in the file patterns. Including a revision range lists all changes that affect files within the range; providing a single revision specifier lists all changes from 1 to the specified revision.

Use the -c client and -u user flags to limit output to only those changelists made from the named client workspace or the named user.

Use the -s status flag to limit output to only those changelists with the provided status (pending or submitted) value.

You can combine flags and file patterns to substantially limit the changelists that are displayed. You can also use the -m max flag to further limit output to max changes.

The command p4 changelists is an alias for p4 changes.

-i	Include changelists that affected files that were integrated with the specified files.
-t	Display the time as well as the date of each change.
-1	List long output, with the full text of each changelist description.
-L	List long output, with the full text of each changelist description truncated at 250 characters.
-c client	List only changes made from the named client workspace.
-m max	List only the highest numbered max changes.
-s status	Limit the list to the changelists with the given status (pending or submitted)
-u user	List only changes made from the named user.
g-opts	See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	list

• If p4 changes is called with multiple file arguments, the sets of changelists that affect each argument are evaluated individually. The final output is neither combined nor sorted; the effect is the same as calling p4 changes multiple times, once for each file argument.

# **Examples**

p4 changes -m 5 //depot/project/	Show the last five submitted changelists that include any file under the project directory
p4 changes -m 5 -c eds_elm	Show the last five submitted changelists from client workspace eds_elm.
p4 changes -m 5 -u edk	Show the last five submitted changelists from user edk.

p4 changes file.c@2000/05/01,2000/06/01	Show any changelists that include file file.c, as mapped to the depot through the client view, during the month of May 2000.
p4 changes -m 1 -s submitted	Output a single line showing the changelist number of the last submitted changelist.
p4 changes @2001/04/01,@now	Display all changelists submitted from April 1, 2001 to the present.
p4 changes @2001/04/01	Display all changelists submitted before April 1, 2000.

# **Related Commands**

To submit a pending changelist	p4 submit
To create a new pending changelist	p4 change
To read a detailed report on a single changelist	p4 describe

## p4 client

#### **Synopsis**

Create or edit a client workspace specification and its view.

#### **Syntax**

```
p4 [g-opts] client [-f -t template] [clientname]
p4 [g-opts] client -o [-t template] [clientname]
p4 [g-opts] client -d [-f] clientname
p4 [g-opts] client -i [-f]
```

#### Description

A Perforce client workspace is a set of files on a user's machine that mirror a subset of the files in the depot. The p4 client command is used to create or edit a client workspace specification; invoking this command displays a form in which the user enters the information required by Perforce to maintain the client workspace.

Although there is always a one-to-one mapping between a client workspace file and a depot file, these files do not need to be stored at the same relative locations, nor must they have the same names. The *client view*, which is specified in the p4 client form's View: field, specifies how files in the client workspace are mapped to the depot, and vice-versa.

When called without a *clientname* argument, p4 client operates on the client workspace specified by the P4CLIENT environment variable or one of its equivalents. If called with a *clientname* argument on a locked client, the client specification is readonly.

When p4 client completes, the new or altered client workspace specification is stored within the Perforce database; the files in the client workspace are not touched. The new client view doesn't take effect until the next p4 sync.

The command p4 workspace is an alias for p4 client.

#### Form Fields

Field Name	Туре	Description
Client:	Read-only	The client workspace name, as specified in the P4CLIENT environment variable or its equivalents.
Owner:	Writable	The Perforce user name of the user who owns the client workspace. The default is the user who created the client workspace.
Update:	Read-only	The date the client workspace specification was last modified.

Field Name	Туре	Description
Access:	Read-only	The date and time that any part of the client workspace specification was last accessed by any Perforce command.
Host:	Writable, optional	The name of the host machine on which this client workspace resides. If included, operations on this client workspace can be run <i>only</i> from this host.
		The hostname must be provided exactly as it appears in the output of p4 info when run from that host.
		This field is meant to prevent accidental misuse of client workspaces on the wrong machine. It doesn't provide security, since the actual value of the host name can be overridden with the -H flag to any p4 command, or with the P4HOST environment variable. For a similar mechanism that does provide security, use the IP address restriction feature of p4 protect.
Description:	Writable, optional	A textual description of the client workspace. The default text is Created by owner.
Root:	Writable, mandatory	The directory (on the local host) relative to which all the files in the View: are specified. The default is the current working directory.
AltRoots:	Writable,	Up to two optional alternate client workspace roots.
	optional	Perforce client programs use the first of the main and alternate roots to match the client program's current working directory.
		This enables users to use the same Perforce client specification on multiple platforms with different directory naming conventions.
		If you are using a Windows directory in any of your client roots, you must specify the Windows directory as your main client root and specify your other client root directories in the Altroots: field.
		For example, an engineer building products on multiple platforms might specify a main client root of C:\Projects\Build for Windows builds, and an alternate root of /staff/userid/projects/build for any work on UNIX builds.

Field Name	Туре	Description
Options:	Writable, mandatory	A set of seven switches that control particular client options. See the <i>Usage Notes</i> , below, for a listing of these options.
SubmitOptions:	Writable,	Flags to govern the default behavior of p4 submit.
	mandatory	<ul> <li>submitunchanged         All open files (with or without changes) are submitted to the depot. This is the default behavior of Perforce.</li> <li>submitunchanged+reopen         All open files (with or without changes) are submitted to the depot, and all files are automatically reopened in the default changelist.</li> <li>revertunchanged</li> </ul>
		Only those files with content or type changes are submitted to the depot. Unchanged files are reverted.
		<ul> <li>revertunchanged+reopen</li> <li>Only those files with content or type changes are submitted to the depot and reopened in the default changelist. Unchanged files are reverted and not reopened in the default changelist.</li> </ul>
		<ul> <li>leaveunchanged         Only those files with content or type changes are submitted to the depot. Any unchanged files are moved to the default changelist.     </li> </ul>
		• leaveunchanged+reopen  Only those files with content or type changes are submitted to the depot. Unchanged files are moved to the default changelist, and changed files are reopened in the default changelist. This option is similar to submitunchanged+reopen, except that no unchanged files are submitted to the depot.
LineEnd:	Writable, mandatory	A set of four switches that control carriage- return/linefeed (CR/LF) conversion. See the <i>Usage</i> <i>Notes</i> , below, for a listing of these options.
View:	Writable, multi-line	Specifies the mappings between files in the depot and files in the client workspace. See <i>Views</i> for more information.

-t clientname	Copy client workspace <i>clientname</i> 's view and client options into the View: and Options: field of this client workspace. (i.e, use <i>clientname</i> 's View: as a template)
-f	Allows the last modification date, which is normally read-only, to be set. Administrators can use this flag to delete or modify locked workspaces owned by other users.
-d clientname	Delete the specified client workspace if it is unlocked, whether or not the client is owned by the user. (The -f flag allows Perforce administrators to delete locked client workspaces that they don't own.)
-i	Read the client description from standard input.
-0	Write the client specification to standard output.
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	list

- Use quotation marks to enclose depot-side or client side mappings of file or directory names that contain spaces.
- Spaces in client workspace names are translated to underscores. For example, typing the command p4 client "my client" creates a client workspace called my\_client.
- The Options: field contains six values, separated by spaces. Each of the six options have two possible settings; the following table provides the option values and their meanings:

Option	Choice	Default
[no]allwrite	If set, unopened files on the client are left writable.	noallwrite
	If allwrite is set, this option overrides noclobber.	
[no]clobber	If set, a p4 sync overwrites ("clobbers") writable- but-unopened files in the client that have the same name as the newly-synced files.	noclobber
	If allwrite is set, the noclobber option is ignored.	

Option	Choice	Default
[no] compress	If set, the data stream between the client and the server is compressed. (Both client and server must be version 99.1 or higher, or this setting is ignored.)	nocompress
[no]crlf	Note: 2000.2 or earlier only!	crlf
	On Windows, if crlf is set, CR/LF translation is performed automatically when copying files between the depot and the client workspace.	
[un]locked	Grant or deny other users permission to edit or delete the client specification (To make a locked client specification truly effective, you should also set the workspace's owner's password with p4 passwd.)	unlocked
	If locked, only the owner is able to use or edit the client spec. Perforce administrators can override the lock by using the -f (force) flag with p4 client.	
[no] modtime	For files <i>without</i> the +m (modtime) file type modifier:	nomodtime
	• For Perforce clients at the 99.2 level or earlier, if modtime is set, the modification date (on the local filesystem) of a newly synced file is the date and time at the server when the file was submitted to the depot.	(i.e. date and time of sync) for most files. Ignored for files with the
	• For Perforce clients at the 2000.1 level or higher, if modtime is set, the modification date (on the local filesystem) of a newly synced file is the datestamp on the file when the file was last modified.	+m file type modifier.
	• If nomodtime is set, the modification date is the date and time <i>of sync</i> , regardless of Perforce client version.	
	For files $with$ the +m (modtime) file type modifier:	
	<ul> <li>For Perforce clients at the 99.2 level or earlier, the +m modifier is ignored, and the behavior of modtime and nomodtime is as documented above.</li> <li>For Perforce clients at the 2000.1 level or higher, the modification date (on the local filesystem) of a newly synced file is the datestamp on the file when the file was submitted to the depot, regardless of the setting of modtime or nomodtime on the client.</li> </ul>	

Option	Choice	Default
[no]rmdir	If set, p4 sync deletes empty directories in a client if all files in the directory have been removed.	normdir

- By default, any user can edit any workspace specification with p4 client -c clientname. To prevent this from happening, set the locked option and use p4 passwd to create a password for the client workspace owner.
- The compress option speeds up client/server communications over slow links by reducing the amount of data that has to be transmitted. Over fast links, the compression process itself may consume more time than is saved in transmission. In general, compress should be set for line speeds under T1, and should be left unset otherwise.
- The LineEnd: field controls the line-ending character(s) used for text files in the client workspace.

# Note The LineEnd: option is new to Perforce 2001.1. It renders the previous convention of specifying crlf or nocrlf in the Options: field obsolete. The behavior of the mutually-contradictory combination of LineEnd: win

The LineEnd: field accepts one of five values:

and Options: crlf is undefined.

Option	Meaning
local	Use mode native to the client (default)
unix	UNIX-style (and Mac OS X) line endings: LF
mac	Macintosh pre-OS X: CR only
win	Windows-style: CR, LF.
share	The share option normalizes mixed line-endings into UNIX line-end format. The share option does not affect files that are synced into a client workspace; however, when files are submitted back to the Perforce Server, the share option converts all Windows-style CR/LF line-endings and all Mac-style CR line-endings to the UNIX-style LF, leaving lone LFS untouched.
	When you sync your client workspace, line endings are set to LF. If you edit the file on a Windows machine, and your editor inserts CRs before each LF, the extra CRs do not appear in the archive file.
	The most common use of the share option is for users of Windows workstations who mount their UNIX home directories as network drives; if you sync files from UNIX, but edit the files on a Windows machine.

For more information about how Perforce uses the line-ending settings, see Tech Note 63 on the Perforce web site:

```
http://www.perforce.com/perforce/technotes/note063.html
```

• By default, if a directory in the client workspace is empty, (for instance, because all files in the depot mapped to that directory have been deleted since the last sync), a p4 sync operation will still leave the directory intact. If you use the rmdir option, however, p4 sync deletes the empty directories in the client workspace.

If the rmdir option is active, a p4 sync operation may sometimes remove your current working directory. If this happens, just change to an existing directory before continuing on with your work.

- Files with the modtime (+m) type are primarily intended for use by developers who need to preserve original timestamps on files. The use of +m in a file type overrides the client's modtime or nomodtime setting. For a more complete discussion of the +m modifier, see the *File Types* section.
- If you are using multiple or alternate client roots (the AltRoots: field), you can always tell which client root is in effect by looking at the Client root: reported by p4 info.
- To specify a Perforce client on Windows that spans multiple drives, use a Root: of null, and specify the drive letters in the client workspace view. For instance, the following client spec with a null client root maps //depot/main/... to an area of the C: drive, and other releases to the D: drive:

```
Client: eds_win
Owner: edk
Description:
    Ed's Windows Workspace
Root: null
Options: nomodtime noclobber
SubmitOptions: submitunchanged
View:
    //depot/main/... "//eds_win/c:/Current Release/..."
    //depot/rel1.0/... //eds_win/d:/old/rel1.0/...
    //depot/rel2.0/... //eds_win/d:/old/rel2.0/...
```

Use lowercase drive letters when specifying workspaces across multiple drives.

#### **Examples**

p4 client	Edit or create the client workspace specification named by
	the value of P4CLIENT or its equivalents.

p4 client -t sue joe	Create or edit client workspace joe, opening the form with the field values and workspace options in client workspace sue as defaults.
p4 client -d release1	Delete the client workspace release1.

To list client workspaces known to the system	p4 clients
To read files from the depot into the client workspace	p4 sync
To open new files in the client workspace for addition to the depot	p4 add
To open files in the client workspace for edit	p4 edit
To open files in the client workspace for deletion	p4 delete
To write changes in client workspace files to the depot	p4 submit

# p4 clients

## **Synopsis**

List all client workspaces currently known to the system.

#### **Syntax**

```
p4 [g-opts] clients [ -u user ] [ -e namefilter -m max ]
```

# **Description**

p4 clients lists all the client workspaces known to the Perforce server. Each workspace is reported on a single line of the report. The format of each line is:

Client clientname moddate root clientroot description

#### For example:

```
Client paris 1999/02/19 root /usr/src 'Joe's client'
```

describes a client workspace named paris, last modified on February 19, 1999 with a root of /usr/src. The description of the workspace entered in the p4 client form is Joe's client.

Use the -m max option to limit the output to the first max client workspaces.

Use the -e namefilter option to limit the output to labels whose name matches the namefilter pattern.

Use the -u user option to limit the output to workspaces owned by the named user.

The command p4 workspaces is an alias for p4 clients.

# **Options**

-m max	List only the first max client workspaces.
-e namefilter	List only client workspaces matching namefilter.
-u user	List only client workspaces owned by user.
g-opts	See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	list

To edit or view a client workspace specification	p4 client
To see the name of the current client workspace and other useful data	p4 info
To view a list of Perforce users	p4 users

# p4 counter

## **Synopsis**

Access, set, increment, or delete a persistent variable.

# **Syntax**

```
p4 [g-opts] counter countername
p4 [g-opts] counter countername value
p4 [g-opts] counter -d countername
p4 [g-opts] counter -f [ change|job|journal|monitor|security ] value
p4 [g-opts] counter -i countername
```

## **Description**

Counters provide long-term variable storage for scripts that access Perforce. For example, the Perforce review daemon uses a counter (review) that stores the number of the last processed changelist.

When used in the form p4 counter countername, the value of variable countername is returned. When p4 counter countername value is used, the value of variable countername is set to value, and if countername does not already exist, it is created.

The Perforce server uses three counters in the course of its regular operations: change, job, and journal. Superusers can use the -f flag to force changes to these counters. Changes to these counters are not without risk; see the *Release Notes* for examples of the types of situations in which manually resetting these counters might be appropriate.

You can control server process monitoring by setting the monitor counter to 0 (disable monitoring), 1 (enable monitoring of active processes), or 2 (enable monitoring of both active and idle processes). You must stop and restart the Perforce server for any change in this counter to take effect. After you have enabled process monitoring, you can use p4 monitor to observe activity on the Perforce server.

To configure password strength requirements or to require the use of the ticket-based authentication mechanism, set the security counter to the desired level. You must stop and restart the Perforce server for this change to take effect. See the *System Administrator's Guide* for details.

## **Options**

-d countername	Delete variable <i>countername</i> from the Perforce server.
-f [change job journal]	Force a change to one of three internal counters used by Perforce. Most installations rarely, if ever, need to use this flag.
-f monitor [ 0   1   2 ]	Server process monitoring off, monitor active processes only, or monitor both active and idle processes.
	See p4 monitor for details.
-f security [ 0   1   2   3 ]	Set the server security level.
	See the System Administrator's Guide for details.
-i countername	Increment variable <i>countername</i> by 1 and return the new value. This option can only be used with numeric counters.
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	list to display a counter's value; review to set a new value super to use the -f flag

- If a counter does not exist, its value is returned as zero; counter names are not stored in the database until set to a nonzero value.
- The last changelist number known to the Perforce server (the output of p4 counter change) includes pending changelists created by users, but not yet submitted to the depot. If you're writing change review daemons, you may also want to know the changelist number of the last *submitted* changelist, which is the second field of the output of the command:

```
p4 changes -m 1 -s submitted
```

• Counters are represented internally as strings. (Prior to release 2008.1, they were stored as signed ints)

# **Examples**

p4 counter mycounter 123	Set the value of a counter mycounter to 123. If mycounter does not exist, it is created.
	Requires review access.
p4 counter mycounter	Display the value of mycounter. If mycounter does not exist, its value is displayed as 0.
	Requires list access.

To list all counters and their values	p4 counters	
List and track changelists	p4 review	
List users who have subscribed to particular files	p4 reviews	

# p4 counters

# **Synopsis**

Display list of long-term variables used by Perforce and associated scripts.

# **Syntax**

p4 [g-opts] counters

# **Description**

The Perforce server uses counters as variables to store the number of the last submitted changelist and the number of the next job. p4 counters provides the current list of counters, along with their values.

# **Options**

*g-opts* See the *Global Options* section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	list

#### **Related Commands**

To view or change the value of a counter p4 counter

# p4 dbschema

## **Synopsis**

Report information about metadata in the Perforce database.

## **Syntax**

```
p4 [g-opts] dbschema [ tablename [ :tableversion ] ]
```

# **Description**

The p4 dbschema command reports information about the database structure in which the Perforce Server stores metadata.

By default, all current tables are reported. To restrict output to a specified table, use the name of the corresponding db.tablename file in the Perforce server root.

The results are returned as tagged output.

This command is intended for systems integrators.

# **Options**

tablename	Restrict output to the specified table name.
tableversion	Restrict output to the specified table version.
g-opts	See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	super

## **Examples**

p4 dbschema db.protect Display information about the db.protect database table.

# p4 dbstat

# **Synopsis**

Display size or simple statistics for a database table.

## **Syntax**

```
p4 [g-opts] dbstat [ -h ] { -a | dbtable... }
p4 [g-opts] dbstat -s
```

# **Description**

The p4 dbstat command displays statistics on the internal state of the Perforce Server's database. The dbtable corresponds to the db.\* files in your server's root directory. This command is typically used in conjunction with Perforce technical support for purposes of estimating disk seeks due to sequential database scans.

To obtain size information, use p4 admin dbstat -s.

## **Options**

-a	For p4 admin dbstat, display statistics for all tables.
-h	Display a histogram showing distances between leaf pages.
dbtable	Display statistics for only the specified tables (for instance, db.have, db.user, and so on.)
- s	Report file sizes of database tables.
g-opts	See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	super

Because p4 dbstat locks out write access to the database while it scans the tables, use
this command with care. You will most often use this command when working with
Perforce technical support.

# p4 delete

## Synopsis

Open file(s) in a client workspace for deletion from the depot.

## Syntax 5 4 1

```
p4 [g-opts] delete [-c changelist#] [-n -v] file...
```

# Description

The p4 delete command opens file(s) in a client workspace for deletion from the depot. The files are immediately removed from the client workspace, but are not deleted from the depot until the corresponding changelist is sent to the server with p4 submit.

Although it will *appear* that a deleted file has been deleted from the depot, the file is never truly deleted, as older revisions of the same file are always accessible. Instead, a new head revision of the file is created which marks the file as being deleted. If p4 sync is used to bring the head revision of this file into another workspace, the file is deleted from that workspace.

A file that is open for deletion will not appear on the client's *have list*.

## **Options**

-c change#	Opens the files for delete within the specified changelist.
	If this flag is not provided, the files are linked to the default changelist.
-n	Preview which files would be opened for delete, without actually changing any files or metadata.
-v	Delete a file that is not synced into the client workspace.
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	open

• A file that has been deleted from the client workspace with p4 delete can be reinstated in the client workspace and removed from the pending changelist with p4 revert. To do this, you must revert the deletion before submitting the changelist.

• Perforce does not prevent users from opening files that are already open; its default scheme is to allow multiple users to open a file simultaneously, and then resolve file conflicts with p4 resolve. To prevent someone else from opening a file once you've opened it, use p4 lock. To determine whether or not another user already has a particular file open, use p4 opened -a file.

# **Examples**

p4 delete //depot/README	Opens the file called README in the depot's top level directory for deletion. The corresponding file within the client workspace is immediately deleted, but the file is not deleted from the depot until the default changelist is submitted.
p4 delete -c 40 file	Opens file in the current client workspace for deletion. The file is immediately removed from the client workspace, but won't be deleted from the depot until changelist 40 is sent to the server with p4 submit.

To open a file for add	p4 add
To open a file for edit	p4 edit
To copy all open files to the depot	p4 submit
To read files from the depot into the client workspace	p4 sync
To create or edit a new changelist	p4 change
To list all opened files	p4 opened
To revert a file to its unopened state	p4 revert
To move an open file to a different changelist	p4 reopen

# p4 depot

## **Synopsis**

Create or edit a depot specification.

## **Syntax**

```
p4 [g-opts] depot depotname
p4 [g-opts] depot -d depotname
p4 [g-opts] depot -o depotname
p4 [g-opts] depot -i
```

# Description

The files on a Perforce server are stored in a depot. By default, there is one depot on every Perforce server, and its name is depot.

To create or edit a depot, use p4 depot depotname and edit the fields in the form. Depots can be of type local, remote, or spec.

Other local depots work the same way the default depot is used. For example, to sync a file README in the rel2 directory of the depot new, add //new/rel2/... to the left-hand side of your client workspace mapping, and run p4 sync //new/rel2/README.

If you are using remote depots, your Perforce server (that is, the machine specified in P4PORT) is configured to permit your Perforce client program to read files from a different Perforce server. Remote depots are restricted to read-only access; Perforce client programs cannot add, edit, delete, or integrate files in the depots on the other servers. For more information about remote depots, see the *Perforce System Administrator's Guide*.

The spec depot, if present, tracks changes to user-edited forms such as client workspace specifications, jobs, branch mappings, and so on. There can be only one spec depot per server. Files in the spec depot are automatically generated by the server, and are represented in Perforce syntax as follows:

```
//specdepotname/formtype/objectname[suffix]
```

For instance, if the spec depot is present and named spec, and uses the default suffix of .p4s, you can obtain the history of changes to job000123 by typing:

```
p4 filelog //spec/job/job000123.p4s
```

For more information about setting up a spec depot, see the System Administrator's Guide.

After you have created the spec depot, use p4 admin updatespecdepot to pre-populate it with current set of client, depot, branch, label, typemap, group, user, and job forms.

# **Form Fields**

Field Name	Туре	Description
Depot:	Read-Only	The depot name as provided in p4 depot depotname.
Owner:	Writable	The user who owns the depot. By default, this is the user who created the depot.
Description:	Writable	A short description of the depot's purpose. Optional.
Type:	Writable	local, remote, or spec. Local depots are writable; remote depots are proxies for depots residing on other servers, and cannot be written to. The spec depot, if present, archives edited forms.
Address:	Writable	If the Type: is remote, the address should be the P4PORT address of the remote server.
		If the Type: is local or spec, this field is ignored.
Suffix:	Writable	If the Type: is spec, this field holds an optional suffix for generated paths to objects in the spec depot.
		The default suffix is .p4s. You do not need a suffix to use the spec depot, but supplying a file extension to your Perforce server's versioned specs enables users of GUI client software to associate Perforce specifications with a preferred text editor.
		If the Type: is local or remote, this field is ignored.
Map:	Writable	If the Type: is local or spec, set the map to point to the relative location of the depot subdirectory relative to the Perforce server's P4ROOT. The map must contain the wildcard; for example, a local depot new might have a Map: of new/
		If the Type: is remote, set the map to point to a location in the remote depot's physical namespace, for example, //depot/new/rel2/ This directory will be the root of the local representation of the remote depot.

## **Options**

-d depotname	Delete the depot <i>depotname</i> . The depot must not contain any files; the Perforce superuser can remove files with p4 obliterate.	
	If the depot is remote, p4 obliterate must still be run: no files are deleted, but any outstanding client or label records referring to that depot are eliminated.	
-i	Read a depot specification from standard input.	
-o depotname	Write a depot specification to standard output.	
g-opts	See the Global Options section.	

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	super

- A depot created with p4 depot is not physically created in the server until files have been added to it with p4 add.
- Users are not able to access a new depot created with p4 depot until permission to access the depot is granted with p4 protect.
- Remote depots are always accessed by a virtual user named remote, and by default, all files on any Perforce server can be accessed remotely. To limit or eliminate remote access to a particular server, use p4 protect to set permissions for user remote on that server.

For example, to eliminate remote access to all files in all depots on a particular server, set the following permission on that server:

```
read user remote * -//...
```

Because remote depots can only be used for read access, it is not necessary to remove write or super access.

The virtual user remote does not consume a Perforce license.

• By default, the Map: field on a local depot points to a depot directory matching the depot name, relative to the server root (P4ROOT) setting for your server. To store a depot's versioned files on another volume or drive, specify an absolute path in the Map: field. This path need not be under P4ROOT.

To view a list of all depots known to the Perforce server	p4	depots
To populate a new depot with files	p4	add
To add mappings from an existing client workspace to the new depot	p4	client
To remove all traces of a file from a depot	p4	obliterate
To limit remote access to a depot	p4	protect

# p4 depots

# **Synopsis**

Display a list of depots known to the Perforce server.

# **Syntax**

p4 [g-opts] depots

# **Description**

Lists all the remote and local depots known to the Perforce server, in the form:

Depot name date type address map description

where name, date, type, address, map, and description are as defined in the p4 depot form.

# **Options**

g-opts See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	list

To create a remote depot or a new local depot	p4 depot
To remove all traces of a file from a depot	p4 obliterate

# p4 describe

## **Synopsis**

Provides information about changelists and the changelists' files.

## **Syntax**

```
p4 [g-opts] describe [ -dflag -s ] changelist#...
```

# **Description**

p4 describe displays the details of one or more changelists. For each changelist, the output includes the changelist's number, the changelist's creator, the client workspace name, the date the changelist was created, and the changelist's description.

If a changelist has been submitted, the default output also includes a list of affected files and the diffs of those files relative to the previous revision.

If a changelist is pending, it is flagged as such in the output, and the list of open files is shown. (Diffs for pending changelists are not displayed because the files have yet to be submitted to the server.)

You cannot run p4 describe on the default changelist.

While running p4 describe, the server uses Perforce's built-in client-side diff subroutine. The P4DIFF variable has no effect on this command.

# **Options**

-s	Display a shortened output that excludes the files' diffs.
-dflag	Runs the diff routine with one of a subset of the standard UNIX diff flags. See the <i>Usage Notes</i> below for a flag listing.
g-opts	See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	read; list for p4 describe -s

The diff flags supported by p4 describe are:

Flag	Meaning
-dn	RCS
-dc	context
-ds	summary
-du	unified
-db	ignore changes made within whitespace
-dw	ignore whitespace altogether

To view a list of changelists	p4 changes
To view a list of all opened files	p4 opened
To compare any two depot file revisions	p4 diff2
To compare a changed file in the client to a depot file revision	p4 diff

# p4 diff

## **Synopsis**

Compare a client workspace file to a revision in the depot.

## **Syntax**

```
p4 [g-opts] diff [-dflag -f -m max -sa -sb -sd -se -sr -sl -t] [file[rev#]...]
```

# **Description**

p4 diff runs a diff program on the Perforce client, comparing files in the client workspace to revisions in the depot.

This command takes a file argument, which can contain a revision specifier. If a revision specifier is included, the file in the client workspace is diffed against the specified revision. If a revision specifier is not included, the client workspace file is compared against the revision currently being edited (usually the head revision). In either case, the client file must be open for edit, or the comparison must be against a revision other than the one to which the client file was last synced.

If the file argument includes wildcards, all open files that match the file pattern are diffed. If no file argument is provided, all open files are diffed against their depot counterparts.

By default, the diff routine used is the one built into the p4 client program. To change this diff routine to an external diff program, set the P4DIFF environment or registry variable to point to the new program.

# **Options**

-f	Force the diff (if no revision is specified, against the head revision), even when the client file is not open for edit.
-dflags	Pass flags to the underlying diff routine (see the <i>Usage Notes</i> below for details)
-m max	Limit output to diffs (or status) of only the first max files.
-sa	Show only the names of opened files that are different from the revision in the depot, or are missing.
-sb	Show only the names of files opened for integrate that have been resolved, but that have been modified after being resolved.
-sd	Show only the names of unopened files that are missing from the client workspace, but present in the depot.
-se	Show only the names of unopened files in the client workspace that are different than the revision in the depot.

-sr	Show only the names of opened files in the client workspace that are identical to the revision in the depot.
-sl file	Every unopened file is compared with the depot, and listed with a status of same, diff, or missing.
	If you use the -f flag together with the -sl flag, files that are open for edit are also compared and their status is listed.
-t	Diff the revisions even if the files are not of type text.
g-opts	See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	No	read

• The diff flags supported by p4 diff are:

Flag	Name
-dn	RCS output format, showing additions and deletions made to the file and associated line ranges.
-dc	context output format, showing line number ranges and three lines of context around the changes.
-ds	summary output format, showing only the number of chunks and lines added, deleted, or changed.
-du	unified output format, showing added and deleted lines with sufficient context for compatibility with the patch(1) utility.
-dl	ignore line-ending (CR/LF) convention when finding diffs
-db	ignore changes made within whitespace; this flag implies -dl.
-dw	ignore whitespace altogether; this flag implies -d1.

- To pass more than one flag to the diff routine, group them together. For example: p4 diff -dub file
  - specifies a unified diff that ignores changes in whitespace.
- The header line of a unified diff produced with the -du option for use with patch (1) displays filenames in Perforce syntax, not local syntax.

# **Examples**

p4 diff	f file#5	Compare the client workspace revision of file file to the fifth depot revision.
p4 dif	E @1999/05/22	Compare all open files in the client workspace to the revisions in the depot as of midnight on May 22, 1999.
p4 diff	f -du file	Run the comparison on file file, displaying output in a format suitable for the patch(1) utility.
p4 diff	f -sr   p4 -x - revert	Revert all open, unchanged files.
		This differs from p4 revert -a (revert all unchanged files, where resolving a file, even if no changes are made, counts as a change), in that it reverts files whose workspace content matches the depot content, including resolved files that happen to be identical to those in the depot.
		The first command shows all open, unchanged files. The second command (running p4 -x and taking arguments, one per line, from standard input, abbreviated as "-") reverts each file in that list.
		(This is the UNIX version of this command; it uses a pipe. Most operating systems have some equivalent way of performing these operations in series).
		For more information about the $-x$ option to p4, see the <i>Global Options</i> section.

To compare two depot revisions	p4 diff2
To view the entire contents of a file	p4 print

# p4 diff2

## **Synopsis**

Compare two depot file revisions.

# **Syntax**

```
p4 [g-opts] diff2 [-dflags -q -t -u] file1[rev] file2[rev]
p4 [g-opts] diff2 [-dflags -q -t -u] -b branch [[fromfile[rev]] tofile[rev]]
```

# **Description**

p4 diff2 uses the Perforce server's built-in diff routine to compare two file revisions from the depot. These revisions are usually two versions of the same file, but they can be revisions of entirely separate files. If no file revision is explicitly provided with the file argument, the head revision is used.

p4 diff2 does not use the diff program specified by the environment variable P4DIFF. The diff algorithm used by p4 diff2 runs on the machine hosting the Perforce server, and always uses the server's built-in diff routine.

You can specify file patterns as arguments in place of specific files, with or without revision specifiers; this causes Perforce to perform multiple diffs for each pair of files that match the given pattern. If you invoke p4 diff2 with file patterns, escape the file patterns from the OS shell by using quotes or backslashes, and be sure that the wildcards in the two file patterns match.

Perforce presents the diffs in UNIX diff format, prepended with a header. The header is formatted as follows:

```
==== file1 (filetype1) - file2 (filetype2) ==== summary
```

The possible values and meanings of summary are:

- content: the file revisions' contents are different,
- types: the revisions' contents are identical, but the filetypes are different,
- identical: the revisions' contents and filetypes are identical.

If either file1 or file2 does not exist at the specified revision, the header will display the summary as <none>.

# **Options**

-d	Quiet diff. Display only the header, and don't even display that when the file revisions' contents and types are identical.
-dflags	Runs the diff routine with one of a subset of the standard UNIX diff flags. See the <i>Usage Notes</i> below for a listing of these flags.
-b branchname fromfile[rev] tofile[rev]	Use a branch mapping to diff files in two branched codelines. The files that are compared can be limited by file patterns in either <code>fromfile</code> or <code>tofile</code> .
-t	Diff the file revisions even if the file(s) are not of type text.
-u	Generate unified output format, showing added and deleted lines with sufficient context for compatibility with the patch (1) utility. Only those files that differ are included. File names and dates remain in Perforce syntax.
g-opts	See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	No	read access necessary for both file revisions

• The diff flags supported by p4 diff2 are:

Flag	Name
-dn	RCS output format, showing additions and deletions made to the file and associated line ranges.
-dc	context output format, showing line number ranges and three lines of context around the changes.
-ds	summary output format, showing only the number of chunks and lines added, deleted, or changed.
-du	unified output format, showing added and deleted lines with sufficient context for compatibility with the patch(1) utility.

Flag	Name
-db	ignore changes made within whitespace
-dw	ignore whitespace altogether

• To pass more than one flag to the diff routine, group them together. For example:

```
p4 diff2 -dub file1 file2
```

specifies a unified diff that ignores changes in whitespace.

- The header line of a unified diff produced with the -du option for patch (1) use displays the diffed files in Perforce syntax, not local syntax.
- When p4 diff2 is used to diff binary files, the line

```
... files differ ...
```

is printed if they are not identical.

- The option -b <code>branch</code> [ <code>[fromfile[rev]]</code> <code>tofile[rev]</code> ] may seem incorrect at first. Since the branch mapping maps <code>fromfiles</code> to <code>tofiles</code>, why would you specify both <code>fromfile</code> and <code>tofile</code> file patterns? You wouldn't, but this syntax allows you to specify a <code>fromfile</code> file pattern and a <code>tofile</code> revision, or a <code>fromfile</code> revision and a <code>tofile</code> file pattern.
- RCS keywords within files are not expanded with p4 diff2.

## **Examples**

p4 diff2 -ds file#1 file	Compare the second revision of file file to its head revision, and display a summary of what chunks were added to, deleted from, or changed within the file.
p4 diff2 file@34 file@1998/12/04	Diff the revision of file that was in the depot after changelist 34 was submitted against the revision in the depot at midnight on December 4, 1998.
p4 diff2 //depot/rel1/ //depot/rel2/#4	Compare the head revisions of all files under //depot/rel1 to the fourth revision of all files under //depot/rel2

```
p4 diff2 //depot/rel1/* //depot/rel2/...

p4 diff2 pattern must match.

p4 diff2 Compare the second revision of the files in //depot/rel2/... to the files branched from it by branch mapping branch2 at the revision they were at in changelist 50.
```

To compare a client workspace file to a depot file revision	p4 diff
To view the entire contents of a file	p4 print

# p4 dirs

# **Synopsis**

List the immediate subdirectories of specified depot directories.

## **Syntax**

```
p4 [g-opts] dirs [-C -D -H] depot directory[revRange]...
```

# **Description**

Use p4 dirs to find the immediate subdirectories of any depot directories provided as arguments. Any directory argument must be provided in depot syntax and must end with the \* wildcard. If you use the "..." wildcard, you will receive the wrong results!

p4 dirs only lists the immediate subdirectories of the directory arguments. To recursively list all of a directory's subdirectories, call p4 dirs multiple times.

By default, only subdirectories that contain at least one undeleted file will be returned. To include those subdirectories that contain only deleted files, use the -D flag.

This command is meant to be used in scripts that call Perforce; it is unlikely that you'll have a need to call it from the command line.

## **Options**

-C	Display only those directories that are mapped through the current client workspace view.
-D	Include subdirectories that contain only deleted files. By default, these directories are not displayed.
-H	Include only those directories that contain files on the current client workspace's p4 have list.
g-opts	See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	list

If you include a revision specifier or revision range as part of a directory argument, then
the only subdirectories returned are those that contain at least one file revision that
matches the given specifier.

• Perforce does not track directories in its database; thus, the subdirectory values are not looked up, but are computed. This accounts for some of the strange details of the p4 dirs implementation, such as the fact that the "..." wildcard is not supported.

# **Examples**

p4 dirs //depot/projects/*	Returns a list of all the immediate subdirectories of //depot/projects.
p4 dirs //depot/a/* //depot/b/*	Returns a list of all immediate subdirectories of //depot/a and //depot/b.
p4 dirs //depot/	The "" wildcard is not supported by p4 dirs.

To list all the files that meet particular criteria	p4 files
To list all depots on the current Perforce server	p4 depots

## p4 edit

## Synopsis

Opens file(s) in a client workspace for edit.

## **Syntax**

```
p4 [g-opts] edit [-c changelist#] [-k] [-n] [-t type] file...
```

# Description

p4 edit opens files for editing within the client workspace. The specified file(s) are linked to a changelist, but the files are not actually changed in the depot until the changelist is sent to the server by p4 submit.

Perforce controls the local OS file permissions; when p4 edit is run, the OS write permission is turned on for the specified files.

When a file that has been opened for edit with p4 edit is submitted to the depot, the file revision that exists in the depot is not replaced. Instead, the new file revision is assigned the next revision number in sequence, and previous revisions are still accessible. By default, the newest revision (the *head revision*) is used by all commands that refer to the file.

By default, the specified files are added to the default changelist. Use -c to specify a different changelist. (Or use the p4 change command to move files from the default changelist to a numbered changelist.)

To move files already opened for edit from one changelist to another, use p4 reopen.

# **Options**

-c change#	Opens the files for edit within the specified changelist. If this flag is not provided, the files are linked to the default changelist.
-t type	Stores the new file revision as the specified type, overriding the file type of the previous revision of the same file. See the <i>File Types</i> section for a list of file types.
-k	Keep existing workspace files; mark the file as open for edit even if the file is not in the client workspace view. Use p4 edit -k only in the context of reconciling work performed while disconnected from the Perforce Server.
-n	Preview which files would be opened for edit, without actually changing any files or metadata.
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	open

Since p4 edit turns local OS write permissions on for the specified files, this command should be given before the file is actually edited. The process is:

- 1. Use p4 edit to open the file in the client workspace,
- 2. Edit the file with any editor,
- 3. Submit the file to the depot with p4 submit.

To edit an older revision of a file, use p4 sync to retrieve the previously stored file revision into the client workspace, and then p4 edit the file. Since this file revision is not the head revision, you muse use p4 resolve before the file can be stored in the depot with p4 submit.

By default, Perforce does not prevent users from opening files that are already open; its default scheme is to allow multiple users to edit the file simultaneously, and then resolve file conflicts with p4 resolve. To determine whether or not another user already has a particular file opened, use p4 opened -a file.

If you need to prevent other users from working on files you've already opened, you can either use the p4 lock command (to allow other users to edit files you have open, but prevent them from submitting the files until you first submit your changes), or you can use the +1 (exclusive-open) filetype to prevent other users from opening the files for edit at all.

In older versions of Perforce, p4 edit was called p4 open.

## **Examples**

p4 edit -t text+k doc/*.txt	Opens all files ending in .txt within the current directory's doc subdirectory for edit. These files are linked to the default changelist; these files are stored as type text with keyword expansion.
p4 edit -t +1 //depotname/	Implements pessimistic locking (exclusive-open) for all files in a depot. After this changelist is submitted, only one user at a time will be able to edit files in the depot named <code>depotname</code> .

p4 edit -c 14	Opens all files anywhere within the current working directory's file tree for edit. These files are examined to determine whether they are text or binary, and changes to these files are linked to changelist 14.
p4 edit status%40jan1.txt	Open a file named status@jan1.txt for edit.  For details about how to specify other characters reserved for use as Perforce wildcards, see "Limitations on characters in filenames and entities" on page 274.

To open a file for add	p4 add
To open a file for deletion	p4 delete
To copy all open files to the depot	p4 submit
To copy files from the depot into the client workspace	p4 sync
To create or edit a new changelist	p4 change
To list all opened files	p4 opened
To revert a file to its unopened state	p4 revert
To move an open file to a different changelist or change its filetype	p4 reopen

# p4 export

## **Synopsis**

Extract journal or checkpoint records.

## **Syntax**

```
p4 export -c token [-J prefix] [-f] [-l lines] [-F filter] p4 export -j token [-J prefix] [-f] [-l lines] [-F filter] p4 export -j token [-J prefix] -r [-F filter]
```

# **Description**

This command reports checkpoint and journal metadata from a Perforce server. With no options, the records are reported in tagged form.

Some fields are added to the tagged output to indicate either transactional consistency, or to indicate the end of the journal.

# **Options**

-C	Specifies a checkpoint number or position token of the form checkpointnum#byteoffset.
-j	Specify a journal number or position token of the form journalnum/byteoffset.
-f	Format the output so that non-textual datatypes are formatted appropriately.
-r	Display raw journal output; this argument applies to journals only.
-J prefix	Specifies a filename prefix for the journal, such as that used with p4d -jc prefix
-1 lines	Limit output to the specified number of lines of journal records.
-F filter	Limit output to records that match the specified filter pattern.
g-opts	See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	super

• Compressed journals or checkpoints are not supported.

# p4 filelog

## **Synopsis**

Print detailed information about files' revisions.

#### **Syntax**

```
p4 [g-opts] filelog [ -c change -h -i -l -L -t -m maxrev -s ] file...
```

# Description

p4 filelog describes each revision of the files provided as arguments. At least one file or file pattern must be provided as an argument.

By default, the output consists of one line per revision in reverse chronological order. The format of each line is:

```
... #rev change chnum action on date by user@client (type) 'description' where:
```

- rev is the revision number;
- chnum is the number of the submitting changelist;
- action is the operation the file was open for: add, edit, delete, branch, import, or integrate;

If the action is import (that is, integrate from a remote depot) or integrate, Perforce displays a second line description, formatted as

```
... #integration-action partner-file
```

See p4 integrated for a full description of integration actions.

- date is the submission date (by default), or date and time (if the -t flag is used).
- user is the name of the user who submitted the revision;
- client is the name of the client workspace from which the revision was submitted;
- type is the type of the file at the given revision; and
- *description* is the first 30 characters of the corresponding changelist's description.

If the -1 option is used, the <code>description</code> is the full changelist description as entered when the changelist was submitted. If the -L option is used, the description is the full changelist description, truncated to 250 characters.

## **Options**

a abanas	Display only files submitted at the specified shapedist number
-c change	Display only files submitted at the specified changelist number.
-h	Display file content history instead of file name history. The revisions that are listed include revisions of other files that were branched/copied (using p4 integrate and p4 resolve -at) to the specified revision. Revisions that were replaced by copying or branching are not displayed, even if they are in the history of the specified revision.
-i	Follow file history across branches. If a file was created by integration via p4 integrate, Perforce describes the file's revisions and displays the revisions of the file from which it was branched (back to the branch point of the original file).
-1	List long output, with the full text of each changelist description.
-L	List long output, with the full text of each changelist description truncated at 250 characters.
-t	Display the time as well as the date.
-m maxrev	List only the first maxrev changes per file output.
-s	Display a shortened form of output by ignoring non-contributory integrations (for example, integrations involving "branch into" or copy into" operations are not displayed)
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	No	list

- Because p4 filelog's output can be quite large when called with highly non-restrictive file arguments (for example, p4 filelog //depot/... displays the revision history for every file in the depot), p4 filelog commands may be subject to a maxresults limitation as set in p4 group.
- If both the -i and the -m maxrev flags are used, and a branch is encountered within the most recent maxrev revisions of the file, the most recent maxrev revisions of the file prior to the branch point are also displayed. p4 filelog -i follows branches down to a depth of 50 levels, which should be more than sufficient for any site.
- Old revisions of temporary object files (file type modifier +Sn) are displayed with an action of purge.

# **Examples**

p4	filelog	//depot/proj1/	Display the revision history for every file under the depot's proj1 directory.
p4	filelog	file1.c file1.h	Show the revision history for files file1.c and file1.h, which reside locally in the current working directory.

To read additional information about each file	p4 files
To display file information in a format suitable for scripts	p4 fstat
To view a list of open files	p4 opened
To view a list of files you've synced to your client workspace	p4 have

# p4 files

## **Synopsis**

Provide information about files in the depot without accessing their contents.

## **Syntax**

```
p4 [g-opts] files [-a] file[revRange]...
```

# Description

This command lists each file that matches the *file patterns* provided as arguments. If a revision specifier is given, the files are described at the given revision. One file is listed per line, and the format of each line is:

```
depot-file-location #rev - action change change # (filetype)
```

#### where

- *depot-file-location* is the file's location relative to the top of the depot
- rev is the revision number of the head revision of that file
- action is the action taken at the head revision: add, edit, delete, branch, or integrate
- change# is the number of the changelist that this revision was submitted in, and
- *filetype* is the Perforce *file type* of this file at the head revision.

Unlike most Perforce commands, p4 files reports on any file in the depot; it is not limited to only those files that are visible through the client view. Of course, if a file pattern on the command line is given in client syntax, only client files are shown.

# **Options**

-a	For each file, list all revisions within a specified revision range, rather
	than only the highest revision in the range.
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	list

- The specified revision can be a revision range; in this case, only those files with revisions within the specified range are listed, and by default, only the highest revision in that range is listed. (To display information for all files within a revision range, use p4 files -a.)
- Since the output of p4 files can be quite large when called with highly non-restrictive file arguments (for example, p4 files //depot/... prints information about all the files in the depot), it may be subject to a maxresults limitation as set in p4 group.

## **Examples**

p4 files //depot/	Provides information about all files in the depot.
p4 files //clientname/	Provides information about all depot files visible through the client view.
p4 files @2000/12/10	Provides information about all depot file revisions that existed on December 10, 2000.
p4 files @2001/03/31:08:00,@2001/03/31:17:00	Lists all files and revisions changed during business hours on March 31, 2001.
p4 files //depot/proj2/@p2lab	Lists files and revisions under the directory //depot/proj2/ that are included in label p2lab.
p4 files //depot/file.c	Show information on the head revision of //depot/file.c. (that is, the <i>highest</i> revision in the implied range of #1, #head)
p4 files -a //depot/file.c	Show information on every revision of //depot/file.c (that is, <i>all</i> revisions in the implied range of #1, #head)

To list the revision history of files	p4 filelog
To see a list of all currently opened files	p4 opened
To see a list of the file revisions you've synced to	p4 have
To view the contents of depot files	p4 print

## p4 fix

#### **Synopsis**

Link jobs to the changelists that fix them.

#### **Syntax**

```
p4 [g-opts] fix [ -d ] [ -s status ] -c changelist# jobName ...
```

## **Description**

The p4 fix command links jobs (descriptions of work to be done) to a changelist (a set of changes to files that does the work described by a job).

If the changelist has not yet been submitted, the job appears on the p4 submit or p4 change form for the changelist to which it's linked, and under normal circumstances, the status of the job is changed to closed when the changelist is submitted. If the changelist has already been submitted when you run p4 fix, the job's status is changed to a default status (typically closed) immediately.

To change a job status to something other than the default status (typically closed) when you submit a changelist, supply the -s option to p4 fix, p4 submit, or p4 change.

Because described work can be fixed over multiple changelists, one job can be linked to multiple changelists. Since a single changelist might fix ten bugs, multiple jobs can be linked to the same changelist. You can do this in one command execution by providing multiple jobs as arguments to p4 fix.

## **Options**

-d	Delete the fix record for the specified job at the specified changelist. The job's status will not change.
-s status	Upon submission of the changelist, change the job's status to <i>status</i> , rather than the default value closed (or some other value as defined in the Presets: of field 102 of the p4 jobspec form).
	If the changelist to which you're linking the job been submitted, the status value is immediately reflected in the job's status.
	If the changelist is pending, the job status is changed on submission of the changelist, provided that the -s flag is also supplied to p4 submit and the desired status appears next to the job in the p4 submit form's Jobs: field.
	To leave a job unchanged, use the special status of same.
g-opts	See the Global Options section.

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	open

- Because the format of jobs can be changed from site to site, it is possible that the jobs on your system no longer have a Status: field. If so, you can still link jobs to changelists with p4 fix, but Perforce will not change any of the job fields' values when the changelist is submitted.
- You can change a fixed or unfixed job's status at any time by editing the job with p4 job.
- Another way to fix (or unfix) a job is to add it to (or delete it from) the Jobs: field of an unsubmitted changelist's p4 submit or p4 change form.
- You can't p4 fix a job to the default changelist; instead, add the job to the Jobs: field of the default changelist's p4 submit form when submitting it to the depot.
- If you use p4 fix -s status on a job, and then use the -s option with p4 submit or p4 change, the Jobs: field of the changelist's form will also require a status value (the default value being the one specified by p4 fix -s status). The job(s) will be assigned the specified status upon successful submission of the changelist. If no status value is specified in the form, the error message:

Wrong number of words for field 'Jobs'.

is displayed.

p4 fix -s status, p4 submit -s, and p4 change -s are intended for use in conjunction with defect tracking systems.

Under normal circumstances, end users do not use these commands, and use p4 submit and p4 change without the -s option. In this case, only the job number is required in the Jobs: field, and each job's status is set to a default value (typically closed) on completion of the submit.

## **Examples**

p4 fix -c 201 job000141 j	job002034	Mark two jobs as being fixed by changelist 201.
		If changelist 201 is still pending, the jobs' status is changed to closed when the changelist is submitted.

p4 fix -c 201 -s suspended job002433 Mark job002433 as suspended, rather than closed, when changelist 201 is submitted.

Requires use of the -s flag with p4 submit.

To add or delete a job from a pending changelist	p4 change
To add or delete a job from the default changelist	p4 submit
To view a list of connections between jobs and changelists	p4 fixes
To create or edit a job	p4 job
To list all jobs, or a subset of jobs	p4 jobs
To change the format of jobs at your site ( <i>superuser only</i> )	p4 jobspec
To read information about the format of jobs at your site	p4 jobspec -o

## p4 fixes

#### **Synopsis**

List jobs and the changelists that fix them.

#### **Syntax**

```
p4 [g-opts] fixes [-i -m max -j job -c changelist#] [file[revRange]...]
```

## Description

After a job has been linked to a particular numbered changelist with p4 fix, p4 change, or p4 submit, the job is said to have been *fixed* by the changelist (even if the changelist is still pending). The p4 fixes command lists changelists and the jobs they fix.

If invoked without arguments, p4 fixes displays all fix records. Fix records are displayed in the following format:

```
jobname fixed by change changelist# on date by user (status)
```

You can limit the listed fixes by combining the following flags when calling p4 fixes:

- Use the -c changelist option to list only the jobs fixed by that pending or submitted changelist.
- Use the -j *job* option to list only those pending or submitted changelists that fix that job.
- Provide one or more file pattern arguments. If you provide a file argument, only submitted changelists affecting files that match the file patterns are listed; pending changelists are not included. If a revision specifier or revision range is included, only submitted changelists that affected files at the given revisions are listed. You can use the -i flag with a file pattern argument to include fixes made by changelists that were integrated into the specified files.
- Use the -m max flag to limit the output to the first max fixes.

#### **Options**

-c changelist#	Limit the displayed fixes to those that include the specified changelist.
-j jobname	Limit the displayed fixes to those that include the specified job.
-i files	Include fixes made by changelists that affected files integrated into the specified files.
-m max	List only the first max fixes.
g-opts	See the Global Options section.

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	list

# Examples

p4 fixes //depot/proj1/	Display all fixes made by submitted changelists that
	included any files under //depot/proj1.
p4 fixes -c 414	Display all jobs fixed by pending or submitted changelist 414.

To create or edit an existing job	p4 job
To list all jobs known to the system	p4 jobs
To attach a job to a particular changelist; the job is fixed by that changelist	p4 fix
To change the format of jobs at your site (superuser only)	p4 jobspec
To read information about the format of jobs at your site	p4 jobspec -o

## p4 flush

#### **Synopsis**

Update a client workspace's have list without actually copying any files.

#### **Syntax**

```
p4 [g-opts] flush [-n] [file[revRange]...]
```

## Warning

Using p4 flush incorrectly can be dangerous.

If you use p4 flush incorrectly, the server's metadata will not reflect the actual state of your client workspace, and subsequent Perforce commands will not operate on the files you expect! Do not use p4 flush until you fully understand its purpose.

It is rarely necessary to use p4 flush.

## Description

p4 flush performs half the work of a p4 sync. Running p4 sync filespec has two effects:

- The file revisions in the filespec are copied from the depot to the client workspace;
- The client workspace's have list (which tracks which file revisions have been synced, and is stored on the Perforce server) is updated to reflect the new client workspace contents.

p4 flush performs only the *second* of these steps. Under most circumstances, this is not desirable, since a client workspace's have list should always reflect the client workspace's true contents. However, if the client workspace's contents are already out of sync with the have list, p4 flush can sometimes be used to bring the have list in sync with the actual contents. Since p4 flush performs no actual file transfers, this command is much faster then the corresponding p4 sync.

Use p4 flush only when you need to update the have list to match the actual state of the client workspace. The *Examples* subsection describes two such situations.

## **Options**

-n	Display the results of the flush without actually performing the flush. This lets you make sure that the flush does what you think it will do	
	before you do it.	
g-opts	See the Global Options section.	

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	read

• Since p4 flush updates the have list without copying files, and p4 sync -f updates the client workspace to match the have list, p4 flush files followed by p4 sync -f files is almost equivalent to p4 sync files. This means that a bad flush can be almost entirely fixed by following it with a p4 sync -f of the same file revisions that were originally flushed.

Unfortunately, this is not a complete remedy, since any file revisions that were deleted from the have list by p4 flush will remain in the client workspace even after the p4 sync -f. In this case, you will need to manually remove deleted file revisions from the client workspace.

#### **Examples**

- Ten users at the same site need to set up new, identical client workspaces from the same depot at a remote location over a slow link. The standard method calls for each user to run identical p4 sync commands, but since the line speed is slow, there's a faster way:
  - One user runs p4 sync files from his client workspace firstworkspace.
  - The other users copy the newly synced files from the first user's client workspace into their own client workspaces using their local OS file-copying commands.
  - The other users run p4 flush *files* @firstworkspace, which brings their client workspaces' have lists into sync with the files copied into the client workspaces in the last step.

Since p4 flush moves no files across the slow link, the process can be much faster then running the same p4 sync command ten separate times.

• Joe has a client workspace called ws that has a Root: of

```
/usr/joe/project1/subproj

and a View: of
//depot/joe/proj1/subproj/...//joe/...
```

He decides that all the files under /usr/joe/project1 need to be included in the workspace, and accomplishes this by using p4 client to change the Root: to

```
/usr/joe/project1
and the View: to
//depot/joe/proj1/... //joe/...
```

This keeps his current client workspace files in the same place, while extending the scope of the workspace to include other files. But when Joe runs his next p4 sync, he's surprised to see that Perforce deletes every non-open file in the client workspace and replaces it with an identical copy of the same file!

Perforce behaves this way because the have list describes each file's location relative to the client root, and the physical location of each file is only computed when each Perforce command is run. Thus, Perforce thinks that each file has been relocated, and the p4 sync deletes the file from its old location and copies it into its new location.

To make better use of Perforce, Joe might have performed a p4 flush #have instead. This would have updated his client workspace's have list to reflect the files' "new" locations without actually copying any files.

-f

## p4 fstat

#### **Synopsis**

Dump file info in format suitable for parsing by scripts.

#### **Syntax**

```
p4 [g-opts] fstat [-F \ filter \ -T \ fields \ -m \ max \ -r] [-c|-e \ change] [-Ox \ -Rx \ -Sx] file[rev]...
```

## **Description**

The p4 fstat command dumps information about each file, with each item of information on a separate line.

Use the -m max option to limit the output to the first max files.

To change the field on which output is sorted, use one of the -Sx options, and to reverse sort order, use the -r option.

To filter the output on some function of the form fields (for example, all files larger than a certain size and with a certain filetype), use the -F filter flag.

To limit output to the set of fields specified in a fields argument, use the -T fields flag.

The output is best used within a Perforce API application where the items can be accessed as variables, but is also suitable for parsing by scripts.

#### Form Fields

Field Name	Description	Example/Notes
clientFile	local path to file (in local	/staff/userid/src/file.c
	syntax by default, or in Perforce syntax with the -op option)	(or //workspace/src/file.c in Perforce syntax)
depotFile	depot path to file	//depot/src/file.c
path	local path to file	//workspace/src/file.c
isMapped	set if mapped client file is synced	set ( isMapped) or not present
shelved	set if file is shelved	
headAction	action taken at head revision, if in depot	<pre>one of add, edit, delete, branch, or integrate</pre>

Field Name	Description	Example/Notes
headChange	head revision changelist number, if in depot	1, 2, 3 <i>n</i>
headRev	head revision number, if in depot	1, 2, 3 <i>n</i>
headTime	Head revision changelist time, if in depot. Time is measured in seconds since 00:00:00 UTC, January 1, 1970	919283152 is a date in early 1999
headRevModTime	Head revision modification time (the time that the file was last modified on the client before submit), if in depot.	919280483 is a date in early 1999
headType	head revision type, if in depot	text, binary, text+k, etc. (see the chapter on <i>File Types</i> .)
haveRev	revision last synced to workspace, if on workspace	1, 2, 3 <i>n</i>
desc	changelist description (if using -e changelist and if the file was part of changelist)	A Perforce changelist
digest	MD5 digest of a file (requires -01 option)	A 32 hexadecimal digit string
fileSize	file length in bytes (requires -01 option)	63488
action	open action, if opened in your workspace	one of add, edit, delete, branch, or integrate
type	open type, if opened in your workspace	A Perforce file type
actionOwner	the user who opened the file, if open	A Perforce username
change	open changelist number, if opened in your workspace	1, 2, 3 <i>n</i>

Field Name	Description	Example/Notes
resolved	the number, if any, of resolved integration records	1, 2, 3 <i>n</i>
unresolved	the number, if any, of unresolved integration records	1, 2, 3 <i>n</i>
otherOpen	the number of other users who have the file open, blank if no other users have the file open	1, 2, 3 $n$ , preceded by $n$ records listing the users (0 through $n$ -1) with otherOpen $n$ , otherAction $n$ , and otherLock $n$ fields as applicable. For example: otherOpen 3 otherOpen0 user1@cws1 otherOpen1 user2@cws2 otherOpen2 user3@cws3
otherOpenn	for each user with the file open, the workspace and user with the open file	user123@workstation9
otherLock	present and set to null if another user has the file locked, otherwise not present	unset ( otherLock) or not present
otherLock <i>n</i>	for each user with the	user123@workstation9
worksp	vorkspace and user	Because only one user at a time can lock a file, if $n$ is set, $n$ is always 0.
otherAction <i>n</i>	for each user with the file open, the action taken	one of add, edit, delete, branch, or integrate
otherChangen	for every changelist with the file open, the changelist	A changelist number
ourLock	present and set to null if the current user has the file locked, otherwise not present	unset ( ourLock) or not present

Field Name	Description	Example/Notes
resolveActionn resolveBaseFilen resolveFromFilen resolveStartFromRevn resolveEndFromRevn	Pending integration action, base file, base revision number, from file, starting, and ending revision, respectively.	For pending integration record information, use the -Or option.
totalFileCount	The number of files examined.	Appears in the first file's output when you use the -m max option in conjunction with one of the -sx or -r sorting options.

# Options

-F filter	List only those files that match the criteria specified by filter. Please see the <i>Usage Notes</i> below for a discussion of filters.
-T fields	List only those fields that match the field names specified by fields. The list of field names can be separated by spaces or commas.
-c change	Display only files affected after the given changelist number. This operation is much faster than using a revision range on the affected files.
-e change	Display only files affected by the given changelist number. This option is much faster than using a revision range on the affected files.
-m max	Produce fstat output for only the first max files.
-r	Sort the output in reverse order.
-Of	Output all revisions for the given files, suppressing the other [] and resolve [] fields.
-01	Output a fileSize field displaying the length of the file and a digest field for each revision.
	On servers older than release 2005.1, this field may be expensive to compute, particularly for text files with many revisions.
-Op	Display the clientFile in Perforce syntax, as opposed to local syntax.
-Or	Display pending integration record data for files open in the current workspace.
-0s	Shorten output by excluding client workspace data (for instance, the clientFile field).
-Rc	Limit output to files mapped into the current workspace.
-Rh	Limit output to files on your have list; that is, to files synced to the current workspace.

-Rn	Limit output to files opened at revisions not at the head revision.
-Ro	Limit output to open files in the current workspace.
-Rr	Limit output to open files that have been resolved.
-Rs	Limit output to shelved files. Requires -e changelist option.
-Ru	Limit output to open files that are unresolved.
-St	Sort by filetype.
-Sd	Sort by date.
-Sr	Sort by head revision.
-Sh	Sort by have revision.
-Ss	Sort by filesize.
g-opts	See the Global Options section.
	The -s global option (which prefixes each line of output with a tag describing the type of output as error, warning, info, text, or exit) can be particularly useful when used with p4 fstat.

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	list

#### **Filters**

Use p4 fstat -F filter to limit the list of files to those that meet certain criteria. You can use logical operators on any of the form fields displayed by p4 fstat.

Text matching is case-insensitive. All alphanumeric strings (including words including embedded punctuation) separated by whitespace are indexed as words.

Spaces between search terms in a filter are treated as boolean AND operations. To find files that contain any of the key/value pairs (boolean OR), separate the terms with the "|" character.

Ampersands (&) can be used as boolean ANDs as well; the boolean operators bind in the order &, |, space (highest precedence to lowest precedence). Use parentheses to change the grouping order.

Search results can be narrowed by matching values within specific fields with the filter syntax "fieldname=value". The value must be a single token, including both alphanumeric characters and punctuation.

The wildcard "\*" allows for partial word matches. The filter "fieldname=string\*" matches "string", "stringy", "stringlike", and so on.

Date fields can be matched by expressing the filter date as yyyy/mm/dd or yyyy/mm/dd:hh:mm:ss. If a specific time is not provided, the equality operator (=) matches the entire day.

The usual comparison operators (=, >, <, >=, and <=) are available.

Additionally, you can use the NOT operator (^) to negate the sense of some comparisons.

To search for text containing characters that are filter expression operators, escape the characters with a backslash (\) character.

The behavior of these operators depends on the type of field you're comparing against:

Use of Comparison Operators in Filters
The equality operator (=) must match the value in the word field
exactly.
The relational operators perform comparisons in ASCII order.
The equality operator (=) matches the file if the word given as the value is found anywhere in the specified field.
The relational operators are of limited use here, since they match the file if <i>any</i> word in the specified field matches the provided value.
For example, if a changelist has a text field desc that contains the phrase bug not fixed, and the filter is "desc <fixed", because="" bug<fixed.<="" file="" filter,="" matches="" td="" the=""></fixed",>
As for field type text, above.
The equality operator (=) matches a file if the value of the named field is the specified word. The relational operators perform comparisons in ASCII order.
Dates are matched chronologically. If a specific time is not provided, the operators =, <=, and >= match the entire day.

#### Other Usage Notes

- If you use -e changelist# with the -Ro option, only pending changes are considered, so that files open for add are included in the output.
- The syntax of p4 fstat was changed in Release 2004.2. The older -C, -H, -W, -P, -1, and -s options are supported for compatibility purposes.

- For files containing the special characters @, #, \*, and %, the clientFile displays the special character, and the depotFile displays the filename containing the ASCII expression of the character's hexadecimal value.
- The size and digest fields are based on the normalized (UNIX linefeed convention) and uncompressed version of the depot file, regardless of how the file is represented when synced to a client workspace.

#### **Examples**

p4 fstat file.c	Displays information on file.c
p4 fstat -Rc 20 *.c	Displays information on all .c files affected after the checking-in of files under changelist 20.
p4 fstat -Os file.c	No client workspace information lines (i.e. clientFile) are displayed
p4 fstat -Osl file.c	No client workspace information lines are displayed, but the fileSize and digest lines are displayed.
p4 fstat -Os -Ol file.c	Equivalent to p4 fstat -Osl.
<pre>p4 fstat -01 -F "fileSize &lt; 1024 &amp; headType=text" //depot/main/</pre>	Display information on all text files under $//\text{depot/main/}$ that are smaller than 1024 bytes in length.
<pre>p4 fstat -T 'depotFile, headRev' file.c</pre>	Display only the depotFile and headRev fields for file.c.

To read additional information about each file	p4 files
To display file information including change descriptions	p4 filelog

## p4 grep

## **Synopsis**

Print lines in files (or revisions of files) that match a pattern.

#### **Syntax**

```
p4 [g-opts] grep [ options ] -e pattern file[revRange]... options: -a -i -n -v -Anum -Bnum -Cnum -l -L -T -s -F -G
```

## **Description**

The p4 grep command searches for lines that match a given regular expression.

By default, p4 grep operates on the head revision. If the file argument specifies a revision, all files as of that revision number are searched. If the file argument has a revision range, only those files selected by that revision range are searched, and the highest revision in that range is used for each file.

## **Options**

-e pattern	The patterns used by p4 grep are regular expressions comparable to those used in UNIX; their syntax is fully defined in the output of p4 help grep.
-a	Search all revisions within the specified range, rather than only the highest revision in the range
-i	Perform case-insensitive pattern matching. (By default, matching is case-sensitive.)
-n	Display a matching line number after the file revision number.
-v	Display files with non-matching lines.
- F	Interpret the pattern as a fixed string
-G	Interpret the pattern as a regular expression.
-L	Display the name of each selected file from which no output would normally have been displayed; scanning stops at the first match.
-1	Display the name of each selected file from which output would have been displayed; scanning stops at the first match.
-s	Suppress error messages from files with more than 4096 characters in a single line. (By default, p4 grep abandons these files and reports an error)

-t	Treat binary files as text. (By default, only files of type text are selected for pattern matching.)
-A num	Display num lines of trailing context after matching lines.
-B <i>num</i>	Display num lines of trailing context before matching lines.
-C num	Display num lines of output context.
g-opts	See the Global Options section.

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	list

## p4 group

## **Synopsis**

Add or delete users from a group, or set the maxresults, maxscanrows, maxlocktime, and timeout limits for the members of a group.

## **Syntax**

```
p4 [g-opts] group [ -a ] groupname
p4 [g-opts] group -d [ -a ] groupname
p4 [g-opts] group -o groupname
p4 [g-opts] group -i [ -a ]
```

#### Description

A *group* is a list of Perforce users. Use groups to set access levels in the p4 protect form, limit the maximum amount of data that can be accessed from the server by particular users within a single command, and to set the timeout period for p4 login tickets.

To delete a group, use p4 group -d groupname, or call p4 group groupname and remove all the users from the resulting form.

#### Form Fields

Field Name	Туре	Description
Group:	Read-only	The name of the group, as entered on the command line.
MaxResults:	Writable	The maximum number of results that members of this group can access from the server from a single command. The default value is unset. See the <i>Usage Notes</i> below for more details.
MaxScanRows:	Writable	The maximum number of rows that members of this group can scan from the server from a single command. The default value is unset. See the <i>Usage Notes</i> below for more details.
MaxLockTime	Writable	The maximum length of time (in milliseconds) that any one operation can lock any database table when scanning data. The default value is unset. See the <i>Usage Notes</i> below for more details.

Field Name	Туре	Description
Timeout:	Writable	The duration (in seconds) of the validity of a session ticket created by p4 login. The default value is 43200 seconds (12 hours). To create a ticket that does not expire, set the Timeout: field to unlimited.
Users:	Writable, multi-line	The Perforce usernames of the group members. Each user name must be typed on its own line, and should be indented.
Subgroups:	Writable,	Names of other Perforce groups.
	multi-line	To add all users in a previously defined group to the group you're presently working with, include the group name in the Subgroups: field of the p4 group form. Note that user and group names occupy separate namespaces, and thus, groups and users can have the same names.
		Every member of any previously defined group you list in the Subgroups: field will be a member of the group you're now defining.
Owners:	Writable, multi-line	Names of other Perforce users.
		Group owners without super access are permitted to administer this group, provided that they use the -a flag.
		Group owners are not necessarily members of a group; if a group owner is to be a member of the group, the userid must also be added to the Users: field.

# Options

-a	Allow a (non-superuser) group owner to administer the group. The user must be listed in the Owner: field of the group.
-d groupname	Delete group <i>groupname</i> . The members of the group are affected only if their access level or maxresults value changes as a result of the group's deletion.
-i	Read the form from standard input without invoking the user's editor. The new group specification replaces the previous one.

-0	Write the form to standard output without invoking the user's editor.
g-opts	See the <i>Global Options</i> section.

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	super (list for p4 group -o or -a)

- Ticket Timeout values for users who belong to multiple groups are calculated the same
  way as maxresults values: the largest timeout value for all the groups of which the
  user is a member (including unlimited, but ignoring unset). Users in no groups have
  the default timeout value of 43200. To create a ticket that does not expire, set the
  Timeout to unlimited.
- As the number of files in the depot grows, certain commands can significantly slow down the server if called with no parameters, or if called with non-restrictive arguments. For example, p4 print //depot/... will print the contents of every file in the depot on the user's screen, and p4 filelog //depot/... will attempt to retrieve data on every file in the depot at *every revision*.

The Perforce superuser can limit the amount of data that the server returns to the client by setting the MaxResults value for groups of users. The superuser can also limit the amount of data scanned by the server (whether returned to the client or not) by setting the MaxScanRows value, and the length of time any database table can be locked in by any single operation by setting the MaxLockTime value.

If any of the MaxResults, MaxScanRows, or MaxLockTime limits are violated, the server request fails and the user is asked to limit his query.

If a user belongs to multiple groups, the server computes her MaxResults value to be the maximum of the MaxResults for all the groups of which the user is a member (removing the limit if it encounters a setting of unlimited, but ignoring any settings still at the default value of unset). If a particular user is not in any groups, her MaxResults value is unset. (The user's MaxScanRows and MaxLockTime limits are computed in the same way.)

The speed of most server hardware should make it unnecessary to ever set a MaxResults value below 10000, a MaxScanRows value below 50000, or a MaxLockTime value below 1000.

• To display a group's maxresults, maxscanrows, maxlocktime, and timeout limits, use p4 groups -v groupname.

• Use p4 help maxresults to obtain the list of commands that are affected by any of the three limiting values.

To modify users' access levels	p4 protect
To view a list of existing groups	p4 groups

## p4 groups

#### **Synopsis**

List groups of users.

#### **Syntax**

```
p4 [g-opts] groups [ -m max ] [ [ [ -i ] user | group ] | [ -v group ] ]
```

#### **Description**

Shows a list of all current groups of users as created by p4 group. Only the group names are displayed.

If the optional *user* argument is provided, only the groups containing that user are listed. If the optional *group* argument is provided, only groups containing the named group are listed.

Use the -i option to include groups to which the user (or group) belongs by means of being a member of a subgroup. If a group argument is given, only groups that contain the named group are displayed.

Use the -v option to display the MaxResults, MaxScanRows, MaxLockTime, and Timeout values for the named group, or, if no group is specified, for all groups.

Use the -m max option to limit the output to the first max groups.

#### **Options**

-m max	List only the first max groups.
-i [ user   group ]	Display groups to which the <i>user</i> or <i>group</i> is an indirect member (that is, by means of inclusion in a subgroup).
-v [ group ]	Display verbose output: include MaxResults, MaxScanRows, MaxLockTime, and Timeout values.
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	list

- To see all the members of a particular group, use p4 group -o groupname. This variation of p4 group requires only list access.
- The -v and -i options are mutually exclusive.

## **Examples**

p4 groups bob Display the names of all groups of which user bob is a member.

To create or edit an existing group of users	p4 group
To view a list of all the members and specifications of a	p4 group -o groupname
particular group	
To set Perforce access levels for the members of a particular	p4 protect
group	

## p4 have

#### **Synopsis**

List files and revisions that have been synced to the client workspace

#### **Syntax**

```
p4 [g-opts] have [file...]
```

## Description

List those files and revisions that have been copied to the client workspace with p4 sync. If file patterns are provided, the list is limited to those files that match one of the patterns, and to those files that are mapped to the client view.

p4 have lists the files, one per line, in the format:

```
depot-file#revision-number - local-path
```

- *depot-file* is the path to the file in *depot syntax*.
- revision-number is the have revision; the revision presently in the current client workspace
- *local-path* is the path as represented in terms of the local filesystem (i.e., in *local syntax*).

## **Options**

g-opts See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	list

Some Perforce documentation refers to a client workspace's have list. The have list is the
list of files reported by p4 have, and is the list of file revisions that have been most
recently synced from the depot. It does not include files that exist in your client
workspace but not in the depot.

For instance, if you use p4 add to open a newly created file in your client workspace for add, or if you use p4 integrate to create a group of files in your client workspace, but haven't submitted them, the new files do not appear in the output of p4 have.

The set of all files in your client workspace is the union of the set of files listed by p4 have with the set of files listed by p4 opened.

• For files containing the special characters @, #, \*, and %, the depot-file field shows the ASCII expression of the character's hexadecimal value, and the local-path shows the special character. For example:

```
//depot/status/100%25.txt#1 - /staff/status/100%.txt
```

#### **Examples**

```
p4 sync //depot/name...
p4 have //depot/name

p4 sync //depot/name/...#4
p4 have //depot/name

The first p4 have shows that the highest revision of the file has been copied to the client workspace.

The second p4 have shows that the fourth revision is the revision currently in the client workspace.
```

#### **Related Commands**

To copy file revisions from the depot to the client workspace p4 sync

## p4 help

#### **Synopsis**

Provide on-line help for Perforce.

## **Syntax**

```
p4 [g-opts] help
p4 [g-opts] help keyword
p4 [g-opts] help command
```

## **Description**

p4 help displays a help screen describing the named *command* or *keyword*. It's very similar to this manual, but the text is written by the developers.

p4 help with no arguments lists all the available p4 help options. p4 help *command* provides help on the named *command*. p4 help *keyword* takes the following keywords as arguments:

Command and Keyword	Meaning	Equivalent Chapter in this Manual
p4 help simple	Provides short descriptions of the eight most basic Perforce commands.	(none)
p4 help commands	Lists all the Perforce commands	Table of Contents
p4 help charset	Describes how to control Unicode translation	P4CHARSET description.
p4 help environment	Lists the Perforce environment variables and their meanings	Environment and Registry Variables
p4 help filetypes	Lists the Perforce filetypes and their meanings	File Types
p4 help jobview	Describes Perforce jobviews	p4 jobs description
p4 help revisions	Describes Perforce revision specifiers	File Specifications
p4 help usage	Lists the six flags available with all Perforce commands	Global Options
p4 help views	Describes the meaning of Perforce views	Views

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	none

## **Related Commands**

To view information about the current Perforce configuration p4 info

## p4 info

#### **Synopsis**

Display information about the current client and server.

## **Syntax**

```
p4 [g-opts] info
```

## **Description**

The p4 info command displays information about the Perforce client and server.

Here's an example of the output from p4 info:

```
User name: joe
Client name: joes_client
Client host: joes_workstation
Client root: /usr/joe/projects
Current directory: /usr/joe/projects/source
Client address: 192.168.0.123:1818
Server address: p4server:1666
Server root: /usr/depot/p4d
Server date: 2008/06/28 12:11:47 -0700 PDT
Server uptime: 752:41:33
Server version: P4D/FREEBSD/2010.1/246375 (2010/05/25)
Server license: P4Admin P4Admin cp4adm> 20 users (expires 2011/01/01)
Server license-ip: 10.0.0.2
Case handling: sensitive
```

To obtain the version of the Perforce client program (p4), use p4 -V.

## **Options**

```
g-opts See the Global Options section.
```

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	none

To read Perforce's help files	p4 help
To view version information for your Perforce client program	p4 -V

## p4 integrate

#### **Synopsis**

Open files for branching or merging.

## **Syntax**

```
p4 [g-opts] integrate [options] fromFile[revRange] toFile
p4 [g-opts] integrate [options] -b branch [toFile[fromRevRange]...]
p4 [g-opts] integrate [options] -b branch -s fromFile[revRange] [toFile...]
    options: -c changelist# -d -Dflag -f -h -i -I -o -n -r -t -v
```

#### **Description**

When you've made changes to a file that need to be propagated to another file, start the process with p4 integrate. The simplest form of this command is p4 integrate fromFile toFile; this lets the Perforce server know that changes in fromFile need to be propagated to toFile, and has the following effects:

- If toFile doesn't yet exist, fromFile is copied to toFile, then toFile is opened for branch in the client workspace.
- If toFile exists, and shares a common ancestor with fromfile as above, then toFile is opened for integrate. You can then use p4 resolve to propagate all of, portions of, or none of the changes in fromFile to toFile. The p4 resolve command uses fromFile as theirs, toFile as yours, and the common ancestor of fromFile as base.
- If both toFile and fromFile exist, but toFile shares no common ancestor with fromFile, the integration is rejected. Use the -i flag to force a baseless merge.
- If fromFile was deleted at its last revision (and all previous changes have already been integrated between fromFile and toFile), toFile is opened for delete in the client workspace.

(Some of the available flags modify this behavior. See the Options section for details.)

The process is complete when you p4 submit toFile to the depot.

To specify multiple files, use wildcards in *fromFile* and *toFile*. Any wildcards used in *fromFile* must match identical wildcards in *toFile*. Perforce compares the *fromFile* pattern to the *toFile* pattern, creates a list of *fromFile*/*toFile* pairs, and performs an integration on each pair.

The syntax p4 integrate fromFiles toFiles requires you to specify the mapping between fromFiles and toFiles each time changes need to be propagated from fromFiles to toFiles. Alternatively, use p4 branch to store the mappings between fromFiles and toFiles in a branch view, and then use p4 integrate -b branchview whenever you need to propagate changes between fromFiles and toFiles.

## **Options**

Because some of the more recent integration flags add complexity to the integration process, we've divided the options into *Basic Integration Flags* and *Advanced Integration Flags* 

#### **Basic Integration Flags**

-b branchname [toFiles]	Integrate the files using the <code>sourceFile/targetFile</code> mappings included in the branch view of <code>branchname</code> . If the <code>toFiles</code> argument is included, include only those target files in the branch view that match the pattern specified by <code>toFiles</code> .
-n	Display the integrations this command would perform without actually performing them.
- V	Open files for branching without copying <i>toFiles</i> into the client workspace.
	Without this flag, p4 integrate copies newly-branched toFiles into the client workspace from fromFiles. When the -v (virtual) flag is used, Perforce won't copy toFiles to the client workspace. Instead, you can fetch them with p4 sync when you need them.
-c changelist#	Open the toFiles for branch, integrate, or delete in the specified pending changelist.
	If this option is not provided, the files are opened in the default changelist.
g-opts	See the Global Options section.

#### Advanced Integration Flags

-b branchname -s fromFile[RevRange] [ToFiles...]

In its simplest form, p4 integrate -b branchname -s fromFile allows you to integrate files using the source/target mappings included in the branch view of branchname, but include only those source files that match the patterns specified by fromFile.

In its more complicated form, when both fromFile and toFile are specified, integration is performed bidirectionally: first, integration is performed from from File to toFile; then integration is performed from toFile to fromFile.

This variation of p4 integrate was written to provide some needed functionality to graphical Perforce client programs; it is unlikely that you'll need to use this more complex form.

-b branchname -r [toFiles...]

Reverse the mappings in the branch view, integrating from the target files to the source files.

-d

The -d flag enables integrations around deleted revisions. Using -d implies -Dt, -Ds, and -Di.

If the target file has been deleted and the source file has changed, (or the source file has changed and subsequently been deleted), using -d re-branches the changes from the source file on top of the target file.

If the source file has been deleted and the target file has changed, using -d deletes the target file.

If the source file has been deleted and re-added, using -d integrates all outstanding revisions of the file, including those revisions prior to the file's deletion.

If you do not use the -d flag, outstanding edits cannot be mixed with a deleted file.

-Dt -Ds -Di	The -Dt flag allows integration around a deleted target file; if the target file is deleted, it is restored with the branched source file.
	The -Ds flag allows integration around a deleted source file; if the source file has been deleted, any modified target file is also deleted.
	The -Di flag ignores the fact that a source file was deleted and re-added when searching for an integration base.
-f	Force the integration on all revisions of <i>fromFile</i> and <i>toFile</i> , even if some revisions have been integrated in the past. Best used with a revision range.
-h	Don't automatically sync target files to the head revision before integrating. Use the have revision instead.
-i	Perform the integration even if toFile and fromFile share no common ancestor, using the first revision as the base.
- I	Equivalent to -i, the -I flag exists for compatibility purposes.
-0	The -o flag outputs the base file name and revision to be used in subsequent resolves, if a resolve is needed.
-t	Propagate the source file's filetype to the target file.
	(Newly-branched files always use the source file's filetype, but without -t, the target file retains its previous filetype.)

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	open

- FromFiles are often called *source files*, and *toFiles* are often called *target files*.
- Any toFiles that p4 integrate needs to operate on must be included in the p4 client workspace view.
- By default, files that have been opened for branch or integrate with p4 integrate are read-only in the client workspace. You can edit these files before submitting them using p4 edit to reopen the file for edit.
- p4 integrate can be abbreviated as p4 integ. (This abbreviation is used the examples below).

• Whenever a toFile is integrated from a fromFile, Perforce creates an integration record in its database that describes the effect of the integration. The integration record includes the names of the fromFile, and toFile, the revisions of fromFile that were integrated into toFile, the new revision number for toFile, and the action that was taken at the time of the integration. See p4 integrated for a full description of integration actions.

## **Examples**

p4 int	eg //depot/dev/	//depot/rel2/	Branch or merge all files in //depot/dev/ to the corresponding files in //depot/rel2/
			If there is no corresponding file in //depot/rel2/, this creates it.
p4 int	eg -b rel2br		Branch or merge all fromFiles contained in the branch view rel2br into the corresponding toFiles as mapped through the branch view.
p4 int	eg -b rel2br //dep	oot/rel2/headers/	Branch or merge those fromFiles contained in the branch view rel2br that map to the toFiles //depot/rel2/headers/
p4 int	eg -b rel2br -r //	depot/rel2/README	Branch or merge fromFile //depot/rel2/README from its toFile as mapped through the branch view rel2br.

To create or edit a branch mapping	p4 branch
To view a list of existing branch mappings	p4 branches
To view a list of integrations that have already been	p4 integrated
performed and submitted	

To propagate changes from one file to another after opening files with p4 integrate	p4 resolve
To view a history of all integrations performed on a particular file	p4 filelog

## p4 integrated

## **Synopsis**

Show integrations that have been submitted.

#### **Syntax**

```
p4 [g-opts] integrated [ -r ] [ -b branch ] file...
```

## **Description**

The p4 integrated command shows the integration history of the selected files, in the format:

 $\label{lem:file} \textit{file} \texttt{\#revision-range-integrate-action partner-file} \texttt{\#revision-range-where}$  where

- file is the file argument provided to p4 integrated;
- partner-file is the file it was integrated from or into; and
- *integrate-action* describes what the user did during the p4 resolve process, and is one of the following:

Integrate Action	What the User Did During the p4 Resolve Process
branch from	file did not previously exist; it was created as a copy of partner-file.
branch into	partner-file did not previously exist; it was created as a copy of file.
merge from	file was integrated from partner-file, accepting merge.
merge into	file was integrated into partner-file, accepting merge.
copy from	file was integrated from partner-file, accepting theirs.
copy into	file was integrated into partner-file, accepting theirs.
ignored	file was integrated from partner-file, accepting yours.
ignored by	file was integrated into partner-file, accepting yours.
delete from	file was integrated from partner-file, and partner-file had been previously deleted.
delete into	file was integrated into partner-file, and file had been previously deleted.

Integrate Action	What the User Did During the p4 Resolve Process
edit from	file was integrated from partner-file, and file was edited within the p4 resolve process. This allows you to determine whether the change should ever be integrated back; automated changes (merge from) needn't be, but original user edits (edit from) performed during the resolve should be (Perforce 2001.1 and later).
edit into	file was integrated into partner-file, and partner-file was reopened for edit before submission (Perforce 99.2 and later).
add into	file was integrated into previously nonexistent partner-file, and partner-file was reopened for add before submission (Perforce 99.2 and later).

If a file toFile was ever integrated from a file fromFile, and both toFile and fromFile match the p4 integrated filepattern argument, each integrated action is listed twice in the p4 integrated output: once in its from form, and once in its into form, as described above.

If the optional -b branch flag is used, only files integrated from the source to target files in the branch view are shown.

If the optional -r flag is provided, the mappings in the branch view are reversed. This flag requires the use of the -b branch flag.

## **Options**

g-opts	See the Global Options section.	
--------	---------------------------------	--

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	list

To see a list of integrations that have not yet been resolved	p4 resolve -n
To view a list of integrations that have been resolved but not yet submitted	p4 resolved
To perform an integration	p4 integrate
To view the actions taken for all revisions of a particular file (including all the files from which that particular file was integrated)	p4 filelog [-i] file

## p4 job

#### **Synopsis**

Create or edit a defect, enhancement request, or other job specification.

#### **Syntax**

```
p4 [g-opts] job [ -f ] [ jobName ]
p4 [g-opts] job -d jobName
p4 [g-opts] job -o [ jobName ]
p4 [g-opts] job -i [ -f ]
```

#### **Description**

A *job* is a written-language description of work that needs to be performed on files in the depot. It might be a description of a bug (for instance, "the scroll mechanism isn't working correctly") or an enhancement request (for instance, "please add a flag that forces a certain operation to occur") or anything else requiring a change to some files under Perforce control.

Jobs are similar to changelist descriptions in that they both describe changes to the system as arbitrary text, but whereas changelist descriptions describe completed work, jobs tell developers what work needs to be done.

Jobs are created and edited in forms displayed by p4 job. The user enters the textual description of the job into the form, along with information such as the severity of the bug, the developer to whom the bug is assigned, and so on. Since the Perforce superuser can change the fields in the job form with p4 jobspec, the fields that make up a job may vary from one Perforce server to another.

When p4 job is called with no arguments, a new job named jobNNNNNN is created, where NNNNNN is a sequential six-digit number. You can change the job's name within the form before quitting the editor. If p4 job is called with a jobname argument, a job of that name is created; if that job already exists, it is edited.

Once a job has been created, you can link the job to the changelist(s) that fix the job with p4 fix, p4 change, or p4 submit. When a job is linked to a changelist, under most circumstances the job's status is set to closed. (See the *Usage Notes* below for more information).

#### **Form Fields**

These are the fields as found in the default job form. Since the fields that describe a job can be changed by the Perforce superuser, the form you see at your site may be very different.

Field Name	Туре	Description	
Job:	Writable	The job's name. For a new job, this is new. When the form is closed, this is replaced with the name <code>jobnnnnn</code> , where <code>nnnnnn</code> is the next six-digit number in the job numbering sequence.	
		Alternately, you can name the job anything at all by replacing the text in this field.	
Status:	Writable Value	The value of this field must be open, closed, or suspended. When the job is linked to a changelist, the value of this field is set to closed when the changelist is submitted.	
User:	Writable	The name of the user who created the job.	
Date:	Writable	The date the job was created.	
Description:	Writable	An arbitrary text description of the job.	

# **Options**

-d jobname	Delete job jobname, but only if it has no associated pending or submitted fixes.
-f	Force flag. Allows Perforce administrators to edit read-only fields.
-i	Read the job form from standard input without invoking an editor.
-0	Write the job form to standard output without invoking an editor.
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required	
N/A	N/A	open	

• If the Perforce superuser has eliminated field ID# 102 (the Status: field) with p4 jobspec, Perforce is unable to close jobs when the changelists to which they are linked are submitted. Please see the p4 jobspec page and the *Perforce System Administrator's Guide* for more information.

• After a job has been created or changed, Perforce indexes the job so that p4 jobs -e can locate the job quickly. The index keys are word, fieldname where word is a case-insensitive alphanumeric word. Values in date fields are stored as the number of seconds since January 1, 1970, 00:00:00.

## **Examples**

p4 job	Create a new job; by default, its name is of the form <code>jobNNNNNN</code> .
p4 job job000135	Edit job job000135.

To list all jobs, or a subset of jobs	p4 jobs
To attach a job to an existing changelist	p4 fix
To view a list of connections between jobs and changelists	p4 fixes
To add or delete a job from a pending changelist	p4 change
To change the format of jobs at your site (superuser only)	p4 jobspec
To read information about the format of jobs at your site	p4 jobspec -o

## p4 jobs

#### **Synopsis**

List jobs known to the Perforce server.

#### **Syntax**

```
p4 [g-opts] jobs [-e\ jobview] [-i] [-l] [-m\ max] [file[rev]\ \dots] p4 jobs -R
```

## **Description**

When called without any arguments, p4 jobs lists all jobs stored on the server. You can limit the output of the command by specifying various criteria with flags and arguments. If you specify a file pattern, the jobs listed will be limited to those linked to changelists affecting particular files. The -e flag can be used to further limit the listed jobs to jobs containing certain words.

Jobs are listed in alphanumeric order (or, if you use the -r flag, in reverse alphanumeric order) by name, one job per line. The format of each line is:

```
jobname on date by user *status* description
```

The description is limited to the first 31 characters, unless the -1 (long) flag is used.

If any of the date, user, status, or description fields have been removed by the Perforce superuser with p4 jobspec, the corresponding value will be missing from each job's output.

To limit the list of jobs to those that have been fixed by changelists that affected particular files, use p4 <code>jobs filespec</code>. The files or file patterns provided can contain revision specifiers or a revision range.

#### **Options**

-e jobview	List only those jobs that match the criteria specified by <code>jobview</code> . Please see the <code>Usage Notes</code> below for a discussion of job views.
-i files	Include jobs fixed by changelists that affect files integrated into the named files.
-1	Output the full description of each job.
-m max	Include only the first $max$ jobs, sorted alphanumerically. If used with the $-r$ flag, the last $max$ jobs are included.
-r	Display jobs in reverse alphabetical order by job name.

-R	Rebuild the job table and reindex each job.
	Reindexing the table is necessary either when upgrading from version 98.2 or earlier, or when upgrading from 99.1 to 2001.1 or higher and you wish to search your body of existing jobs for strings containing punctuation.
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	list

#### **Job Views**

Use p4 jobs -e jobview to limit the list of jobs to those that contain particular words. You can specify that the search terms be matched only in particular fields, or anywhere in the text of the job. You can use jobviews to match jobs by values in date fields, though there are fewer options for dates than there are for text. Job fields of type bulk are not indexed for searching.

Text matching is case-insensitive. All alphanumeric strings (including words including embedded punctuation) separated by whitespace are indexed as words.

The jobview `word1 word2 ... wordN' can be used to find jobs that contain all of word1 through wordN in any of the job's fields.

Spaces between search terms in jobviews act as boolean AND operations. To find jobs that contain any of the terms (boolean OR), separate the terms with the "|" character.

Ampersands (&) can be used as boolean ANDs as well; the boolean operators bind in the order &, |, space (highest precedence to lowest precedence). Use parentheses to change the grouping order.

Search results can be narrowed by matching values within specific fields with the jobview syntax "fieldname=value". The value must be a single token, including both alphanumeric characters and punctuation.

The wildcard "\*" allows for partial word matches. The jobview "fieldname=string\*" matches "string", "stringy", "stringlike", and so on.

Date fields can be matched by expressing the jobview date as yyyy/mm/dd or yyyy/mm/dd:hh:mm:ss. If a specific time is not provided, the equality operator (=) matches the entire day.

The usual comparison operators (=, >, <, >=, and <=) are available.

Additionally, you can use the NOT operator (^) to negate the sense of some comparisons. (See *Limitations* below for details).

To search for words containing characters that are job search expression operators, escape the characters with a backslash ( $\setminus$ ) character.

The behavior of these operators depends on the type of job field you're comparing against:

Field Type	Use of Comparison Operators in Jobviews	
word	The equality operator (=) must match the value in the word field exactly.	
	The relational operators perform comparisons in ASCII order.	
The equality operator (=) matches the job if the word given as the is found anywhere in the specified field.		
	The relational operators are of limited use here, since they match the job if <i>any</i> word in the specified field matches the provided value.	
	For example, if a job has a text field ShortDescription that contains only the phrase gui bug, and the jobview is "ShortDesc <filter", because="" bug<filter.<="" job="" jobview,="" matches="" td="" the=""></filter",>	
line	As for field type text, above.	
select	The equality operator (=) matches a job if the value of the named field is the specified word. The relational operators perform comparisons in ASCII order.	
date	Dates are matched chronologically. If a specific time is not provided, the operators =, <=, and >= match the entire day.	

If you're not sure of a field's type, run p4 jobspec -o, which outputs the job specification used at your site. The p4 jobspec field called Fields: contains the job fields' names and datatypes. See p4 jobspec for a discussion of the different field types.

#### Other Usage Notes

- The p4 user form has a JobView: field that allows a jobview to be linked to a particular user. After a user enters a jobview into this field, any changelists he creates automatically list jobs that match the jobview in this field. The jobs that are fixed by the changelist can be left in the form, and the jobs that aren't should be deleted.
- p4 jobs sorts its output alphanumerically by job name, which also happens to be the chronological order in which the jobs were entered. If you use job names other than the standard Perforce names, this ordering may not help much.

- The -m max -r construct displays the last max jobs in alphanumeric order, not the max most recent jobs, but if you're using Perforce's default job naming scheme (jobs numbered like job001394), alphanumeric job order is identical to order by entry date.
- You can use the \* wildcard to determine if a text field contains a value or not by checking for the jobview "field=\*"; any non-null value for field matches.
- When querying for jobs using the -e <code>jobview</code> option, be aware of your operating system and command shell's behavior for parsing, quoting, and escaping special characters, particularly when using wildcards, logical operators, and parentheses.

#### Limitations

- Jobviews cannot be used to search for jobs containing null-valued fields. In other words, if a field has been deleted from an existing job, then the field is not indexed, and there is no jobview that matches this "deleted field" value.
- The jobview NOT operator (^) can be used only after an AND within the jobview. Thus, the jobviews "gui ^name=joe" and "gui&^name=joe" are valid, while the jobviews "gui |^name=joe" and "^name=joe" are not.
- The \* wildcard is a useful way of getting around both of these limitations.

For instance, to obtain all jobs without the string "unwanted", query for 'job=\* ^unwanted". All jobs will be selected by the first portion of the jobview and logically ANDed with all jobs NOT containing the string "unwanted".

Likewise, because the jobview "field=\*" matches any non-null value for field, (and the job field can be assumed not to be null), you can search for jobs with null-valued fields with "job=\* ^field=\*"

• You cannot currently search on space-delimited fields with conditionals. For example, instead of using p4 jobs -e "field=word1 word2", you must use p4 jobs -e "field=word1 field=word2".

p4 jobs //depot/proj/file#1	List all jobs attached to changelists that include revisions of //depot/proj/file.
p4 jobs -i //depot/proj/file	List all jobs attached to changelists that include revisions of //depot/proj/file or revisions of files that were integrated into //depot/proj/file
p4 jobs -e gui	List all jobs that contain the word gui in any field.

List all jobs that contain the word gui in any field and the word joe in the Submitted-By: field.  P4 jobs -e "gui ^Submitted-By=joe"  List all jobs that contain the word gui in any field and any value other than joe in the Submitted-By: field.  P4 jobs -e "window*"  List all jobs containing the word "window", "window.c", "Windows", in any field. The quotation marks are used to prevent the local shell from expanding the "*" on the command line.  P4 jobs -e "job=* ^unwanted"  List all jobs referring to window.c in any field.  P4 jobs -e "job=* ^unwanted"  List all jobs not containing the word unwanted in any field.  List all jobs that contain the word fast or quick in any field, and have a date: field pointing to a date on or after 3/14/98.  P4 jobs -e "fast   quick" //depot/proj/  List all jobs that have the word fast or quick in any field, and that are linked to changelists that affected files under //depot/proj.		
any field and any value other than joe in the Submitted-By: field.  p4 jobs -e "window*"  List all jobs containing the word "window", "window.c", "Windows", in any field. The quotation marks are used to prevent the local shell from expanding the "*" on the command line.  p4 jobs -e window.c  List all jobs referring to window.c in any field.  p4 jobs -e "job=* ^unwanted"  List all jobs not containing the word unwanted in any field.  p4 jobs -e  "(fast quick)&date>1998/03/14"  List all jobs that contain the word fast or quick in any field, and have a date: field pointing to a date on or after 3/14/98.  p4 jobs -e  "fast quick" //depot/proj/  List all jobs that have the word fast or quick in any field, and that are linked to changelists that affected files under	p4 jobs -e "gui Submitted-By=joe"	any field and the word joe in the
"window.c", "Windows", in any field. The quotation marks are used to prevent the local shell from expanding the "*" on the command line.  p4 jobs -e window.c  p4 jobs -e "job=* ^unwanted"  List all jobs not containing the word unwanted in any field.  p4 jobs -e  "(fast quick)&date>1998/03/14"  p4 jobs -e  "fast quick in any field, and have a date: field pointing to a date on or after 3/14/98.  p4 jobs -e  "fast quick" //depot/proj/  List all jobs that have the word fast or quick in any field, and that are linked to changelists that affected files under	p4 jobs -e "gui ^Submitted-By=joe"	any field and any value other than joe in
field.  p4 jobs -e "job=* ^unwanted"  List all jobs not containing the word unwanted in any field.  p4 jobs -e  "(fast quick) &date>1998/03/14"  p4 jobs -e  "fast quick" //depot/proj/  p4 jobs -e  "fast quick" //depot/proj/  p4 jobs -e  "fast quick" //depot/proj/	p4 jobs -e "window*"	"window.c", "Windows", in any field. The quotation marks are used to prevent the local shell from expanding the "*" on the
unwanted in any field.  p4 jobs -e  "(fast quick) &date>1998/03/14"  List all jobs that contain the word fast or quick in any field, and have a date: field pointing to a date on or after 3/14/98.  p4 jobs -e  "fast quick" //depot/proj/  List all jobs that have the word fast or quick in any field, and that are linked to changelists that affected files under	p4 jobs -e window.c	,
"(fast quick) &date>1998/03/14" quick in any field, and have a date: field pointing to a date on or after 3/14/98.  p4 jobs -e "fast quick" //depot/proj/  List all jobs that have the word fast or quick in any field, and that are linked to changelists that affected files under	p4 jobs -e "job=* ^unwanted"	, o
"fast quick" //depot/proj/ quick in any field, and that are linked to changelists that affected files under		quick in any field, and have a date: field
		quick in any field, and that are linked to changelists that affected files under

To create or edit an existing job	p4	job
To attach a job to a particular changelist, indicating that the job is fixed by that changelist	p4	fix
To list all jobs and changelists that have been linked together	p4	fixes
To view all the information about a particular changelist, including the jobs linked to the changelist	p4	describe
To change the format of the jobs used on your server (superuser only)	p4	jobspec
To read information about the format of jobs used on your site (any user)	p4	jobspec -o
To set a default jobview that includes jobs matching the jobview in all new changelists	p4	user

## p4 jobspec

## **Synopsis**

Edit the jobs template.

#### **Syntax**

```
p4 [g-opts] jobspec
p4 [g-opts] jobspec [-i]
p4 [g-opts] jobspec -o
```

## **Description**

The p4 jobspec command presents the Perforce administrator with a form in which job fields can be edited, created, deleted, and refined.

Do not confuse the names of the fields in the p4 jobspec form with the names of the fields within a job. The fields in the p4 jobspec form are used to store information *about* the fields in the p4 jobs form.

#### **Form Fields**

Field Name	Description
Fields:	A list of field definitions for your site's jobs, one field per line. Each line is of the form code name datatype length persistence.
	• code: a unique integer that identifies the field internally to Perforce. The code must be between 106 and 199. Codes 101 to 105 are reserved for Perforce use; see the <i>Usage Notes</i> below for more details.
	• name: the name of the field. This can be changed at any time, while the code should not change once jobs have been created.
	Field names must not contain spaces.
	<ul> <li>datatype: the datatype of the field. Possible values are:</li> </ul>
	<ul> <li>word: a single arbitrary word (a string with no spaces)</li> </ul>
	• date: a date/time field
	<ul> <li>select: one of a fixed set of words</li> </ul>
	• line: one line of text
	• text: a block of text, starting on the line underneath the fieldname.
	• bulk: like text, but not indexed for searching with p4 jobs -e.

Field Name	Description
Fields: (cont'd)	• length: recommended length for display boxes in GUI clients accessing this field. Use a value of 0 to let a Perforce client program choose its own value.
	• persistence: does the field have a default value? Is it required? Is it read-only? Possible values are:
	<ul> <li>optional: field can take any value or be erased.</li> </ul>
	• default: a default value is provided; it can be changed or erased.
	<ul> <li>required: a default value is provided; it can be changed but the user must enter a value.</li> </ul>
	<ul> <li>once: read-only; the field value is set once to a default value and is never changed.</li> </ul>
	• always: read-only; the field's value is set to a new default when the job is edited. This is useful only with the \$now and \$user variables; it allows you to change the date a job was modified and the name of the modifying user.
Values:	Contains a lists of fields and valid values for select fields.
	Enter one line for each field of datatype select. Each line must contain the fieldname, a space, and the list of acceptable values separated by slashes. For example:
	JobType bug/request/problem.
Presets:	Contains a list of fields and their default values for each field that has a persistence of default, required, once, or always.
	Each line must contain the field name and the default value, separated by a space. For example:
	JobType bug
	Any one-line string can be used, or one of three built-in variables:
	• \$user: the user who created the job
	• \$now: the current date
	• \$blank: the phrase <enter description="" here=""></enter>
	When users enter jobs, any fields in your jobspec with a preset of \$blank must be filled in by the user before the job is added to the system.
	See the <i>Usage Notes</i> below for special considerations for field 102.

Field Name	Description
Comments:	Textual comments that appear at the top of each p4 job form. Each line must begin with the comment character #.
	See the <i>Usage Notes</i> below for special considerations for these comments if your users need to enter jobs through P4V, the Perforce Visual Client.

#### **Options**

-0	Write the jobspec form to standard output.
-i	Read the jobspec form from standard input.
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	admin, or list to use the -o flag

• Do not attempt to change, rename, or redefine fields 101 through 105. These fields are used by Perforce and should not be deleted or changed. Only use p4 jobspec to add new fields (106 and above) to your jobs.

Field 101 is required by Perforce and cannot be renamed nor deleted.

Fields 102 through 105 are reserved for use by Perforce client programs. Although it is possible to rename or delete these fields, it is highly undesirable to do so. Perforce client programs may continue to set the value of field 102 (the Status: field) to closed (or some other value defined in the Presets: for field 102) upon changelist submission, even if the administrator has redefined field 102 to for use as a field that does not contain closed as a permissible value, leading to unpredictable and confusing results.

• The information in the Comments: fields is the only information available to your users to tell them how to fill in the job form, and is also used by P4V, the Perforce Visual Client, to display tooltips. Please make your comments complete and understandable.

- The Presets: entry for the job status field (field 102) has a special syntax for providing a default fix status for p4 fix, p4 change -s, and p4 submit -s.
  - By default, a job's status is set to closed after you use p4 fix, p4 change, or p4 submit. To change the default fix status from closed to some other <code>fixStatus</code> (assuming that you have defined the <code>fixStatus</code> as a valid <code>select</code> setting in the <code>Values</code>: field), use the special syntax of <code>jobStatus</code>, <code>fix/fixStatus</code> in the <code>Presets</code>: field for field 102 (job status). To change the behavior of p4 <code>fix</code>, p4 <code>change</code>, and p4 <code>submit</code> to leave job status unchanged, use the special <code>fixStatus</code> of <code>same</code>.
- See the jobspecs chapter of the *System Administrator's Guide* for an example of a customized jobspec.

To create, edit, or view a job	p4 job
To attach a job to a changelist	p4 fix
To list jobs	p4 jobs
To list jobs attached to specific changelists or changelists attached to specific jobs	p4 fixes

## p4 label

#### **Synopsis**

Create or edit a label specification and its view.

#### **Syntax**

```
p4 [g-opts] label [ -f -t template ] labelname
p4 [g-opts] label -o [ -t template ] labelname
p4 [g-opts] label -d [ -f ] labelname
p4 [g-opts] label -i [ -f ]
```

## **Description**

Use p4 label to create a new label specification or edit an existing label specification. A labelname is required.

Running p4 label allows you to configure the mapping that controls the set of files that are allowed to be included in the label. After configuring the label, use p4 labelsync or p4 tag to tag files with the label.

Labels can be either automatic or static. Automatic labels refer to the revisions provided in the View: and Revision: fields. Static labels refer only to those specific revisions tagged by the label by means of either the p4 labelsync or p4 tag commands.

Only the Owner: of an unlocked label can use p4 labelsync or p4 tag to tag files with that label.

#### Form Fields

Field Name	Туре	Description
Label:	Read-only	The label name as provided in the invoking command.
Owner:	Writable, optional	The label's owner. By default, the user who created the label. Only the owner of a label can update which files are tagged with the label.
Update:	Read-only	The date the label specification was last modified.
Access:	Read-only	The date and time the label was last accessed, either by running p4 labelsync on the label, or by otherwise referring to a file with the label revision specifier @label.
Description:	Writable, optional	An optional description of the label's purpose.

Field Name	Туре	Description
Options:	Writable	locked or unlocked. If the label is locked, the list of files tagged with the label cannot be changed with p4 labelsync.
Revision:	Writable	An optional revision specification for an automatic label.
		If you use the # character to specify a revision number, you must use quotes around it in order to ensure that the # is parsed as a revision specifier, and not as a comment field in the form.
View:	Writable	A list of depot files that can be tagged with this label. No files are actually tagged until p4 labelsync is invoked.
		Unlike client views or branch views, which map one set of files to another, label views consist of a simple list of depot files. Please see the <i>Views</i> chapter for more information.

# Options

-d [-f]	Delete the named label if it's unlocked. The -f flag forces the deletion even if the label is locked. (Deleting a locked label requires admin or super access.)
-i	Read the label definition from standard input without invoking the editor.
-0	Write the label definition to standard output without invoking the editor.
-f	Allow the Update: field's date to be set. Can be used with either the -i flag or the -t flag for the same purpose.
-t template	Copy label template's view and options into the View: and Options: fields of this label.
g-opts	See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	open

To tag revisions in your client workspace with a label	p4	labelsync
To list all labels known to the system	p4	labels
To create a label and tag files with the label	p4	tag

## p4 labels

#### Synopsis

Display list of defined labels.

#### **Syntax**

```
p4 [g-opts] labels [-t] [-u user] [-e namefilter -m max] [file[revrange]]
```

## **Description**

p4 labels lists all the labels known to the Perforce server in the form:

Label labelname date description

Use the -t option to display the time of the last update to the label.

Label labelname date time description

To see a list of static labels that tag specific files, specify a file pattern, with an optional revision range. (Because automatic labels refer to all files in the label view at a specified revision range, automatic labels are not shown when you use p4 labels with a file pattern.)

Use the -m max option to limit the output to the first max labels.

Use the -e namefilter option to limit the output to labels whose name matches the namefilter pattern.

Use the -u *user* option to limit the output to labels owned by the named user.

## **Options**

-t	Display the time as well as the date of the last update to the label.
-u user	List only labels owned by user.
-e namefilter	List only labels matching namefilter.
-m max	List only the first max labels.
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	list

• To see a list of files tagged by a particular label, use p4 files @labelname.

# **Examples**

To list all labels in the system	p4 labels
To list all labels that contain any revision of file.c	p4 labels file.c
To list only labels containing revisions #3 through #5 of	p4 labels file.c#3,5
file.c	

To create a label and tag files with the label	p4 tag
To create or edit a label specification	p4 label
To add, delete, or change the files included in a label	p4 labelsync
To view a list of files included in a label	p4 files @labelname

## p4 labelsync

#### **Synopsis**

Synchronize a label with the contents of the current client workspace.

#### Syntax 5 4 1

```
p4 [g-opts] labelsync [-a -d -n] -l labelname [file[revRange]...]
```

## **Description**

p4 labelsync causes the named label to reflect the current contents of the client workspace by tagging the last revision of each file synced into the workspace with the label name. The label name can subsequently be used in a revision specification as @label to refer to the revision of the file that was tagged with the label.

Without a file argument, p4 labelsync causes the label to reflect the contents of the client workspace by adding, deleting, and updating the set of files tagged with the label.

If a file is given, p4 labelsync updates the tag for only that named file. If the file argument includes a revision specification, the client workspace view is ignored; the specified revision is used instead of the revision existing in the workspace. If the file argument includes a revision range, then only the highest revision in that range is used.

Only the Owner: of an unlocked label can use p4 labelsync to tag files with that label.

A label that has its Options: field set to locked cannot be updated with p4 labelsync.

#### **Options**

-a	Add the label to files that match the file pattern arguments; no files are deleted from the label.
-d	Delete the label tag from the named files.
-1 labelname	Specify the label to be applied to file revisions
-n	Display what p4 labelsync would do without actually performing the operation.
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	list

• By default, p4 labelsync operates on the revisions of files last synced to your client workspace. To tag the head revisions of files (or the highest revision in a specified range), use p4 tag.

To create or edit a label	p4 label
To list all labels known to the system	p4 labels
To create a label and tag files with the label	p4 tag

## p4 license

#### **Synopsis**

Update or display the license file.

#### **Syntax**

```
p4 [g-opts] license [ -o ]
p4 [g-opts] license [ -i ]
```

## **Description**

The p4 license command allows Perforce superusers to update or display the Perforce license file. This command requires that there is already a valid license file in the Perforce server root directory.

Use p4 license to add licensed users to a Perforce server without having to shut down the server and manually copy the license file into the server root.

Most new license files obtained from Perforce can be installed with p4 license, (or by copying over the existing license file) except for when the server IP address or port has changed. If either the server IP address or port number has changed, you must stop the Perforce Server, manually copy the license file into place, and restart the Server.

## **Options**

-0	Display the current license file on the standard output.
-i	Read in a new license file from the standard input.
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	super

p4 license -o	Display the current license file on the standard output.
p4 license -i	Read in a new license file from the standard input.

## p4 lock

#### **Synopsis**

Lock an opened file against changelist submission.

#### **Syntax**

```
p4 [g-opts] lock [-c changelist#] [file ...]
```

## Description

Locking files prevents all other users from submitting changes to those files. If the files are already locked by another user, p4 lock fails. When the user who locked a particular file submits the file, the lock is released.

This command is normally called with a specific file argument; if no file argument is provided, all open files in the default changelist are locked. If the -c changelist# flag is used, all open files matching the given file pattern in changelist changelist# are locked.

## **Options**

-c changelist#	Lock only files included in changelist changelist#
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	write

To unlock locked files	p4 unlock
To display all your open, locked files (UNIX)	p4 opened   grep "*locked*"

# p4 lockstat

#### **Synopsis**

Report lock status of database tables.

## **Syntax**

p4 [g-opts] lockstat

# **Description**

The p4 admin lockstat command reports any database tables that are currently locked for a read or write operation.

## **Options**

g-opts See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	super

## p4 logger

#### **Synopsis**

Report changed jobs and changelists.

#### **Syntax**

```
p4 [g-opts] logger [-c sequence#] [-t countername]
```

#### **Description**

The p4 logger command is meant for use in external programs that call Perforce.

The Perforce Defect Tracking Integration (P4DTI) uses p4 logger.

## **Options**

-c sequence#	List all events happening after this sequence number.
-t countername	List all events after this counter number.
-c sequence# -t countername	Update the supplied counter with the current sequence number and clear the log; as this clears the log regardless of which counter name is specified, only one user can make use of this option.
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	review

• The p4 logger command is not intended for use by end users. It exists to support propagation of information to an external defect tracking system.

To list users who have subscribed to review particular files	p4 reviews
To set or read the value of a Perforce counter	p4 counter
To see full information about a particular changelist	p4 describe
To see a list of all changelists, limited by particular criteria	p4 changes

## p4 login

#### **Synopsis**

Log in to a Perforce server by obtaining a ticket.

#### **Syntax**

```
p4 [g-opts] login [ -a -p ] [ user ] p4 [g-opts] login [ -s ]
```

## **Description**

The p4 login command authenticates a user and creates a ticket that represents a session with a Perforce server. Once authenticated, a user can access the Perforce server until either the ticket expires or until the user issues the p4 logout command.

By default, tickets are valid for 12 hours.

To obtain a ticket valid for all IP addresses (for instance, to use Perforce simultaneously on more than one machine), use p4 login -a. Users with tickets that are valid for all IP addresses still consume only one Perforce license.

## **Options**

-a	Obtain a ticket that is valid for all IP addresses.
-p	Display the ticket, rather than storing it in the local ticket file.
-s	Display the status of the current ticket, if one exists.
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	list

- The default timeout value of 43200 seconds (12 hours) is defined on a per-group basis in the p4 group form.
- To create tickets that do not expire, set the timeout value to unlimited in the p4 group form.
- To extend a ticket's lifespan, use p4 login while already logged in. Your ticket's lifespan is extended by 1/3 of its initial timeout setting, subject to a maximum of your ticket's initial timeout setting.

- Perforce superusers can obtain login tickets for users other than themselves without entering passwords. Non-superusers who attempt to log in as other users must use the p4 -u username login form of the command, and correctly supply the other user's password.
- Tickets are stored in the file specified by the P4TICKETS environment variable. If this variable is not set, tickets are stored in %USERPROFILE%\p4tickets.txt on Windows, and in \$HOME/.p4tickets on other operating systems.

#### **Examples**

p4 login	Prompt the user for a password; if the password is entered correctly, issue a ticket valid on the user's machine.
p4 -u builder login -a	Attempt to log in as user builder; if the password is entered correctly, issue a ticket valid on all machines.

To end a login session	p4 logout
To display tickets	p4 tickets

## p4 logout

## **Synopsis**

Log out of a Perforce server by removing or invalidating a ticket.

#### **Syntax**

```
p4 [g-opts] logout [ -a ]
```

## **Description**

Log a user out of Perforce by removing a ticket on the user's workstation, or by invalidating the ticket on the server.

If you use p4 logout -a, the ticket remains in the ticket file, but is invalidated on the server: all users of the ticket are logged out simultaneously.

# **Options**

-a	Log out all users of the ticket by invalidating the ticket on the
	server.
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	list

• Tickets are stored in the file specified by the P4TICKETS environment variable. If this variable is not set, tickets are stored in %USERPROFILE%\p4tickets.txt on Windows, and in \$HOME/.p4tickets on other operating systems.

p4 logout	Log out of Perforce by removing the local session ticket.
p4 logout -a	Log out of Perforce by removing the local session ticket and instructing the Perforce server to invalidate the ticket on all other workstations from which they were logged in.

To start a login session (to obtain a ticket)	p4 login	
To display tickets	p4 tickets	

# p4 logstat

#### **Synopsis**

Report size of journal, error log, and/or audit log files.

# **Syntax**

p4 [g-opts] logstat

## **Description**

The p4 admin logstat command reports the sizes of the journal, error log (if it exists), and audit log (if it exists).

## **Options**

g-opts

See the *Global Options* section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	super

## p4 logtail

#### **Synopsis**

Display the last block(s) of the error log.

#### **Syntax**

```
p4 [g-opts] logtail [ -b blocksize ] [ -s start offset ] [ -m maxBlocks ]
```

## **Description**

The p4 logtail command displays the last block(s) of the error log, and the offset for the next block, when available.

Output consists of a series of lines in tagged format. The first line is "... file LOG", followed by multiple blocks of log data. By default, all blocks from the <code>start\_offset</code> are output until the end of the file. The data is returned in blocks of size <code>blocksize</code>, each of which is tagged with "... data". The last line is "... offset <code>next\_offset</code>", where <code>next\_offset</code> is the offset in the logfile from which the next block of data is to be retrieved.

## **Options**

-s start	The offset (from the beginning of the file), in bytes.
-b blocksize	The block size, in bytes. The default is 8192 bytes.
-m maxBlocks	The maximum number of blocks to output.
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	super

• For more about administering Perforce, see the Perforce System Administrator's Guide.

p4 logtail -b 1024 -m 2	Display the last two kilobytes of the log file, as two
	separate blocks of 1024 bytes each.

## p4 monitor

#### **Synopsis**

Display Perforce process information

## **Syntax**

```
p4 [g-opts] monitor show [ -a ] [ -e ] [ -l ] p4 [g-opts] monitor terminate id p4 [g-opts] monitor clear id p4 [g-opts] monitor clear all
```

## Description

p4 monitor allows a system administrator to observe what Perforce-related processes are running on the Perforce server machine. Each line of output consists of the following fields:

```
pid status owner hh:mm:ss command [args]
```

where pid is the process ID under UNIX (or thread ID under Windows), status is R or T depending on whether the process is running or marked for termination, owner is the Perforce user name of the user who invoked the command, hh:mm:ss is the time elapsed since the command was called, and command and args are the command and arguments as received by the Perforce server.

To list current process information, use p4 monitor show. All processes are listed, but only the command (for example, sync, edit, submit) is shown, without arguments. This form of p4 monitor requires list level access.

To show the list of arguments associated with each command, use the -a (arguments) flag or -1 (long) flag. For additional information from the user environment, use the -e (environment) flag. These options require admin level access.

To mark a process for termination, use p4 monitor terminate *id*. This command requires super level access.

To remove an entry from the monitor table, use p4 monitor clear *id*. You can clear the entire table with p4 monitor clear all. Both of these commands require super level access.

In order for p4 monitor to work, you must enable monitoring on the Perforce Server by setting the monitor counter with p4 counter, and restarting the server. You can control server process monitoring by setting the monitor counter to 0 (disable monitoring), 1 (enable monitoring of active processes), or 2 (enable monitoring of both active and idle processes). You must stop and restart the Perforce server for any change in this counter to take effect.

#### **Options**

g-opts	See the Global Options section.
-a	Show all arguments associated with the process (for example, edit file.c, or sync -f //depot/src/).
	Perforce user names are truncated to 10 characters, and each line is limited to a total of 80 characters of output.
-e	Show environment information including Perforce client application (if known), host IP address, and client workspace name.
-1	Show all arguments in long form; that is, without truncating user names or the list of command line arguments.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	list, super

- Processes marked as running continue to run to completion even if removed from the monitor table with p4 monitor clear.
- If a command terminates prematurely on the server side, it may be erroneously listed as running. Superusers can clear such processes with p4 monitor clear.
- The p4 monitor terminate command will not mark a process for termination unless the process has already been running for at least ten seconds.
- Some commands (for instance, p4 submit) invoke multiple processes. For example, dm\_CommitSubmit or dm\_SubmitChange may appear in the output of p4 monitor as two separate phases of the p4 submit command.
- Some commands, such as p4 obliterate, cannot be terminated.
- If you have enabled idle process monitoring for your server (by setting the monitor counter to 2), idle processes appear with a *status* of R, but with a *command* of IDLE.

p4 monitor show	Show Perforce processes information (commands only). Requires list access only.
p4 monitor show -1	Show arguments and commands, without limits on line length. Requires super access.
p4 monitor show -a	Show arguments and commands, limited to 80 characters per line of output. Requires super access.

p4 monitor terminate 123	Instruct the Perforce server to mark process 123 for termination. Requires super access.
p4 monitor clear all	Clears the monitor table of all entries. Requires super access.

To turn on server monitoring (requires server restart)	p4	counter	-f	monitor	1
To turn off server monitoring (requires server restart)	p4	counter	-f	monitor	0

## p4 move

## **Synopsis**

Move (rename) a file from one location to another.

#### **Syntax**

```
p4 [g\text{-}opts] move [-c \ change] [-f] [-k] [-n] [-t \ filetype] from File to File
```

## **Description**

The p4 move command takes a file already opened for edit or add and moves it to the destination provided.

An open file can be moved many times before it is submitted; moving a file back to its original location undoes the pending move, leaving it open for edit. Using p4 revert on a moved file both undoes the move and reverts the unsubmitted content.

#### **Options**

-c change	If a changelist number is provided, the files are opened in the numbered pending changelist.
-t filetype	If a filetype is specified, the file is reopened as the new filetype.
-f	Force a move to an existing target file. The file must be synced, but not opened. The originating source file will no longer be synced to the workspace.
-k	Keep existing workspace files by bypassing the renaming in the client workspace. Use p4 move -k only in the context of reconciling work performed while disconnected from the Perforce Server.
-n	Preview the move that would be performed, without actually moving files.
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
fromFile: Yes toFile: No	No	read access for fromFile write access for toFile

- Files must be open for add or open for edit before they can be moved.
- To move and resolve a file that is open for edit but has been renamed at the head revision, you can use the -f option to force the move.

p4 move file1.c fi	le2.c	Assuming that file1.c is open for add or edit, move file1.c to file2.c.
p4 move //depot/d1	/ //depot/d2/	Moving open files from directory d1 to directory d2.

## p4 obliterate

#### **Synopsis**

Removes files and their history from the depot.

#### **Syntax**

```
p4 [g-opts] obliterate [ -y ] file[revRange] ...
```

#### Warning

The p4 delete command marks the latest revision as deleted, but leaves the file information intact in the depot. As such, recovery from the server data is always possible.

In contrast, p4 obliterate deletes the file data itself, precluding any possibility of recovery.

*Use* p4 obliterate *with caution*. This is the only command in Perforce that actually removes file data.

## **Description**

p4 obliterate can be used by Perforce administrators to permanently remove files from the depot. All information about the files is wiped out, including the files' revisions, the files' metadata, and any records in any labels or client workspace records that refer directly to those files. Once p4 obliterate completes, it appears to the server as if the affected file(s) had never existed. Copies of files in client workspaces are left untouched, but are no longer recognized as being under Perforce control.

p4 obliterate requires at least one file pattern as an argument. To actually perform the obliteration, the -y flag is required; without it, p4 obliterate merely reports what it would do without actually performing the obliteration.

If you specify a single revision (for instance, p4 obliterate file#3), only that revision of the file is obliterated. If you specify a revision range (for instance, p4 obliterate file#3,5), only the revisions in that range are obliterated.

## **Options**

-y filespec	Perform the obliterate operation. Without this flag, p4 obliterate
	merely reports what it would do.
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	admin

- p4 obliterate is the correct way to reclaim disk space from files that are no longer required, or to clean up mistakes made by users who create file hierarchies in the wrong place. Do not use operating system commands (erase, rm, and their equivalents) to remove files from the Perforce server root by hand.
- Obliterating files can alter the behavior of user commands. Syncing to an obliterated
  revision will remove the file from your client workspace, syncing to the head revision
  will either remove the file from your client workspace (if all revisions were obliterated),
  or provide you with the most recent non-obliterated revision of the file.
- Obliterating files in revision ranges can also change the behavior of scripts, as revision numbers of files may "skip" obliterated revisions. For instance, the output of p4 filelog after obliterating revisions #2 and #3 might look like this:

```
... #4 change 1276 edit on 2001/04/18 by user@dev1 (binary) 'Fixed' ... #1 change 1231 add on 2001/04/12 by user@dev1 (binary) 'First try'
```

In this case, a developer using the #4 in the first line of the output to assume the existence of four change descriptions in the output of p4 filelog would be in trouble.

p4 obliterate dir/	Do not obliterate any files; list the files that would be obliterated with the $-y$ option.
	In this case, all files in directory <code>dir</code> and below would be subject to deletion with the <code>-y</code> option.
p4 obliterate -y file	Obliterate file from the depot. All history and metadata for every revision of file are erased.
p4 obliterate -y file#3	Obliterate only the third revision of file.
	If #3 <i>was</i> the head revision, the new head revision is now #2 and the next revision will be revision #3.
	If #3 was <i>not</i> the head revision, the head revision remains unchanged.

p4 obliterate -y file#3,5 Obliterate revisions 3, 4, and 5 of file.

If #5 was the head revision, the new head revision is now #2, and the next revision will be #3.

If #5 was not the head revision, the head revision remains unchanged.

#### **Related Commands**

To mark a file deleted at its head revision but leave it in the depot. p4 delete This is the normal way of deleting files.

# p4 opened

#### **Synopsis**

List files that are open in pending changelists.

#### Syntax 5 4 1

```
p4 [g-opts] opened [-a -c change -C workspace -u user -m max] [file ...]
```

# Description

Use p4 opened to list files that are currently open via p4 add, p4 edit, p4 delete, or p4 integrate. By default, all open files in the current client workspace are listed. You can use command line arguments to list only those files in a particular pending changelist, or to show open files in all pending changelists, and to limit the number of files displayed.

If file specifications are provided as arguments to p4 opened, only those files that match the file specifications are included in the report.

The information displayed for each opened file includes the file's name, its location in the depot, the revision number that the file was last synced to, the number of the changelist under which the file was opened, the operation it is opened for (add, edit, delete, or integrate), and the type of the file. The output for each file looks like this:

```
depot-file#rev - action chnum change (type) [lock-status]
```

#### where:

- depot-file is the path in depot syntax;
- rev is the revision number;
- action is the operation the file was open for: add, edit, delete, branch, or integrate;
- chnum is the number of the submitting changelist; and
- *type* is the *type* of the file at the given revision.
- If the file is locked (see p4 lock), a warning that it is \*locked\* appears at the line's end.

#### **Options**

-a	List opened files in any client workspace.
-c change	List the files in pending changelist <i>change</i> . To list files in the default changelist, use p4 opened -c default.
-C workspace	List only files that are open in the specified client workspace.
-m max	List only the first max open files.

-u user	List only those files that were opened by user.
g-opts	See the Global Options section.

### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	list

- Perforce does not prevent users from opening already open files; its default scheme is to allow multiple users to edit the file simultaneously, and then resolve file conflicts with p4 resolve. To determine whether or not another user already has a particular file opened, use p4 opened -a file.
- Locked files appear in the output of p4 opened with an indication of \*locked\*. On UNIX, you can find all locked files you have open with the following command:
   p4 opened | grep "\*locked\*"

This lists all open files you have locked with p4 lock.

### **Examples**

p4 opened -c 35 //depot/main/	List all files in pending changelist 35 that lie under the depot's main subdirectory.
p4 opened -a -c default	List all opened files in the default changelists for all client workspaces.

To open a file in a client workspace and list it in a changelist	p4	add
	p4	edit
	p4	delete
	p4	integrate
To move a file from one changelist to another	p4	reopen
To remove a file from all changelists, reverting it to its previous	p4	revert
state		
To create a new, numbered changelist	p4	change
To view a list of changelists that meet particular criteria	p4	changes

# p4 passwd

#### **Synopsis**

Change a user's Perforce password on the server.

#### **Syntax**

```
p4 [g-opts] passwd [-O oldpassword] [-P newpassword] [user]
```

# **Description**

By default, user records are created without passwords, and any Perforce user can impersonate another by setting P4USER or by using the *globally-available* -u flag. To prevent another user from impersonating you, use p4 passwd to set your password to any string that doesn't contain the comment character #.

After you have set a password, you can authenticate with the password by providing it to the Perforce server program whenever you run any Perforce command. You can provide passwords to the Perforce server in one of three ways:

- Set the environment or registry variable P4PASSWD to the password value;
- Create a setting for P4PASSWD within the P4CONFIG file;
- Use the -P password flag on the Perforce client command line, for example:

```
p4 -u ida -P idaspassword sync
```

Each of these three methods overrides the methods above it. Some of these methods may not be permitted depending on your server's security level.

On Windows clients connecting to servers at security levels 0 and 1, p4 passwd stores the password by using p4 set to change the local registry variable. (The registry variable holds only the encrypted MD5 hash, not the password itself.) On Windows clients connecting to servers at security levels 2 and 3, password hashes are neither stored in, nor read from, the registry.

You can improve security by using ticket-based authentication instead of password-based authentication. To authenticate with tickets instead of passwords, first set a password with p4 passwd, and then use the p4 login and p4 logout commands to manage your authentication. For more about how ticket-based authentication works, see the *System Administrator's Guide*.

Certain combinations of server security level and Perforce client software releases require users to set "strong" passwords. A password is considered strong if it is at least eight characters long, and at least two of the following are true:

- Password contains uppercase letters
- Password contains lowercase letters
- Password contains non-alphabetic characters.

For example, the passwords alb2c3d4, AlB2C3D4, aBcDeFgH are considered strong. For information about how higher security levels work, see the *System Administrator's Guide*.

# **Options**

-0 oldpassword	Avoid prompting by specifying the old password on the command line. This option is not supported if your server is using security level 3.
-P newpassword	Avoid prompting by specifying the new password on the command line. This option is not supported if your server is using security level 3.
user	Superusers can provide this argument to change the password of another user.
g-opts	See the Global Options section.

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	list

- The p4 passwd command never sends plaintext passwords over the network; a challenge/response mechanism is used to send the encrypted password to the server.
- Passwords can contain spaces; command line use of such passwords requires quotes.
   For instance, to pass the password my passw, to Perforce, use p4 -P "my passw" command.
- If a user forgets his or her password, a Perforce superuser can reset it by specifying the username on the command line: p4 passwd username
- The maximum password length is 1024 characters on all platforms.
- To delete a password, set the password value to an empty string. Depending on your server's security level, your server may not permit you to set a null password.

• If you are using ticket-based authentication, changing your password automatically invalidates all of your tickets and logs you out; that is, changing your password is equivalent to p4 logout -a.

To change other user options	p4 user
To change users' access levels	p4 protect
To log in using tickets instead of passwords	p4 login

# p4 print

#### **Synopsis**

Print the contents of a depot file revision.

#### **Syntax**

```
p4 [g-opts] print [ -a ] [ -o outfile ] [ -q ] file[revRange] ...
```

# **Description**

The p4 print command writes the contents of a depot file to standard output. A revision range can be included; in this case, only the files with revisions in the specified range are printed, and by default, only the highest revision in that range is listed. (To output each file at every revision within a specified revision range, use p4 print -a.)

Any file in the depot can be printed, subject to permission limitations as granted by p4 protect. If the file argument does not map through the client view, you must provide it in depot syntax.

By default, the file is written with a header that describes the location of the file in the depot, the revision number of the printed file, and the number of the changelist that the revision was submitted under. To suppress the header, use the -q (quiet) flag.

Multiple file patterns can be included; all files matching any of the patterns are printed.

# **Options**

-a	For each file, print all revisions within a specified revision range, rather than only the highest revision in the range.
-q	Suppress the one-line file header normally added by Perforce.
-o outfile	Redirect output to the specified output file on the local disk, preserving the same file type, attributes, and/or permission bits as the original file in the depot.
g-opts	See the Global Options section.

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	read

 Because most terminals are unable to display UTF16 content, the default behavior of the p4 print command is to return UTF8 content. You can override this behavior by bypassing terminal output entirely and specifying an output file, for example:

```
p4 print -q -o outputfile //depot/file
```

If your terminal supports UTF16 output, specify standard output as the output file: p4 print -q -o - //depot/file

- p4 print's file arguments can take a revision range. By default, only the highest revision matched by any particular file is printed (that is, when no range is specified, the implied range is #1, #head, and the highest revision is #head). To print all files in a specified (or implied) range, use the -a option.
- Because p4 print's output can be quite large when called with highly non-restrictive file arguments (for instance, p4 print //depot/... prints the contents of all files in the depot), it may be subject to a maxresults limitation as set in p4 group.
- In many cases, redirecting p4 print's output to a file via your OS shell will suffice.

The -o option is intended for users who require the automatic setting of file type and/or permission bits. This is handy for files such as UNIX symbolic links (stored as type symlink), files of type apple, automatically setting the execute bit on UNIX shell scripts stored as type text+x, and so on.

To compare the contents of two depot file revisions	p4	diff2
To compare the contents of an opened file in the client workspace to a depot file revision	p4	diff

# p4 protect

#### **Synopsis**

Control users' access to files, directories, and commands.

### **Syntax**

```
p4 [g-opts] protect
p4 [g-opts] protect -o
p4 [g-opts] protect -i
```

#### **Description**

Use p4 protect to control Perforce permissions. You can use p4 protect to:

- Control which files particular users can access;
- Manage which commands particular users are allowed to use;
- Combine the two, allowing one user to write one set of files but only be able to read other files;
- Grant permissions to groups of users, as defined with p4 group;
- Grant or deny specific rights to users by using the =read, =open, =write, and =branch rights, without having to re-grant lesser permissions.
- Limit access to particular IP addresses, so that only users at these IP addresses can run Perforce.

In general, one typically grants an access level to a user or group, after which, if finer-grained control is required, one or more specific rights can then be denied.

The permission levels and access rights are:

•	
Permission Level / Right	What the User Can Do
list	The user can access all Perforce metadata, but has no access to file contents. The user can run all the commands that describe Perforce objects, such as p4 files, p4 client, p4 job, p4 describe, p4 branch, etc.
read	The user can do everything permitted with list access, and also run any command that involves reading file data, including p4 print, p4 diff, p4 sync, and so on.
=read	If this right is denied, users cannot use p4 print, p4 diff, or p4 sync on files.

Permission Level / Right	What the User Can Do
open	This gives the user permission to do everything she can do with read access, and gives her permission to p4 add, p4 edit, p4 delete, and p4 integrate files. However, the user is not allowed to lock files or submit files to the depot.
=open	If this right is denied, users cannot open files with p4 add, p4 edit, p4 delete, or p4 integrate.
write	The user can do all of the above, and can also write files with p4 submit and lock them with p4 lock.
=write	If this right is denied, users cannot submit open files.
=branch	If this right is denied, users cannot use files as a source for p4 integrate.
review	This permission is meant for external programs that access Perforce. It gives the external programs permission to do anything that list and read can do, and grants permission to run p4 review and p4 counter. It does not include open or write access.
admin	Includes all of the above, including administrative commands that override changes to metadata, but do not affect server operation.
	These include p4 branch -f,p4 change -f,p4 client -f,p4 job -f,p4 jobspec,p4 label -f,p4 obliterate,p4 typemap,p4 unlock -f,andp4 verify.
super	Includes all of the above, plus access to the superuser commands such as p4 admin, p4 counter, p4 triggers, p4 protect, and so on.

#### **Form Fields**

When you run p4 protect, Perforce displays a form with a single field, Protections:. Each permission is specified in its own indented line under the Protections: header, and has five values:

Column	Description
Access Level	One of the access levels list, read, open, write, review, or super, or one of the rights of =read, =open, =write, and =branch, as defined above
User or Group	Does this protection apply to a user or a group? The value of this field must be user or group.
Group Name or User Name	The name of the user or the name of the group, as defined by p4 group. To grant this permission to all users, use the * wildcard.

Column	Description
Host	The IP address. CIDR notation is supported. The * wildcard can also be used to refer to all IP addresses, but only when you are not using CIDR notation.
Depot File Path	The depot file path this permission is granted on, in Perforce <i>depot syntax</i> . The file specification can contain Perforce <i>wildcards</i> .
	To exclude this mapping from the permission set, use a dash (-) as the first character of this value.

When exclusionary mappings are not used, a user is granted the highest permission level listed in the union of all the mappings that match the user, the user's IP address, and the files the user is trying to access. In this case, the order of the mappings is irrelevant.

When exclusionary mappings are used, order is relevant: the exclusionary mapping overrides any matching protections listed above it in the table. No matter what access level is being denied in the exclusionary protection, all the access levels for the matching users, files, and IP addresses are denied.


If you use exclusionary mappings to deny access to an area of the depot to members of group1, but grant access to the same area of the depot to members of group2, a user who is a member of both group1 and group2 is either granted or denied access based on whichever line appears last in the protections table.

# **Options**

-i	Read the form from standard input without invoking an editor.
-0	Write the form to standard output without invoking an editor.
g-opts	See the Global Options section.

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	super

• Each permission level includes all the access levels below it, as illustrated in this chart:



• The specific rights of =read, =open, =write, and =branch can be used to override the automatic inclusion of lower access levels. This makes it possible to deny individual rights without having to then re-grant lesser rights.

For example, if you want administrators to have the ability to run administrative commands, but to deny them the ability to make changes in certain parts of the depot, you could set up a permissions table as follows:

admin	user	joe	*	//
=write	user	joe	*	-//depot/build/
=open	user	joe	*	-//depot/build/

In this example, user joe can perform administrative functions, which may include reading or listing files in //depot/build/..., but he is prohibited from opening files for edit (or submitting any changes he might have open.) He can, however, continue to create and modify files outside of the protected //depot/build/... area.

• Access levels determine which commands you can use. The following table lists the minimum access level required for each command. For example, because p4 add requires at least open access, you can run p4 add if you have open, write, admin, or super access.

Command	Access Level	Notes
add	open	
admin	super	
annotate	read	
branch	open	The -f flag to override existing metadata or other users' data requires admin access.
branches	list	
browse	none	
change	open	The -f flag to override existing metadata or other users' data requires admin access.
changes	list	This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depot.
client	list	The -f flag to override existing metadata or other users' data requires admin access.
clients	list	
counter	review	list access to at least one file in any depot is required to view an existing counter's value; review access is required to change a counter's value or create a new counter.
counters	list	
dbschema	super	
dbstat	super	
delete	open	
depot	super	The -o flag to this command, which allows the form to be read but not edited, requires only list access.
depots	list	This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depot.
describe	read	The -s flag to this command, which does not display file content, requires only list access.
diff	read	

diff2 read dirs list edit open export super filelog list files list fix open fixes list This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depot fstat list group super The -o flag to this command, which allows the form to be read but not edited, requires only list access. The -a flag to this command requires only list access, provided that the user is also listed as a group owner.  groups list This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depot. have list help none info none integrate open The user must have open access on the target files and read access on the source files.
edit open export super filelog list files list fix open fixes list This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depot.  fstat list grep list group super The -o flag to this command, which allows the form to be read but not edited, requires only list access. The -a flag to this command requires only list access, provided that the user is also listed as a group owner.  groups list This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depot.  have list help none info none integrate open The user must have open access on the target files and
export  filelog list  files list  fix open  fixes list  This command doesn't operate on specific files.  Permission is granted to run the command if the user has the specified access to at least one file in any depotence of several part of the se
filelog list files list fix open fixes list This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depot.  fstat list grep list group Super The -o flag to this command, which allows the form to be read but not edited, requires only list access. The -a flag to this command requires only list access, provided that the user is also listed as a group owner.  groups list This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depot.  have list help none info none integrate open The user must have open access on the target files and
files list fix open  fixes list This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depotence of stat list grep list group super The -o flag to this command, which allows the form to be read but not edited, requires only list access. The -a flag to this command requires only list access, provided that the user is also listed as a group owner.  groups list This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depotence of the property of the propert
fixes list This command doesn't operate on specific files.  Permission is granted to run the command if the user has the specified access to at least one file in any depote fixed list  group Super The -o flag to this command, which allows the form to be read but not edited, requires only list access.  The -a flag to this command requires only list access, provided that the user is also listed as a group owner.  Groups list This command doesn't operate on specific files.  Permission is granted to run the command if the user has the specified access to at least one file in any depote have list  help none info none  integrate open The user must have open access on the target files and
This command doesn't operate on specific files.  Permission is granted to run the command if the user has the specified access to at least one file in any depote group  Super  The -o flag to this command, which allows the form to be read but not edited, requires only list access.  The -a flag to this command requires only list access, provided that the user is also listed as a group owner.  Groups  list  This command doesn't operate on specific files.  Permission is granted to run the command if the user has the specified access to at least one file in any depote have  list  help  none  info  none  The user must have open access on the target files and
Permission is granted to run the command if the user has the specified access to at least one file in any depoted fistat.  grep list group super The -o flag to this command, which allows the form to be read but not edited, requires only list access.  The -a flag to this command requires only list access, provided that the user is also listed as a group owner.  groups list This command doesn't operate on specific files.  Permission is granted to run the command if the user has the specified access to at least one file in any depotence of the property of
group super The -o flag to this command, which allows the form to be read but not edited, requires only list access.  The -a flag to this command requires only list access, provided that the user is also listed as a group owner.  groups list This command doesn't operate on specific files.  Permission is granted to run the command if the user has the specified access to at least one file in any depotence of the provided that the user has the specified access to at least one file in any depotence of the provided that the user is also listed as a group owner.  This command doesn't operate on specific files.  Permission is granted to run the command if the user has the specified access to at least one file in any depotence of the provided that the user is also listed as a group owner.  This command doesn't operate on specific files.  Permission is granted to run the command if the user has the specified access to at least one file in any depotence of the provided that the user is also listed as a group owner.  The user must have open access on the target files and the provided that the user is also listed as a group owner.
group super The -o flag to this command, which allows the form to be read but not edited, requires only list access.  The -a flag to this command requires only list access, provided that the user is also listed as a group owner.  This command doesn't operate on specific files.  Permission is granted to run the command if the user has the specified access to at least one file in any depot.  have list  help none  info none  integrate open The user must have open access on the target files and
be read but not edited, requires only list access.  The -a flag to this command requires only list access, provided that the user is also listed as a group owner.  This command doesn't operate on specific files.  Permission is granted to run the command if the user has the specified access to at least one file in any depot.  have list  help none  info none  integrate open The user must have open access on the target files and
provided that the user is also listed as a group owner.  This command doesn't operate on specific files.  Permission is granted to run the command if the user has the specified access to at least one file in any depot.  have list  help none  info none  integrate open The user must have open access on the target files and
Permission is granted to run the command if the user has the specified access to at least one file in any depote have list help none info none integrate open The user must have open access on the target files and
help none info none integrate open The user must have open access on the target files and
info none integrate open The user must have open access on the target files and
integrate open The user must have open access on the target files and
integrated list
The -o flag to this command, which allows the form to be read but not edited, requires only list access.
The -f flag to override existing metadata or other users' data requires admin access.
This command doesn't operate on specific files.  Permission is granted to run the command if the user has the specified access to at least one file in any depote
jobspec admin The -o flag to this command, which allows the form to be read but not edited, requires only list access.

Command	Access Level	Notes
label	open	This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depot.
		The -f flag to override existing metadata or other users' data requires admin access.
labels	list	This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depot.
labelsync	list	
license	super	
lock	write	
lockstat	super	
login	list	
logout	list	
logstat	super	
logtail	super	
monitor	list	super access is required to terminate or clear processes, or to view arguments.
move	open	
obliterate	admin	
opened	list	
passwd	list	
print	read	
protect	super	
protects	list	super access is required to use the -a, -g, and -u flags.
reopen	open	
replicate	super	
resolve	open	
resolved	open	
revert	list	
review	review	This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depot.

Command	Access Level	Notes
reviews	list	This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depot.
set	none	
shelve	open	
sizes	list	
submit	write	
sync	read	
tag	list	
tickets	none	
triggers	super	
typemap	admin	The -o flag to this command, which allows the form to be read but not edited, requires only list access.
unlock	open	The -f flag to override existing metadata or other users' data requires admin access.
unshelve	open	
user	list	This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depot.
users	list	This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depot.
verify	admin	
where	list	This command doesn't operate on specific files. Permission is granted to run the command if the user has the specified access to at least one file in any depot.

- When a new Perforce server is installed, anyone who wants to use Perforce is allowed to, and all Perforce users are superusers. The first time anyone runs p4 protect, the invoking user is made the superuser, and everyone else is given write permission on all files. Run p4 protect immediately after installation.
- In the course of normal operation, you'll primarily grant users list, read, write, and super access levels. The open and review access levels are used less often.
- Those commands that list files, such as p4 describe, will only list those files to which the user has at least list access.

- Some commands (for instance, p4 change, when editing a previously submitted changelist) take a -f flag that requires admin or super access.
- The open access level gives the user permission to change files but not submit them to the depot. Use this when you're temporarily freezing a codeline, but don't want to stop your developers from working, or when you employ testers who are allowed to change code for their own use but aren't allowed to make permanent changes to the codeline.
- The review access level is meant for review daemons that need to access counter values.
- If you write a review daemon that requires both review and write access, but shouldn't have super access, grant the daemon both review and write access on two separate lines of the protections table.
- To limit or eliminate the use of the files on a particular server as a remote depot from a different server (as defined by p4 depot), create protections for user remote. Remote depots are always accessed by a virtual user named remote.
- For further information, see the *Protections* chapter of the *System Administrator's Guide*.

#### **Examples**

Suppose that user joe is a member of groups devgroup and buggroup, as set by p4 group, and the protections table reads as follows:

```
bill
                                                      //...
super
          user
write
          group
                     devgroup
                                                      //depot/...
                                                      -//depot/proj/...
write
          group
                     buggroup
write
                                 192.168.100.0/24
                                                      //...
          user
                     joe
```

Joe attempts a number of operations. His success or failure at each is described below:

From IP address	Joe tries	Results
10.14.10.1	p4 print //depot/misc/	Succeeds. The second line grants Joe write access on these files; write access includes read access, and this protection isn't excluded by any subsequent lines.
10.14.10.1	p4 print //depot/proj/README	Fails. The third line removes all of Joe's permissions on any files in this directory. (If the second protection and the third protection had been switched, then the subsequent protection would have overridden this one, and Joe would have succeeded).
192.168.100.123	p4 print //depot/proj/README	Succeeds. Joe is sitting at an IP address from which he is granted this permission in the fourth line.
192.168.100.123	p4 verify //depot/misc/	Fails. p4 verify requires super access; Joe doesn't have this access level no matter which IP address he's coming from.

To create or edit groups of users	p4 group
To list all user groups	p4 groups

# p4 protects

#### **Synopsis**

Display protections in place for a given user, group, or path.

#### **Syntax**

```
p4 [g-opts] protects [ -a | -u user | -g group | -h host ] [-m] [ file... ]
```

# **Description**

Use the p4 protects command to display the lines from the protections table that apply to a user, group, or set of files.

With no options, p4 protects displays the lines in the protections table that apply to the current user. If a file argument is provided, only those lines in the protection table that apply to the named files are displayed.

Use the -a flag to display lines for all users, or -u user, -g group, or -h host flags to display lines for a specific user, group, or host IP address.

Use the -m flag to display a one-word summary of the maximum applicable access level.

# **Options**

-a	Displays protection lines for all users. This option requires super access.
-g group	Displays protection lines that apply to the named group. This option requires super access.
-h host	Displays protection lines that apply to the specified host IP address. This option requires super access.
-u user	Displays protection lines that apply to the named user. This option requires super access.
- m	Display a one-word summary of the maximum applicable access level. (Note: this does not take into account exclusionary mappings.)
g-opts	See the Global Options section.

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	list, super for -a, -h, -g, -u

# **Related Commands**

To edit the protections table

p4 protect

# p4 rename

### **Synopsis**

Renaming files under Perforce.

### **Syntax**

```
p4 [g-opts] move fromFile toFile
p4 [g-opts] integrate fromFile toFile
p4 [g-opts] delete fromFile
p4 [g-opts] submit fromFile toFile
```

#### **Description**

Use p4 move to move or rename files.

Prior to release 2009.1, moving files was accomplished by using p4 integrate to copy fromFile into a new toFile, using p4 delete to delete fromFile, and then using p4 submit to store these file changes in the depot.

You can rename multiple files with either method by including matching wildcards in fromFile and toFile.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
fromFile: Yes toFile: No	No	read access for fromFile write access for toFile

#### **Examples**

Moving files from d1 to d2.
Files must be open for edit before they can be moved.
Renaming a set of files prior to 2009.1:
• p4 integrate copies all the files in the d1 directory to the d2 directory.
• p4 delete deletes all files in d1.
• p4 submit sends these changes to the depot in a single changelist.

Moving a file	p4 move
To copy a file and keep it under Perforce's control	p4 integrate
To delete a file from the depot	p4 delete
To submit changes to the depot	p4 submit

# p4 reopen

#### **Synopsis**

Move opened files between changelists or change the files' type.

#### **Syntax**

```
p4 [g-opts] reopen [-c changelist#] [-t filetype] file...
```

#### **Description**

p4 reopen has two different but related uses:

- Use p4 reopen -c changelist# file to move an open file from its current pending changelist to pending changelist changelist#.
- Use p4 reopen -c default to move a file to the default changelist.
- Use p4 reopen -t filetype to change the type of a file.

If file patterns are provided, all open files matching the patterns are moved or retyped. The two flags can be combined to move a file and change its type in the same operation.

#### **Options**

-c changelist# file	Move all open files matching file pattern file to pending changelist changelist#. To move a file to the default changelist, use default as the changelist number.
-t filetype file	When submitted, store file as type filetype. All subsequent revisions will be of that file type until the type is changed again.
	See the File Types section for a list of file types.
g-opts	See the Global Options section.

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	open

# **Examples**

p4 reopen -t text+k //	Reopen all open files as text files with keyword expansion.
p4 reopen -c 410 //depot/proj1//README	Move all open files under directory //depot/proj1 or that are named README to pending changelist 410.
p4 reopen -c default -t binary+S //exe	Move all open .exe files to the default changelist, overwriting older revisions of those files in the depot.

p4 submit
p4 change
p4 revert
p4 opened
p4 opened -c changelist#
p4 changes -p pending
p4 edit -c changelist# -t type
p4 add -c changelist# -t type
p4 edit -t +l //depotname/

# p4 replicate

### **Synopsis**

Poll for journal changes on one Perforce Server for forwarding to another Perforce Server.

### **Syntax**

```
p4 replicate [-j token] [-s statefile] [-i interval] [-k -x] [-J prefix] [-o output] [command]
```

# **Description**

This command polls for new journal entries from a Perforce Server, and either outputs them to standard output, or, if a *command* is specified, pipe the journal records to the *command*, which is spawned as a subprocess.

# **Options**

-j token	Specify a journal number or position token of the form <code>journalnum/byteoffset</code> from which to start replicating metadata. If this flag is specified, it overrides any state file specification.
-s statefile	Specify a state file which tracks the most recent journal position.
-i interval	Specify a polling interval, in seconds. The default is two seconds. To disable polling (that is, to check once for updated journal entries and then exit), specify an <i>interval</i> of 0.
-J prefix	Specifies a filename prefix for the journal, such as that used with p4d -jc prefix
-k	Keep the pipe to the <i>command</i> subprocess open between polling intervals.
-x	Exit the p4 replicate command when journal rotation is detected.
-o savefile	Specify a file for output. If a <i>command</i> subprocess is specified, both the subprocess and the specified savefile are provided with the output.
g-opts	See the Global Options section.

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	super

• For more information, see the *System Administrator's Guide* and the following Perforce Knowledge Base article:

http://kb.perforce.com/?article=1099

# p4 resolve

#### **Synopsis**

Resolve conflicts between file revisions.

#### **Syntax**

```
p4 [g-opts] resolve [-af -am -as -at -ay -dflag -f -n -o -t -v] [file...]
```

# **Description**

Use p4 resolve to combine the contents of two files or file revisions into a single file revision in your workspace. Two situations require the use of p4 resolve before a file can be submitted:

• When a simple conflict exists: the revision of a file last synced to the client workspace is not the head revision at the time of the submit.

For example, Alice does a p4 sync followed by a p4 edit of file file.c, and Bob does the same thing. Alice p4 submits file.c, and then Bob tries to submit file.c. Bob's submit fails because if his version of file.c were to be accepted into the depot, Alice's changes to file.c would no longer be visible. Bob must resolve the conflict before he can submit the file.

• When p4 integrate has been used to schedule the integration of changes from one file to another.

The primary difference between these two cases is that resolving a simple file conflict involves multiple revisions of a single file, but resolving for integration involves combining two separate files. In either case:

- If the file is of type text, p4 resolve allows the user to use the file in the client workspace instead of the file in the depot, overwrite the file in the client workspace with the file in the depot, or merge changes from both the depot revision and the client workspace revision into a single file.
- If the file is of type binary, only the first two options (use the file in the workspace, or overwrite the file in the workspace with the file in the depot) are normally available, because merges generally do not work with binary files.

The output of p4 resolve is primarily diagnostic in nature; files are either resolved against ("vs") another file, copied, merged, edited, branched, added, deleted, moved, or ignored with respect to other files. The actual work performed by p4 resolve is reflected by the changes it makes to files in the client workspace.

The p4 resolve dialog refers to four file revisions whose meaning depends on whether or not the resolution fixes a simple file conflict or is resolving for integration:

Term	Meaning when Resolving Con- flicts	Meaning when Resolving for Integration
yours	The revision of the file in the client workspace	The file to which changes are being propagated (in integration terminology, this is the <i>target</i> file). Changes are made to the version of this file in the client workspace, and this file is later submitted to the depot.
theirs	The head revision of the file in the depot.	The file revision in the depot from which changes are being propagated (in integration terminology, this is the <i>source</i> file). This file is not changed in the depot or the client workspace.
base	The file revision synced to the client workspace before it was opened for edit.	The previously-integrated revision of theirs. The latest common ancestor of both yours and theirs.
merge	A file version generated by Perforce from <i>yours</i> , <i>theirs</i> , and <i>base</i> . The user can edit this revision during the resolve process if the file is a text file.	Same as the meaning at left.

The interactive p4 resolve dialog presents the following options. Note that the dialog options are not the same as the command line flags.

Dialog Option	Short Meaning	What it Does	Available by Default for Binary Files?
е	edit merged	Edit the preliminary merge file generated by Perforce.	no
еу	edit yours	Edit the revision of the file currently in the workspace.	yes
et	edit theirs	Edit the revision in the depot with which the workspace revision conflicts (usually the head revision). This edit is read-only.	yes
dy	diff yours	Show diffs between yours and base.	no

Dialog Option	Short Meaning	What it Does	Available by Default for Binary Files?
dt	diff theirs	Show diffs between theirs and base.	no
dm	diff merge	Show diffs between merge and base.	no
d	diff	Show diffs between merge and yours.	yes
m	merge	Invoke the command:	no
		P4MERGE base theirs yours merge	
		To use this option, you must set the environment variable P4MERGE to the name of a third-party program that merges the first three files and writes the fourth as a result. This command has no effect if P4MERGE is not set.	
?	help	Display help for p4 resolve.	yes
s	skip	Don't perform the resolve right now.	yes
ay	accept yours	Accept <i>yours</i> , ignoring changes that may have been made in <i>theirs</i> .	yes
at	accept theirs	Accept theirs into the client workspace as the resolved revision. The revision (yours) that was in the client workspace is overwritten.	yes
		When resolving simple conflicts, this option is identical to performing p4 revert on the client workspace file. When resolving for integrate, this copies the source file to the target file.	
am	accept merge	Accept the merged file into the client workspace as the resolved revision without any modification. The revision (yours) originally in the client workspace is overwritten.	no

Dialog Option	Short Meaning	What it Does	Available by Default for Binary Files?
ae	accept edit	If you edited the file (i.e., by selecting "e" from the p4 resolve dialog), accept the edited version into the client workspace. The revision (yours) originally in the client workspace is overwritten.	no
a	accept	<ul> <li>Keep Perforce's recommended result:</li> <li>if theirs is identical to base, accept yours;</li> <li>if yours is identical to base, accept theirs;</li> <li>if yours and theirs are different from base, and there are no conflicts between yours and theirs; accept merge;</li> <li>otherwise, there are conflicts between yours and theirs, so skip this file</li> </ul>	no

Resolution of a file is completed when any of the accept dialog options are chosen. To resolve the file later or to revert the change, skip the file.

To help decide which option to choose, counts of four types of changes that have been made to the file revisions are displayed by p4 resolve:

Diff Chunks: 2 yours + 3 theirs + 5 both + 7 conflicting

The meanings of these values are:

Count	Meaning
n yours	n non-conflicting segments of yours are different than base.
n theirs	n non-conflicting segments of theirs are different than base.
n both	n non-conflicting segments appear identically in both theirs and yours, but are different from base.
n conflicting	n segments of theirs and yours are different from base and different from each other.

If there are no conflicting chunks, it is often safe to accept Perforce's generated merge file, since Perforce will substitute all the changes from *yours* and *theirs* into *base*.

If there are conflicting chunks, the *merge* file must be edited. In this case, Perforce will include the conflicting *yours*, *theirs*, and *base* text in the *merge* file; it's up to you to choose which version of the chunk you want to keep.

The different text is clearly delineated with file markers:

```
>>>> ORIGINAL VERSION file#n
<text>
==== THEIR VERSION file#m
<text>
==== YOUR VERSION file
<text>
<<<<
```

Choose the text you want to keep; delete the conflicting chunks and all the difference markers.

# **Options**

-am -af -as -at -ay	<ul> <li>Skip the resolution dialog, and resolve the files automatically as follows:</li> <li>-am: Automatic Mode. Automatically accept the Perforce-recommended file revision: if theirs is identical to base, accept yours; if yours is identical to base, accept theirs; if yours and theirs are different from base, and there are no conflicts between yours and theirs; accept merge; otherwise, there are conflicts between yours and theirs, so skip this file.</li> <li>-ay: Accept Yours, ignore theirs.</li> <li>-at: Accept Theirs. Use this flag with caution, as the file in the client workspace will be overwritten!</li> <li>-as: Safe Accept. If either yours or theirs is different from base, (and the changes are in common) accept that revision. If both are different from base, skip this file.</li> <li>-af: Force Accept. Accept the merge file no matter what. If the merge file has conflict markers, they will be left in, and you'll need to remove them by editing the file.</li> </ul>
-dflag	When merging files, ignore specified differences in whitespace or line- ending convention. (If you use these flags, and the files differ by whitespace only, p4 resolve uses the text in the workspace file.)
	<ul> <li>-db: Ignore whitespace-only changes (for instance, a tab replaced by eight spaces)</li> </ul>
	<ul> <li>-dw: Ignore whitespace altogether (for instance, deletion of tabs or other whitespace)</li> </ul>
	<ul> <li>-d1: Ignore differences in line-ending convention</li> </ul>
-f	Allow already resolved, but not yet submitted, files to be resolved again.
-n	List the files that need resolving without actually performing the resolve.
-0	Output the base file name and revision to be used during the resolve.

-t	Force a three-way merge, even on binary (non-text) files. This allows you to inspect diffs between files of any type, and lets you merge non-text files if P4MERGE is set to a utility that can do such a thing.
-v	Include conflict markers in the file for all changes between yours and base, and between theirs and base. Normally, conflict markers are included only when yours and theirs conflict.
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	open

- p4 resolve works only with files that have been scheduled for resolve. Three operations schedule files for resolution:
  - Integrating the file with p4 integrate.
  - Submitting an open file that was synced from a revision other then the current head revision; the submit fails, and the file is scheduled for resolve.
  - Running p4 sync instead of running p4 submit on the open file. Nothing is copied
    into the client workspace; instead, the file is scheduled for resolve. (The only benefit
    of scheduling files for resolve with p4 sync instead of a failed submit is that the
    submit will not fail).

When p4 resolve is run with no file arguments, it operates on all files in the client workspace that have been scheduled for resolve.

• If translation errors occur during integrations between text and unicode files, the most likely cause is the presence of non-ASCII characters in the text file. Either remove the non-ASCII characters from the file before integration, or set P4CHARSET to utf8 and attempt the merge again.

To view a list of resolved but unsubmitted files	p4 resolved
To schedule the propagation of changes between two separate files	p4 integrate
To submit a set of changed files to the depot	p4 submit
To copy a file to the client workspace, or schedule an open file for resolve	p4 sync

# p4 resolved

#### **Synopsis**

Display a list of files that have been resolved but not yet submitted.

#### **Syntax**

```
p4 [g-opts] resolved [-o] [file...]
```

#### **Description**

p4 resolved lists files that have been resolved, but have not yet been submitted. The files are displayed one per line in the following format:

```
localFilePath - action from depotFilePath#revisionRange
```

where <code>localFilePath</code> is the full path name of the resolved file on the local host, <code>depotFilePath</code> is the path of the depot file relative to the top of the depot, <code>revisionRange</code> is the revision range that was integrated, and <code>action</code> is one of merge, branch, or <code>delete</code>.

If file pattern arguments are provided, only resolved, unsubmitted files that match the file patterns are included.

Although the name p4 resolved seems to imply that only files that have gone through the p4 resolve process are listed, this is not the case. A file is also considered to be resolved if it has been opened by p4 integrate for branch, opened by p4 integrate for delete, or has been resolved with p4 resolve.

# **Options**

-0	Output the base file name and revision that was used during the resolve.
g-opts	See the Global Options section.

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	open

To see a list of integrations that have been submitted	p4	integrated
To view a list of integrations that have not yet been resolved	p4	resolve -n
To schedule the propagation of changes from one file to another	p4	integrate
To resolve file conflicts, or to propagate changes as scheduled by p4 integrate	p4	resolve

# p4 revert

#### **Synopsis**

Discard changes made to open files.

#### **Syntax**

```
p4 [g-opts] revert [ -a -n -k -c changelist# ] file...
```

# **Description**

Use p4 revert to discard changes made to open files, reverting them to the revisions last p4 synced from the depot. This command also removes the reverted files from the pending changelists with which they're associated.

When you revert files you opened with p4 delete, the files are reinstated in the client workspace. When you revert files that have been opened by p4 add, Perforce leaves the client workspace files intact. When you revert files you've opened with p4 integrate, Perforce removes the files from the client workspace.

# **Options**

-a	Revert only those files that haven't changed (in terms of content or filetype) since they were opened.
	The only files reverted are those whose client revisions are:
	<ul> <li>open for edit but have unchanged content and unchanged file- type; or</li> </ul>
	• open for integrate via p4 integrate and have not yet been resolved with p4 resolve.
-n	List the files that would be reverted without actually performing the revert.
	This lets you make sure the revert does what you think it does before actually reverting the files.
-k	Keep workspace files; the file(s) are removed from any changelists, and the server records the files as being no longer open, but the file(s) are unchanged in the client workspace.
-c changelist#	Reverts only those files in the specified changelist.
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	list

• p4 revert differs from most Perforce commands in that it usually *requires* a file argument. The files that are reverted are those that lie in the intersection of the command line file arguments and the client workspace view.

You don't need to specify a file argument when using the -a flag.

• Reverting a file that has been opened for edit will overwrite any changes you have made to the file since the file was opened. It may be prudent to use p4 revert -n to preview the results before running p4 revert.

# **Examples**

p4 revert //	Revert every file you have open, in every one of your pending changelists, to its pre-opened state.
p4 revert -c default //	Revert every file open in the default changelist to its pre-opened state.
p4 revert -n *.txt	Preview a reversion of all open .txt files in the current directory, but don't actually perform the revert.
p4 revert -c 31 *.txt	Revert all .txt files in the current directory that were open in changelist 31.
p4 revert -a	Revert all unchanged files. This command is often used before submitting a changelist.

To open a file for add	p4 add
To open a file for deletion	p4 delete
To copy all open files to the depot	p4 submit
To read files from the depot into the client workspace	p4 sync
To list all opened files	p4 opened
To forcibly bring the client workspace in sync with the files that Perforce thinks you have, overwriting any unopened, writable files in the process.	p4 sync -f

## p4 review

#### **Synopsis**

List all submitted changelists above a provided changelist number.

#### **Syntax**

```
p4 [g-opts] review [-c changelist#] [-t countername]
```

## **Description**

p4 review -c changelist# provides a list of all submitted changelists between changelist# and the highest-numbered submitted changelist. Each line in the list has this format:

```
Change changelist# username <email-addr> (realname)
```

The username, email-addr, and realname are taken from the p4 user form for username whenever p4 review is executed.

When used as p4 review -t countername, all submitted changelists above the value of the Perforce counter variable countername are listed. (Counters are set by p4 counter). When used with no arguments, p4 review lists all submitted changelists.

The p4 review command is meant for use in external programs that call Perforce. The Perforce change review daemon, which is described in the *Perforce System Administrator's Guide*, and is available from our Web site, uses p4 review.

## **Options**

-c changelist#	List all submitted changelists above and including changelist#.
-t countername	List all submitted changelists above the value of the Perforce counter countername.
-c changelist# -t countername	Set the value of counter countername to changelist#. This command has been replaced by p4 counter, but has been maintained for backwards compatibility.
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	review

- The commands p4 review, p4 reviews, and p4 counter are all intended for use by external programs that call Perforce.
- The warnings applicable to p4 counter apply here as well.

To list users who have subscribed to review particular files	p4	reviews
To set or read the value of a Perforce counter	p4	counter
To see full information about a particular changelist	p4	describe
To see a list of all changelists, limited by particular criteria	p4	changes

## p4 reviews

#### **Synopsis**

List all the users who have subscribed to review particular files.

#### **Syntax**

```
p4 [g-opts] reviews [-c changelist#] [file...]
```

## Description

The p4 reviews command is intended for use in external programs that call Perforce.

Users subscribe to review files by providing file patterns in the Reviews: field in their p4 user form.

p4 reviews -c changelist#lists each user who has subscribed to review any files included in the submitted changelist changelist#. The alternate form, (p4 reviews file...), lists the users who have subscribed to review any files that match the file patterns provided as arguments. If you provide no arguments to p4 reviews, all users who have subscribed to review any files are listed.

#### **Options**

-c changelist#	List all users who have subscribed to reviews any files included in submitted changelist <code>changelist#</code> .
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	list

- The syntax p4 reviews -c changelist# file... ignores the file arguments entirely.
- p4 reviews is an unusual command. It was created to support external daemons, but it does nothing without the Reviews: field of the p4 users form, which has a very specific meaning.

It is possible to enter values in the Reviews: field that mean something originally unintended by Perforce in order to create more generalized daemons. At Perforce, for example, we run a jobs daemon that sends email to any users who have subscribed to review jobs anytime a new job is submitted. Since there's nothing built into Perforce that allows users to subscribe to review jobs, we co-opt a single line of the Reviews: field: Perforce sends job email to any users who have subscribed to review the non-existent path //depot/jobs/.

To subscribe to review files	p4	user
List all submitted changelists above a provided changelist number	p4	review
To set or read the value of a Perforce counter	p4	counter
To read full information about a particular changelist	p4	describe

## p4 set

#### **Synopsis**

Set Perforce variables in the Windows registry.

#### **Syntax**

```
p4 [g-opts] set [ -s ] [ -S svcname ] [ var=[value] ]
```

## **Description**

The Perforce client and server require the use of certain system variables.

On Windows, you can set the values of these variables in the registry with p4 set; on other operating systems, Perforce uses environment variables for the same purpose.

To set the value of a registry variable for the current user, use p4 set *var=value*. Windows administrators can use p4 set *-s var=value* to set the registry variable's default values for all users on the local machine.

Windows administrators running the Perforce server as a service can set variables used by the service (for instance, P4JOURNAL and others) with p4 set -S svcname var=value.

To unset the value for a particular variable, leave value empty.

To view a list of the values of all Perforce variables, use p4 set without any arguments. On UNIX, this displays the values of the associated environment variables. On Windows, this displays either the MS-DOS environment variable (if set), or the value in the registry and whether it was defined with p4 set (for the current user) or p4 set -s (for the local machine).

p4 set can be used on non-Windows operating systems to view the values of variables, but if you try to use p4 set to set variables on non-Windows operating systems, Perforce will display an error message.

## **Options**

-s	Set the value of the registry variables for the local machine.
	Without this flag, p4 set sets the variables in the HKEY_CURRENT_USER hive; when you use the -s flag, the variables are set in the HKEY_LOCAL_MACHINE hive.
	These locations are reflected in the output of p4 set on Windows.
-S svcname	Set the value of the registry variables as used by service <i>svcname</i> . You must have administrator privileges to do this.
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	none

- You'll find a listing and discussion of the Perforce variables in the *Environment Variables* section of this manual.
- Changes to registry values under Windows affect the local machine only; an administrator setting P4JOURNAL for a Perforce Windows service must be present at the machine running the service.
- On Windows, you can override the values of the registry keys in any of three ways:
  - Environment variables with the same names have precedence;
  - Values within P4CONFIG files have precedence over both of these;
  - The *global option* flags have the highest precedence.
- If you're working in a UNIX-like environment on a Windows machine (e.g. Cygwin), use environment variables instead of p4 set. (In such cases, the Perforce Command-Line Client behaves just as though it were in a UNIX environment.)

## **Examples**

p4 set	On all platforms, display a list of Perforce variables without changing their values.
p4 set P4MERGE=	On Windows, unset the value of P4MERGE.
p4 set P4PORT=tea:1666	On Windows, set a registry variable telling Perforce client programs to connect to a Perforce server at host tea, port 1666.
	The variable would be set only for the current local user
p4 set -s P4PORT=tea:1666	Set P4PORT as above, but for all users on the system.
	You must have administrative privileges to do this.

p4 set -S p4svc P4PORT=1666	For the NT service p4svc, instruct p4s.exe to listen on port 1666 for incoming connections from Perforce client programs.	
	You must have administrative privileges to do this.	
p4 set P4EDITOR="C:\File Editor\editor.exe"	On Windows, for the current local user, set the path for the default text editor.	
	The presence of spaces in the path to the editor's executable requires that the path be enclosed in quotation marks.	

## p4 shelve

## **Synopsis**

Store files from a pending changelist in the depot, without submitting them.

#### Syntax 5 4 1

```
p4 shelve [files ...]
p4 shelve -i [-f | -r ]
p4 shelve -r -c changelist
p4 shelve -c changelist [-f] [file ...]
p4 shelve -d -c changelist [-f] [file ...]
```

#### **Description**

Shelving is the process of temporarily storing work in progress on a Perforce Server without submitting a changelist. Shelving is useful when you need to perform multiple development tasks (such as interruptions from higher-priority work, testing across multiple platforms) on the same set of files, or share files for code review before committing your work to the depot.

The p4 shelve command creates, modifies, or discards shelved files in a pending changelist. Shelved files persist in the depot until they are discarded (by means of p4 shelve -d) or replaced by subsequent p4 shelve commands.

After shelving files, you can revert or modify them in your client workspace, and restore the shelved versions of those files to your workspace with the p4 unshelve command.

While files are shelved, other users can unshelve the shelved files into their own workspaces, or into other client workspaces.

Files that have been shelved can also be accessed with the p4 diff, p4 diff2, p4 files, and p4 print commands, using the revision specifier @=change, where change is the pending changelist number.

If no arguments are specified, p4 shelve creates a new changelist, adds files from the user's default changelist, and (after the user completes a form similar to that used by p4 submit), shelves the specified files into the depot. If a file pattern is given, p4 shelve shelves only the files that match the pattern.

# Options

-f	Force the overwriting of any existing shelved files in a pending changelist with the contents of their client workspace copies.
	Perforce administrators can use this flag with -d to force the discarding of shelved files in a specified changelist.
-i	Read a changelist description from standard input. Input must be in the same format used by the p4 shelve form. (When modifying an existing changelist with shelved files, this option also implies -c).
-c changelist	Specify the pending changelist in which shelved files are to be created, discarded, or modified.
	Only the user and client workspace that owns the pending changelist can add or modify its shelved files. (Administrators can use -f to discard files.)
-d	Discard the shelved files in the specified changelist so that they are no longer available for p4 unshelve operations.
	Only the user and workspace that owns the pending changelist can discard its shelved files. (Administrators can use -f to discard files.)
-r	Replace all shelved files in the changelist with the files that are opened in your workspace. (To replace the files in the changelist with files open at a specific change number, use the -c or -i options.) Only the user and workspace associated with a pending changelist can replace its shelved files.
-n	Preview the results of the shelve operation without actually shelving the files (that is, without overwriting any existing shelved files.)
g-opts	See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	write

To restore shelved files into a workspace	p4 unshelve	
---	-------------	--

## p4 sizes

#### Synopsis

Display size information for files in the depot.

#### Syntax 5 4 1

```
p4 [g-opts] sizes [-a -S] [-s | -z] [-b blocksize] file[revRange] ...
```

## Description

The p4 sizes command displays the sizes of files stored in the depot. When called with no options, only the size of the head revision of the file or files is displayed. One line of output is provided per file.

Use the -a option to see how much space is occupied by each individual revision in the specified revision range, rather than just the highest revision in the specified range. One line of output is provided per file, per revision.

Use the -s option to obtain the sum of all files specified. Only one line of output is provided, showing the file specification, the number of files summarized, the total number of bytes required, and (if the -b option is provided) the total number of blocks required.

The -z option works the same way as -s, but excludes space occupied by lazy copies (files that exist by virtue of integration operations). Use -z to estimate the space occupied by files on a Perforce server, and use -s to estimate the local diskspace requirement if files were synced to a client workspace.)

#### **Options**

-a	Include all revisions within the range, rather than just the highest revision in the range.
-b blocksize	Display results in blocks of blocksize bytes. Each accumulated file size is rounded up to the nearest blocksize bytes.
-s	Calculate the sum of the file sizes for the specified file argument.
-S	Display size information for shelved files only. If you use this option, revision specifications are not permitted.
- z	When calculating size information, exclude lazy copies.
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	list

- The p4 sizes command is functionally similar to the UNIX du command.
- If no revision range is specified, the implicit revision range of #1 through #head is assumed.
- File sizes are based on the normalized (UNIX linefeed convention) and uncompressed version of the depot file, regardless of how the file is represented when synced to a client workspace.

#### **Examples**

p4 sizes file.c	Show the size of the head revision of file.c in the depot.
p4 sizes -a file.c	Show the sizes of each revision of file.c stored in the depot.
p4 sizes -s -a file.c	Show the total size of all revisions of file.c stored in the depot.
p4 sizes -s -a -b 512 //depot/	Show the number of files and the total diskspace (in bytes and 512-byte blocks) currently used by a Perforce Server hosting //depot/
p4 sizes -s //workspace/	Show the number of files and the total local diskspace (in bytes) required to sync the head revisions of files mapped to the client workspace named workspace.

## p4 submit

#### **Synopsis**

Send changes made to open files to the depot.

## **Syntax**

```
p4 [g-opts] submit [-r] [-s] [-f submitoption]
p4 [g-opts] submit [-r] [-s] [-f submitoption] files
p4 [g-opts] submit [-r] [-f submitoption] -d description
p4 [g-opts] submit [-r] [-f submitoption] -d description files
p4 [g-opts] submit [-r] [-f submitoption] -c changelist#
p4 [g-opts] submit -i [-r] [-s] [-f submitoption]
```

## **Description**

When a file has been opened by p4 add, p4 edit, p4 delete, or p4 integrate, the file is listed in a *changelist*. The user's changes to the file are made only within in the client workspace copy until the changelist is sent to the depot with p4 submit.

By default, files are opened within the default changelist, but new numbered changelists can be created with p4 change. To submit the default changelist, use p4 submit; to submit a numbered changelist, use p4 submit -c changelist#.

By default, all files in the changelist are submitted to the depot, and files open for edit, add, and branch are closed when submitted, whether there are any changes to the files or not. To change this default behavior, set the SubmitOptions: field in the p4 client form for your workspace. To override your workspace's SubmitOptions: setting from the command line, use p4 submit -f submitoption.

When used with the default changelist, p4 submit brings up a form for editing in the editor defined by the EDITOR (or P4EDITOR) environment or registry variable. Files can be deleted from the changelist by deleting them from the form, but these files will remain open in the next default changelist. To close a file and remove it from all changelists, use p4 revert.

All changelists have a Status: field; the value of this field is pending or submitted. Submitted changelists have been successfully submitted with p4 submit; pending changelists have been created by the user but not yet been submitted successfully.

p4 submit works atomically: either all the files listed in the changelist are saved in the depot, or none of them are. p4 submit fails if it is interrupted, or if any of the files in the changelist are not found in the current client workspace, are locked in another client workspace, or require resolution and remain unresolved.

If p4 submit fails while processing the default changelist, the changelist is assigned the next number in the changelist sequence, and the default changelist is emptied. The

changelist that failed submission must be resubmitted by number after the problems are fixed.

To supply a changelist description from the command line, use the -d flag. No change description dialog is presented. The -d flag works only with the default changelist, not with numbered changelists.

#### **Form Fields**

Field Name	Туре	Description
Change:	Read-only	The change number, or new if submitting the default changelist.
Client:	Read-only	Name of current client workspace.
User:	Read-only	Name of current Perforce user.
Status:	Read-only, value	One of pending, submitted, or new. Not editable by the user.
		The status is new when the changelist is created; pending when it has been created but has not yet been submitted to the depot with p4 submit, and submitted when its contents have been stored in the depot with p4 submit.
Description:	Writable	Textual description of changelist. This value <i>must</i> be changed.
Jobs:	List	A list of jobs that are fixed by this changelist. This field does not appear if there are no relevant jobs.
		Any job that meets the jobview criteria as specified on the p4 user form are listed here by default, but can be deleted from this list.
Files:	List	A list of files being submitted in this changelist. Files can be deleted from this list, but cannot be changed or added.

# **Options**

-c changelist#	Submit changelist number changelist#.
	Changelists are assigned numbers either manually by the user with p4 change, or automatically by Perforce when submission of the default changelist fails.
-d description	Immediately submit the default changelist with the description supplied on the command line, and bypass the interactive form. This option is useful when scripting, but does not allow for jobs to be added, nor for the default changelist to be modified.
-f submitoption	Override the SubmitOptions: setting in the p4 client form. Valid submitoption values are:
	• submitunchanged
	All open files (with or without changes) are submitted to the depot. This is the default behavior of Perforce.
	• submitunchanged+reopen
	All open files (with or without changes) are submitted to the depot, and all files are automatically reopened in the default changelist.
	• revertunchanged
	Only those files with content or type changes are submitted to the depot. Unchanged files are reverted.
	• revertunchanged+reopen
	Only those files with content or type changes are submitted to the depot and reopened in the default changelist. Unchanged files are reverted and <i>not</i> reopened in the default changelist.
	• leaveunchanged
	Only those files with content or type changes are submitted to the depot. Any unchanged files are moved to the default changelist.
	• leaveunchanged+reopen
	Only those files with content or type changes are submitted to the depot. Unchanged files are moved to the default changelist, and changed files are reopened in the default changelist. This option is similar to submitunchanged+reopen, except that no unchanged files are submitted to the depot.
-i	Read a changelist specification from standard input. Input must be in the same format at that used by the p4 submit form.

-r	Reopen files for edit in the default changelist after submission. Files opened for add or edit in will remain open after the submit has completed.
-s	Allows jobs to be assigned arbitrary status values on submission of the changelist, rather than the default status of closed. To leave a job unchanged, use the special status of same.
	On new changelists, the fix status is displayed as the special status ignore. (If the status is left unchanged, the job is not fixed by the submission of the changelist.)
	This option works in conjunction with the -s option to p4 fix, and is intended for use in conjunction with defect tracking systems.
g-opts	See the Global Options section.

### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	write

- A file's location within the depot is determined by intersection of its locations in the client workspace with the client view as set within the p4 client form.
- The atomic nature of p4 submit allows files to be grouped in changelists according to their purpose. For example, a single changelist might contain changes to three files that fix a single bug.
- When used with a numbered changelist, p4 submit does not display a form. To change
  the description information for a numbered changelist, use p4 change -c
  changelist#.
- A single file pattern can be specified as a parameter to a p4 submit of the default changelist. This file pattern limits which files in the default changelist are included in the submission; files that don't match the file pattern are moved to the next default changelist.

The file pattern parameter to p4 submit can only be used when submitting the default changelist.

# **Examples**

p4 submit	Submit the default changelist. The user's revisions of the files in this changelist are stored in the depot.
p4 submit -c 41	Submit changelist 41.
p4 submit *.txt	Submit only those files in the default changelist that have a suffix of .txt. Move all the other files in the default changelist to the next default changelist.
p4 submit -d "header files" *.h	Submit only those files in the default changelist that have a suffix of .h, with a description of header files. No changelist form is displayed. Move all the other files in the default changelist to the next default changelist.

To create a new, numbered changelist	p4 chang	ge
To open a file in a client workspace and list it in a changelist	p4 add	
	p4 edit	
	p4 delet	ce
	p4 integ	grate
To move a file from one changelist to another	p4 reope	en
To remove a file from all changelists, reverting it to its previous state	p4 reve	rt
To view a list of changelists that meet particular criteria	p4 chang	ges
To read a full description of a particular changelist	p4 desci	ribe
To read files from the depot into the client workspace	p4 sync	
To edit the mappings between files in the client workspace and files in the depot	p4 clier	nt

## p4 sync

#### **Synopsis**

Copy files from the depot into the workspace.

#### **Syntax**

```
p4 [g-opts] sync [-f] [-k] [-n] [file[revRange]...]
p4 [g-opts] sync [-n] [-p] [file[revRange]...]
```

## **Description**

p4 sync brings the client workspace into sync with the depot by copying files matching its file pattern arguments from the depot to the client workspace. When no file patterns are specified on the command line, p4 sync copies a particular depot file only if it meets all of the following criteria:

- The file must be visible through the *client workspace view*;
- It must not already be opened by p4 edit, p4 delete, p4 add, or p4 integrate;
- It must not already exist in the client workspace at its latest revision (the head revision).

In new, empty, workspaces, all depot files meet the last two criteria, so all the files visible through the workspace view are copied into the user's workspace.

If file patterns are specified on the command line, only those files that match the file patterns and that meet the above criteria are copied.

If the file pattern contains a revision specifier, the specified revision is copied into the client workspace.

If the file argument includes a revision range, only files selected by the revision range are updated, and the highest revision in the range is used. Files that are no longer in the workspace view are not affected if the file argument includes a revision range.

The newly synced files are not available for editing until opened with p4 edit or p4 delete. Newly synced files are read-only; p4 edit and p4 delete make the files writable. Under normal circumstances, do not use your operating system's commands to make the files writable; instead, use Perforce to do this for you.

## **Options**

V	Force the sync. Perforce performs the sync even if the client workspace already has the file at the specified revision. If the file is writable, it is overwritten.
	This flag does not affect open files, but it <i>does</i> override the noclobber client option.
ť	Keep existing workspace files; update the have list without updating the client workspace. Use p4 sync -k only when you need to update the have list to match the actual state of the client workspace.
-n I	Display the results of the sync without actually performing the sync.
	This lets you make sure that the sync does what you think it does pefore you do it.
	Populate a client workspace, but do not update the have list. Any file that is already synced or opened is bypassed with a warning message.
a	This option is typically used for workspaces used in processes (such as certain build or publication environments) where there is no need to track the state of the workspace after it has first been synced.
g-opts S	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	read

- If the client view has changed since the last sync, the next sync removes from the client workspace those files that are no longer visible through the client view (unless a revision range is used), and copies into the client workspace those depot files that were not previously visible.
  - By default, any empty directories in the client view are cleared of files, but the directories themselves are not deleted. To remove empty directories upon syncing, turn on the rmdir option in the p4 client form.
- If a user has made certain files writable by using OS commands outside of Perforce's control, p4 sync will not normally overwrite those files. If the clobber option in the p4 client form has been turned on, however, these files will be overwritten.
- p4 flush is an alias for p4 sync -k. All of the warnings that apply to p4 flush also apply to p4 sync -k.

# Examples

•		
p4 synd		Copy the latest revision of all files from the depot to the client workspace, as mapped through the client view.
		If the file is already open in the client workspace, or if the latest revision of the file exists in the client workspace, it is not copied.
p4 synd	c file.c#4	Copy the fourth revision of file.c to the client workspace, with the same exceptions as in the example above.
p4 synd	c //depot/proj1/@21	Copy all the files under the //depot/proj1 directory from the depot to the client workspace, as mapped through the client view.
		Don't copy the latest revision; use the revision of the file in the depot after changelist 21 was submitted.
p4 synd	c @labelname	If <code>labelname</code> is a label created with p4 label, and populated with p4 labelsync, bring the workspace into sync with the files and revision levels specified in <code>labelname</code> .
		Files listed in <i>labelname</i> , but not in the workspace view, are not copied into the workspace.
		Files <i>not</i> listed in <i>labelname</i> are deleted from the workspace. (That is, @ <i>labelname</i> is assumed to apply to all revisions up to, and including, the revisions specified in <i>labelname</i> . This includes the nonexistent revision of the unlisted files.)
p4 synd	c @labelname,@labelname	Bring the workspace into sync with a label as with p4 sync @labelname, but preserve unlabeled files in the workspace.
		(The revision range @labelname, @labelname applies only to the revisions specified in the label name itself, and excludes the nonexistent revision of the unlisted files.)
p4 synd	@2001/06/24	Bring the workspace into sync with the depot as of midnight, June 24, 2001. (That is, include all changes made during June 23.)

p4 sync status%40june1st.txt	Sync a filename containing a Perforce wildcard by using the ASCII expression of the character's hexadecimal value. In this case, the file in the client workspace is status@junelst.txt.
	For details, see "Limitations on characters in filenames and entities" on page 274.
p4 sync file.c#none	Sync to the nonexistent revision of file.c; the file is deleted from the workspace.
p4 sync#none	Sync to the nonexistent revision of all files; all files in the workspace (that are under Perforce control) are removed.

To open a file in a client workspace and list it in a changelist	p4 add
	p4 edit
	p4 delete
	p4 integrate
To copy changes to files in the client workspace to the depot	p4 submit
To view a list of files and revisions that have been synced to the client workspace	p4 have

#### p4 tag

#### **Synopsis**

Tag files with a label.

#### **Syntax**

```
p4 [g-opts] tag [ -d -n ] -l labelname file[revRange]...
```

## **Description**

Use p4 tag to tag specified file revisions with a label. A <code>labelname</code> is required. If a label named <code>labelname</code> does not exist, it is created automatically. If the label already exists, you must be the <code>Owner:</code> of the label and the label must be <code>unlocked</code> in order for you to tag or untag files with the label. (Use p4 <code>label</code> to change label ownership or lock status.)

If the file argument does not include a revision specification, the head revision is tagged with the label. If the file argument includes a revision range specification, only files with revisions in that range are tagged. (If more than one revision of the file exists in the specified range, the highest revision in the specified range is tagged.)

## **Options**

-d	Delete the label tag from the named files.
-n	Display what p4 tag would do without actually performing the operation.
-1 labelname	Specify the label to be applied to file revisions
g-opts	See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	list

 By default, p4 tag operates on the head revision of files in the depot. To preserve the state of a client workspace, use p4 labelsync, which operates on the revision of files last synced to your workspace.

# **Examples**

p4 tag -l rel1 //depot/1.0/	Tag the head revisions of files in //depot/1.0/ with label rel1.
	If the label rel1 does not exist, create it.
p4 tag -l build //depot/1.0/@1234	Tag the most recent revisions as of the submission of changelist 1234 of files in //depot/1.0/ with label build.
	If the label build does not exist, create it.
p4 files @labelname	List the file revisions tagged by <code>labelname</code> .

To create or edit a label	p4	label
To list all labels known to the system	p4	labels
To tag revisions in your client workspace with a label	p4	labelsync
To create a label and tag files with the label	p4	tag

## p4 tickets

#### **Synopsis**

Display all tickets granted to a user by p4 login.

#### **Syntax**

p4 [g-opts] tickets

## **Description**

The p4 tickets command lists all tickets stored in the user's ticket file.

#### **Options**

g-opts See the Global Options section.

#### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	none

• Tickets are stored in the file specified by the P4TICKETS environment variable. If this variable is not set, tickets are stored in %USERPROFILE%\p4tickets.txt on Windows, and in \$HOME/.p4tickets on other operating systems.

#### **Examples**

p4 tickets	Display all tickets stored in a user's local ticket file.
------------	---

To start a login session (to obtain a ticket)	p4 login
To end a login session (to delete a ticket)	p4 logout

## p4 triggers

## **Synopsis**

Edit a list of scripts to be run conditionally whenever changelists are submitted, forms are updated, or when integrating Perforce with external authentication mechanisms.

## **Syntax**

```
p4 [g-opts] triggers
p4 [g-opts] triggers -i
p4 [g-opts] triggers -o
```

#### **Description**

Perforce *triggers* are user-written scripts that are called by a Perforce server whenever certain operations (such as changelist submission or changes to forms) are performed. If the script returns a value of 0, the operation continues; if the script returns any other value, the operation fails. Upon failure, the script's standard output (not error output) is used as the text of the failed operation's error message.

Perforce supports a wide range of trigger types, divided into six categories.

- Changelist submission triggers (change-submit, change-content, and change-commit) are fired when users submit changelists.
- Shelve triggers (shelve-submit, shelve-commit, and shelve-delete) are similar to changelist submission triggers, but fire when users shelve files or delete shelved files.
- Fix triggers (fix-add and fix-delete) are fired when fixes are added or deleted from changelists by means of the p4 fix, p4 submit, or p4 change commands.
- *Form triggers* (form-save, form-out, form-in, form-commit, and form-delete) are fired when users generate or modify data in form specifications.
- Authentication triggers (auth-check and auth-set) are fired when administrators wish
  to integrate Perforce with external authentication mechanisms such as LDAP or Active
  Directory.
- Archive triggers (archive) are used to work with content archived outside the Perforcemanaged repository.

Use the change-submit trigger type to create triggers that fire after changelist creation, but before files are transferred to the server. Because change-submit triggers fire before files are transferred to the server, submit triggers cannot access file contents. Submit triggers are useful for integration with reporting tools or systems that do not require access to file contents.

Use the change-content trigger type to create triggers that fire after changelist creation and file transfer, but prior to committing the submit to the database.

Use the change-commit trigger type to create triggers that fire after changelist creation, file transfer, and changelist commission to the database. Use commit triggers for processes that assume (or require) the successful submission of a changelist.

Even when a change-submit or change-content trigger script succeeds, the submit can fail because of subsequent trigger failures, or for other reasons. Use change-submit and change-content triggers only for validation, and use change-commit triggers or daemons for operations that are contingent on the successful completion of the submit.

To configure Perforce to run trigger scripts when users fix jobs, use *fix triggers*: these are triggers of type fix-add and fix-delete. Use fix triggers to execute commands when users add or remove fixes from changelists.

To configure Perforce to run trigger scripts when users edit specification forms, use *form triggers*: these are triggers of type form-save, form-in, form-out, form-commit, and form-delete. Use form triggers to generate customized specification values for users, validate data submitted in forms, to notify other users of attempted changes to the values stored in specification forms, and to otherwise interact with process control and management tools.

To use an external password authentication manager (such as LDAP or Active Directory) with Perforce, use *authentication triggers* (auth-check and auth-set). Use the <code>%user%</code> variable to pass the user's username in the command for the script. Passwords typed by the user as part of the authentication process are supplied to authentication scripts as standard input; never on the command line. For further information, see the *System Administrator's Guide*.

Archive triggers (archive) are a special case, and are reserved for storing, managing, or generating content archived outside of the Perforce repository.

Triggers are run in the order listed in the table; if a trigger script fails for a specified type, subsequent trigger scripts also associated with that type are not run.

To use the same trigger script with multiple file patterns, list the same trigger multiple times in the trigger table. Use exclusionary mappings to prevent files from activating the trigger script; the order of the trigger entries matters, just as it does when exclusionary mappings are used in views. If a particular trigger name and type is listed multiple times, only the script corresponding to the first use of the trigger name and type is activated.

## **Form Fields**

The p4 triggers form contains a single Triggers: field. Like other Perforce forms, indent each row under the Triggers: field with tabs. Each row holds four values:

Field	Meaning
name	The user-defined name of the trigger.
	A run of the same trigger name on contiguous lines is treated as a single trigger, so that multiple paths can be specified. In this case, only the command of the first such trigger line is used.
type	Trigger types are divided into six subtypes: changelist submission triggers, shelve triggers, fix triggers, form triggers, authentication triggers, and archive triggers.
	Changelist submission triggers:
	• change-submit: Execute a changelist trigger after changelist creation, but before file transfer. Trigger cannot access file contents.
	<ul> <li>change-content: Execute a changelist trigger after changelist creation and file transfer, but before file commit.</li> </ul>
	To obtain file contents, use commands such as p4 diff2, p4 files, p4 fstat, and p4 print with the revision specifier @=change, where change is the changelist number of the pending changelist as passed to the script in the %changelist% variable.
	• change-commit: Execute a changelist trigger after changelist creation, file transfer, and changelist commit.
	Shelve triggers:
	<ul> <li>shelve-submit: Execute a pre-shelve trigger after changelist has been created and files locked, but prior to file transfer.</li> </ul>
	• shelve-commit: Execute a post-shelve trigger after files are shelved.
	<ul> <li>shelve-delete: Execute a shelve trigger prior to discarding shelved files.</li> </ul>
	Fix triggers:
	The special variable <code>%jobs%</code> is available for expansion; it expands to one argument for every job listed on the p4 fix command line (or in the Jobs: field of a p4 change or p4 submit form), and must therefore be the last argument supplied to the trigger script.
	<ul><li>fix-add: Execute fix trigger prior to adding a fix.</li><li>fix-delete: Execute fix trigger prior to deleting a fix.</li></ul>

#### Field Meaning

#### Form triggers:

- form-save: Execute a form trigger after the form contents are parsed, but before the contents are stored in the Perforce database. The trigger cannot modify the form specified in <code>%formfile%</code> variable.
- form-out: Execute form trigger upon generation of form to end user. The trigger can modify the form.
- form-in: Execute form trigger on edited form before contents are parsed and validated by the Perforce server. The trigger can modify the form.
- form-delete: Execute form trigger after the form contents are parsed, but before the specification is deleted from the Perforce database. Trigger cannot modify form.
- form-commit: Execute form trigger after the form has been committed for access to automatically-generated fields such as jobname, dates, etc.

  For job forms, this trigger is run by p4 job as well as p4 fix (after the status is updated). The form-commit trigger has access to the new job name created by p4 job; any form-in and form-save triggers are run before the job name is created.
  - For job forms, this trigger is also run by p4 change (if a job is added or deleted by editing the Jobs: field of the changelist), and p4 submit (for any jobs present in the Jobs: field of the changelist). In these cases, the special variable %action% is available for expansion on the job formcommit trigger command line. The trigger cannot modify the form.

#### Authentication triggers:

- auth-check: Execute an authentication check trigger to verify a user's password against an external password manager during login, or when setting a new password If an auth-check trigger is present, the Perforce security counter (and any associated password strength requirement) is ignored, as authentication is now controlled by the trigger script.
- auth-set: Execute an authentication set trigger to send a new password to an external password manager.

You must restart the Perforce server after adding an auth-check trigger. Archive triggers:

• archive: Execute the script when a user accesses any file with a filetype containing the +x filetype modifier.

The script is run once per file requested.

For read operations, scripts should deliver the file to the user on standard output. For write operations, scripts receive the file on standard input.

Field	Meaning
path	For changelist and shelve triggers (change-submit, change-content, change-commit, shelve-submit, shelve-commit, and shelve-delete), a file pattern in depot syntax. When a user submits a changelist that contains any files that match this file pattern, the script linked to this trigger is run. Use exclusionary mappings to prevent triggers from running on specified files.
	For fix triggers (fix-add or fix-delete), use fix as the path value.
	For form triggers (form-save, form-out, form-in, form-commit, or form-delete), the name of the type of form, (one of branch, change, client, depot, group, job, label, protect, spec, triggers, typemap, or user).
	For authentication triggers (auth-check or auth-set), use auth as the path value.
command	The command for the Perforce server to run when a matching <code>path</code> applies for the trigger type. Specify the command in a way that allows the Perforce server account to locate and run the command. The command must be quoted, and can take the variables specified below as arguments.
	For change-submit and change-content triggers, changelist submission continues if the trigger script exits with 0, or fails if the script exits with a nonzero value. For change-commit triggers, changelist submission succeeds regardless of the trigger script's exit code, but subsequent change-commit triggers do not fire if the script exits with a nonzero value.
	For form-in, form-out, form-save, and form-delete triggers, the data in the specification becomes part of the Perforce database if the script exits with 0. Otherwise, the database is not updated.
	The form-commit trigger type never rejects a change; it exists primarily so that scripts can access a job number (from the %formname% variable) during the process of job creation.
	For fix-add and fix-delete triggers, fix addition or deletion continues if the trigger script exits with 0, or fails if the script exits with a nonzero value.
	For auth-check triggers (fired by p4 login), the user's typed password is supplied to the trigger command as standard input. If the trigger executes successfully, the Perforce ticket is issued. The user name is available as <code>%user%</code> to be passed on the command line.
	For auth-set triggers, (fired by p4 passwd, but only after also passing an auth-check trigger check) the user's old password and new password are passed to the trigger as standard input. The user name is available as <code>%user%</code> to be passed on the command line.

## **Options**

-i	Read the trigger table from standard input without invoking the editor.
-0	Write the trigger table to standard output without invoking the editor.
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	super

**Warning!** Never use a Perforce command in an out trigger that fires the same out trigger, or infinite recursion will result. For example, never run p4 job -o from within an out trigger script that fires on job specifications.

**Warning!** If you write a trigger that fires on trigger forms, and the trigger fails in such a way that the p4 triggers command no longer works, the only recourse is to remove the db.triggers file in the server root directory.

• To pass arguments to the trigger script, use the following variables:

Argument	Description	Available for type
%action%	Either null or a string reflecting an action taken to a changelist or job.	form-commit
	For example, "pending change 123 added" or "submitted change 124 deleted" are possible %action% values on change forms, and "job000123 created" or "job000123 edited" are possible %action% values for job forms.	
<pre>%changelist% %change%</pre>	The number of the changelist being submitted. The abbreviated form %change% is equivalent to %changelist%.  A change-submit trigger is passed the pending changelist number; a change-commit trigger receives the committed changelist number.	change-submit, change-content, change-commit, fix-add, fix-delete, form-commit
%changeroot%	The root path of files submitted	change-commit
%client%	Triggering user's client workspace name.	all but archive

%clienthost%         Hostname of the client.         all but archive           %clientip%         The IP address of the client.         all but archive           %jobs%         A string of job numbers, expanded to one argument for each job number specified on a p4 fix command or for each job number added to (or removed from) the Jobs: field in a p4 submit, or p4 change form.         change-commit           %oldchangelist%         If a changelist is renumbered on submit, this variable contains the old changelist number.         change-commit           %serverhost%         Hostname of the Perforce server.         all but archive           %serverport%         The IP address of the server.         all but archive           %serverport%         The IP address and port of the Perforce server, in the format ip_address:port.         all but archive           %serverport%         The P4ROOT directory of the Perforce server.         all but archive           %serverport%         The P4ROOT directory of the Perforce server.         all but archive           %serverport%         The p4ROOT directory of the Perforce server.         all but archive           %serverport%         The p4ROOT directory of the Perforce server.         all but archive           %serverport%         Path to temporary form specification file. To modify the form from an in or out trigger, overwrite this file. The file is read-only for form-out, form-out, form-save, form-out, form-save, form-out, form-save, form-out, form-save, form-out, form-	Argument	Description	Available for type
#jobs* A string of job numbers, expanded to one argument for each job number specified on a p4 fix command or for each job number added to (or removed from) the Jobs: field in a p4 submit, or p4 change form.  *oldchangelist* If a changelist is renumbered on submit, this variable contains the old changelist number.  *serverhost* Hostname of the Perforce server.  *serverip* The IP address of the server.  *serverport* The IP address and port of the Perforce server, in the format ip_address:port.  *serverroot* The P4ROOT directory of the Perforce server.  *serveriple* Perforce username of the triggering user.  *formfile* Path to temporary form specification file. To modify the form from an in or out trigger, overwrite this file. The file is read-only for triggers of type save and delete.  *formname* Name of form (for instance, a branch name or a changelist number).  *form save, form-out, form-delete  *formtype* Type of form (for instance, branch, change, and so on).  Type of form (for instance, branch, change, and so on).  *form-save, form-out, form-delete  *form-save, form-out,	%clienthost%	Hostname of the client.	all but archive
argument for each job number specified on a p4 fix command or for each job number added to (or removed from) the Jobs: field in a p4 submit, or p4 change form.  *oldchangelist* If a changelist is renumbered on submit, this variable contains the old changelist number.  *serverhost* Hostname of the Perforce server.  *serverip* The IP address of the server.  *serverport* The IP address and port of the Perforce server, in the format ip_address:port.  *serverroot* The P4ROOT directory of the Perforce server.  *serverip* Perforce username of the triggering user.  *formfile* Path to temporary form specification file. To modify the form from an in or out trigger, overwrite this file. The file is read-only for triggers of type save and delete.  *form-out, form-delete  *formname* Name of form (for instance, a branch name or a changelist number).  *form-out, form-out, form-delete  *formtype* Type of form (for instance, branch, change, and so on).  *form-out, form-out, form-delete  *form* Operation: read, write, or delete  *form* Operation: read, write, or delete  *file* Path of archive file based on depot's Map: field.  If the Map: field is relative to P4ROOT, the  *file* is a server-side path relative to P4ROOT.  If the Map: field is an absolute path, the *file* is an absolute server-side path.	%clientip%	The IP address of the client.	all but archive
variable contains the old changelist number.  *serverhost* Hostname of the Perforce server. all but archive  *serverip* The IP address of the server. all but archive  *serverport* The IP address and port of the Perforce server, in the format ip_address:port.  *serverroot* The P4ROOT directory of the Perforce server.  *user* Perforce username of the triggering user.  *formfile* Path to temporary form specification file. To modify the form from an in or out trigger, overwrite this file. The file is read-only for triggers of type save and delete.  *form-out, form-delete  *formname* Name of form (for instance, a branch name or a changelist number).  *form-save, form-out, form-delete  *formtype* Type of form (for instance, branch, change, and so on).  *op* Operation: read, write, or delete  *file* Path of archive file based on depot's Map: field.  If the Map: field is relative to P4ROOT, the  *file* is a server-side path relative to P4ROOT.  If the Map: field is an absolute path, the *file* is an absolute server-side path.	%jobs%	argument for each job number specified on a p4 fix command or for each job number added to (or removed from) the Jobs: field in	
**serverip* The IP address of the server.  **serverport* The IP address and port of the Perforce server, in the format ip_address:port.  **serverroot* The P4ROOT directory of the Perforce server.  **user* Perforce username of the triggering user.  *formfile* Path to temporary form specification file. To modify the form from an in or out trigger, overwrite this file. The file is read-only for triggers of type save and delete.  *form-out, form-in, form-delete  *formtype* Type of form (for instance, a branch name or a changelist number).  Type of form (for instance, branch, change, and so on).  Type of form (for instance, branch, change, and so on).  *form-out, form-out,	%oldchangelist%	· · · · · · · · · · · · · · · · · · ·	change-commit
The IP address and port of the Perforce server, in the format $ip\_address:port$ .  *serverroot* The P4ROOT directory of the Perforce server.  *user* Perforce username of the triggering user.  *formfile* Path to temporary form specification file. To modify the form from an in or out trigger, overwrite this file. The file is read-only for triggers of type save and delete.  *form-out, form-delete  *formname* Name of form (for instance, a branch name or a changelist number).  Type of form (for instance, branch, change, and so on).  Type of form (for instance, branch, change, form-commit, form-delete  *form-out, form-out, fo	%serverhost%	Hostname of the Perforce server.	all but archive
in the format $ip\_adress:port$ .  *serverroot* The P4ROOT directory of the Perforce server. all but archive  *user* Perforce username of the triggering user.  *formfile* Path to temporary form specification file. To modify the form from an in or out trigger, overwrite this file. The file is read-only for triggers of type save and delete.  *form-out, form-delete  *formname* Name of form (for instance, a branch name or a changelist number).  Type of form (for instance, branch, change, and so on).  Type of form (for instance, branch, change, form-out, fo	%serverip%	The IP address of the server.	all but archive
Perforce username of the triggering user.  Path to temporary form specification file. To modify the form from an in or out trigger, overwrite this file. The file is read-only for triggers of type save and delete.  Path of form (for instance, a branch name or a changelist number).  Name of form (for instance, a branch name or a changelist number).  Type of form (for instance, branch, change, and so on).  Type of form (for instance, branch, change, form-commit, form-save, form-out, form-out, form-out, form-out, form-out, form-out, form-in, form-delete  Path of archive file based on depot's Map: field.  If the Map: field is relative to P4ROOT, the %file% is a server-side path, the %file% is an absolute server-side path.	%serverport%		all but archive
Path to temporary form specification file. To modify the form from an in or out trigger, form-save, form-out, triggers of type save and delete.  Name of form (for instance, a branch name or a changelist number).  Type of form (for instance, branch, change, and so on).  Type of form (for instance, branch, change, form-commit, form-save, form-out, form-out	%serverroot%	The P4ROOT directory of the Perforce server.	all but archive
modify the form from an in or out trigger, overwrite this file. The file is read-only for triggers of type save and delete.  *form-out, form-in, form-delete  *formname*  Name of form (for instance, a branch name or a changelist number).  Type of form (for instance, branch, change, and so on).  Type of form (for instance, branch, change, form-commit, form-save, form-out, form-out, form-out, form-out, form-out, form-out, form-in, form-delete  *op*  Operation: read, write, or delete archive  file* is a server-side path relative to P4ROOT.  If the Map: field is an absolute path, the *file* is an absolute server-side path.	%user%	Perforce username of the triggering user.	all but archive
changelist number).  changelist number).  form-save, form-out, form-delete  form-commit, form-save, form-save, form-out, form-out, form-out, form-in, form-delete  %op%  Operation: read, write, or delete  %file%  Path of archive file based on depot's Map: field.  If the Map: field is relative to P4ROOT, the %file% is a server-side path relative to P4ROOT.  If the Map: field is an absolute path, the %file% is an absolute server-side path.	%formfile%	modify the form from an in or out trigger, overwrite this file. The file is read-only for	form-save, form-out, form-in,
and so on).  and so on).  form-save, form-out, form-in, form-delete  Operation: read, write, or delete  archive  Path of archive file based on depot's Map: field.  If the Map: field is relative to P4ROOT, the %file% is a server-side path relative to P4ROOT.  If the Map: field is an absolute path, the %file% is an absolute server-side path.	%formname%	· · · · · · · · · · · · · · · · · · ·	form-save, form-out,
%file% Path of archive file based on depot's Map: field. archive  If the Map: field is relative to P4ROOT, the %file% is a server-side path relative to P4ROOT.  If the Map: field is an absolute path, the %file% is an absolute server-side path.	%formtype%		form-save, form-out, form-in,
If the Map: field is relative to P4ROOT, the %file% is a server-side path relative to P4ROOT.  If the Map: field is an absolute path, the %file% is an absolute server-side path.	%op%	Operation: read, write, or delete	archive
<pre>%file% is a server-side path relative to P4ROOT.  If the Map: field is an absolute path, the %file% is an absolute server-side path.</pre>	%file%	Path of archive file based on depot's Map: field.	archive
is an absolute server-side path.			
%rev% Revision of archive file archive			
	%rev%	Revision of archive file	archive

- If your trigger script needs to know what files were (or are about to be) submitted in the changelist, use the command p4 opened -ac changelist.
- Pre-submit trigger scripts cannot access submitted file contents from the server, because
  at the time a pre-submit trigger runs, file contents have not yet been transferred to the
  server.
- Perforce commands in trigger scripts are always run by a specific Perforce user. If no user is specified, an extra Perforce license for a user named SYSTEM (or on UNIX, the user that owns the p4d process) is assumed. To prevent this from happening:
  - Pass a <code>%user%</code> argument to the script that calls each Perforce command to ensure that each command is called by. For example, if Joe submits a changelist that activates trigger script trigger.pl, and trigger.pl calls the p4 changes command, the script can run the command as p4 -u <code>%user%</code> changes.
  - Set P4USER for the account that runs the trigger script to the name of an existing user. (If your Perforce server is installed as a service under Windows, note that Windows services cannot have a P4USER value; on Windows, you must therefore pass a user value to each command as described above.)
- For the four form trigger types (form-in, form-out, form-save, and form-delete), the %formname% variable is unset on job creation. This limitation is due to the fact that a job's name is unknown to the server until after job creation.

To access a job's name *during* job creation, use the form-commit trigger; it is the only trigger type that has access to a job's name (in the \*formname\* variable) during the process of job creation.

After job creation, subsequent user changes to a job correctly set %formname% for use by form trigger scripts.

• Trigger types were renamed in Release 2005.2. The following old trigger type names will continue to work but are deprecated:

Old trigger type	New trigger type (as of 2005.2)
submit	change-submit
content	change-content
commit	change-commit
out	form-out
in	form-in
save	form-save
delete	form-delete

- As of Release 2007.3, trigger standard output is passed to the client program on both success and failure of the trigger script. Prior to this, standard output was only passed to the client program upon failure of a trigger.
- You must specify the name of the trigger script or executable in ASCII, even when the server is running in Unicode mode and passes arguments to the trigger script in UTF8.

#### **Examples**

Suppose that the trigger table consists of the following entries:

```
Triggers:

trig1 change-submit //depot/dir/... "/usr/bin/s1.pl %changelist%"

trig2 change-submit //depot/dir/file "/usr/bin/s2.pl %user%"

trig1 change-submit -//depot/dir/z* "/usr/bin/s1.pl %user%"

trig1 change-submit //depot/dir/zed "/usr/bin/s3.pl %client%"
```

Both the first and third lines call the script /bin/s1.pl %changelist%, because the first occurrence of a particular trigger name determines which script is run when the trigger name is subsequently used.

No triggers are activated if someone submits file //depot/dir/zebra, because the third line excludes this file. If someone submits //depot/dir/zed, the trig1 script /usr/bin/s1.pl %changelist% is run: although the fourth line overrides the third, only the first script associated with the name trig1 is called.

For more detailed examples, see the System Administrator's Guide.

To obtain information about the changelist being submitted	p4 describe
	p4 opened
To aid daemon creation	p4 review
	p4 reviews
	p4 counter
	p4 counters
	p4 user

## p4 typemap

#### **Synopsis**

Modify the file name-to-type mapping table.

#### **Syntax**

```
p4 [g-opts] typemap
p4 [g-opts] typemap -i
p4 [g-opts] typemap -o
```

## **Description**

The p4 typemap command allows Perforce administrators to set up a table linking Perforce file types to file name specifications. If a filename matches an entry in the typemap table, it overrides the file type that would otherwise have been assigned by the Perforce client.

By default, Perforce automatically determines if a file is of type text or binary based on an analysis of the first 8192 bytes of a file. If the high bit is clear in each of the first 8192 bytes, Perforce assumes it to be text; otherwise, it's binary. Files compressed in the .zip format (including .jar files) are also automatically detected and assigned the type ubinary.

Although this default behavior can be overridden by the use of the -t filetype flag, it's easy to overlook this, particularly in cases where files' types were usually (but not always) detected correctly. The most common examples of this are associated with PDF files (which sometimes begin with over 8192 bytes of ASCII comments) and RTF files, which usually contain embedded formatting codes.

The p4 typemap command provides a more complete solution, allowing administrators to bypass the default type detection mechanism, ensuring that certain files (for example, those ending in .pdf or .rtf) will always be assigned the desired Perforce filetype upon addition to the depot.

Users can override any file type mapping defined in the typemap table by explicitly specifying the file type on the Perforce command line.

#### Form Fields

The p4 typemap form contains a single TypeMap: field, consisting of pairs of values linking file types to file patterns specified in depot syntax:

Column	Description
filetype	Any valid Perforce file type.
	For a list of valid file types, see the File Types section.
pattern	A file pattern in depot syntax.
	When a user adds a file matching this pattern, its default filetype will be the file type specified in the table.

#### **Options**

-i	Reads the typemap table from standard input without invoking the user's editor.
-0	Writes the typemap table to standard output without invoking the user's editor.
g-opts	See the <i>Global Options</i> section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	admin, or list to use the -o flag

- To specify all files with a given extension at or below a desired subdirectory, use four periods after the directory name, followed by the extension. (for instance, //path/...ext) The first three periods specify "all files below this level". The fourth period and accompanying file extension are parsed as "ending in these characters".
- File type modifiers can be used in the typemap table. Useful applications include forcing keyword expansion on or off across directory trees, enforcing the preservation of original file modification times (the +m file type modifier) in directories of third-party DLLs, or implementing pessimistic locking policies.
- Specify multiple file type modifiers consecutively. For example, binary+1FS10 refers to a binary file with exclusive-open (1), stored in full (F) rather than compressed, and for which only the most recent ten revisions are stored (S10). For more information on syntax, see the *File Types* section.

• If you use the -t flag and file type modifiers to specify a file type on the command line, and the file to which you are referring falls under a p4 typemap mapping, the file type specified on the command line overrides the file type specified by the typemap table.

#### **Examples**

To tell the Perforce server to regard all PDF and RTF files as binary, use p4 typemap to modify the typemap table as follows:

```
Typemap:

binary //...pdf

binary //...rtf
```

The first three periods ("...") in the specification are a Perforce wildcard specifying that all files beneath the root directory are included as part of the mapping. The fourth period and the file extension specify that the specification applies to files ending in ".pdf" (or ".rtf")

A more complicated situation might arise in a site where users in one area of the depot use the extension . doc for plain ASCII text files containing documentation, and users working in another area use . doc to refer to files in a binary file format used by a popular word processor. A useful typemap table in this situation might be:

```
Typemap:
    text //depot/dev_projects/....doc
    binary //depot/corporate/annual_reports/....doc
```

To enable keyword expansion for all .c and .h files, but disable it for your .txt files, do the following:

```
Typemap:
    text+k //depot/dev_projects/main/src/...c
    text+k //depot/dev_projects/main/src/...h
    text //depot/dev_projects/main/src/....txt
```

To ensure that files in a specific directory have their original file modification times preserved (regardless of submission date), use the following:

```
Typemap:

binary //depot/dev_projects/main/bin/...

binary+m //depot/dev_projects/main/bin/thirdpartydll/...
```

All files at or below the bin directory are assigned type binary. Because later mappings override earlier mappings, files in the bin/thirdpartydll subdirectory are assigned type binary+m instead. For more information about the +m (modtime) file type modifier, see the *File Types* section.

By default, Perforce supports concurrent development, but environments in which only one person is expected to have a file for edit at a time can implement pessimistic locking by using the +1 (exclusive open) modifier as a partial filetype. If you use the following typemap, the +1 modifier is automatically applied to all newly-added files in the depot:

```
Typemap:
     +1 //depot/...
```

To add a new file with a specific type, overriding the	p4 add -t <i>type file</i>
typemap table	
To change the filetype of an opened file, overriding any settings in the typemap table	p4 reopen -t type file

# p4 unlock

### **Synopsis**

Release the lock on a file.

### **Syntax**

```
p4 [g-opts] unlock [-c changelist#] [-f] file...
```

### **Description**

The p4 unlock command releases locks created by p4 lock.

If the file is open in a pending changelist other than default, then you must use the -c flag to specify the pending changelist. If no changelist is specified, p4 unlock unlocks files in the default changelist.

Administrators can use the -f option to forcibly unlock a file opened by another user.

If no file name is given, all files in the designated changelist are unlocked.

## **Options**

-c changelist#	Unlock files in pending changelist changelist#
-f	Superuser force flag; allows unlocking of files opened by other users.
g-opts	See the Global Options section.

## **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	write

#### **Related Commands**

To lock files so other users can't submit them	p4 lock
To display all your open, locked files (UNIX)	p4 opened   grep "*locked*"

# p4 unshelve

# **Synopsis**

Restore shelved files from a pending change into a workspace

### **Syntax**

```
p4 unshelve -s changelist [-f] [-n] [-c changelist] [file ...]
```

# **Description**

The p4 unshelve command retrieves files that are shelved in a pending changelist into a pending changelist on the invoking user's workspace. Access to shelved files from a pending changelist is controlled by the user's permissions on the files.

You can limit the files to be unshelved by specifying a file pattern.

Unshelving copies the shelved files into the user's workspace as they existed when they were shelved. (For example, a file open for edit when shelved will also be open for edit in the unshelving user's workspace.)

## **Options**

-s changelist	Specify the pending changelist number that contains the originally-shelved files.
-c changelist	Specify a changelist number in the user's workspace into which the files are to be unshelved. By default, p4 unshelve retrieves files into the default changelist.
-f	Force the overwriting of writable (but unopened) files during the unshelve operation.
-n	Preview the results of the unshelve operation without actually restoring the files to your workspace.
g-opts	See the Global Options section.

### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	open

### **Related Commands**

To store files from a pending changelist into the p4 shelve depot without submitting them.

### p4 user

### **Synopsis**

Create or edit Perforce user specifications and preferences.

### Syntax 5 4 1

```
p4 [g-opts] user [-f] [username]
p4 [g-opts] user -d [-f] username
p4 [g-opts] user -o [username]
p4 [g-opts] user -i [-f]
```

## Description

By default, any system user becomes a valid Perforce user the first time he uses any Perforce command that can update the depot or its metadata. Perforce automatically creates a user spec with default settings for the invoking user. Use the p4 user command to edit these settings or to create new user records. (After installing Perforce, use p4 protect as a Perforce superuser to prevent automatic creation of new users.)

When called without a *username*, p4 user edits specification of the current user. When called with a *username*, the user specification is displayed, but cannot be changed. The form appears in the editor defined by the P4EDITOR environment or registry variable.

Perforce superusers can create new users or edit existing users' specifications with the -f (force) flag: p4 user -f username.

The user who gives a Perforce command is not necessarily the user under whose name the command runs. The user for any particular command is determined by the following:

- If the user running the command is a Perforce superuser, and uses the syntax p4 user -f username, user username is edited.
- If the -u username flag is used on the command line (for instance, p4 -u joe submit), the command runs as that user (a password may be required);
- If the above hasn't been done, but the file pointed to by the P4CONFIG environment or registry variable contains a setting for P4USER, then the command runs as that user.
- If neither of the above has been done, but the P4USER environment or registry variable
  has been set, then the command runs as that user.
- If none of the above apply, then the username is taken from the OS level USER or USERNAME environment variable.

### **Form Fields**

Field Name	Туре	Description
User:	Read-only	The Perforce username under which p4 user was invoked. By default, this is the user's system username.
Email:	Writable	The user's email address. By default, this is user@client.
Update:	Read-only	The date and time this specification was last updated.
Access:	Read-only	The date and time this user last ran a Perforce command.
FullName:	Writable	The user's full name.
JobView:	Writable	A description of the jobs to appear automatically on all new changelists (described in the <i>Usage Notes</i> below).
Password:	Writable	The user's password (described in the <i>Usage Notes</i> below).
Reviews:	Writable List	A list of files the user would like to review (see the <i>Usage Notes</i> below).

# **Options**

-d username	Deletes the specified user. Only user <i>username</i> , or the Perforce superuser, can run this command.
-f	Superuser force flag; allows the superuser to modify or delete the specified user, or to change the last modified date.
-i	Read the user specification from standard input. The input must conform to the p4 user form's format.
-0	Write the user specification to standard output.
g-opts	See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	list

- The -d flag can be used by non-superusers only to delete the user specification that invoked the p4 user command. Perforce superusers can delete any Perforce user.
- User deletion fails if the specified user has any open files. Submit or revert these files before deleting users.

• By default, user records are created without passwords, and any Perforce user can impersonate another by setting P4USER or by using the *globally available* -u flag. To prevent another user from impersonating you, set a password with the p4 passwd command.

Passwords can be created, edited, or changed in the p4 user form or by using the p4 passwd command. Setting your password in the p4 user form is only supported at security levels 0 or 1. You can p4 passwd to set passwords at any server security level, and you *must* use p4 passwd to set passwords at higher security levels. For more about how the various security levels, see the *System Administrator's Guide*.

If you edit a password in the p4 user form, do not use the comment character # within the password; Perforce interprets everything following that character on the same line as a comment, and does not store it as part of the password.

- Passwords are displayed as six asterisks in the p4 user form regardless of their length.
- If you are using ticket-based authentication (see p4 login for details), changing your password automatically invalidates all of your outstanding tickets.
- The collected values of the Email: fields can be listed for each user with the p4 users command, and can used for any purpose.
- The p4 reviews command, which is used by the Perforce change review daemon, uses the values in the Reviews: field; when activated, it will send email to users whenever files they've subscribed to in the Reviews: field have changed. Files listed in this field must be specified in depot syntax; for example, if user joe has a Reviews: field value of

```
//depot/main/...
//depot/.../README
```

then the change review daemon sends joe email whenever any README file has been submitted, and whenever any file under //depot/main has been submitted.

• There is a special setting for job review when used with the Perforce change review daemon. If you include the value:

```
//depot/jobs
```

in your Reviews: field, you will receive email when jobs are changed.

• If you set the Jobview: field to any valid jobview, jobs matching the jobview appear on any changelists created by this user. Jobs that are fixed by the changelist should be left in the changelist when it's submitted with p4 submit; other jobs should be deleted from the form before submission.

For example, suppose the jobs at your site have a field called Owned-By:. If you set the Jobview: field on your p4 user form to Owned-By=yourname&status=open, all open jobs owned by you appear on all changelists you create. See p4 jobs for a full description of jobview usage and syntax.

# **Examples**

p4 user joe	View the user specification of Perforce user joe.
p4 user	Edit the user specification for the current Perforce user.
p4 user -d sammy	Delete the user specification for the Perforce user sammy.
p4 -u joe -P hey submit	Run p4 submit as user joe, whose password is hey.
	This command does not work at higher security levels.
p4 user -f joe2	Create a new Perforce user named joe2 if the caller is a Perforce superuser, and joe2 doesn't already exist as a Perforce user. If user joe2 already exists, allow a Perforce superuser to modify the user's settings.

# **Related Commands**

To view a list of all Perforce users	p4 users
To change a user's password	p4 passwd
To view a list of users who have subscribed to review particular files	p4 reviews

# p4 users

### **Synopsis**

Print a list of all known users of the current server.

### **Syntax**

```
p4 [g-opts] users [ -m max ] [ user... ]
```

## **Description**

p4 users displays a list of all the users known to the current Perforce server. For each user, the information displayed includes their Perforce user name, their email address, their real name, and the date and time the user last accessed the server.

If a *user* argument is provided, only information pertaining to that user is displayed. The *user* argument can contain the \* wildcard; in this case, all users matching the given pattern are reported on. (If you use a wildcard, be sure to quote the user argument, because the OS will likely attempt to expand the wildcard to match file names in the current directory).

Use the -m max option to limit the output to the first max users.

## **Options**

-m max	List only the first max users.
g-opts	See the Global Options section.

# **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
N/A	N/A	list

### **Related Commands**

To add or edit information about a particular user	p4 user
To edit information about the current client workspace	p4 client

# p4 verify

### **Synopsis**

Verify that the server archives are intact.

### **Syntax**

```
p4 [g-opts] verify [ -m maxRevs ] [-q ] [ -u | -v | -z ] file[revRange] ...
```

# **Description**

p4 verify reports the revision specific information and an MD5 digest (fingerprint) of the revision's contents.

If invoked without arguments, p4 verify computes and displays the MD5 digest of each revision. If a revision is missing from the archive and therefore can't be reproduced, the revision's output line ends with MISSING! If the digests differ, the output line for the corrupt file ends with BAD!

# **Options**

-q	Run quietly; verify the integrity of files for which MD5 digests have previously been generated, and only display output if there are errors.
-u	Store the filesize and MD5 digest of each file in the Perforce database if and only if no filesize and/or digest has been previously stored. Subsequent uses of p4 verify will compare the computed version against this stored version.
-v	Store the MD5 digest of each file in the Perforce database, even if there's already a digest stored for that file, overwriting the existing digest. (The -v flag is used only to update the saved digests of archive files which have been deliberately altered outside of Perforce control by a Perforce system administrator.)
- Z	Skip revisions that have already been computed in the current pass; this option speeds verifications in the cases of revisions which exist via lazy copies.
-m maxRevs	Limit p4 verify to maxRevs revisions.
g-opts	See the Global Options section.

### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
Yes	Yes	admin

- If p4 verify returns errors, contact Perforce technical support.
- It is good administrative practice to regularly verify the integrity of your depot files with p4 verify -q //...

For details, see the Perforce System Administrator's Guide.

As of Release 2005.1, Perforce Servers track file length metadata on a per-revision basis.
 Newly submitted files have file length metadata added to the database automatically.
 (You must still run p4 verify -u at least once following an upgrade to 2005.1, in order to update file length metadata for any pre-2005.1 files for which file lengths were not stored.)

Administrators of very large sites (such as those with tens of millions of revisions) may encounter memory constraints immediately following an upgrade to 2005.1 if they attempt to update file length metadata for the entire repository at once. If this is the case, use the -m maxRevs flag to limit the number of revisions updated per command; p4 verify -u -m 1000000 //... limits file length metadata recomputation to a million files at a time, enabling an administrator to divide file length metadata recomputation over several calls to p4 verify.

# p4 where

### **Synopsis**

Show where a particular file is located, as determined by the client view.

### **Syntax**

```
p4 [g-opts] where [file...]
```

## **Description**

p4 where uses the client view and client root, as set in p4 client, to print files' locations relative to the top of the depot, relative to the top of the client workspace, and relative to the top of the local OS directory tree. The command does not check to see if the file exists; it merely reports where the file *would be* located if it *did* exist.

For each file provided as a parameter, a set of mappings is output. Each set of mappings is composed of lines consisting of three parts: the first part is the filename expressed in depot syntax, the second part is the filename expressed in client syntax, and the third is the local OS path of the file.

### **Options**

g-opts See the Global Options section.

### **Usage Notes**

Can File Arguments Use Revision Specifier?	Can File Arguments Use Revision Range?	Minimal Access Level Required
No	No	list

• The mappings are derived from the client view: a simple client view, mapping the depot to one directory in the client workspace, produces one line of output.

More complex client views produce multiple lines of output, possibly including exclusionary mappings. For instance, given the client view:

Running p4 where //a/b/file.txt gives:

```
-//a/b/file.txt //client/a/b/file.txt //home/user/root/a/b/file.txt
//a/b/file.txt //client/b/file.txt /home/user/root/b/file.txt
```

This can be interpreted as saying that the first line of the client view would have caused the file to appear in /home/user/root/a/b/file.txt, except that it was overridden by the second mapping in the view. An exclusionary mapping was applied to perform the override, and the second mapping applies, sending the file to /home/user/root/b/file.txt.

• The simplest case (one line of output per file, showing each filename in depot, client, and local syntax) is by far the most common.

# **Examples**

p4 where file.c	Show depot, client workspace, and local filesystem locations of file.c (or where file.c would appear if it existed in the depot.)
p4 where 100%25.txt	Use ASCII expansion of "%" character to locations for file 100%.txt.
	ASCII expansion is supported for the following four special characters: @ (%40), # (%23), * (%2A), and % (%25).

#### **Related Commands**

To list the revisions of files as synced from the depot p4 have

# p4 workspace

## **Synopsis**

Create or edit a client workspace specification and its view.

# **Syntax**

```
p4 [g-opts] workspace [-f -t template] [workspacename]
p4 [g-opts] workspace -o [-t template] [workspacename]
p4 [g-opts] workspace -d [-f] workspacename
p4 [g-opts] workspace -i [-f]
```

## **Description**

The command p4 workspace is an alias for p4 client.

# p4 workspaces

# **Synopsis**

List all client workspaces currently known to the system.

# **Syntax**

```
p4 [g-opts] workspaces [ -u user ] [ -e namefilter -m max ]
```

# **Description**

The command p4 workspaces is an alias for p4 clients.

# **Environment and Registry Variables**

Each operating system and shell has its own syntax for setting environment variables. The following table shows how to set the P4CLIENT environment variable in each OS and shell:

OS or Shell	Environment Variable Example
UNIX: ksh, sh, bash	P4CLIENT=value ; export P4CLIENT
UNIX: csh	setenv P4CLIENT value
VMS	def/j P4CLIENT "value"
Mac OS X (bash)	P4CLIENT=value ; export P4CLIENT
Windows	p4 set P4CLIENT=value
	Windows administrators running Perforce as a service can set variables for use by a specific service with p4 set -S svcname var=value, or set variables for all users on the local machine with p4 set -s var=value.
	(See the p4 set command for more details on setting Perforce's registry variables in Windows).

Perforce's environment variables can be loosely grouped into the following four categories:

- *Crucial*: The variable must almost always be set on the client; default values are rarely sufficient. Understanding these variables is crucial for users and administrators alike.
- *Useful*: Setting this variable can provide additional functionality to the user, but is not required for most Perforce operations.
- *Esoteric*: The default value of this variable is normally sufficient; it rarely needs to be changed.

• *Server*: The variable is set by the Perforce system administrator on the machine running the Perforce server. Some of these variables are used by Perforce clients as well; in these cases, the variable is listed twice.

Crucial Variables	Useful Variables	<b>Esoteric Variables</b>	Server Variables
P4CLIENT	P4CONFIG	P4 PAGER	P4AUDIT
P4PORT	P4DIFF	PWD	P4JOURNAL
P4PASSWD	P4EDITOR	TMP, TEMP	P4LOG
P4USER	P4MERGE	P4TICKETS	P4PORT
	P4CHARSET	P4LANGUAGE	P4ROOT
		P4COMMANDCHARSET	P4DEBUG
		P4DIFFUNICODE	P4NAME
		P4MERGEUNICODE	P4DESCRIPTION
			P4ZEROCONF

## **P4AUDIT**

### **Description**

Location of the server audit log file.

### **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
No	Yes	p4d -A auditlog	N/A

# Value if not Explicitly Set

Operating System	Value
All	None. If no log file is specified, auditing is disabled.

#### **Notes**

P4AUDIT specifies the location of the audit log file.

When auditing is enabled, the server adds a line to the audit log file every time file content is transferred from the server to the client. On an active server, the audit log file will grow very quickly.

Lines in the audit log appear in the form:

```
date time user@client clientIP command file#rev
```

#### For example:

```
2006/05/09 09:52:45 karl@nail 192.168.0.12 diff //depot/src/x.c#1 2006/05/09 09:54:13 jim@stone 127.0.0.1 sync //depot/inc/file.h#1
```

If a command is run on the machine that runs the Perforce Server, the *clientIP* is shown as 127.0.0.1.

For more information, see the *System Administrator's Guide*.

## **P4CHARSET**

### **Description**

Character set used for translation of unicode files.

### **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	p4 -C charset cmd	Yes

### Value if not Explicitly Set

Operating System	Value
All	None. If the Perforce server is operating in unicode mode and P4CHARSET is unset, Perforce client programs return an error message.

#### **Notes**

P4CHARSET only affects files of type unicode and utf16; non-unicode files are never translated.

For servers operating in the default (non-Unicode mode), P4CHARSET must be left unset on client machines. If P4CHARSET is set, but the server is not operating in internationalized mode, the server returns the following error message:

Unicode clients require a unicode enabled server.

For servers operating in Unicode mode, P4CHARSET must be set on client machines. If P4CHARSET is unset, but the server is operating in Unicode mode, client programs return the following error message:

Unicode server permits only unicode enabled clients.

For more about Unicode mode, including settings of P4CHARSET for various UTF-8, UTF-16, and UTF-32 character sets, with and without byte-order marks, see the *Internationalization Notes*:

http://www.perforce.com/perforce/doc.current/user/i18nnotes.txt

### **P4COMMANDCHARSET**

## **Description**

Used to support UTF-16 and UTF-32 character sets from the Command-line Client.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	p4 -Q commandcharset cmd	Yes

## Value if not Explicitly Set

Operating System	Value
All	None.

#### **Notes**

If you have set P4CHARSET to a UTF-16 or UTF-32 value, you must set P4COMMANDCHARSET to a non-UTF-16 or -32 value in order to use the p4 Command-line Client. For details, see the *Internationalization Notes*:

http://www.perforce.com/perforce/doc.current/user/i18nnotes.txt

# **P4CLIENT**

# **Description**

Name of current client workspace.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	p4 -c clientname cmd	Yes

# Value if not Explicitly Set

Operating System	Value
Windows	Value of COMPUTERNAME environment variable
All others	Name of host machine

# **Examples**

cinnamon
computer1
WORKSTATION

#### P4CONFIG

### **Description**

Contains a file name without a path. The file(s) it points to are used to store other Perforce environment or registry variables. The current working directory (returned by PWD) and its parents are searched for the file. If the file exists, then the variable settings within the file are used.

The variable settings in the file must sit alone on each line and be in the form <code>variable=value</code>.

### **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	None	N/A

# Value if not Explicitly Set

Operating System	Value
All	If not set, this variable is not used.

# **Examples**

A sample P4CONFIG file might contain the following lines:

```
P4CLIENT=joes_client
P4USER=joe
P4PORT=ida:3548
```

#### **Notes**

P4CONFIG makes it trivial to switch Perforce settings when switching between different projects. If you place a configuration file in each of your client workspaces and set P4CONFIG to point to that file, your Perforce settings will change to the settings in the configuration files automatically as you move from directories in one workspace to another.

You can set the following variables from within the P4CONFIG file:

- P4CHARSET
- P4CLIENT
- P4DIFF
- P4EDITOR
- P4HOST
- P4LANGUAGE
- P4MERGE
- P4PASSWD
- P4PORT
- P4TICKETS
- P4USER

### **P4DEBUG**

### **Description**

Set Perforce server or proxy trace flags.

### **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
No	Yes	None	No

### Value if not Explicitly Set

Operating System	Value
All	If not set, this variable is not used.

### **Examples**



#### **Notes**

In most cases, the Perforce server trace flags are useful only to administrators working with Perforce Technical Support to diagnose or investigate a problem.

The preferred way to set trace flags for the Perforce server (or proxy) is to set them on the p4d (or p4p) command line. For technical reasons, this does not work for sites running Perforce servers or proxies as services under Windows. Administrators at such sites can use p4 set to set the trace flags within P4DEBUG, allowing the service to run with the flags enabled.

Some server debug levels require specific server release levels.

Setting server debug levels on a Perforce server (p4d) has no effect on the debug level of a Perforce Proxy (p4p) process, and vice versa.

For further information, see the Perforce System Administrator's Guide.

# **P4DESCRIPTION**

# **Description**

In a Zeroconf environment, a comment describing a Perforce server.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
No	Yes	p4d -0 -Id description	N/A

# Value if not Explicitly Set

Operating System	Value
All	None

# **Examples**

Art assets are stored on this Perforce Server

#### **Notes**

### P4DIFF

### **Description**

The name and location of the diff program used by p4 resolve and p4 diff.

### **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	None	Yes

## Value if not Explicitly Set

Operating System	Value
Windows	If the environment variable DIFF has been set, then the value of DIFF; otherwise, if the environment variable SHELL has been set to <i>any</i> value, then the program diff is used; otherwise, p4diff.exe.
All Others	If the environment variable DIFF has been set, then the value of DIFF; otherwise, Perforce's internal diff routine is used.

# **Examples**

diff
diff -b
windiff.exe

#### **Notes**

The value of P4DIFF can contain flags to the called program, for example, diff -u.

The commands p4 describe, p4 diff2, and p4 submit all use a diff program built into the Perforce server program p4d. This cannot be changed.

## **P4DIFFUNICODE**

## **Description**

Used to support UTF-16 and UTF-32 character sets from the Command-line Client.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	None	Yes

## Value if not Explicitly Set

Operating System	Value
All	None.

#### **Notes**

This environment variable is used in place of P4DIFF if the file being diffed is of type unicode or utf16, and the character set is passed as the first argument to the command. For details, see the *Release Notes*:

http://www.perforce.com/perforce/doc.current/user/relnotes.txt

#### **P4EDITOR**

### **Description**

The editor invoked by those Perforce commands that use forms.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	None	Yes

## Value if not Explicitly Set

Operating System	Value
UNIX and OS X	If EDITOR is set to any value, then the value of EDITOR;
	otherwise, vi.
Windows	If shell is set to any value, then vi;
	otherwise, notepad
VMS	If POSIX\$SHELL is set, then vi;
	otherwise, edit.
Macintosh	If <code>EDITOR_SIGNATURE</code> is set, then the program with that four-character creator;
	otherwise, SimpleText.

# **Examples**

/usr/bin/vi emacs SimpleText

#### Notes

The regular Perforce commands that use forms (and therefore, use this variable), are p4 branch, p4 change, p4 client, p4 job, p4 label, p4 submit, and p4 user.

The superuser commands that use forms are p4 depot, p4 group, p4 jobspec, p4 protect, p4 triggers, and p4 typemap.

#### **P4HOST**

### **Description**

Name of host computer to impersonate.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	p4 -H hostname command	Yes

## Value if not Explicitly Set

Operating System	Value
All	The value of the client hostname as returned by p4 info.

# **Examples**

workstation123.perforce.com

#### **Notes**

Perforce users can use the <code>Host:</code> field of the p4 <code>client</code> form to specify that a particular client workspace can be used only from a particular host machine. When this field has been set, the <code>P4HOST</code> variable can be used to fool the server into thinking that the user is on the specified host machine regardless of the machine being used by the user. As this is a very esoteric need, there's usually no reason to set this variable.

The hostname must be provided exactly as it appears in the output of p4 info when run from that host.

## **P4JOURNAL**

## **Description**

A file that holds the Perforce server database's journal data.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
No	Yes	p4d -J file	N/A

# Value if not Explicitly Set

Operating System	Value
All	P4ROOT/journal

# **Examples**

```
journal
off
/disk2/perforce/journal
```

#### **Notes**

If a relative path is provided, it should be specified relative to the Perforce server root.

Setting P4JOURNAL to off will disable journaling. This is not recommended.

For further information, see the *Perforce System Administrator's Guide*.

# **P4LANGUAGE**

# **Description**

This environment variable is reserved for system integrators.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	p4 -L language cmd	Yes

# Value if not Explicitly Set

Operating System	Value
All	N/A

# P4LOG

## **Description**

Name and path of the file to which Perforce server errors are written.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
No	Yes	p4d -L file p4p -L file	N/A

# Value if not Explicitly Set

Operating System	Value
All	Standard error

# **Examples**

log /disk2/perforce/log

#### **Notes**

If a relative path is provided, it should be specified relative to the Perforce server root. For further information, see the *Perforce System Administrator's Guide*.

#### P4MERGE

### **Description**

A third-party merge program to be used by p4 resolve's merge option.

### **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	None	Yes

### Value if not Explicitly Set

Operating System	Value
All	If the MERGE environment variable (or registry variable on Windows, as set by p4 set) is set, then its value; otherwise, nothing.

### **Examples**

```
c:\Perforce\p4merge.exe
c:\progra~1\Perforce\p4merge.exe
```

#### **Notes**

The program represented by the program name stored in this variable is used only by p4 resolve's merge option. When p4 resolve calls this program, it passes four arguments, representing (in order) base, theirs, and yours, with the fourth argument holding the resulting merge file.

If the program you use takes its arguments in a different order, set P4MERGE to a shell script or batch file that reorders the arguments and calls the proper merge program with the arguments in the correct order.

If you are running under Windows, you must call a batch file, even if your third-party merge program already accepts arguments in the order provided by Perforce. This is due to a limitation within Windows. For instance, if you want to use a program called MERGE. EXE under Windows, your batch file might look something like this:

```
SET base=%1
SET theirs=%2
SET yours=%3
SET merge=%4
C:\FULL\PATH\TO\MERGE.EXE %base %theirs %yours %merge
```

### **P4MERGEUNICODE**

### **Description**

Used to support UTF-16 and UTF-32 character sets from the Command-line Client.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	None	Yes

## Value if not Explicitly Set

Operating System	Value
All	None.

#### **Notes**

This environment variable is used in place of P4MERGE if the file being resolved is of type unicode or utf16, and the character set is passed as the first argument to the command. For details, see the *Release Notes*:

http://www.perforce.com/perforce/doc.current/user/relnotes.txt

## **P4NAME**

# **Description**

In a Zeroconf environment, the unique identifiable name for a Perforce server.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
No	Yes	p4d -0 -In name	N/A

# Value if not Explicitly Set

Operating System	Value
All	None

# **Examples**

Artists' Store

### **Notes**

### **P4PAGER**

# **Description**

The program used to page output from p4 resolve's diff option.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	None	No

# Value if not Explicitly Set

Operating System	Value
All	If the variable PAGER is set, then the value of PAGER; otherwise,
	none.

# **Examples**

/bin/more(UNIX)

#### **Notes**

The value of this variable is used *only* to display the output for p4 resolve's diff routine. If the variable is not set, the output is not paged.

### P4PASSWD

### **Description**

Supplies the current Perforce user's password for any Perforce client command.

### **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	p4 -P passwd command	Yes

### Value if not Explicitly Set

Operating System	Value
All	None

#### **Notes**

Perforce passwords are set via p4 passwd, or in the form invoked by p4 user. The setting of P4PASSWD is used to verify the user's identity. If a password has not been set, the value P4PASSWD is not used, even if set.

While it is possible to manually set the P4PASSWD environment variable to your plaintext password, the more secure way is to use the p4 passwd command. On UNIX, this will invoke a challenge/response mechanism which securely sends your password to the Perforce server. On Windows, this sets P4PASSWD to the encrypted MD5 hash of your password.

On Windows platforms, if you set a password in P4V, the value of the registry variable P4PASSWD is set for you. Setting the password in P4V is like using p4 passwd (or p4 set P4PASSWD) from the MS-DOS command line, setting the registry variable to the encrypted MD5 hash of the password. The unencrypted password itself is never stored in the registry.

If you are using ticket-based authentication, but have a script that relies on a P4PASSWD setting, use p4 login -p to display the value of a ticket that can be passed to Perforce commands as though it were a password (that is, either from the command line, or by setting P4PASSWD to the value of the valid ticket).

# **P4PCACHE**

# **Description**

For the Perforce Proxy, the directory in which the proxy stores its files and subdirectories.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
No	Yes	p4p -r directory	N/A

# Value if not Explicitly Set

<b>Operating System</b>	Value
All	p4p's directory.
	Windows administrators running the Perforce Proxy process as a service should use p4 set -S svcname P4PCACHE=directory to set the value of P4PCACHE for the named service.

### **Notes**

Create this directory before starting the Perforce Proxy (p4p).

Only the account running p4p needs to have read/write permissions in this directory.

For more information on setting up a Perforce Proxy, see the *Perforce System Administrator's Guide*.

# **P4PFSIZE**

# **Description**

For the Perforce Proxy, the size (in bytes) of the smallest file to be cached. All files larger than P4PFSIZE bytes in length are cached.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
No	Yes	p4p -e <i>size</i>	N/A

# Value if not Explicitly Set

Operating System	Value
All	0; that is, cache all files

# **Notes**

For more information on setting up a Perforce Proxy, see the *Perforce System Administrator's Guide*.

### **P4POPTIONS**

## **Description**

Set Perforce Proxy options for a Windows service.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
No	Yes	p4p %P4POPTIONS%	N/A

# Value if not Explicitly Set

Operating System	Value
All	Null

#### **Notes**

For example, if you normally run the Proxy with the command

```
p4p -p 1999 -t mainserver:1666
```

you can set the P4POPTIONS variable for the Windows proxysvc to run with

```
p4 set -S "Perforce Proxy" P4POPTIONS="-p 1999 -t mainserver:1666"
```

When you run P4P under the "Perforce Proxy" service, the Proxy will listen to port 1999 and communicate with the Perforce Server at mainserver:1666.

Most installations do not need to use P4POPTIONS, because there are already environment variables associated with most p4p flags; in the example shown above, you can use P4PORT and P4TARGET. Use P4POPTIONS when you need to call p4p with flags for which there are no corresponding environment variables, and when you are doing so within the context of a Windows service.

For more information on setting up a Perforce Proxy, see the *Perforce System Administrator's Guide*.

# **P4PORT**

# **Description**

For the Perforce server, and Perforce Proxy, the port number on which it listens.

For Perforce clients, the host and port number of the Perforce server or proxy with which to communicate.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	Yes	p4 -p host:port cmd	Yes

# Value if not Explicitly Set

Program	Value
Perforce server	1666
Perforce proxy	1666
Perforce client	perforce:1666

# **Examples**

Perforce client examples	Perforce server examples
1818	1818
squid:1234	1234
example.com:1234	1234
192.168.0.123:1818	1818

### **Notes**

The format of P4PORT on the Perforce client is *host:port*, or *port* by itself if both the Perforce client and server are running on the same host. Port numbers must be in the range 1024 through 32767.

If you specify both an IP address *and* a port number in P4PORT, the Perforce server ignores requests from any IP addresses other than the one specified in P4PORT.

To use the default value perforce with a Perforce server, define perforce as an alias to the host running the server in /etc/hosts on UNIX, or in %SystemRoot%\system32\drivers\etc\hosts on Windows, or use DNS.

If your network environment and Perforce Server have been configured to support Zeroconf services, you can set P4PORT to the value of the service name.

# P4ROOT

# **Description**

Directory in which the Perforce server stores its files and subdirectories.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
No	Yes	p4d -r directory	N/A

# Value if not Explicitly Set

Operating System	Value
All	p4d's directory.
	Windows administrators running the Perforce back-end process as a service should use p4 set -S svcname P4ROOT=directory to set the value of P4ROOT for the named service.

### **Notes**

Create this directory before starting the Perforce server (p4d).

Only the account running p4d needs to have read/write permissions in this directory.

For more information on setting up a Perforce server, see the *Perforce System Administrator's Guide*.

### **P4TARGET**

# **Description**

For the Perforce Proxy, the name and port number of the target Perforce server (that is, the Perforce server for which P4P acts as a proxy).

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
No	Yes	p4p -t host:port	N/A

# Value if not Explicitly Set

Program	Value
Perforce Proxy	perforce:1666

# **Examples**

Perforce client examples	Perforce server examples
1818	1818
squid:1234	squid:1234
perforce.squid.com:1234	perforce.squid.com:1234
192.168.0.123:1818	192.168.0.123:1818

#### **Notes**

The format of P4TARGET on the Perforce Proxy is *host:port*, or *port* by itself if both the Perforce server is running on the same host (an unlikely configuration).

Port numbers must be in the range 1024 through 32767.

For more about the Perforce Proxy, see the System Administrator's Guide.

# **P4TICKETS**

# **Description**

The location of the ticket file used by p4 login.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	N/A	Yes

# Value if not Explicitly Set

Program	Value
Windows	%USERPROFILE%\p4tickets.txt
All others	\$HOME/.p4tickets

# **Examples**

/staff/username/p4tickets.txt

#### **Notes**

The P4TICKETS environment variable must point to the actual ticket file, not merely a directory in which p4tickets.txt or .p4tickets is expected to exist. If you set P4TICKETS to point to a directory, you will not be able to log in.

### P4USER

# **Description**

Current Perforce username.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	p4 -u username command	Yes

# Value if not Explicitly Set

Operating System	Value
Windows	The value of the USERNAME environment variable.
All Others	The value of the USER environment variable.

### **Examples**

edk lisag

#### **Notes**

By default, the Perforce username is the same as the OS username.

If a particular Perforce user does not have a password set, then any other Perforce user can impersonate this user by using the -u flag with their Perforce client commands. To prevent this, users should set their password with the p4 user or p4 passwd command.

If a user has set their Perforce password, you can still run commands as that user (if you know the password) with p4 -u username -P password command.

Perforce superusers can impersonate users without knowing their passwords. For more information, see the *Perforce System Administrator's Guide*.

# **P4ZEROCONF**

# **Description**

If set, p4d attempts to advertise itself as a zeroconf service upon startup.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
No	Yes	p4d -0	N/A

# Value if not Explicitly Set

Operating System	Value
All	None

### **PWD**

# **Description**

The directory used to resolve relative filename arguments to Perforce client commands.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	No	p4 -d directory command	No

# Value if not Explicitly Set

Operating System	Value
UNIX	The value of PWD as set by the shell; if not set by the shell, $getcwd()$ is used.
All Others	The actual current working directory.

#### **Notes**

Sometimes the PWD variable isn't inherited properly across shells. For instance, if you're running ksh or sh on top of csh, PWD will be inherited from your csh environment but not updated properly, causing possible confusion in subsequent Perforce commands.

If you encounter such difficulties, check to be sure you've unset PWD in your .profile or .kshrc file. (If you're running sh or ksh as your login shell, PWD will be managed properly by the shell regardless of any unsettings you've placed in your startup files; the confusion only occurs when variables are exported to subshells.)

# TMP, TEMP

# **Description**

The directory to which Perforce clients and servers write temporary files.

# **Usage Notes**

Used by Client?	Used by Server?	Command-Line Alternative	Can be set in P4CONFIG file?
Yes	Yes	None	No

# Value if not Explicitly Set

Operating System	Value
UNIX	/tmp
All Others	On Perforce clients: the current working directory.
	On Perforce servers: P4ROOT

### **Notes**

If TEMP is set, TEMP is used. Otherwise, if TMP is set, this is used. If neither TEMP nor TMP are set, temporary files will be written in the directories described in the table above.

# **Additional Information**

This section describes features of Perforce that you'll use with multiple commands. We've included information on the following topics:

- Flags that can be used with any Perforce command,
- How to use Perforce file specifications in depot syntax, client syntax, and local syntax,
- Perforce file types, and
- How to create and use *views* to describe client workspaces, branches, and labels.

For an in-depth treatment of these and other topics from a conceptual level, please see the *Introduction to Perforce*, which is available at our web site: http://www.perforce.com.

# **Global Options**

# **Synopsis**

Global options for Perforce commands; these options can be supplied on the command line before any Perforce command.

# **Syntax**

```
p4 [-cclient -ddir -Hhost -pport -Ppass -uuser -xfile -Ccharset -Qcharset -Llanguage] [-G] [-s] [-z tag] cmd [args ...]
p4 -V
p4 -h
```

# **Options**

-c client	Overrides any P4CLIENT setting with the specified client name.
-d dir	Overrides any PWD setting (i.e. current working directory) and replaces it with the specified directory.
-G	Causes all output (and batch input for form commands with -i) to be formatted as marshalled Python dictionary objects. This is most often used when scripting.
-H host	Overrides any P4HOST setting and replaces it with the specified hostname.
-p port	Overrides any P4PORT setting with the specified port number.
-P pass	Overrides any P4PASSWD setting with the specified password.
-s	Prepends a descriptive field (for example, text:, info:, error:, exit:) to each line of output produced by a Perforce command. This is most often used when scripting.
-u <i>user</i>	Overrides any P4USER, USER, or USERNAME setting with the specified user name.
-x file	Instructs Perforce to read arguments, one per line, from the specified file. If file is a single hyphen (-), then standard input is read.
-C charset	Overrides any P4CHARSET setting with the specified character set.
-Q charset	Overrides any P4COMMANDCHARSET setting with the specified character set.
-L language	This feature is reserved for system integrators.
-z tag	Causes output of many reporting commands to be in the same tagged format as that generated by p4 fstat.

- V	Displays the version of the p4 client program and exits.
-h	Displays basic usage information and exits.

# **Usage Notes**

 Be aware that the global options must be specified on the command line before the Perforce command. Options specified after the Perforce command will not be interpreted as global options, but as options for the command being invoked. It is therefore possible to have the same command line option appearing twice in the same command, being interpreted differently each time.

For example, the command p4 -c anotherclient edit -c 140 file.c will open file file.c for edit in pending changelist 140 under client workspace anotherclient.

• The -x option is useful for automating tedious tasks; a user adding several files at once could create a text file with the names of these files and invoke p4 -x textfile add to add them all at once.

The -x option can be extremely powerful - as powerful as whatever generates its input. For example, a UNIX developer wishing to edit any file referring to an included file.h file, for instance, could grep -1 file.h \*.c | cut -f1 -d: | p4 -x - edit.

In this example, the grep command lists occurrences of file.h in the \*.c files, the -1 option tells grep to list each file only once, and the cut command splits off the filename from grep's output before passing it to the p4 -x command.

• The -s option can be useful in automated scripts.

For example, a script could be written as part of an in-house build process which executes p4 -s commands, discards any output lines beginning with "info:", and alerts the user if any output lines begin with "error:".

• Python developers will find the -G option extremely useful for scripting. For instance, to get a dictionary of all fields of a job whose ID is known, use the following:

```
job_dict = marshal.load(os.popen('p4 -G job -o ' + job_id, 'rb'))
```

In some cases, it may not be intuitively obvious what keys are used by the client program. If you pipe the output of any p4 -G invocation to the following script, you will see every record printed out in key/value pairs:

```
#!/usr/local/bin/python
import marshal, sys

try:
    num=0
    while 1:
        num=num+1
        print '\n--%d--' % num
        dict = marshal.load(sys.stdin, 'rb')
        for key in dict.keys(): print "%s: %s" % (key,dict[key])
except EOFError: pass
```

Python developers on Windows should be aware of potential CR/LF translation issues; in the example, it is necessary to call marshal.load() to read the data in binary ("rb") mode.

• Some uses of the global options are absurd.

For example, p4 -c anotherclient help provides exactly the same output as p4 help.

## **Examples**

p4 -p <i>new_server</i> :1234 sync	Performs a sync using server <i>new_server</i> and port 1234, regardless of the settings of the P4PORT environment variable or registry setting.
p4 -c new_client submit -c 100	The first -c is the global option to specify the client name. The second -c specifies a changelist number.
p4 -s -x filelist.txt edit	If filelist.txt contains a list of files, this command opens each file on the list for editing, and produces output suitable for parsing by scripts.
	Any errors as a result of the automated p4 edit commands (for example, a file in filelist.txt not being found) can then be easily detected by examining the command's output for lines beginning with "error:"

# File Specifications

# **Synopsis**

Any file can be specified within any Perforce command in client syntax, depot syntax, or local syntax. Client workspace names and depot names share the same namespace; there is no way for the Perforce server to confuse a client name with a depot name.

### Syntax forms

Local syntax refers to filenames as specified by the local shell or operating system. Filenames referred to in local syntax can be specified by their absolute paths or relative to the current working directory. (Relative path components can only appear at the beginning of a file specifier.)

Perforce has its own method of file specification which remains unchanged across operating systems. If a file is specified relative to a client root, it is said to be in *client syntax*. If it is specified relative to the top of the depot, it is said to be in *depot syntax*. A file specified in either manner can be said to have been specified in Perforce syntax.

Perforce file specifiers always begin with two slashes (//), followed by the client or depot name, followed by the full pathname of the file relative to the client or depot root directory.

Path components in client and depot syntax are always separated by slashes (/), regardless of the component separator used by the local operating system or shell.

An example of each syntax is provided below

Syntax	Example
Local syntax	/staff/user/usercws/file.c
Depot syntax	//depot/source/module/file.c
Client syntax	//usercws/file.c

#### Wildcards

The Perforce system allows the use of three wildcards:

Wildcard	Meaning
*	Matches all characters except slashes within one directory.
	Matches all files under the current working directory and all subdirectories. (matches anything, including slashes, and does so across subdirectories)
<b>%%1 - %%9</b>	Positional specifiers for substring rearrangement in filenames, when used in views.

# For example:

Expression	Matches
J*	Files in the current directory starting with J
*/help	All files called help in current subdirectories
./	All files under the current directory and its subdirectories
./c	All files under the current directory and its subdirectories, that end in .c
/usr/bruno/	All files under /usr/bruno
//bruno_ws/	All files in the workspace or depot that is named bruno_ws
//depot/	All files in the depot
//	All files in all depots

# Using revision specifiers

File specifiers can be modified by appending # or @ to them.

The # and @ specifiers refer to specific revisions of files as stored in the depot:

Modifier	Meaning
file#n	Revision specifier: The <i>n</i> th revision of <i>file</i> .
file#none file#0	The nonexistent revision: If a revision of file exists in the depot, it is ignored.
	This is useful when you want to remove a file from the client workspace while leaving it intact in the depot, as in p4 sync file#none.
	The filespec #0 can be used as a synonym for #none - the nonexistent revision can be thought of as the one that "existed" before the first revision was submitted to the depot.
file#head	The head revision (latest version) of file. Except where explicitly noted, this is equivalent to referring to the file without a revision specifier.
file#have	The revision on the current client: the revision of file last p4 synced into the client workspace
file@n	Change number: The revision of $file$ immediately after changelist $n$ was submitted.
file@labelname	Label name: The revision of file in the label labelname.

Modifier	Meaning
file@clientname	Client name: The revision of file last taken into client workspace clientname.
file@datespec	Date and time: The revision of file at the date and time specified.
	If no time is specified, the head revision at 00:00:00 on the morning of the date specified is returned.
	Dates are specified yyyy/mm/dd:hh:mm:ss or yyyy/mm/dd hh:mm:ss (with either a space or a colon between the date and the time).
	The datespec @now can be used as a synonym for the current date and time.

Revision specifiers can be used to operate on many files at once: p4 sync //myclient/...#4 copies the fourth revision of all non-open files into the client workspace.

If specifying files by date and time (i.e., using specifiers of the form <code>file@datespec</code>), the date specification should be parsed by your local shell as a single token. You may need to use quotation marks around the date specification if you use it to specify a time as well as a date.

Some Perforce file specification characters may be intercepted and interpreted by the local shell, and need to be escaped before use. For instance, # is used as the comment character in most UNIX shells, and / may be interpreted by (non-Perforce) DOS commands as an option specifier. File names with spaces in them may have to be quoted on the command line.

For information on these and other platform-specific issues, see the release notes for your platform.

# **Using revision ranges**

A few Perforce commands can use revision ranges to modify file arguments. Revision ranges are two separate revision specifications, separated by a comma. For example, p4 changes file#3,5 lists the changelists that submitted file file at its third, fourth, and fifth revisions.

Revision ranges have two separate meanings, depending on which command you're using. The two meanings are:

• Run the command on all revisions in the specified range. For example, p4 jobs //...#20,52 lists all jobs fixed by any changelist that submitted any file at its 20th through 52nd revision.

This interpretation of revision ranges applies to p4 changes, p4 fixes, p4 integrate, p4 jobs, and p4 verify.

• Run the command on only the highest revision in the specified range. For example, the command p4 print file@30,50 prints the highest revision of file file submitted between changelists 30 and 50. This is different than p4 print file@50: if revision 1 of file file was submitted in changelist 20, and revision 2 of file file was submitted in changelist 60, then p4 print file@30,50 prints nothing, while p4 print file@50 prints revision 1 of file.

The commands p4 files, p4 print, and p4 sync all use revision ranges in this fashion.

Revision ranges can be very powerful. For example, the command p4 changes file#3,@labelname lists all changelists that submitted file file between its third revision and the revision stored in label labelname.

#### Limitations on characters in filenames and entities

To support internationalization, Perforce permits the use of "unprintable" (non-ASCII) characters in filenames, label names, client workspace names, and other identifiers.

The pathname component separator (/) is not permitted in filenames, depot names, or client workspace names, but can appear in label names, job names, or user names. The recursive subdirectory wildcard (...) is not permitted in file names, label names, or other identifiers.

Character	Reason
	Perforce wildcard: matches anything, works at the current directory level and includes files in all directory levels below the current level.
/	Perforce separator for pathname components.

To refer to files containing the Perforce revision specifier wildcards (@ and #), file matching wildcard (\*), or positional substitution wildcard (%%) in either the file name or any directory component, use the ASCII expression of the character's hexadecimal value. ASCII expansion applies only to the following four characters:

Character	ASCII expansion
@	<b>%4</b> 0
#	%23
*	%2A
%	%25

To add a file such as status@june.txt, force a literal interpretation of special characters by using:

```
p4 add -f //depot/path/status@june.txt
```

When you submit the changelist, the characters are automatically expanded and appear in the change submission form as follows:

```
//depot/path/status%40june.txt
```

After submitting the changelist with the file's addition, you must use the ASCII expansion in order to sync it to your workspace or edit it within your workspace:

```
p4 sync //depot/path/status%40june.txt
p4 edit //depot/path/status%40june.txt
```

Most special characters tend to be difficult to use in filenames in cross-platform environments: UNIX separates path components with /, while many DOS commands interpret / as a command line switch. Most UNIX shells interpret # as the beginning of a comment. Both DOS and UNIX shells automatically expand \* to match multiple files, and the DOS command line uses % to refer to variables.

Similarly, although non-ASCII characters are allowed in filenames and Perforce identifiers, entering these characters from the command line may require platform-specific solutions. Users of GUI-based file managers can manipulate such files with dragand-drop operations.

### **Views**

# **Synopsis**

There are three types of views: client views, branch views, and label views.

- Client views map files in the depot to files in the client workspace
- Branch views map files in the depot to other parts of the depot
- Label views associate groups of files in the depot with a single label.

Each type of view consists of lines which map files from the depot into the appropriate namespace. For client and branch views, the mappings consist of two file specifications. The left side of the mapping always refers to the depot namespace, and the right side of the mapping refers to the client workspace or depot namespace. For label views, only the left side (the depot namespace) of the mapping need be provided - the files are automatically associated with the desired label.

All views construct a one-to-one mapping between files in the depot and the files in the client workspace, branch, or label. If more than one mapping line refers to the same file(s), the earlier mappings are overridden. Mappings beginning with a hyphen (-) specifically exclude any files that match that mapping. In client views, mappings beginning with a plus sign (+) overlay previous mappings. (Overlay mappings do not apply to branch or label views.)

File specifications within mappings are provided in the usual Perforce syntax, beginning with //, followed by the depot name or workspace name, and followed by the actual file name(s) within the depot or workspace. (You cannot use revision specifiers in views.)

# **Usage Notes**

Views are set up through the p4 client, p4 branch, or p4 label commands as part of the process of creating a client workspace, label view, or branch view respectively.

The order of mappings in a client or branch view is important. For instance, in the view defined by the following two mappings:

```
//depot/... //cws/...
//depot/dir1/... //cws/dir2/...
```

the entire depot is mapped to the client workspace, but the file //depot/dir1/file.c is mapped to //cws/dir2/file.c. If the order of the lines in the view is reversed, however:

```
//depot/dir1/... //cws/dir2/...
//depot/... //cws/...
```

then the file //depot/dir1/file.c is mapped to //cws/dir1/file.c, as the first mapping (mapping the file into //cws/dir2) is overridden by the second mapping

(which maps the entire depot onto the client workspace). A later mapping in a view always overrides an earlier mapping.

#### Spaces in path and file names

If a path or file name in a workspace view, branch view, or label view contains spaces, make sure to quote the path:

```
//depot/dir1/... "//cws/dir one/..."
```

#### Special characters in path and file names

To map file and directory names that contain the characters @, #, \*, or %, (that is, to interpret such characters as components of path and filenames, and *not* as Perforce wildcards), expand the characters to their ASCII equivalents as follows:

Character	ASCII expansion
@	%40
#	%23
*	%2A
%	%25

#### **Client Views**

Client views are used to map files in the depot to files in client workspaces, and vice versa. A client workspace is an area in which users perform their work; files are synced to a client workspace, opened for editing, edited, and checked back into the depot.

When files are synced, they are copied from the depot to the locations in the client workspace to which they were mapped. Likewise, when files are submitted back into the depot, the mapping is reversed and the files are copied from the client workspace back to their proper locations in the depot.

The following table lists some examples of client views:

Client View	Sample Mapping
Full client workspace mapped to entire depot	//depot/ //cws/
Full client workspace mapped to part of depot	//depot/dir1/ //cws/
Some files in the depot are mapped to a different part of the client workspace	//depot/ //cws/ //depot/rel1/ //cws/release1/

Client View	Sample Mapping
Some files in the depot are excluded from the client workspace	<pre>//depot/dir1/ //cws///depot/dir1/exclude/ //cws/dir1/exclude/</pre>
Files in the client workspace are mapped to different names than their depot names.	//depot/dir1/old.* //cws/renamed/new.*
Portions of filenames in the depot are rearranged in the client workspace	//depot/dir1/%%1.%%2 //cws/dir1/%%2.%%1
The files do not map the same way in each direction. The second line takes precedence, and the first line is ignored.	<pre>//depot/dir1/ //cws/build/ //depot/dir2/ //cws/build/</pre>
An overlay mapping is used to map files from more than one depot directory into the same place in the workspace.	<pre>//depot/dir1/ //cws/build/ +//depot/dir2/ //cws/build/</pre>

To create a client view, use p4 client to bring up a screen where you can specify how files in the depot are mapped to the files in your client workspace.

#### **Branch Views**

Branching of the source tree allows multiple sets of files to evolve along different paths. The creation of a branch view allows Perforce to automatically manage the file copying and edit propagation tasks associated with branching.

Branch views map existing areas of the depot (the source files) onto new areas of the depot (the target files). They are defined in a manner similar to that used for defining client views, but rather than mapping files directly into a client workspace, they merely set up mappings within the depot. Because integration can take place in either direction,

every line in a branch view must be unambiguous in both directions; overlay mappings are therefore not permitted in branch views.

Branch View	Sample Mapping	
New code branching off from the main codeline	//depot/main/	//depot/1.1dev/
Rearranging directories in the new release	//depot/main/*.c	//depot/1.1dev/ //depot/1.1dev/src/*.c //depot/1.1dev/doc/*.txt

To create a branch view, use p4 branch newbranch. This will bring up a screen (similar to the one associated with p4 client) and allow you to map the donor files from the main source tree onto the target files of the new branch.

No files are copied when a branch view is first created. To copy the files, you must ensure that the newly-created files are included in any client workspace view intending to use those files. You can do this by adding the newly-mapped branch of the depot to your current client workspace view and performing a p4 sync command.

#### **Label Views**

Label views assign a label to a set of files in the depot. Unlike client views and branch views, a label view doesn't copy any files; label views are used to limit the set of files that are taggable by a label.

Label View	Sample Mapping
A new release	//depot/1.1final/
The source code for the new release	//depot/1.1final/src/
A distribution suitable for clients	<pre>//depot/1.1final/bin/ //depot/1.1final/doc/ //depot/1.1final/readme.txt</pre>

To create a label, use p4 label labelname, and enter the depot side of the view. Because a label is merely a list of files and revision levels, only the depot side (the left side) of the view needs to be specified, and overlay mappings are not permitted.

# File Types

# **Synopsis**

Perforce supports six base file types:

- text files,
- compressed binary files,
- native apple files on the Macintosh,
- Mac resource forks,
- symbolic links (symlinks), and
- unicode and utf16 files.

File type modifiers are then applied to the base types allowing for support of RCS keyword expansion, file compression on the server, and more.

When a file is opened for add, Perforce attempts to determine the type of the file automatically. If the file is a regular file or a symbolic link, its type is set accordingly. Perforce then examines the first 8192 bytes of the file to determine whether it is text or binary. If any non-text characters are found, the file is assumed to be binary; otherwise, the file is assumed to be text. Binary files compressed in the .zip format (including .jar files) are automatically detected and assigned the type ubinary. If a text file is 10MB or larger, it is assumed to be of type ctext (text+C), and the file is compressed and stored in full on the server, rather than as deltas.

(Files in unicode environments are detected differently; for details, see the *Internationalization Notes*.)

Perforce administrators can use the type mapping feature (p4 typemap) to override Perforce's default file type detection mechanism. This feature is useful for binary file formats (such as Adobe PDF, or Rich Text Format) where files can start with 8192 or more characters of ASCII text, and might otherwise be mistaken for text files.

# **Base filetypes**

The base Perforce file types are:

Keyword	Description	Comments	Server Storage
text	Text file	Treated as text on the client. Line-ending translations are performed automatically on Windows and Macintosh clients.	deltas in RCS format
binary	Non-text file	Accessed as binary files on the client. Stored compressed within the depot.	full file, compressed

Keyword	Description	Comments	Server Storage
symlink	Symbolic link	UNIX clients (and the BeOS client) access these as symbolic links. Non-UNIX clients treat them as (small) text files.	deltas in RCS format
apple	Multi-forked Macintosh file	AppleSingle storage of Mac data fork, resource fork, file type and file creator.	full file, compressed,
		For full details, please see the Mac client release notes.	AppleSingle format.
resource	Macintosh resource fork	The only file type for Mac resource forks in Perforce 99.1 and before. Still supported, but the apple file type is preferred.	full file, compressed
		For full details, please see the Mac client release notes.	
unicode	Unicode file	Perforce servers operating in unicode mode support the unicode file type. These files are translated into the local character set specified by P4CHARSET.	UTF-8
		Perforce servers not in unicode mode do not support the unicode file type.	
		For details, see the <i>Internationalization Notes</i> .	
utf16	Unicode file	If the Perforce server is operating in unicode mode, files are translated into the local character set as specified by P4CHARSET.	UTF-8
		If the Perforce server is operating in non- unicode mode, files are transferred as UTF-8, and translated to UTF-16 (with byte order mark, in the byte order appropriate for the client machine) in the client workspace.	
		For details, see the <i>Internationalization Notes</i> .	

# File type modifiers

The file type modifiers are:

Modifier	Description	Comments
+W	File is always writable on client	
+X	Execute bit set on client	Used for executable files.
+ko	Old-style keyword expansion	Expands only the \$Id\$ and \$Header\$ keywords:
		This pair of modifiers exists primarily for backwards compatibility with versions of Perforce prior to 2000.1, and corresponds to the +k (ktext) modifier in earlier versions of Perforce.
+k	RCS keyword expansion	Expands RCS (Revision Control System) keywords.
		RCS keywords are case-sensitive.
		When using keywords in files, a colon after the keyword (for instance, \$Id:\$) is optional.
		Supported keywords are:
		• \$Id\$
		<ul><li>\$Header\$</li><li>\$Date\$</li></ul>
		• \$DateTime\$
		<ul><li>\$Change\$</li><li>\$File\$</li></ul>
		• \$Revision\$ • \$Author\$
+1	Exclusive open (locking)	If set, only one user at a time will be able to open a file for editing.
		Useful for binary file types (such as graphics) where merging of changes from multiple authors is meaningless.
+C	Server stores the full compressed version of each file revision	Default server storage mechanism for binary files and newly-added text files larger than 10MB.

Modifier	Description	Comments
+D	Server stores deltas in RCS format	Default server storage mechanism for text files.
+F	Server stores full file per revision, uncompressed	Useful for large binaries, or for long ASCII files that aren't read by users as text, such as PostScript files.
+S	Only the head revision is stored on the server	Older revisions are purged from the depot upon submission of new revisions. Useful for executable or .obj files.
+Sn	Only the most recent <i>n</i> revisions are stored on the server, where n is a number from 1 to 10, or 16, 32, 64, 128, 256, or 512.	Older revisions are purged from the depot upon submission of more than $n$ new revisions, or if you change an existing $+Sn$ file's $n$ to a number less than its current value. Earlier revisions unaffected; see the Usage Notes for details.
+m	Preserve original modtime	The file's timestamp on the local filesystem is preserved upon submission and restored upon sync. Useful for third-party DLLs in Windows environments.
+X	Archive trigger required	The server runs an archive trigger to access the file. See the <i>System Administrator's Guide</i> for details.

A file's type is normally preserved between revisions, but can be overridden or changed with the -t flag during add, edit, or reopen operations:

- p4 add -t filetype filespec adds the files as the specified type.
- p4 edit -t filetype filespec opens the file for edit as the specified type. The file's type is changed to the specified filetype only after it is submitted to the depot.
- p4 reopen -t filetype filespec changes the type of a file already open for add or edit.

The filetype argument is specified as [basetype] +modifiers. For example, to change script.sh's type to executable text with RCS keyword expansion, use p4 edit -t text+kx script.sh.

Partial filetypes are also acceptable. For example, to change an existing text file to text+x, use p4 reopen -t +x script.sh. Most partial filetype modifiers are added to the filetype, but the storage modifiers (+C, +D, and +F) replace the file's storage method. To remove a modifier, you must specify the full filetype.

# Perforce file types for common file extensions

The following table lists recommended Perforce file types and modifiers for common file extensions.

File Type	Perforce file type	Description
.asp	text	Active server page file
.avi	binary+F	Video for Windows file
.bmp	binary	Windows bitmap file
.btr	binary	Btrieve database file
.cnf	text	Conference link file
.css	text	Cascading style sheet file
.doc	binary	Microsoft Word document
.dot	binary	Microsoft Word template
.exp	binary+w	Export file (Microsoft Visual C++)
.gif	binary+F	GIF graphic file
.gz	binary+F	Gzip compressed file
.htm	text	HTML file
.html	text	HTML file
.ico	binary	Icon file
.inc	text	Active Server include file
.ini	text+w	Initial application settings file
·jpg	binary	JPEG graphic file
.js	text	JavaScript language source code file
.lib	binary+w	Library file (several programming languages)
.log	text+w	Log file
.mpg	binary+F	MPEG video file
.pdf	binary	Adobe PDF file
.pdm	text+w	Sybase Power Designer file
.ppt	binary	Microsoft Powerpoint file
.xls	binary	Microsoft Excel file

For more about mapping file names to Perforce filetypes, see the p4 typemap command.

### **Keyword Expansion**

RCS keywords are expanded as follows:

Keyword	Expands To	Example
\$Id\$	File name and revision number in depot syntax	<pre>\$Id: //depot/path/file.txt#3 \$</pre>
\$Header\$	Synonymous with \$Id\$	<pre>\$Header: //depot/path/file.txt#3 \$</pre>
\$Date\$	Date of last submission in format YYYY/MM/DD	\$Date: 2000/08/18 \$
\$DateTime\$	Date and time of last submission in format YYYY/MM/DD hh:mm:ss	\$DateTime: 2000/08/18 23:17:02 \$
	Date and time are as of the local time on the Perforce server at time of submission.	
\$Change\$	Perforce changelist number under which file was submitted	\$Change: 439 \$
\$File\$	File name only, in depot syntax (without revision number)	<pre>\$File: //depot/path/file.txt \$</pre>
\$Revision\$	Perforce revision number	\$Revision: #3 \$
\$Author\$	Perforce user submitting the file	\$Author: edk \$

# **Usage Notes**

- The type of an existing file can be determined with p4 opened or p4 files.
- Delta storage (the default mode with text files) is a method whereby only the differences (or deltas) between revisions of files are stored. Full file storage (the default mode with binary files) involves the storage of the entire file. The file's type determines whether full file or delta storage is used. Perforce uses RCS format for delta storage.
- Some of the file types are compressed to gzip format for storage in the depot. The compression occurs during the submission process, and decompression happens while syncing. The process is transparent to the user; the client workspace always contains the file as it was submitted.

- Symbolic links in non-UNIX client workspaces appear as small text files containing a
  relative path to the linked file. Editing these files on a non-UNIX client should be done
  with caution, as submitting them to the depot may result in a symbolic link pointing to
  a nonexistent file on the UNIX workspace.
- Changing a file's type does not affect earlier revisions stored in the depot.
  - For instance, changing a file's type by adding the +Sn (temporary object) modifier tells Perforce to store only the most recent n revisions of the file in the depot. If you change an existing file into a temporary object, subsequent revisions (after the nth) will purge the revisions stored after the old head revision, but revisions to the file stored in the depot before the +Sn modifier was used will remain unaffected. (Syncing to a non-head revision submitted after the +Sn modifier was used will delete the file from your workspace. Such revisions are displayed as purge operations in the output of p4 filelog.)
- The modtime (+m) modifier is a special case: It is intended for use by developers who need to preserve a file's original timestamp. (Normally, Perforce updates the timestamp when a file is synced.) It allows a user to ensure that the timestamp of a file in a client workspace after a p4 sync will be the original timestamp existing *on the file* at the time of submission (that is, *not* the time at the Perforce server at time of submission, and *not* the time on the client at the time of sync).

The most common case where this is useful is development involving the third-party DLLs often encountered in Windows environments. Because the timestamps on such files are often used as proxies for versioning information (both within the development environment and also by the operating system), it is sometimes necessary to preserve the files' original timestamps regardless of a Perforce user's client settings.

The +m modifier on a file allows this to happen; if set, Perforce will ignore the modtime ("file's timestamp at time of submission") or nomodtime ("date and time on the client at time of sync") option setting of the client workspace when syncing the file, and always restore the file's original timestamp at the time of submit.

• Versions of Perforce prior to 99.1 used a set of keywords to specify file types. The following table lists the older keywords and their current base file types and modifiers:

Old Keyword	Description	Base Filetype	Modifiers
text	Text file	text	none
xtext	Executable text file	text	+X
ktext	Text file with RCS keyword expansion	text	+k
kxtext	Executable text file with RCS keyword expansion	text	+kx
binary	Non-text file	binary	none
xbinary	Executable binary file	binary	+X
ctext	Compressed text file	text	+C
cxtext	Compressed executable text file	text	+Cx
symlink	Symbolic link	symlink	none
resource	Macintosh resource fork	resource	none
uresource	Uncompressed Macintosh resource fork	resource	+F
ltext	Long text file	text	+F
xltext	Executable long text file	text	+Fx
ubinary	Uncompressed binary file	binary	+F
uxbinary	Uncompressed executable binary file	binary	+Fx
tempobj	Temporary object	binary	+FSw
ctempobj	Temporary object (compressed)	binary	+Sw
xtempobj	Temporary executable object	binary	+FSwx
xunicode	Executable unicode	unicode	+X

## Index

Symbols		in views 278
#		^
as co	mment character 119	as boolean NOT 86, 114
as re	vision specifier 272	
	enames 9, 87, 97, 228, 275	as boolean OR 85, 113
	ews 278	A
not a	llowed in passwords 222	access
%	•	admin
in fil	enames 9, 87, 97, 228, 275	154
	ews 278	levels 153
%%n		limiting by IP address 153
as w	ildcard 271	superuser 154
&		access level
as bo	oolean AND 85, 113	and commands, listing of 157
*	,	access levels
as w	ildcard 271	and p4 group 90
	ildcard in fstat filters 86	adding files
	ildcard in job searches 113	specifying default file types 9, 213, 281
	ildcard, in p4 users 224	admin access level 154
	ildcard, in protections table 155	administering Perforce 12
	enames 9, 87, 97, 228, 275	administration
	ews 278	resetting passwords 149
	ks out password in p4 user form 222	allwrite 33
+m	T I	API
	ification time preservation 214	Perforce and p4 fstat 81
	1	asp files 285
as w	ildcard 271	atomic changes 192
wild	card, required with p4 depot 49	audit trail 233
	card, restrictions with p4 add 10	authentication 204
/	, <u>-</u>	.avi files 285
	th component separator 271	В
	llues separator in job templates 118	base file types 281
/tmp	, ,	batch file
and '	ГЕМР <b>264</b>	and pamerge 248
=, >, , >=,		BeOS
	mparison operators 86, 113	and symbolic links 282
@	•	binary files 281
as re	vision specifier 272	comparing 60
	enames 9, 87, 97, 228, 275	.bmp files 285

boolean operators	numbered, changing description of 195
and filters 85	numbering of 21
and jobviews 113	pending vs. submitted 192
branch mapping 19	pending, listing files in 146
branch mappings	purpose of 195
creating and editing 16	removing files from with p4 revert 23
listing 19	specifying when adding files 9
branch view 279	specifying when deleting files 46
and p4 branch 16	specifying when editing files 64
and p4 diff2 18	specifying when resubmitting 193
and p4 integrate 102	submitting 192
and p4 sync 280	changes
codeline example 18	atomic 192
defined 277	conflicting, resolving 171
branches	changing file type
comparing files across 59	with -t 284
branching 16	characters
.btr files 285	allowable in file names 274
C	checkpoint 12
carriage return 34	client syntax 271
change review daemon 154, 161, 181, 183, 222	and p4 files 71
changelist numbers	translating 227
highest possible 41	client view 278
pending vs. submitted changelists 41	and p4 client 30
changelist submission triggers 206	and p4 print 151
changelists	and p4 sync 197
and jobs 22, 73	defined 277
creating or editing 21, 26	client workspace
default, and p4 submit 192	alternate roots 31
defined 21	automatically changing settings for 237
deleting 22	comparing files with depot 55
details, describing 53	creating and editing 30, 229
full descriptions, displaying 27	defined 30
jobviews and users 114	deleting 33
listing 25, 27	files in, vs. p4 have 96
listing associated files with p4 opened 23	listing all 38, 230
listing associated jobs with p4 fixes 23	name of 236
listing jobs linked to 76	options 33
listing with p4 review 181	populating with depot files 197
meaning of 23	root 31
moving files between 167	synchronizing labels with 126
moving files between with p4 reopen 23	using file types to set permissions of files
numbered 192	in 283

client workspace templates 33	cross-platform development
clients	line endings 35
and labels 126	.css files 285
and temporary files 264	current directory 263
clobber 33, 198	and temporary files on non-UNIX clients
closing jobs	264
with p4 submit 193	D
.cnf files 285	-d flag
codelines	deleting changelists with 22
and branch views 18	daemons
comparing files across 59	and review access 161
command-line options	change review 154, 161, 181, 183, 222
globally-available 267	changelist numbers 41
commands	tips for creating 211
controlling access to 153	default changelist
help on 98	listing open files in 146
listed by access level 157	default changelists
comparing	and p4 submit 192
binary files 60	deleting files 46
files 55, 58	deleting passwords 149
comparison operators	deleting users 221
and filters 86	delta storage
and jobviews 113	defined 286
compress 34	depot
compression	and server root 50
of files, automatic 286	comparing files with client workspace 55
COMPUTERNAME	comparing two revisions of files in 58
default client workspace on Windows	files, getting from 197
236	how files are stored in 286
counter	listing files in 71
limits 41	submitting changes to 192
counters	verifying integrity of 225
and p4 review 181	depot syntax 271
and review access 161	and have list 96
listing 43	and p4 branch 16
setting 40	and p4 print 151
CR/LF translation 34	and protections table 155
•	translating 227
and LineEnd setting 35	depots
creating branch views 16	creating or editing 48
depot specifications 48	deleting 50
	empty 10
creating users 220	listing 52
crlf 34	11011116 02

populating 10	P4AUDIT 233
remote 48, 50	P4CHARSET 234
remote, and protections 161	P4CLIENT 236
diff chunks	P4COMMANDCHARSET 235
and file conflicts 174	P4CONFIG 237
diff program	P4DEBUG 239
and p4 describe 53	P4DESCRIPTION 240
and p4 diff 55	P4DIFF 241
and p4 diff2 58	P4DIFFUNICODE 242
Perforce internal routine 241	P4EDITOR 243
third-party, specifying 241	P4HOST 244
diffing files 55, 58	P4JOURNAL 245
directories	P4LANGUAGE 246
and spaces 33	P4LOG 247
directories, empty	P4MERGE 248
removing on sync 35	P4MERGEUNICODE 249
directory	P4NAME 250
current 263	P4PAGER 251
discarding changes 179	P4PASSWD 252
disk space 190	P4PCACHE 253
reclaiming 144	P4PFSIZE 254
distributed development 169	P4POPTIONS 255
DNS	P4PORT 256
and p4port 256	P4ROOT 258
.doc files 285	P4TARGET 259
.dot files 285	P4TICKETS 260
E	P4USER 261
editing	P4ZEROCONF 262
branch views 16	PWD 263
depot specifications 48	setting for a Windows service 231
files 64	setting with P4CONFIG 237
user specifications 220	TMP, TEMP 264
editor	example
form, commands which use 243	branching and codelines 18
form, specifying with P4EDITOR 243	changing file types 168
EDITOR_SIGNATURE	comparing files across a branch 61
and P4EDITOR on Macintosh 243	creating a job 111
empty depots	deleting a user 223
populating 10	editing a job 111
environment variables	editing user information 223
and Windows registry 185	effects of protections 161
how to set 231	generating output for scripts 87
overriding with global options 267	getting files from depot 199

integrating files 105	and p4 add 10
listing jobs by various criteria 115	and p4 edit 64
listing opened files 147	and permissions in client workspace 283
moving files between changelists 168	and storage in depot 286
p4 typemap 215	apple 282
pending changelist, listing files in 147	base 281
pipes and $-x$ 57	binary 281
pre-submit triggers, use of 212	changing 167
propagating changes 105	determined by Perforce 281
protections table 161	help on 98
RCS keyword expansion 286	keywords 288
renaming files 165	listed 288
reverting files to pre-opened states 180	mapping to filenames 213
scheduling a resolve 105	modifiers 283
submitting files in changelists 196	partial 284
syncing a client workspace 199	resource 282
viewing user information 223	showing 286
working as another user 223	specifying 283
exclusionary mappings 277	specifying with -t 284
and p4 protect 155	symlink 282
and triggers 205	text 281
.exp files 285	filenames
external authentication 204	and spaces 33
F	mapping to file types 213
-f flag	special characters 9, 87, 97, 228, 275, 278
editing previously-submitted changelists	files
22	adding to depot 9
editing read-only job fields with 110	adding to label 126
forcing label deletion with 122	adding, specifying default type 9, 213, 281
overriding client workspace settings 33	.asp 285
fields	.avi 285
null, in jobs 115	binary, comparing 60
file names	.bmp 285
valid characters for 274	.btr 285
with spaces, in views 278	changing type 167
with spaces, on command line 273	changing type with -t 284
file size 190	checkpoints and journals 12
file specifications	.cnf 285
and p4 revert 180	comparing 55, 58
and p4 submit 195	comparing between codelines 59
help on 98	conflicts between, resolving 171
interpreted by local shell 273	controlling access 153
file types 281, 285	copying from depot 197

.css 285	obliterating 143
deleting from depot 46	on other depots, accessing 48
deleting from label 126, 201	open, discarding changes 179
deleting permanently 143	open, listing 146
delta and full-file storage 286	open, submitting 192
displaying info for scripts 81	opening 32, 192, 194
displaying revision histories 68	opening for add 9
.doc 285	opening for branch with p4 integrate
.dot 285	101
editing 64	opening for delete 46
editing older revisions 65	opening for delete with p4 integrate
.exp 285	101
getting from depot 197	opening for edit 64
getting latest revision 272	opening for integrate 101
.gif 285	.pdf 285
.gz 285	.pdm 285
.htm 285	permanent removal of 143
.html 285	.ppt 285
.ico 285	preventing other users from editing 129
in a label, listing 124	removing from changelists 23, 179
in changelists, detailed information 53	removing with #none 272
.inc 285	renaming 141
including in labels 121	reopening 23
.ini 285	resolving conflicts between 171
integrated, listing 107	reverting 23, 32, 192, 194
integrating changes between 171	reverting to pre-edit state 179
.jpg 285	saving changes to depot 192
.js 285	scheduled for resolve, listing 177
.lib 285	scheduling for resolve 176
linked to changelist, listing 23	specifying 271
listing 71	specifying by change number 272
listing contents of, by revision 151	specifying by date and time 273
listing open files 146	specifying by revision 272
locating 227	specifying type of 283
locked 147	stored compressed 286
locking 129	submitting 192
.log 285	syncing 197
mapping Perforce file types to filenames	tagging 201
213	types of 281
modification time, preserving 214	unlocking 217
moving between changelists 23, 167	unresolved, listing 177
.mpg 285	verifying integrity of 225
multi-forked 282	.xls 285

yours, theirs, base, merge, meaning	and p4 edit 64
when resolving 172	specifying 272
filters	help
searching files 84	use p4 help 98
fix status	history of changes to forms 48
default 120	hosts file
fixes	and p4port 256
deleting fix records with p4 fix -d73	hosts, impersonating
listing 76	impersonating hosts 244
to jobs over multiple changelists 73	.htm files 285
forms	.html files 285
commands which use 243	1
specifying editor with P4EDITOR 243	-i flag
from 188	changelists and integrated files 28
fstat	ico files 285
* wildcard 86	inc files 285
full file storage	.ini files 285
defined 286	integrate
G	files, opening for 101
-G option 267	integration
getcwd()	listing 107
in lieu of PWD 263	scheduling 171
getting files from depot 197	IP addresses
.gif files 285	controlling access by 153
global options 267	J
help on 98	-J option
groups	and p4d 245
and subgroups 91	job specification
controlling access 153	displaying 114
creating 90	job table
deleting 90	reindexing 113
listing users in 94	job views
.gz files 285	help on 98
gzip 286 <b>H</b>	jobs * wildcard 113
have list	and changelists 22
and p4 delete 46	changing status of 74
defined 96	closing with p4 submit 193
listing with p4 have 96	creating and editing 109
vs. files in workspace 96	defined 109
have revision 96, 272	excluding from query 115
head revision	fixing over multiple changelists 73
and p4 delete 46	linked to changelist, showing 23

linked to changelists, listing 76	labels
linking to changelists with p4 fix 73	and clients 126
listing 112	listing 124
null fields 115	owner of, changing 121, 126
wildcards 115	synchronizing with clients 126
jobs template	labelsync
modifying 117	ownership required 121, 126
JobView field	latest revision
and p4 user form 114	specifying 272
use of 114	LDAP 204
Jobview field	.lib files 285
and changelists 22	licence
and p4 user 222	and pre-submit triggers 211
jobviews	license
and comparison operators 86, 114	and remote virtual user 50
and field types 114	limitations
limitations 115	and jobviews 115
searching jobs 112	line endings 35
journal 12	LineEnd 35
journal file	CR/LF 32
specifying with P4JOURNAL 245	linefeed convention 34
.jpg files 285	list access level 153
.js files 285	listing
K	branches 19
keywords	changelists 25, 27
RCS, examples 286	client workspaces 38, 230
RCS, expanding 283	counters 43
specifying Perforce file types 288	depots 52
L	file contents by revision 151
-L flag	file integrations 107
and long change descriptions 28, 69	files in a label 124
-1 flag	files in depot 71
and long change descriptions 27, 28, 69	files scheduled for resolve 177
and long job descriptions 112	fixes 76
-L option	groups 94
and p4d 247	jobs 112
label 201	jobs linked to changelists 76
adding files to 126	labels 124
deleting files from 126, 201	open files 146
listing files in 124	listing subdirectories 62
unlocking 122	listing users 224
label view 280	local syntax 271
defined 277	and have list 96

translating 227	and passwords 148, 252
locked 34	MERGE environment variable
locked files	and pamerge 248
finding 147	merge programs
locking files 129	third-party, specifying 248
.log files 285	modifier
logging 233	file type, +m 214
M	modtime 34
Macintosh	changes as of 2000.1 34
and file types 282	.mpg files 285
changing default form editor 243	multi-forked file 282
linefeed convention 34	N
resource fork file type 282	network
mappings	data compression 34
and p4 client 30	noallwrite33
and protections table 155	noclobber 33, 198
directories with spaces 33	nocompress 34
exclusionary 277	nocrlf 34
exclusionary, and protections table 155	nomodtime 34
exclusionary, and triggers 205	changes as of 2000.1 34
in branch views 16, 280	nonexistent revision
in client views 278	specifying 272
in label views 122, 280	normdir 35
integration, and p4 branch 102	numbered changelists 192
local and remote depots 49	0
overlay 277	obliterating files 143
mappings, order of	online help
and triggers 205	use p4 help 98
in protections 155	open access level 154
in views 277	open files
maxlocktime	changing type with p4 reopen 167
commands affected by 93	opening files
maxresults	for add 9
and p4 filelog 69	for delete 46
and p4 files 72	for edit 64
and p4 print 152	operators
commands affected by 93	boolean, and filters 85
setting with p4 group 90	boolean, and jobviews 113
maxscanrows	comparison, and filters 86
commands affected by 93	comparison, and jobviews 113
setting with p4 group 90	options
MD5	for client workspaces 33
and p4 verify 225	global 267

output		p4	fix73
	formatting for scripts with -s 267	p4	fixes
overlay mappings 277			and changelists 23
overriding		p4	flush 78
registry variable settings 186		p4	fstat 81
ow	ner	p4	grep 88
	of label, changing 121, 126	p4	group 90
Р		p4	groups 94
p4		p4	have 96
	version of 268		vs. files in workspace 96
p4	add 9	p4	help 98
p4	admin 12	p4	info 100
p4	branch 16	p4	integ
	and p4 integrate 102		abbreviation for p4 integrate 104
p4	branches 19	p4	integrate 101
p4	browse 20	p4	integrated 107
p4	change 21	p4	job 109
p4	changelist 26	p4	jobs 112
p4	changelists 25	p4	jobspec 117
p4	changes 27		and P4V 119
p4	client 30	p4	labels 124
	options, and p4 sync 198	p4	labelsync 126
p4	clients 38		and p4 label 121
p4	counter 40	p4	license 128
p4	counters 43	p4	lock 129
p4	dbschema 44	p4	lockstat 130
p4	dbstat 45	p4	logger 131
p4	delete 46	p4	login 132
	vs.p4 obliterate 143	p4	logout 134
p4	depot 48	p4	logstat 136
p4	depots 52	p4	logtail 137
p4	describe 53	p4	monitor 138
p4	diff 55	p4	obliterate 143
	and P4DIFF 241		and deleting depots 50
p4	diff2 58	p4	open 65
	and branch views 18	p4	opened 146
p4	dirs 62		and changelists 23
	$\mathtt{edit}64$	p4	passwd 148
p4	executable		and P4PASSWD 252
	version of 100		setting passwords with 252
p4	export 67	p4	print 151
_	filelog 68	p4	protect 153
p4	files 71		and Protections field 154

	required after server installation 160	P4COMMANDCHARSET 235
	required when creating new depots 50	P4CONFIG 237
p4	protects 163	p4d
	rename 165	logging errors to a file 247
p4	reopen 167	specifying journal file 245
_	and changelists 23	P4DEBUG 239
p4	replicate 169	P4DESCRIPTION 240
	resolve 171	P4DIFF 241
	and P4DIFF 241	and p4 diff 55
	and P4MERGE 248	not used in p4 describe 53
	and P4PAGER 251	not used in p4 diff2 58
p4	resolved 177	P4DIFFUNICODE 242
p4	revert 179	P4EDITOR 243
	and changelists 23	commands affected by 243
	and p4 resolve -at 173	P4HOST 244
p4	review 181	P4JOURNAL 245
p4	reviews 183	P4LANGUAGE 246
p4	set 185	P4LOG 247
p4	shelve 188	P4MERGE 173, 248
p4	sizes 190	batch file required on Windows 248
p4	submit 192	P4MERGEUNICODE 249
p4	sync 197	P4NAME 250
	and branch view 280	P4 PAGER 251
p4	tag 201	P4PASSWD 252
p4	tickets 203	and p4 passwd 252
p4	triggers 204	P4 PCACHE 253
p4	typemap 213, 281	P4PFSIZE 254
	and p4 add 9	P4POPTIONS 255
p4	unlock 217	P4 PORT 256
p4	unshelve 218	P4ROOT 258
p4	user 220	and depot files 50
	and JobView field 114	and temporary files on Windows servers
	and Reviews field 183	264
	jobviews, and p4 submit 193	P4TARGET 259
	setting passwords with 252	P4TICKETS 260
	specifying username with 261	P4USER 261
p4	users 224	and pre-submit triggers on Windows 211
p4	verify 225	P4V
p4	where 227	tooltips and jobspecs 119
p4	workspace 229	P4ZEROCONF 262
p4	workspaces 230	PAGER environment variable
P40	CHARSET 234	and P4PAGER 251
P4CLIENT 236		password

maximum length of 149	files, and p4 edit 64
passwords	granting and denying 153
and P4PASSWD 252	required before accessing new depot 50
and users 222, 261	setting in client workspace via file type
deleting 149	283
resetting 149	populating depots 10
setting 148	port number
special characters in 222	setting, on clients and servers 256
specifying on command line 148, 261	positional specifiers 271
.pdf files 285	POSIX\$SHELL
.pdm files 285	and P4EDITOR on VMS 243
pending changelists 192	.ppt files 285
editing description of 21	preserving modification times 214
listing 25, 27	pre-submit triggers 204
listing files in 146	tips for creating scripts 211
Perforce API	protections
and p4 fstat 81	and IP addresses 153
Perforce client	granting and denying 153
and p4port 256	viewing 163
and temporary files 264	Protections field 154
Perforce client and server	protections table 153
obtaining version of 100	example 161
Perforce file types 285	proxy
Perforce Proxy	and P4PCACHE 253
and P4PCACHE 253	and P4PFSIZHE 254
and P4PFSIZE 254	and P4POPTIONS 255
and P4POPTIONS 255	and P4PORT 256
and p4port 256	and P4TARGET 259
and p4target 259	PWD 263
Perforce server	Python 267
administering 12	R
and P4PORT 256	RCS file format 286
and P4ROOT 258	RCS keyword expansion 283
and temporary files 264	examples 286
and triggers 208	read access level 153
checkpoints and journals 12	registry
installing securely 160	never stores plaintext passwords 148, 252
stopping 12	setting variables in 185
verifying integrity of 225	registry variables
Perforce syntax 271	overriding settings of 186
Perforce usernames	remote depots 48, 50
and passwords 261	and protections 161
permissions	removing files

permanently 143	and -s option 267
renaming files 141	and triggers 204
replication 169	and -x option 267
resetting passwords 149	-s and p4 fstat 85
resolve	triggers, tips for creating scripts 211
scheduling files for 176	with Python 267
resolving files 171	-x option, example 57
resource fork 282	searching
reverting changes 23, 179	files, with fstat 84
review access level 154	for null job fields 115
Reviews field	jobs, with jobviews 112
and p4 user 183	security
use of 222	and p4 protect 160
revision	security level 222
latest, specifying 272	server
of file on current client 272	administering 12
of file, displaying 151	and p4port 256
specifying 272	and temporary files 264
revision history	and triggers 208
displaying 68	changing IP address 128
obliterating 143	checkpoints and journals 12
revision ranges	installation, and p4 protect 160
and p4 changes 27	licensing 128
and p4 files 72	reclaiming disk space 144
and p4 fixes 76	specifying error log file 247
and p4 integrate 101	specifying journal file 245
and p4 print 151, 152	stopping 12
and p4 resolved 177	upgrading 113
and p4 sync 197	verifying integrity of 225
specifying 273	server root 258
revision specifiers 272	and depots 50
and labels 126	and temporary files on Windows servers
and p4 changes 27	264
and p4 sync 197	server variables
help on 98	listing 43
rmdir 35	setting 40
S	setting environment variables 231
-s option	for Windows services 185
and p4 fstat 85	on Windows services 231
formatting output for scripting 267	shell
scripting	interpreting file specifications 224, 273
and p4 dirs 62	SHELL environment variable
and p4 fstat 81	and P4DIFF on Windows 241

and P4EDITOR on Windows 243	and p4 submit 192
shelving 188, 218	storage
spaces	of files in depot 286
within filenames 33	subdirectories
spaces and client workspaces	listing 62
translated to underscores 33	subgroups
spaces in file names	and groups 91
quotes around 273	submit
spaces in filenames	reverting files 32, 192, 194
quotes around, in views 278	submitted changelists 192
spaces in passwords	listing 25, 27
quotes around 149	viewing 21
spec depot	submitting changelists 192
populating 12	submitting files 192
spec depot 48	super access level 154
specification	superuser 154
job, displaying 114	and creating users 220
specification triggers 206	and new server 160
specifiers	symbolic links 282
positional 271	on non-UNIX systems 282, 287
revision 272	sync 197
specifying	syntax forms
default editor with P4EDITOR 243	local, client, depot 271
file types 283	translating between with p4 where 227
files for integration 101	T
files, by change number 272	-t flag
files, by date and time 273	and client workspace templates 33
files, by revision 272	and file type 284
files, for integration 101	tag 201
files, latest version of 272	target server
program to display p4 resolve output	and Perforce Proxy 259
251	template
revision ranges 273	jobs, modifying 117
third-party diff programs 241	templates
third-party merge programs 248	client workspace 33
username with -u and P4USER 261	temporary files
standard input	where stored 264
reading from 267	text files 281
standard output	ticket file
and p4 print 151	location 260
status	timestamps
of jobs, changing 74	on DLLs, preserving 36, 287
Status field	TMP, TEMP 264

tooltips 119	and P4PASSWD 252
translation	and passwords 148, 222, 261
CR/LF 34	changing with P4CONFIG and P4USER 220
triggers 204	controlling access 153
and Windows services 211	creating and editing 220
naming 206	deleting 221
passing arguments to 209	groups of, listing 94
script, specifying arguments to 208	groups, granting access to 153
types of 206	listing 224
troubleshooting	listing with p4 reviews 183
local shell and file specifications 273	preventing others from editing files 129
type mapping 213	running commands as 222, 261
typemap 9	virtual, remote 50, 161
types	UTF-16 234, 235
of files, changing 167	UTF-32 234, 235
U	UTF-8 234
-u flag	V
impersonating users with 261	variables
unchanged files	environment, how to set 231
reverting 32, 192, 194	overriding with global options 267
undoing file edits 179	registry 185
unicode 234, 235, 242, 249, 282	server, listing 43
UNIX	server, setting 40
line endings on mounted drives 35	verifying file integrity 225
linefeed convention 34	version
UNIX	of p4 268
linefeed convention 35	of Perforce client and server programs
unlocked 34	100
unlocking files 217	versioned specifications 48
unresolved files	view
listing 177	branch 279
upgrading	branch, and p4 diff2 18
from 98.2 or earlier 113	branch, and p4 integrate 102
USER	branch, and p4 sync 280
and P4USER 261	branch, creating or editing 16
user preferences	client 278
setting 220	client, and p4 sync 197
USERNAME	help on 98
and P4USER on Windows 261	introduced 277
users	label 280
and files, unlocking 217	VMS
and forgotten passwords 149	changing default form editor 243
and groups 90	

```
W
                                                 Z
                                                 Zeroconf 20, 257
warnings
    about counters and p4 review 182
    about p4 counters 40
    about p4 flush 78
    about p4 jobspec 110
    about p4 obliterate 143
    about p4 revert 180
    about pre-submit triggers 204
    superuser access and p4 protect 160
wildcards
    and p4 add 10
    and p4 integrate 101
    in filters 86
    in jobviews 113
    listing users with 224
    specifying files with 271
Windows
    batch file required for P4MERGE 248
    COMPUTERNAME as default client work-
            space 236
    default client workspace name 236
    default forms editor 243
    line endings 35
    linefeed convention 34, 35
    overriding registry variables 186
    registry variables 185
    services, and triggers 211
    setting passwords on 252
    setting variables for Windows services
            231
    third-party DLLs 36, 287
workspace
    client, alternate roots 31
    client, creating and editing 30, 229
    client, listing 38, 230
    files in, vs. have list 96
write access level 154
X
-x option
    example with p4 diff 57
    reading from standard input 267
.xls files 285
```