Testing Conventional Applications

Adapted from Pressman

What is a “Good” Test?

- A good test has a high probability of finding an error
- A good test is not redundant.
- A good test should be “best of breed”
- A good test should be neither too simple nor too complex

Internal and External Views

- Any engineered product (and most other things) can be tested in one of two ways:
  - Knowing the specified function that a product has been designed to perform, tests can be conducted that demonstrate each function is fully operational while at the same time searching for errors in each function;
  - Knowing the internal workings of a product, tests can be conducted to ensure that "all gears mesh," that is, internal operations are performed according to specifications and all internal components have been adequately exercised.

Test Case Design

"Bugs lurk in corners and congregate at boundaries ..."

Boris Beizer



OBJECTIVE	**to uncover errors**
CRITERIA	**in a complete manner**
CONSTRAINT	**with a minimum of effort and time**

Exhaustive Testing



There are 10^{14} possible paths! If we execute one test per millisecond, it would take 3,170 years to test this program!!

Selective Testing



Software Testing



White-Box Testing



... our goal is to ensure that all statements and conditions have been executed at least once ...

Why Cover?

- **logic errors and incorrect assumptions are inversely proportional to a path's execution probability**
- **we often <u>believe</u> that a path is not likely to be executed; in fact, reality is often counter intuitive**
- **typographical errors are random; it's likely that untested paths will contain some**

Basis Path Testing



First, we compute the cyclomatic complexity:

number of simple decisions + 1

or

number of enclosed areas + 1

In this case, V(G) = 4

Cyclomatic Complexity

A number of industry studies have indicated that the higher V(G), the higher the probability or errors.



modules in this range are more error prone

Basis Path Testing



Next, we derive the independent paths:

Since V(G) = 4, there are four paths

Path 1: 1,2,3,6,7,8

Path 2: 1,2,3,5,7,8

Path 3: 1,2,4,7,8

Path 4: 1,2,4,7,2,4,...7,8

Finally, we derive test cases to exercise these paths.

Basis Path Testing Notes



- you don't need a flow chart, but the picture will help when you trace program paths
- count each simple logical test, compound tests count as 2 or more
- basis path testing should be applied to critical modules

Deriving Test Cases

- *Summarizing:*
  - Using the design or code as a foundation, draw a corresponding flow graph.
  - Determine the cyclomatic complexity of the resultant flow graph.
  - Determine a basis set of linearly independent paths.
  - Prepare test cases that will force execution of each path in the basis set.

Control Structure Testing

- Condition testing — a test case design method that exercises the logical conditions contained in a program module
- Data flow testing — selects test paths of a program according to the locations of definitions and uses of variables in the program

Black-Box Testing



Black-Box Testing

- How is functional validity tested?
- How is system behavior and performance tested?
- What classes of input will make good test cases?
- Is the system particularly sensitive to certain input values?
- How are the boundaries of a data class isolated?
- What data rates and data volume can the system tolerate?
- What effect will specific combinations of data have on system operation?

Equivalence Partitioning



Sample Equivalence Classes

Valid data

- user supplied commands
- responses to system prompts
- file names
- computational data
  - physical parameters
  - bounding values
  - initiation values
- output data formatting
- responses to error messages
- graphical data (e.g., mouse picks)

Invalid data

- data outside bounds of the program
- physically impossible data
- proper value supplied in wrong place

Boundary Value Analysis