



Connector On-Premises

Virtual Machine Setup

Table of Contents

Deploy Connector On-Premises	1
Choose Deployment Packaging	2
Deploy VM Appliance	4
Install Docker on RedHat	4
Install Using Docker Host	5

Deploy Connector On-Premises

Use the on-premises option to deploy Appthority Connector in your datacenter and virtual server environment.

Tip: It is recommended that for your production environment, you should deploy a single Appthority Connector on a single virtual machine or Docker container. For staging or testing environments, you can deploy and configure multiple Connectors on a single virtual machine, or multiple Connector Docker containers, whichever you use.

Under **Appthority Connector**, click **On-Premises**.



Proceed to [choose packaging](#).

 DASHBOARD

 DEVICES

 APPS

 COMPLIANCE

 ADMIN

OrganizationUsersEMM

Enterprise Mobility Management ?

☒ Enable EMM Integration

EMM SYSTEM

Select VendorSelect Product

AirWatchOn-Premises

APPTHORITY CONNECTOR • Inactive

CloudOn-Premises

PACKAGING OPTIONS

[Option 1: VM Appliance](#)

[Connector VM deployment instructions](#)

[Download VM appliance for Airwatch](#)

[Option 2: Docker Host](#)

[Connector Docker deployment instructions](#)

Appthority Mobile Agent ?

☐ Enable Mobile Agent

☐ iOS

☐ Android

Save Configuration

Choose Deployment Packaging

Choose which deployment packaging option to use for Connector On-Premises:

- RedHat Linux and Docker on your own machine (virtual or physical)
- Appthority's virtual machine appliance (OVA VM pre-packaged with the necessary software)

In order to install or update Connector, you will need your Appthority org credentials.

Note: For the Appliance option, the Docker host and virtual machine will be configured by default with 4GB RAM, 50GB of storage, and 1 vCPU for up to 50,000 devices. We recommend that you do not set these lower than the default.


Follow the guidelines for the packaging option you want to use.

To use Appthority's Virtual Machine

- To use the prepackaged [Virtual Machine Appliance](#):
Download the OVA from the 'Download VM appliance' link on the **Admin > Organization** tab and configure. This will install a virtual machine with RedHat Linux and Docker. Your system admin may need the hash information in case of failed download: MD5 Checksum: a0239b2c2ecabe68070e9117c9684151

To install Connector on your own environment

- If you have RedHat Linux 7.3 but do not have Docker installed:
See [Install Docker on RedHat Linux](#) - Install Docker on your own RedHat Linux environment, then proceed to [install Connector](#) on Docker.
- If you have RedHat Linux 7.3 and already have Docker installed:
See [Install Connector on Docker](#) - Log in to your Docker host and run the [script](#) to install Connector.





Deploy VM Appliance

To install Appthority Connector using the downloaded VM Appliance, have your VM administrator follow these steps. The VM administrator may be the same as your Appthority administrator.

Note: Deploy the VM Appliance using your virtual machine admin tool instructions. Once the VM is correctly configured, continue to these steps.

To register your RedHat instance, you must subscribe and agree to their terms. Configure your Red Hat licensing to open the Appthority image the first time you log in. The VM is in RedHat Enterprise Linux version 7.3.

Appthority creates two user accounts, 'root' and 'appthority'.

To install Connector on the VM Appliance

1. Log in to the Virtual Machine as appthority user.
2. Run the command (you can copy and paste it).

```
curl -Ls http://connector.appthority.com/appthority.sh> appthority.sh  
; chmod +x appthority.sh ; ./appthority.sh
```

This will download and start the script to install the Connector image.
3. Step through the [script](#) in the command line.

Install Docker on RedHat

If you want to install Connector using a Docker host on your own RedHat VM, follow these steps.

Install Docker

The basic steps and exact commands to run are here. Refer to the detailed [instructions](#) for more information.

To install Docker on RedHat

1. Run this command to install Docker on RedHat

```
curl -fsSL https://get.docker.com/ | sh
```

2. Add user 'appthority' to 'docker' group (run as root):

```
useradd appthority  
usermod -aG docker appthority
```

3. Run the command to start Docker at boot (run as root):

```
systemctl enable docker
```

Next: [Install Connector](#)

Note: When you install Connector, it is recommended that you use an account called 'appthority' that has access to the Docker group.

Install Using Docker Host

To install the Appthority Connector using your Docker host environment, have your Docker administrator follow these instructions. The Docker administrator may be the same as your Appthority administrator.

Note: If you need to install Docker first, follow these [instructions](#).

To install Connector on Docker

1. Log in to your Docker host.
2. Run the command (you can copy and paste it).

```
curl -Ls http://connector.appthority.com/appthority.sh> appthority.sh  
; chmod +x appthority.sh ; ./appthority.sh
```

This will download and run the script to install the Connector image on your Docker host.

3. Step through the [script](#) in the command line or terminal app.