MACHINE LANGUAGE

As humans, communicating with a machine is a tedious task. We can't, for example, just say "add this number and that number and store the result here". Computers have no way of even beginning to understand what this means.

- As we stated before, the alphabet of the machine's language is binary it simply contains the digits 0 and 1.
- Continuing with this analogy, *instructions* are the words of a machine's language. That is, they are meaningful constructions of the machine alphabet.
- The *instruction set*, then, constitutes the vocabulary of the machine. These are the words understood by the machine itself.

MACHINE LANGUAGE

To work with the machine, we need a translator.

Assembly languages serve as an intermediate form between the human-readable programming language and the machine-understandable binary form.

Generally speaking, compiling a program into an executable format involves the following stages:

High-level Language —— Assembly Language —— Machine Language

EXAMPLE OF TRANSLATING A C PROGRAM

High-Level Language Program

```
swap(int v[], int k){
   int temp;
                               Assembly Language Program
   temp = v[k];
   v[k] = v[k+1];
                               swap:
   v[k+1] = temp;
                                        multi
                                               $2, $5,
                                               $2, $4, $2
                                        add
                                               $15, 0($2)
                                        lw
                                               $16, 4($2)
                                               $16, 0($2)
                                        SW
       Compiler
                                               $15, 4($2)
                                        SW
                                               $31
                                        jr
                                        Assembler
```

Binary Machine Language Program

MACHINE LANGUAGE

- A single human-readable high-level language instruction is generally translated into multiple assembly instructions.
- A single assembly instruction is a symbolic representation of a single machine language instruction.
- A single machine language instruction is a set of bits representing a basic operation that can be performed by the machine.
- The instruction set is the set of possible instructions for a given machine.

ADVANTAGES OF HIGH-LEVEL LANGUAGES

Requiring these translation steps may seem cumbersome but there are a couple of high-level language advantages that make this scheme worthwhile.

- High-level languages allow the programmer to think in more natural, less tedious terms specifically in the case of application-specific languages.
- Improve programmer productivity.
- Improve program maintainability.
- Applications can be independent of the computer on which they were developed.
- Highly-optimizing compilers can produce very efficient machine code optimized for a target machine.

WHY LEARN ASSEMBLY LANGUAGE?

So, if high-level languages are so great...why bother learning assembly?

- Knowing assembly language illuminates concepts not only in computer organization, but operating systems, compilers, parallel systems, etc.
- Understanding how high-level constructs are implemented leads to more effective use of those structures.
 - Control constructs (if, do-while, etc.)
 - Pointers
 - Parameter passing (pass-by-value, pass-by-reference, etc.)
- Helps to understand performance implications of programming language features.

MIPS

We will start with a lightning review of MIPS.

- MIPS is a RISC (Reduced Instruction Set Computer) instruction set, meaning that it has simple and few instructions.
- Originally introduced in the early 1980's.
- An acronym for Microprocessor without Interlocked Pipeline Stages.
- MIPS architecture has been used in many computer products, especially in the late 80's and early 90's. N64, Playstation, and Playstation 2 all used MIPS implementations.
- Many ISAs that have since been designed are very similar to MIPS.
- ullet In the mid to late 90's, approximately 1/3 of all RISC microprocessors were MIPS implementations.

RISC ARCHITECTURE

- CISC (Complex Instruction Set Computer)
 - Intel x86
- RISC (Reduced Instruction Set Computer)
 - MIPS, Sun SPARC, IBM, PowerPC, ARM
- RISC Philosophy
 - fixed instruction lengths
 - load-store instruction sets
 - limited number of addressing modes
 - limited number of operations

THE FOUR ISA DESIGN PRINCIPLES

1. Simplicity favors regularity

- Consistent instruction size, instruction formats, data formats
- Eases implementation by simplifying hardware

Smaller is faster

- Fewer bits to access and modify
- Use the register file instead of slower memory

3. Make the common case fast

- e.g. Small constants are common, thus small immediate fields should be used.
- 4. Good design demands good compromises
 - Compromise with special formats for important exceptions
 - e.g. A long jump (beyond a small constant)

MIPS REVIEW


Now we'll jump right into our lightning review of MIPS. The general classes of MIPS instructions are

- Arithmetic
 - add, subtract, multiply, divide
- Logical
 - and, or, nor, not, shift
- Data transfer
 - load from or store to memory
- Transfers of control
 - jumps, branches, calls, returns

Here is an example of one of the simplest and most common MIPS instructions.

This MIPS instruction symbolizes the machine instruction for adding the contents of register t1 to the contents of register t2 and storing the result in t0.

Here is an example of one of the simplest and most common MIPS instructions.



Here is an example of one of the simplest and most common MIPS instructions.

The corresponding binary machine instruction is

000000 01001 01010 01000 00000 100000

This portion tells the machine exactly which operation we're performing. In this case, 100000 refers to an addition operation

Here is an example of one of the simplest and most common MIPS instructions.

The corresponding binary machine instruction is

This portion is used for shift instructions, and is therefore not used by the machine in this case.

Here is an example of one of the simplest and most common MIPS instructions.

The corresponding binary machine instruction is

This portion indicates the destination register – this is where the result will be stored. Because \$1000 to represent it.

Here is an example of one of the simplest and most common MIPS instructions.

The corresponding binary machine instruction is

This portion indicates the second source register. Because \$12 is the 10th register, we use 01010 to represent it.

Here is an example of one of the simplest and most common MIPS instructions.

The corresponding binary machine instruction is

This portion indicates the first source register. Because \$11 is the 9th register, we use 01001 to represent it.

Here is an example of one of the simplest and most common MIPS instructions.

The corresponding binary machine instruction is

000000 01001 01010 01000 00000 100000

This last portion holds the operation code relevant for other types of instructions. The add operation, and others like it, always have a value of 0 here.

MIPS INSTRUCTION OPERANDS

So now that we've seen an example MIPS instruction and how it directly corresponds to its binary representation, we can talk about the components of an instruction. MIPS instructions consist of operations on one or more operands. Operands in MIPS fit into one of three categories.

- Integer constants
- Registers
- Memory

INTEGER CONSTANT OPERANDS

Integer constant operands are used frequently. For example, while looping over an array, we might continually increment an index to access the next array element.

To avoid saving the constant elsewhere and having to retrieve it during every use, MIPS allows for *immediate* instructions which can include a constant directly in the instruction.

A simple example is add immediate:

addi \$s3, \$s3, 4 # adds 4 to the value in \$s3 and stores in \$s3

INTEGER CONSTANTS

- Generally represented with 16 bits, but they are extended to 32 bits before being used in an operation.
- Most operations use signed constants, although a few support unsigned.
- Integer constants can be represented in MIPS assembly instructions using decimal, hexadecimal, or octal values.
- A reflection of design principle 3, make the common case fast.
 - Because constants are used frequently, it is faster and more energy efficient to support instructions with built-in constants rather than fetching them from memory all the time.

REGISTERS

We've already seen some simple register usage in our two example MIPS instructions.

```
add $t0, $t1, $t2
addi $s3, $s3, 4
```

In these instructions, \$t0, \$t1, \$t2, and \$s3 are all registers. Registers are special locations built directly into the hardware of the machine. The size of a MIPS register is 32 bits. This size is also commonly known as a word in MIPS architecture.

REGISTERS

- There are only 32 (programmer visible) 32-bit registers residing in a MIPS processor.
- Reflects design principle 2, smaller is faster.
 - Having a small number of registers ensures that accessing a desired register is fast since they can be kept closer.
 - Also means that fewer bits can be used to identify registers \rightarrow decreases instruction size.
- Registers also use much less power than memory accesses.
- MIPS convention is to use two-character names following a dollar sign.
 - Register 0: \$zero stores the constant value 0.
 - Registers 16-23: \$s0-\$s7 saved temporaries (variables in C code).
 - Registers 8-15: \$t0-\$t7 temporaries.


REGISTERS

Name	Number	Use
\$zero	0	Constant value 0.
\$at	1	Assembler temporary. For resolving pseudoinstructions.
\$v0-\$v1	2-3	Function results and expression evaluation.
\$a0-\$a3	4-7	Arguments.
\$tO-\$t9	8-15, 24-25	Temporaries.
\$s0-\$s7	16-23	Saved temporaries.
\$k0-\$k1	26-27	Reserved for OS kernel.
\$gp	28	Global pointer.
\$sp	29	Stack pointer.
\$fp	30	Frame pointer.
\$ra	31	Return address.

MEMORY OPERANDS

Before we talk about memory operands, we should talk generally about how data is stored in memory.

- As we said before, memory contains both data and instructions.
- Memory can be viewed as a large array of bytes.
- The beginning of a variable or instruction is associated with a specific element of this array.
- The address of a variable or instruction is its offset from the beginning of memory.



MEMORY OPERANDS

For a large, complex data structure, there are likely many more data elements than there are registers available. However, arithmetic operations occur only on registers in MIPS.

To facilitate large structures, MIPS includes data transfer instructions for moving data between memory and registers.

As an example, assume we have the following C code, where A is an array of 100 words.

$$g = h + A[8]$$

MEMORY OPERANDS

Let's say g and h are associated with the registers \$s1 and \$s2 respectively. Let's also say that the base address of A is associated with register \$s3.

$$g = h + A[8]$$

To compile this statement into MIPS, we'll need to use the *load word* instruction to transfer A[8] into a register.

```
lw $t0,32($s3) # load the element at a 32 byte offset from $s3
add $s1,$s2,$t0
```

There is an equivalent store word instruction for storing data to memory as well.

MIPS ASSEMBLY FILE

Now, let's turn our attention to the structure of a MIPS assembly file.

- MIPS assembly files contain a set of lines.
- Each line can be either a directive or an instruction.
- Each directive or instruction may start with a *label*, which provides a symbolic name for a data or instruction location.
- Each line may also include a comment, which starts with # and continues until the end of the line.

GENERAL FORMAT

```
.data
# allocation of memory
.text
.global main
main:
# instructions here
jr $ra # instruction indicating a return
```

MIPS DIRECTIVES

Directive	Meaning			
.align <i>n</i>	Align next datum on 2^n boundary.			
.asciiz str	Place the null-terminated string str in memory.			
.byte b1,, bn	Place the n byte values in memory.			
.data	Switch to the data segment.			
.double d1,, dn	Place the n double-precision values in memory.			
.float f1,, fn	Place the n single-precision values in memory.			
.global sym	The label sym can be referenced in other files.			
.half h1,, hn	Place the n half-word values in memory.			
.space n	Allocates n bytes of space.			
.text	Switch to the text segment.			
.word w1,, wn	Place the n word values in memory.			

MIPS INSTRUCTIONS

General format:

```
<optional label> <operation> <operands>
```

Example:

MIPS INSTRUCTIONS

What does this look like in memory?

```
.data
nums:
   .word 10, 20, 30
   .text
   .globl main
main:
   la $t0, nums
   lw $t1, 4($t0)
```

MIPS INSTRUCTION FORMATS

There are three different formats for MIPS instructions.

- R format
 - Used for shifts and instructions that reference only registers.
- I format
 - Used for loads, stores, branches, and immediate instructions.
- J format
 - Used for jump and call instructions.

MIPS INSTRUCTION FORMATS

Name	Fields						
Field Size	6 bits	5 bits	5 bits	5 bits	5 bits	6 bits	
R format	ор	rs	rt	rd	shamt	funct	
I format	ор	rs	rt		immed		
J format	ор			targaddr			

op – instruction opcode.

rs – first register source operand.

rt – second register source operand.

rd – register destination operand.

shamt — shift amount.

funct – additional opcodes.

immed – offsets/constants.

targaddr — jump/call target.

MIPS INSTRUCTION FORMATS

All MIPS instructions are 32 bits — Design principle 1: simplicity favors regularity!

Name	Fields						
Field Size	6 bits	5 bits	5 bits	5 bits	5 bits	6 bits	
R format	ор	rs	rt	rd	shamt	funct	
I format	ор	rs	rt		immed		
J format	ор			targaddr			

op – instruction opcode.

rs – first register source operand.

rt – second register source operand.

rd – register destination operand.

shamt — shift amount.

funct – additional opcodes.

immed – offsets/constants.

targaddr – jump/call target.

MIPS INSTRUCTION FORMATS

Make simple instructions fast and accomplish other operations as a series of simple instructions – Design principle 3: make the common case fast!

Name	Fields					
Field Size	6 bits	5 bits	5 bits	5 bits	5 bits	6 bits
R format	ор	rs	rt	rd	shamt	funct
I format	ор	rs	rt		immed	
J format	ор			targaddr		

op – instruction opcode.

rs – first register source operand.

rt – second register source operand.

rd – register destination operand.

shamt - shift amount.

funct – additional opcodes.

immed – offsets/constants.

targaddr – jump/call target.

MIPS R FORMAT

- Used for shift operations and instructions that only reference registers.
- The op field has a value of 0 for all R format instructions.
- The funct field indicates the type of R format instruction to be performed.
- The shamt field is used only for the shift instructions (sll and srl, sra)

Name	Fields					
Field Size	6 bits	5 bits	5 bits	5 bits	5 bits	6 bits
R format	ор	rs	rt	rd	shamt	funct

op – instruction opcode.

rs – first register source operand.

rt – second register source operand.

rd – register destination operand.

shamt – shift amount.

funct – additional opcodes.

R FORMAT INSTRUCTION ENCODING EXAMPLE

Consider the following R format instruction:

addu \$t2, \$t3, \$t4

Fields	ор	rs	rt	rd	shamt	funct
Size	6 bits	5 bits	5 bits	5 bits	5 bits	6 bits
Decimal	0	11	12	10	0	33
Binary	000000	01011	01100	01010	00000	100001
Hexadecimal	0x016c5021					

MIPS I FORMAT

- Used for arithmetic/logical immediate instructions, loads, stores, and conditional branches.
- The op field is used to identify the type of instruction.
- The rs field is the source register.
- The rt field is either the source or destination register, depending on the instruction.
- The *immed* field is zero-extended if it is a logical operation. Otherwise, it is sign-extended.

Name	Fields					
Field Size	6 bits	5 bits	5 bits	5 bits	5 bits	6 bits
I format	ор	rs	rt		immed	

I FORMAT INSTRUCTION ENCODING EXAMPLES

Arithmetic example:

addiu \$t0,\$t0,1

Fields	ор	rs	rt	immed
Size	6 bits	5 bits	5 bits	16 bits
Decimal	9	8	8	1
Binary	001001	01000	01000	00000000000001
Hexadecimal			0x25080001	

I FORMAT INSTRUCTION ENCODING EXAMPLES

Memory access example:

lw \$s1,100(\$s2)

Fields	ор	rs	rt	immed
Size	6 bits	5 bits	5 bits	16 bits
Decimal	35	18	1 <i>7</i>	100
Binary	100011	10010	10001	000000001100100
Hexadecimal			0x8e510064	

I FORMAT INSTRUCTION ENCODING EXAMPLES

Conditional branch example:

L2:instruction
instruction
instruction
beq \$t6,\$t7,L2

Note: Branch displacement is a signed value in instructions, not bytes, from the current instruction. Branches use **PC-relative** addressing.

Fields	ор	rs	rt	immed
Size	6 bits	5 bits	5 bits	16 bits
Decimal	4	14	15	-3
Binary	000100	01110	01111	11111111111101
Hexadecimal			0x11cffffd	

ADDRESSING MODES

- Addressing mode a method for evaluating an operand.
- MIPS Addressing Modes
 - Immediate operand contains signed or unsigned integer constant.
 - Register operand contains a register number that is used to access the register file.
 - Base Displacement operand represents a data memory value whose address is the sum of some signed constant (in bytes) and the register value referenced by the register number.
 - **PC relative** operand represents an instruction address that is the sum of the PC and some signed integer constant (in words).
 - **Pseudodirect** operand represents an instruction address (in words) that is the field concatenated with the upper bits of the PC.

PC Relative and Pseudodirect addressing are actually relative to PC + 4, **not** PC. The reason for this will become clearer when we look at the design for the processor, so we'll ignore it for now.

MEMORY ALIGNMENT REQUIREMENTS

- MIPS requires alignment of memory references to be an integer multiple of the size of the data being accessed.
- These alignments are enforced by the compiler.
- The processor checks this alignment requirement by inspecting the least significant bits of the address.

MIPS J FORMAT

- Used for unconditional jumps and function calls.
- The op field is used to identify the type of instruction.
- The targaddr field is used to indicate an absolute target address.

Name	Fields					
Field Size	6 bits	5 bits	5 bits	5 bits	5 bits	6 bits
J format	ор	targaddr				

J FORMAT INSTRUCTION ENCODING EXAMPLE

Jump example: j L1

Assume L1 is at the address 4194340 in decimal, which is 400024 in hexadecimal. We fill the target field as an address in instructions (0x100009) rather than bytes (0x400024). Jump uses **pseudo-direct** addressing to create a 32-bit address.

Fields	ор	target address
Size	6 bits	26 bits
Decimal	2	1048585
Binary	000010	000001000000000000001001
Hexadecimal		0x08100009

ARITHMETIC/LOGICAL GENERAL FORM

- Most MIPS arithmetic/logical instructions require 3 operands.
- Design principle 1: <u>Simplicity favors regularity</u>.

Example	Meaning	Comment
addu \$t0, \$t1, \$t2	\$tO = \$t1 + \$t2	Addition (without overflow)
subu \$t1, \$t2, \$t3	\$t1 = \$t2 - \$t3	Subtraction (without overflow)

• Form 2: <operation> <dstreg>, <srcreg>, <constant>

Example	Meaning	Comment
addiu \$t1,\$t2,1	\$t1 = \$t2 + 1	Addition immediate (without overflow)

USING MIPS ARITHMETIC INSTRUCTIONS

• Consider the following C++ source code fragment.

```
unsigned int f,g,h,i,j;
...
f = (g+h)-(i+j);
```

• Assume the values of f, g, h, i, and j are associated with registers \$t2, \$t3, \$t4, \$t5, and \$t6 respectively. Write MIPS assembly code to perform this assignment assuming \$t7 is available.

USING MIPS ARITHMETIC INSTRUCTIONS

Solution (among others):

```
addu $t2,$t3,$t4 # $t2 = g + h
addu $t7,$t5,$t6 # $t7 = i + j
subu $t2,$t2,$t7 # $t2 = $t2 - $t7
```

MULTIPLY, DIVIDE, AND MODULUS INSTRUCTIONS

- Integer multiplication, division, and modulus operations can also be performed.
- MIPS provides two extra registers, **hi** and **lo**, to support division and modulus operations.

Example	Meaning	Comment
mult \$t1,\$t2	\$lo = \$t1 * \$t2	Multiplication
divu \$t2,\$t3	\$lo = \$t2/\$t3 \$hi = \$t2%\$t3	Division and Modulus
mflo \$t1	\$t1 = \$lo	Move from \$10
mfhi \$t1	\$t1 = \$hi	Move from \$hi

CALCULATING QUOTIENT AND REMAINDER

• Given the values \$11 and \$12, the following sequence of MIPS instructions assigns the quotient (\$1/\$12) to \$50 and the remainder (\$1%\$12) to \$51.

LOGICAL OPERATIONS

- Consist of bitwise Boolean operations and shifting operations.
- Shifting operations can be used to extract or insert fields of bits within a word.

X	Υ	Not X	X and Y	X or Y	X nand Y	X nor Y	X xor Y
0	0	1	0	0	1	1	0
0	1	1	0	1	1	0	1
1	0	0	0	1	1	0	1
1	1	0	1	1	0	0	0

GENERAL FORM OF MIPS BITWISE INSTRUCTIONS

• Bitwise instructions apply Boolean operations on each of the corresponding pairs of bits of two values.

Example	Meaning	Comment
and \$t2,\$t3,\$t4	\$t2 = \$t3 & \$t4	Bitwise and
or \$t3,\$t4,\$t5	\$t3 = \$t4 \$t5	Bitwise or
nor \$t4,\$t3,\$t6	\$t4 = ~(\$t3 \$t6)	Bitwise nor
xor \$t7,\$t2,\$t4	\$t7 = \$t2 ^ \$t4	Bitwise xor
andi \$t2,\$t3,7	\$t2 = \$t3 & 7	Bitwise and with immediate
ori \$t3,\$t4,5	\$t3 = \$t4 5	Bitwise or with immediate
xori \$t7,\$t2,6	\$t7 = \$t2 ^ 6	Bitwise xor with immediate

GENERAL FORM OF MIPS SHIFT INSTRUCTIONS

- Shift instructions move the bits in a word to the left or right by a specified amount.
- Shifting left (right) by i is the same as multiplying (dividing) by 2^{i} .
- An arithmetic right shift replicates the most significant bit to fill in the vacant bits.
- A logical right shift fills in the vacant bits with zero.

Example	Meaning	Comment
sll \$t2,\$t3,2	\$t2 = \$t3 << 2	Shift left logical
sllv \$t3,\$t4,\$t5	\$t3 = \$t4 << \$t5	Shift left logical variable
sra \$t4,\$t3,1	\$t4 = \$t3 >> 1	Shift right arithmetic (signed)
srav \$t7,\$t2,\$t4	\$t7 = \$t2 >> \$t4	Shift right arithmetic variable (signed)
srl \$t2,\$t3,7	\$t2 = \$t3 >> 7	Shift right logical (unsigned)
srlv \$t3,\$t4,\$t6	\$t3 = \$t4 >> \$t6	Shift right logical variable (unsigned)

GLOBAL ADDRESSES AND LARGE CONSTANTS

• The lui instruction can be used to construct large constants or addresses. It loads a 16-bit value in the 16 most significant bits of a word and clears the 16 least significant bits.

Form	Example	Meaning	Comment
lui <dreg>,<const></const></dreg>	lui \$t1,12	\$t1 = 12 << 16	Load upper immediate

• Example: load 131,071 (or 0x1ffff) into \$t2.

- Having all instructions the same size and a reasonable length means having to construct global addresses and some constants using two instructions.
- Design principle 4: Good design demands good compromise!

DATA TRANSFER GENERAL FORM

- MIPS can only access memory with load and store instructions.
- Form:

Example	Meaning	Comment
lw \$t2,8(\$t3)	t2 = Mem[t3 + 8]	32-bit load
lh \$t3,0(\$t4)	\$t3 = Mem[\$t4]	Signed 16-bit load
lhu \$t8,2(\$t3)	\$t8 = Mem[\$t3 + 2]	Unsigned 16-bit load
lb \$t4,0(\$t5)	\$t4 = Mem[\$t5]	Signed 8-bit load
Ibu \$t6,1(\$t9)	\$t6 = Mem[\$t9 + 1]	Unsigned 8-bit load
sw \$t5,-4(\$t2)	Mem[\$t2-4] = \$t5	32-bit store
sh \$t6,12(\$t3)	Mem[\$t3 + 12] = \$t6	16-bit store
sb \$t7,1(\$t3)	Mem[\$t3 + 1] = \$t7	8-bit store

USING DATA TRANSFER INSTRUCTIONS

 Consider the following source code fragment.

```
int a, b, c, d;
...
a = b + c - d;
```

• Assume the addresses of a, b, c, and d are in the registers \$t2, \$t3, \$t4, and \$t5, respectively. The following MIPS assembly code performs this assignment assuming \$t6 and \$t7 are available.

```
lw $t6,0($t3)
lw $t7,0($t4)
add $t6,$t6,$t7
lw $t7,0($t5)
sub $t6,$t6,$t7
sw $t6,0($t2)
```

```
# load b into $t6
# load c into $t7
# $t6 = $t6 + $t7
# load d into $t7
# $t6 = $t6 - $t7
# store $t6 into a
```

INDEXING ARRAY ELEMENTS

 Assembly code can be written to access array elements using a variable index. Consider the following source code fragment.

```
int a[100], i;
a[i] = a[i] + 1;
```

• Assume the value of i is in \$t0. The following MIPS code performs this assignment.

```
.data
a: .space 400
                   # declare space
  la $t1, a
  sll $t2,$t0,2
  add $t2,$t2,$t1
 lw $t3,0($t2)
  addi $t3,$t3,1
  sw $t3,0($t2)
```

```
# load address of a
# determine offset
# add offset and a
# load the value
# add 1 to the value
# store the value
```

TRANSFER OF CONTROL INSTRUCTIONS

- Transfer of control instructions can cause the next instruction to be executed to be other than the next sequential instruction.
- Transfers of control are used to implement control statements in high-level languages.
 - Unconditional (goto, break, continue, call, return)
 - Conditional (if-then, if-then-else, switch)
 - Iterative (while, do, for)

GENERAL FORM OF JUMP AND BRANCH

- MIPS provides direct jumps to support unconditional transfers of control to a specified location.
- MIPS provides indirect jumps to support returns and switch statements.
- MIPS provides conditional branch instructions to support decision making. MIPS conditional branches test if the values of two registers are equal or not equal.

General Form	Example	Meaning	Comment
j <label></label>	j L1	goto L1;	Direct jump (J)
jr <sreg></sreg>	jr \$ra	goto \$ra;	Indirect jump (R)
beq <s1reg>,<s2reg>,<label></label></s2reg></s1reg>	beq \$t2, \$t3, L1	if(\$t2 == \$t3) goto L1;	Branch equal (I)
bne <s1reg>,<s2reg>,<label></label></s2reg></s1reg>	bne \$t2, \$t3, L1	if(\$t2 != \$t3) goto L1;	Branch not equal (I)

IF STATEMENT EXAMPLE

• Consider the following source code:

```
if(i == j)
    k = k + i;
```

• Translate into MIPS instructions assuming the *values* of i, j, and k are associated with the registers \$t2, \$t3, and \$t4, respectively.

```
bne $t2,$t3,L1 # if ($t2 != $t3) goto L1
addu $t4,$t4,$t2 # k = k + i
L1:
```

GENERAL FORM OF COMPARISON INSTRUCTIONS

- MIPS provides set less than instructions that set a register to 1 if the first source register is less than the value of the second operand. Otherwise, it is set to 0.
- There are versions for performing unsigned comparisons as well.

General Form	Example	Meaning	Comment
slt <dreg>,<s1reg>,<s2reg></s2reg></s1reg></dreg>	slt \$t2,\$t3,\$t4	if(\$t3<\$t4) \$t2 = 1; else \$t2 = 0;	Compare less than (R)
sltu <dreg>,<s1reg>,<s2reg></s2reg></s1reg></dreg>	sltu \$t2,\$t3,\$t4	if(\$t3<\$t4) \$t2 = 1; else \$t2 = 0;	Compare less than unsigned (R)
slti <dreg>,<s1reg>,<const></const></s1reg></dreg>	slti \$t2,\$t3,100	if(\$t3<100) \$t2 = 1; else \$t2 = 0;	Compare less than constant (I)
sltiu <dreg>,<s1reg>,<const></const></s1reg></dreg>	sltiu \$t2,\$t3,100	if(\$t3<100) \$t2 = 1; else \$t2 = 0;	Compare less than constant unsigned (I)

TRANSLATING AN IF STATEMENT

 Consider the following source code:

 Translate into MIPS instructions assuming the values of a, b, and

c are associated with the

registers \$t2, \$t3, and \$t4

respectively. Assume \$t5 is available.

L1:

```
slt $t5,$t3,$t2 # b < a
beq $t5,$zero,L1 # if($t5==0)goto L1
or $t4,$t2,$zero # c = a</pre>
```

TRANSLATING AN IF-THEN-ELSE STATEMENT

L1:

L2:

 Consider the following source code:

```
if(a < b)
     c = a;
else
     c = b;</pre>
```

```
slt $t5,$t2,$t3 # a < b
beq $t5,$zero,L1 # if($t5==0)goto L1
move $t4,$t2 # c = a
j    L2 # goto L2
move $t4,$t3 # c = b</pre>
```

• Translate into MIPS instructions assuming the *values* of a, b, and c are associated with the registers \$t2, \$t3, and \$t4 respectively. Assume \$t5 is available.

HIGH-LEVEL CONTROL STATEMENTS

- How do we translate other high-level control statements (while, do, for)?
- We can first express the C statement using C if and goto statements.
- After that, we can translate using MIPS unconditional jumps, comparisons, and conditional branches.

TRANSLATING A FOR STATEMENT

Consider the following source code:

```
sum = 0;
for(i=0; i<100; i++)
    sum += a[i];</pre>
```

• First, we replace the for statement using an if and goto statements.

```
sum = 0;
i = 0;
goto test;
loop: sum += a[i];
i++;
test: if (i < 100) goto loop;</pre>
```

TRANSLATING A FOR STATEMENT

• Now for the MIPS instructions. Assume sum, i and the starting address of a are associated with \$t2, \$t3, and \$t4 respectively and that \$t5 is available.