

## INSIDE MACINTOSH

# Programming With the Mac OS 8.5 Control Manager



January 20, 1999 Technical Publications © 1999 Apple Computer, Inc. ▲ Apple Computer, Inc. © 1998 Apple Computer, Inc. All rights reserved.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, mechanical, electronic, photocopying, recording, or otherwise, without prior written permission of Apple Computer, Inc., except to make a backup copy of any documentation provided on CD-ROM.

The Apple logo is a trademark of Apple Computer, Inc.
Use of the "keyboard" Apple logo (Option-Shift-K) for commercial purposes without the prior written consent of Apple may constitute trademark infringement and unfair competition in violation of federal and state laws.

No licenses, express or implied, are granted with respect to any of the technology described in this book. Apple retains all intellectual property rights associated with the technology described in this book. This book is intended to assist application developers to develop applications only for Apple-labeled or Apple-licensed computers.

Every effort has been made to ensure that the information in this manual is accurate. Apple is not responsible for typographical errors.

Apple Computer, Inc. 1 Infinite Loop Cupertino, CA 95014 408-996-1010

Apple, the Apple logo, Mac, and Macintosh are trademarks of Apple Computer, Inc., registered in the United States and other countries. Adobe, Acrobat, and PostScript are trademarks of Adobe Systems Incorporated or its subsidiaries and may be registered in certain jurisdictions.

Adobe, the Adobe logo, Acrobat, the Acrobat logo, Distiller, PostScript,

and the PostScript logo are trademarks of Adobe Systems Incorporated.

Helvetica and Palatino are registered trademarks of Linotype-Hell AG and/or its subsidiaries.

ITC Zapf Dingbats is a registered trademark of International Typeface Corporation.

Simultaneously published in the United States and Canada.

Even though Apple has reviewed this manual, APPLE MAKES NO WARRANTY OR REPRESENTATION, EITHER EXPRESS OR IMPLIED, WITH RESPECT TO THIS MANUAL, ITS QUALITY, ACCURACY, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. AS A RESULT, THIS MANUAL IS SOLD "AS IS," AND YOU, THE PURCHASER, ARE ASSUMING THE ENTIRE RISK AS TO ITS QUALITY AND ACCURACY.

IN NO EVENT WILL APPLE BE LIABLE FOR DIRECT, INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES RESULTING FROM ANY DEFECT OR INACCURACY IN THIS MANUAL, even if advised of the possibility of such damages.

THE WARRANTY AND REMEDIES SET FORTH ABOVE ARE EXCLUSIVE AND IN LIEU OF ALL OTHERS, ORAL OR WRITTEN, EXPRESS OR IMPLIED. No Apple dealer, agent, or employee is authorized to make any modification, extension, or addition to this warranty.

Some states do not allow the exclusion or limitation of implied warranties or liability for incidental or consequential damages, so the above limitation or exclusion may not apply to you. This warranty gives you specific legal rights, and you may also have other rights which vary from state to state.

## **Contents**

Chapter 1	Using the Mac OS 8.5 Control Manager 5
	Creating a Proportional Scroll Box 7 Validating Editable Text 8
Chapter 2	Mac OS 8.5 Control Manager Reference 11
	Gestalt Selector for the Mac OS 8.5 Control Manager 13  Functions for the Mac OS 8.5 Control Manager 14  Changing Control Settings 14  Associating Data With Controls 20  Displaying Controls 25  Validating Controls 28  Obtaining Control Part Regions 29  Application-Defined Functions for the Mac OS 8.5 Control Manager 30  Data Types for the Mac OS 8.5 Control Manager 32  Constants for the Mac OS 8.5 Control Manager 34  Control Data Tag Constants 34  Control Definition Feature Constants 38  Control Definition Message Constants 42  Control Font Style Flag Constant 43  Control Key Script Behavior Constants 43  Control Part Code Constants 44  Result Codes for the Mac OS 8.5 Control Manager 45
Appendix A	Document Version History 47
	Index 49

## **Contents**

Creating a Proportional Scroll Box 7
Validating Editable Text 8

Contents 5

Your program can use the Control Manager to create and manage controls, onscreen objects that the user can manipulate with the mouse. By manipulating controls, the user can take an immediate action or change settings to modify a future action.

This document describes the Control Manager application programming interface (API) introduced with Mac OS 8.5 and Appearance Manager 1.1. Note that pre-existing Control Manager functions, types, and constants are not discussed in this document. For a description of the Mac OS 8 Control Manager API, see *Mac OS 8 Control Manager Reference*. For descriptions of the pre-Mac OS 8 Control Manager API, see *Inside Macintosh: Macintosh Toolbox Essentials*.

See the following sections for discussions of some programming topics for the Mac OS 8.5 Control Manager.

- "Creating a Proportional Scroll Box" (page 7)
- "Validating Editable Text" (page 8)

## Creating a Proportional Scroll Box

Your application should call the function <code>SetControlViewSize</code> (page 26) to support proportional scroll boxes. If the user selects the systemwide Appearance preference for "Smart Scrolling" and your application doesn't call <code>SetControlViewSize</code>, your application displays the traditional square scroll boxes.

To support a proportional scroll box, simply pass the size of the view area—in terms of whatever units the scroll bar uses—to <code>SetControlViewSize</code>. The system automatically handles resizing the scroll box, once your application supplies this information. Listing 0-1 shows some typical code for setting a scroll bar according to a TextEdit handle, which includes making the scroll box proportional.

1/20/99 @ Apple Computer, Inc.

**Listing 1-1** Adjusting a scroll bar to the viewable text

```
static pascal void AdjustScrollBarToText
    (TEHandle teh, ControlHandle scrollBar)
{
    // get the values needed to reflect the state of the TEHandle
    short nlines
                   = (**teh).nLines; // number of lines in doc.
    long totalHeight= TEGetHeight (nLines, 1, teh); // total doc. height
    Rect viewRect = (**teh).viewRect; // visible area of doc.
    Rect destRect = (**teh).destRect: // total area of doc.
    short viewHeight= viewRect.bottom - viewRect.top; // vis. doc. height
    // set the min, max, and current value of the scroll bar
    SetControl32BitMinimum (scrollBar, 1);
    SetControl32BitMaximum (scrollBar, totalHeight - viewHeight);
    SetControl32BitValue (scrollBar, viewRect.top - destRect.top);
    // set the scroll bar view size to create a proportional scroll box
    SetControlViewSize (scrollBar, viewHeight);
```

## Validating Editable Text

Your application typically uses a MyControlEditTextValidationProc (page 30) function in conjunction with a key filter function to ensure that editable text is valid in cases such as a cut, paste, or clear, where a key filter cannot be called.

Note that if you are using the inline input editable text control variant, the Control Manager will not call your MyControlEditTextValidationProc function during inline input. Instead, you may install your own Text Services Manager TSMTEPostUpdateUPP callback function to validate text during inline input, or your application can validate the input itself, immediately prior to using the text.

Listing 0-2 shows how you can use a MyControlEditTextValidationProc function to ensure that a user-supplied file name does not contain any illegal characters. Note that to enhance readability, no error-checking is included in this sample; a real application would, however, check for errors.

#### **Listing 1-2** Validating a file name with a MyControlEditTextValidationProc function

```
pascal void MyControlEditTextValidationProc (ControlHandle control)
{
   Str31 text:
   Size actualSize:
   UInt8 i:
    // Get the text to be examined from the control.
   GetControlData (control, kControlNoPart, kControlEditTextTextTag,
        sizeof(Str31) - 1, (Ptr)&text[1], &actualSize);
   // Set the string's length byte appropriately for the number of
    // characters in the text, limited to the (current) max filename.
    if (actualSize \le 31)
        text[0] = actualSize;
    else
        text[0] = 31:
    // Replace any colons with dashes.
    // Note: This only works with Roman script systems!
    for (i = 1; i \le text[0]; i++)
    {
        if (\text{text[i]} == ':')
            text[0] = '-':
    // If this were a real app, there'd be code here to check to see
    // whether any text was actually replaced before bothering to redraw.
   // Put the replaced text into the control and redraw.
    SetControlData(control, kControlNoPart, kControlEditTextTextTag,
        text[0], (Ptr)&text[1]);
   DrawOneControl(control);
}
```

#### CHAPTER 1

Using the Mac OS 8.5 Control Manager

## **Contents**

Gestalt Selector for the Mac OS 8.5 C	Control Manager 13
Functions for the Mac OS 8.5 Contro	l Manager 14
Changing Control Settings 14	
GetControl32BitMaximum $15$	
GetControl32BitMinimum 15	i
GetControl32BitValue 16	
SetControl32BitMaximum 17	•
SetControl32BitMinimum 18	3
SetControl32BitValue 19	
Associating Data With Controls	20
GetControlProperty 21	
GetControlPropertySize 22	
RemoveControlProperty 23	
SetControlProperty ${f 24}$	
Displaying Controls 25	
GetControlViewSize $26$	
SetControlViewSize $26$	
SetUpControlTextColor 27	
Validating Controls 28	
IsValidControlHandle 28	
Obtaining Control Part Regions	29
GetControlRegion $29$	
Application-Defined Functions for tl	9
MyControlEditTextValidation	
Data Types for the Mac OS 8.5 Contr	
ControlApplyTextColorRec	32
ControlEditTextValidationPr	ocPtr 33

Contents 11

#### ControlGetRegionRec 33 Constants for the Mac OS 8.5 Control Manager 34 **Control Data Tag Constants Control Definition Feature Constants** 38 **Control Definition IDs** 39 **Control Definition Message Constants** 42 **Control Font Style Flag Constant Control Key Script Behavior Constants** 43 **Control Part Code Constants** 44 Result Codes for the Mac OS 8.5 Control Manager 45

This chapter describes the Control Manager application programming interface (API) introduced with Mac OS 8.5 and Appearance Manager 1.1, as follows:

- "Gestalt Selector for the Mac OS 8.5 Control Manager" (page 13)
- "Functions for the Mac OS 8.5 Control Manager" (page 14)
- "Application-Defined Functions for the Mac OS 8.5 Control Manager" (page 30)
- "Data Types for the Mac OS 8.5 Control Manager" (page 32)
- "Constants for the Mac OS 8.5 Control Manager" (page 34)
- "Result Codes for the Mac OS 8.5 Control Manager" (page 45)

Note that pre-existing Control Manager functions, types, and constants are not discussed in this document. For a description of the Mac OS 8 Control Manager API, see *Mac OS 8 Control Manager Reference*. For descriptions of the pre–Mac OS 8 Control Manager API, see *Inside Macintosh: Macintosh Toolbox Essentials*.

## Gestalt Selector for the Mac OS 8.5 Control Manager

Before calling any functions dependent upon the Control Manager, your application should pass the selector <code>gestaltControlMgrAttr</code> to the <code>Gestalt</code> function to determine which Control Manager functions are available.

```
enum {
    gestaltControlMgrAttr = 'cntl',
    gestaltControlMgrPresent= (1L << 0)
}:</pre>
```

#### Constant descriptions

gestaltControlMgrAttr

The <code>Gestalt</code> selector passed to determine what features of the Control Manager are present. This selector is available with Mac OS 8.5 and later. The <code>Gestalt</code> function produces a 32-bit value whose bits you should test to determine what Control Manager functionality is available.

gestaltControlMgrPresent

If the bit specified by this mask is set, the Control Manager functionality for Appearance Manager 1.1 is available. This bit is set for Mac OS 8.5 and later.

## Functions for the Mac OS 8.5 Control Manager

The Mac OS 8.5 Control Manager provides new functions in the following areas:

- "Changing Control Settings" (page 14)
- "Associating Data With Controls" (page 20)
- "Displaying Controls" (page 25)
- "Validating Controls" (page 28)
- "Obtaining Control Part Regions" (page 29)

## **Changing Control Settings**

The Mac OS 8.5 Control Manager provides the following functions for changing control settings:

- SetControl32BitValue (page 19) changes the current setting of a control and redraws it accordingly.
- GetControl32BitValue (page 16) obtains the current setting of a control.
- SetControl32BitMinimum (page 18) changes the minimum setting of a control and, if appropriate, redraws it accordingly.
- GetControl32BitMinimum (page 15) obtains the minimum setting of a control.
- SetControl32BitMaximum (page 17) changes the maximum setting of a control and, if appropriate, redraws it accordingly.
- GetControl32BitMaximum (page 15) obtains the maximum setting of a control.

#### GetControl32BitMaximum

Obtains the maximum setting of a control.

theControl A value of type Control Handle. Pass a handle to the control

whose maximum setting you wish to obtain.

function result A signed 32-bit integer equal to the maximum setting of the

control.

#### DISCUSSION

Your application may use the GetControl32BitMaximum function to obtain a 32-bit value previously set with the function SetControl32BitMaximum (page 17).

#### SPECIAL CONSIDERATIONS

If your application uses a 32-bit control maximum value, it should not attempt to obtain this value by calling the pre-Mac OS 8.5 function <code>GetControlMaximum</code> or by accessing the <code>controlMax</code> field of the <code>ControlRecord</code> structure, because the stored 16-bit value will not accurately reflect the current 32-bit control value.

#### **VERSION NOTES**

Available with Mac OS 8.5 and later.

#### SEE ALSO

"Settings Values for Standard Controls" in Mac OS 8 Control Manager Reference.

#### GetControl32BitMinimum

Obtains the minimum setting of a control.

theControl A value of type ControlHandle. Pass a handle to the control

whose minimum setting you wish to obtain.

function result A signed 32-bit integer equal to the minimum setting of the

control.

#### DISCUSSION

Your application may use the GetControl32BitMinimum function to obtain a 32-bit value previously set with the function SetControl32BitMinimum (page 18).

#### SPECIAL CONSIDERATIONS

If your application uses a 32-bit control minimum value, it should not attempt to obtain this value by calling the pre-Mac OS 8.5 function <code>GetControlMinimum</code> or by accessing the <code>controlMin</code> field of the <code>ControlRecord</code> structure, because the stored 16-bit value will not accurately reflect the current 32-bit control value.

#### VERSION NOTES

Available with Mac OS 8.5 and later.

#### SEE ALSO

"Settings Values for Standard Controls" in Mac OS 8 Control Manager Reference.

#### GetControl32BitValue

Obtains the current setting of a control.

theControl A value of type ControlHandle. Pass a handle to the control

whose current setting you wish to obtain.

function result A signed 32-bit integer equal to the current setting of the

control.

#### DISCUSSION

Your application may use the GetControl32BitValue function to obtain a 32-bit value previously set with the function SetControl32BitValue (page 19).

#### SPECIAL CONSIDERATIONS

If your application uses a 32-bit control value, it should not attempt to obtain this value by calling the pre-Mac OS 8.5 function <code>GetControlValue</code> or by accessing the <code>controlValue</code> field of the <code>ControlRecord</code> structure, because the stored 16-bit value will not accurately reflect the current 32-bit control value.

#### VERSION NOTES

Available with Mac OS 8.5 and later.

#### SEE ALSO

"Settings Values for Standard Controls" in Mac OS 8 Control Manager Reference.

#### SetControl32BitMaximum

Changes the maximum setting of a control and, if appropriate, redraws it accordingly.

 $\hbox{the Control} \qquad \hbox{A value of type $\tt Control Handle}. \ Pass \ a \ handle \ to \ the \ control$ 

whose maximum setting you wish to change.

newMaximum A signed 32-bit integer. Pass a value specifying the new

maximum setting of the control. In general, to avoid

unpredictable behavior, do not set the maximum control value

lower than the current minimum value.

#### DISCUSSION

Your application may use the SetControl32BitMaximum function to set a 32-bit value as the maximum setting for a control.

#### SPECIAL CONSIDERATIONS

If your application uses a 32-bit control maximum value, it should not attempt to obtain this value by calling the pre–Mac OS 8.5 function <code>GetControlMaximum</code> or by accessing the <code>controlMax</code> field of the <code>ControlRecord</code> structure, because the stored 16-bit value will not accurately reflect the current 32-bit control value. Instead, use the function <code>GetControl32BitMaximum</code> (page 15).

#### VERSION NOTES

Available with Mac OS 8.5 and later.

#### SEE ALSO

"Settings Values for Standard Controls" in Mac OS 8 Control Manager Reference.

#### SetControl32BitMinimum

Changes the minimum setting of a control and, if appropriate, redraws it accordingly.

theControl A value of type ControlHandle. Pass a handle to the control

whose minimum setting you wish to change.

newMinimum A signed 32-bit integer. Pass a value specifying the new

minimum setting of the control. In general, to avoid unpredictable behavior, do not set the minimum control value

higher than the current maximum value.

#### DISCUSSION

Your application may use the SetControl32BitMinimum function to set a 32-bit value as the minimum setting for a control.

#### SPECIAL CONSIDERATIONS

If your application uses a 32-bit control minimum value, it should not attempt to obtain this value by calling the pre–Mac OS 8.5 function <code>GetControlMinimum</code> or by accessing the <code>controlMin</code> field of the <code>ControlRecord</code> structure, because the stored 16-bit value will not accurately reflect the current 32-bit control value. Instead, use the function <code>GetControl32BitMinimum</code> (page 15).

#### VERSION NOTES

Available with Mac OS 8.5 and later.

#### SEE ALSO

"Settings Values for Standard Controls" in Mac OS 8 Control Manager Reference.

#### SetControl32BitValue

Changes the current setting of a control and redraws it accordingly.

theControl A value of type ControlHandle. Pass a handle to the control

whose current setting you wish to change.

newValue A signed 32-bit integer. Pass a value specifying the new setting

of the control. If the specified value is less than the minimum setting for the control, SetControl32BitValue sets the current setting of the control to its minimum setting. If the specified

value is greater than the maximum setting,

SetControl32BitValue sets the control to its maximum.

1/12/99 © Apple Computer, Inc.

#### DISCUSSION

Your application may use the SetControl32BitValue function to set a 32-bit value as the current setting for a control.

#### SPECIAL CONSIDERATIONS

If your application uses a 32-bit control value, it should not attempt to obtain this value by calling the pre-Mac OS 8.5 function <code>GetControlValue</code> or by accessing the <code>controlValue</code> field of the <code>ControlRecord</code> structure, because the stored 16-bit value will not accurately reflect the current 32-bit control value. Instead, use the function <code>GetControl32BitValue</code> (page 16).

#### VERSION NOTES

Available with Mac OS 8.5 and later.

#### SEE ALSO

"Settings Values for Standard Controls" in Mac OS 8 Control Manager Reference.

## **Associating Data With Controls**

The Mac OS 8.5 Control Manager provides the following functions for associating data with controls:

- SetControlProperty (page 24) associates data with a control.
- GetControlProperty (page 21) obtains a piece of data that has been previously associated with a control.
- GetControlPropertySize (page 22) obtains the size of a piece of data that has previously been associated with a control.
- RemoveControlProperty (page 23) removes a piece of data that has been previously associated with a control.

#### **GetControlProperty**

Obtains a piece of data that has been previously associated with a control.

```
pascal OSStatus GetControlProperty (
                     ControlHandle control,
                     OSType propertyCreator,
                     OSType propertyTag,
                     UInt32 bufferSize.
                     UInt32 *actualSize.
                     void *propertyBuffer);
```

control A value of type Control Handle. Pass a handle to the control whose associated data you wish to obtain.

A four-character code. Pass your program's signature, as registered through Apple Developer Technical Support. If your program is of a type that would not normally have a signature (for example, a plug-in), you should still register and use a signature in this case, even though your program's file may not have the same creator code as the signature that you register. The 'macs' property signature is reserved for the system and should not be used.

A four-character code. Pass the application-defined code propertyTag identifying the data.

> An unsigned 32-bit integer. Pass a value specifying the size of the data to be obtained. If the size of the data is unknown, use the function GetControlPropertySize (page 22) to get the data's size. If the size specified in the bufferSize parameter does not match the actual size of the property, GetControlProperty only retrieves data up to the size specified or up to the actual size of the property, whichever is smaller, and an error is returned.

A pointer to an unsigned 32-bit integer. On return, this value is set to the actual size of the associated data. You may pass nil for the actual Size parameter if you are not interested in this information.

propertyBuffer

A pointer to a buffer. On return, this buffer contains a copy of the data that is associated with the specified control.

propertyCreator

actualSize

bufferSize

function result A result code. See "Result Codes for the Mac OS 8.5 Control Manager" (page 45).

#### DISCUSSION

You may use the function <code>GetControlProperty</code> to obtain a copy of data previously set by your application with the function <code>SetControlProperty</code> (page 24).

#### VERSION NOTES

Available with Mac OS 8.5 and later.

#### SEE ALSO

The function RemoveControlProperty (page 23).

## GetControlPropertySize

Obtains the size of a piece of data that has previously been associated with a control.

```
pascal OSStatus GetControlPropertySize (
ControlHandle control,
OSType propertyCreator,
OSType propertyTag,
UInt32 *size):
```

control

A value of type ControlHandle. Pass a handle to the control whose associated data you wish to examine.

propertyCreator

A four-character code. Pass your program's signature, as registered through Apple Developer Technical Support. If your program is of a type that would not normally have a signature (for example, a plug-in), you should still register and use a signature in this case, even though your program's file may not have the same creator code as the signature that you register. The 'macs' property signature is reserved for the system and should not be used.

#### CHAPTER 2

#### Mac OS 8.5 Control Manager Reference

propertyTag A four-character code. Pass the application-defined code

identifying the data.

size A pointer to an unsigned 32-bit integer. On return, this value is

set to the actual size of the data.

function result A result code. See "Result Codes for the Mac OS 8.5 Control

Manager" (page 45).

#### DISCUSSION

If you want to retrieve a piece of associated data with the function <code>GetControlProperty</code> (page 21), you will typically need to use the <code>GetControlPropertySize</code> function beforehand to determine the size of the associated data.

#### VERSION NOTES

Available with Mac OS 8.5 and later.

## RemoveControlProperty

Removes a piece of data that has been previously associated with a control.

control A value of type ControlHandle. Pass a handle to the control

whose associated data you wish to remove.

propertyCreator

A four-character code. Pass your program's signature, as registered through Apple Developer Technical Support. If your program is of a type that would not normally have a signature (for example, a plug-in), you should still register and use a signature in this case, even though your program's file may not have the same creator code as the signature that you register. The 'macs' property signature is reserved for the system and should not be used.

propertyTag A four-character code. Pass the application-defined code

identifying the associated data.

function result A result code. See "Result Codes for the Mac OS 8.5 Control

Manager" (page 45).

#### DISCUSSION

Your application may dissociate data it has previously set with the SetControlProperty (page 24) function by calling the RemoveControlProperty function.

#### **VERSION NOTES**

Available with Mac OS 8.5 and later.

#### **SEE ALSO**

The function GetControlProperty (page 21).

## SetControlProperty

Associates data with a control.

control

A value of type ControlHandle. Pass a handle to the control with which you wish to associate data.

propertyCreator

A four-character code. Pass your program's signature, as registered through Apple Developer Technical Support. If your program is of a type that would not normally have a signature (for example, a plug-in), you should still register and use a signature in this case, even though your program's file may not

have the same creator code as the signature that you register. The ' macs' property signature is reserved for the system and should not be used.

propertyTag A four-character code. Pass a value identifying the data. You define the tag your application uses to identify the data.

propertySize An unsigned 32-bit integer. Pass a value specifying the size of the data.

.

PropertyData A pointer to data of any type. Pass a pointer to a buffer containing the data to be associated; this buffer should be at least as large as the value specified in the propertySize parameter.

function result A result code. See "Result Codes for the Mac OS 8.5 Control Manager" (page 45).

#### DISCUSSION

Your application may use the SetControlProperty function to associate any type of data with a control.

#### VERSION NOTES

Available with Mac OS 8.5 and later.

#### SEE ALSO

The function GetControlProperty (page 21).

The function RemoveControlProperty (page 23).

## **Displaying Controls**

The Mac OS 8.5 Control Manager provides the following functions for displaying controls:

- GetControlViewSize (page 26) obtains the size of the content to which a control's size is proportioned.
- SetControlViewSize (page 26) informs the Control Manager of the size of the content to which a control's size is proportioned.

■ SetUpControlTextColor (page 27) prepares a control to be drawn with a text color consistent with that of any controls in which it is embedded and with the current theme.

#### **GetControlViewSize**

Obtains the size of the content to which a control's size is proportioned.

```
pascal SInt32 GetControlViewSize (
                     ControlHandle theControl);
```

theControl

A value of type Control Handle. Pass a handle to the control whose view size you wish to obtain.

function result A signed 32-bit integer. The GetControlViewSize function returns a value equal to the current size of the content being displayed, expressed in terms of the same units of measurement as are used for the minimum, maximum, and current settings of the control.

#### DISCUSSION

Your application should call the GetControlViewSize function to obtain the current view size of a control. This value is used by the function SetControlViewSize (page 26) to support proportional scroll boxes.

#### VERSION NOTES

Available with Mac OS 8.5 and later.

#### SetControlViewSize

Informs the Control Manager of the size of the content to which a control's size is proportioned.

```
pascal void SetControlViewSize (
                     ControlHandle theControl.
                     SInt32 newViewSize):
```

theControl A value of type Control Handle. Pass a handle to the control

whose view size is to be set.

newViewSize A signed 32-bit integer. Pass a value specifying the size of the

content being displayed. This value should be expressed in terms of the same units of measurement as are used for the minimum, maximum, and current settings of the control.

#### DISCUSSION

Your application should call the <code>SetControlViewSize</code> function to support proportional scroll boxes. If the user selects the systemwide Appearance preference for proportional scroll boxes and your application doesn't call <code>SetControlViewSize</code>, it will still have the traditional square scroll boxes.

To support a proportional scroll box, simply pass the size of the view area—in terms of whatever units the scroll bar uses—to <code>SetControlViewSize</code>. The system automatically handles resizing the scroll box, once your application supplies this information. Listing 0-1 in "Creating a Proportional Scroll Box" (page 7) shows some typical code for setting a scroll bar according to a TextEdit handle, which includes making the scroll box proportional.

#### VERSION NOTES

Available with Mac OS 8.5 and later.

#### SEE ALSO

The function GetControlViewSize (page 26).

## ${\bf Set Up Control Text Color}$

Prepares a control to be drawn with a text color consistent with that of any controls in which it is embedded and with the current theme.

inControl A value of type Control Handle. Pass a handle to the control

whose text color is to be set.

inDepth A signed 16-bit integer. Pass a value specifying the bit depth (in

pixels) of the current graphics port.

inIsColorDevice

A value of type Boolean. Set to true to indicate that you are drawing on a color device. Set to false for a monochrome

device.

function result A result code. See "Result Codes for the Mac OS 8.5 Control

Manager" (page 45).

#### DISCUSSION

Your control definition function may use the SetUpControlTextColor function inside a DeviceLoop drawing procedure to set a control's text color to coordinate with the current theme. Applications do not typically need to use this function.

#### VERSION NOTES

Available with Mac OS 8.5 and later.

## **Validating Controls**

The Mac OS 8.5 Control Manager provides the following function for confirming the validity of a control handle:

■ IsValidControlHandle (page 28) reports whether a given handle is a control handle.

#### **IsValidControlHandle**

Reports whether a given handle is a control handle.

 $\label{lem:control} A \ value \ of \ type \ \texttt{ControlHandle}. \ Pass \ the \ handle \ to \ be \ examined.$ 

function result A value of type Boolean. The IsValidControlHandle function returns true if the specified handle is a valid control handle; otherwise, false.

#### DISCUSSION

The IsValidControlHandle function confirms whether a given handle is a valid control handle, but it does not check the validity of the data contained in the control itself.

#### VERSION NOTES

Available with Mac OS 8.5 and later.

## **Obtaining Control Part Regions**

The Mac OS 8.5 Control Manager provides the following function for obtaining the region corresponding to a control part:

■ GetControlRegion (page 29) obtains the region corresponding to a given control part.

## GetControlRegion

Obtains the region corresponding to a given control part.

```
pascal OSStatus GetControlRegion (
                     ControlHandle inControl,
                     ControlPartCode inPart,
                     RgnHandle outRegion);
```

A value of type Control Handle. Pass a handle to the control inControl containing the part for which a region is to be obtained.

inPart A value of type ControlPartCode. Pass a constant identifying the

control part for which a region is to obtained; you may specify  $the \ \mathsf{kControlStructureMetaPart} \ and \ \mathsf{kControlContentMetaPart}$ control part codes, as well as the standard control part codes. See "Control Part Code Constants" (page 44) for descriptions of

possible values.

outRegion Pass a value of type RgnHandle. On return, GetControlRegion sets

the region to contain the actual dimensions and position of the

control part, in local coordinates.

function result A result code. See "Result Codes for the Mac OS 8.5 Control

Manager" (page 45).

#### VERSION NOTES

Available with Mac OS 8.5 and later.

## Application-Defined Functions for the Mac OS 8.5 Control Manager

The Mac OS 8.5 Control Manager provides the following function for validating the content of an editable text control:

■ MyControlEditTextValidationProc (page 30) validates editable text.

## MyControlEditTextValidationProc

Ensures that the content of an editable text control is valid.

This is how you would declare an editable text validation function, if you were to name the function MyControlEditTextValidationProc:

control

A value of type ControlHandle. You are passed a handle to the control containing the editable text to be validated.

#### DISCUSSION

Your application typically uses a MyControlEditTextValidationProc function in conjunction with a key filter function to ensure that editable text is valid in cases such as a cut, paste, or clear, where a key filter cannot be called. Use the kControlEditTextValidationProcTag control data tag constant, described in

"Control Data Tag Constants" (page 34), with the functions SetControlData and GetControlData to set or retrieve a MyControlEditTextValidationProc function.

Note that if you are using the inline input editable text control variant, the Control Manager will not call your MyControlEditTextValidationProc function during inline input. Instead, you may install your own Text Services Manager TSMTEPostUpdateUPP callback function to validate text during inline input, or your application can validate the input itself, immediately prior to using the text.

Listing 0-2 in "Validating Editable Text" (page 8) demonstrates how you can use a MyControlEditTextValidationProc function to ensure that a user-supplied file name does not contain any illegal characters.

When you implement your editable text validation function, the pointer that you pass to SetControlData must be a universal procedure pointer of the following type:

typedef ControlEditTextValidationProcPtr ControlEditTextValidationUPP:

To create a universal procedure pointer for your application-defined editable text validation function, you should use the NewControlEditTextValidationProc macro as follows:

ControlEditTextValidationUPP myControlEditTextValidationUPP; myControlEditTextValidationUPP = NewControlEditTextValidationProc (MyControlEditTextValidationProc);

You can then pass myControlEditTextValidationUPP in the inData parameter of SetControlData. When you no longer need the universal procedure pointer, you should remove it using the DisposeRoutineDescriptor function.

If you need to call your application-defined function from outside your application for some reason (for example, from a plug-in), you should use the CallControlEditTextValidationProc macro to make the call, as follows:

ControlEditTextValidationUPP myControlEditTextValidationUPP; CallControlEditTextValidationProc (myControlEditTextValidationUPP, control);

Using this macro ensures that the call is made through a universal procedure pointer.

#### VERSION NOTES

Available with Mac OS 8.5 and later.

## Data Types for the Mac OS 8.5 Control Manager

The following data types are available with the Mac OS 8.5 Control Manager:

- ControlApplyTextColorRec (page 32)
- ControlEditTextValidationProcPtr (page 33)
- ControlGetRegionRec (page 33)

## ControlApplyTextColorRec

If you implement a custom control definition function, when the Control Manager passes the message kControlMsgApplyTextColor in your control definition function's message parameter, it also passes a pointer to a structure of type ControlApplyTextColorRec in the param parameter. The Control Manager sets the ControlApplyTextColorRec structure to contain data describing the current drawing environment, and your control definition function is responsible for using that data to apply the proper text color to the current graphics port.

See "Control Definition Message Constants" (page 42) for more details on the kControlMsgApplyTextColor message.

```
struct ControlApplyTextColorRec
{
    SInt16    depth;
    Boolean colorDevice;
    Boolean active;
};
typedef struct ControlApplyTextColorRec ControlApplyTextColorRec;
typedef ControlApplyTextColorRec* ControlApplyTextColorPtr;
```

#### Field descriptions

depth A signed 16-bit integer. The Control Manager sets this field

to specify the bit depth (in pixels) of the current graphics

port.

colorDevice A value of type Boolean. The Control Manager passes a

value of true if you are drawing on a color device;

otherwise, false.

active A value of type Boolean. The Control Manager passes a

value of true to specify a color suitable for active text;

otherwise, false.

#### ControlEditTextValidationProcPtr

You may want to designate an application-defined function in conjunction with a key filter function to ensure that editable text is valid in cases such as a cut, paste, or clear, where a key filter cannot be called. Such a function has the following type definition:

typedef pascal void (ControlEditTextValidationProcPtr) (ControlHandle control);

See MyControlEditTextValidationProc (page 30) for more information about how to implement the application-defined function.

## ControlGetRegionRec

If you implement a custom control definition function, when the Control Manager passes the message kControlMsgGetRegion in your control definition function's message parameter, it also passes a pointer to a structure of type ControlGetRegionRec in the param parameter. Your control definition function is responsible for setting the region field of the ControlGetRegionRec structure to the region that contains the control part which the Control Manager specifies in the part field.

See "Control Definition Message Constants" (page 42) for more details on the kControlMsgGetRegion message.

1/12/99 © Apple Computer, Inc.

```
struct ControlGetRegionRec
{
    RgnHandle region;
    ControlPartCode part;
};
typedef struct ControlGetRegionRec ControlGetRegionRec;
typedef ControlGetRegionRec* ControlGetRegionPtr;
```

#### Field descriptions

region A value of type RgnHandle allocated by the Control

Manager. Your control definition function should set this field to the region that contains the control part specified in

the part field.

part A value of type Control PartCode. The Control Manager

passes a constant identifying the control part for which a region is to be obtained. For descriptions of possible values,

see "Control Part Code Constants" (page 44).

## Constants for the Mac OS 8.5 Control Manager

The following constants are available with the Mac OS 8.5 Control Manager:

- "Control Data Tag Constants" (page 34)
- "Control Definition Feature Constants" (page 38)
- "Control Definition IDs" (page 39)
- "Control Definition Message Constants" (page 42)
- "Control Font Style Flag Constant" (page 43)
- "Control Key Script Behavior Constants" (page 43)
- "Control Part Code Constants" (page 44)

## **Control Data Tag Constants**

The Mac OS 8.5 Control Manager defines the following new control data tag constants. These constants are passed in the inTagName parameters of the functions SetControlData and GetControlData to specify the piece of data in a

control that you wish to set or get. You can also pass these constants in the <code>inTagName</code> parameter of the function <code>GetControlDataSize</code> if you wish to determine the size of variable-length control data (for example, text in an editable text control). These constants can also be used by custom control definition functions that return the feature bit <code>kControlSupportsDataAccess</code> in response to a <code>kControlMsgGetFeatures</code> message.

The data that your application gets or sets can be of various types. The descriptions below show the data types for the information that you can set in the inData parameter to the SetControlData function and that you can get in the inBuffer parameter to the GetControlData function.

For details on other control data tag constants, see *Mac OS 8 Control Manager Reference*.

```
enum {
   kControlScrollTextBoxDelayBeforeAutoScrollTag
                                                   = 'std1',
   kControlScrollTextBoxDelayBetweenAutoScrollTag = 'scdl'.
   kControlScrollTextBoxAutoScrollAmountTag = 'samt'.
   kControlScrollTextBoxContentsTag
                                                   = 'tres',
   kControlEditTextKeyScriptBehaviorTag
                                                   = 'kscr',
   kControlEditTextLockedTag
                                                   = 'lock'.
   kControlEditTextFixedTextTag
                                                   = 'ftxt',
   kControlEditTextValidationProcTag
                                                   = 'vali'.
   kControlEditTextInlinePreUpdateProcTag
                                                   = 'prup',
   kControlEditTextInlinePostUpdateProcTag
                                                   = 'poup'.
   kControlStaticTextTruncTag
                                                   = 'trun'.
   kControlIconResourceIDTag
                                                   = 'ires',
   kControlIconContentTag
                                                   = 'cont'.
   kControlBevelButtonScaleIconTag
                                                   = 'scal'.
   kControlPushButtonCancelTag
                                                   = 'cncl',
   kControlPopupButtonExtraHeightTag
                                                   = 'exht',
                                                   = 'trec'
   kControlGroupBoxTitleRectTag
}:
```

#### **Constant descriptions**

kControlScrollTextBoxDelayBeforeAutoScrollTag

Gets or sets the number of ticks to delay before the initial scrolling of an auto-scrolling text box control begins.

Data type retrieved or set: UInt32

kControlScrollTextBoxDelayBetweenAutoScrollTag

Gets or sets the number of ticks to delay between each unit of scrolling, for an auto-scrolling text box control. (The unit of scrolling for the auto-scrolling text box control is one pixel at a time, unless your application changes this value by calling the SetControlData function.)

Data type retrieved or set: UInt32

kControlScrollTextBoxAutoScrollAmountTag

Gets or sets the number of pixels by which an auto-scrolling text box control scrolls; default is 1. Data type retrieved or set: UInt16

kControlScrollTextBoxContentsTag

Sets the ID of a 'TEXT' resource—and, optionally, a 'styl' resource—to be used as the content in a scrolling or auto-scrolling text box control.

Data type set: SInt16

kControlEditTextKeyScriptBehaviorTag

Gets or sets the kind of behavior to be used in an editable text control with respect to changing and locking the keyboard menu as the field is focused.

Data type retrieved or set: ControlKeyScriptBehavior. The default for password fields is

 $\verb|kControlKeyScriptBehaviorPrefersRoman|. The \ default for \\ non-password \ fields \ is$ 

kControlKeyScriptBehaviorAllowAnyScript. See "Control Key Script Behavior Constants" (page 43) for descriptions of possible values.

kControlEditTextLockedTag

Gets or sets whether the text in an editable text control is currently editable.

Data type retrieved or set: Boolean; if true, the text is locked and cannot be edited; if false, the text is editable.

kControlEditTextFixedTextTag

Gets or sets inline input text in an editable text control, after confirming any text in the active input area with the Text Services Manager function FixTSMDocument.

Data type retrieved or set: character buffer

kControlEditTextValidationProcTag

Gets or sets a universal procedure pointer to a callback

### function such as that described in

MyControlEditTextValidationProc (page 30), which can be used to validate editable text after an operation that changes the text, such as inline text entry, a cut, or paste.

Data type retrieved or set: ControlEditTextValidationUPP

kControlEditTextInlinePreUpdateProcTag

Gets or sets a universal procedure pointer to a Text Services Manager pre-update callback function. See Technote TE 27, "Inline Input for TextEdit with TSMTE" for a description of the TSMTEPreUpdateUPP type.

Data type retrieved or set: TSMTEPreUpdateUPP

kControlEditTextInlinePostUpdateProcTag

Gets or sets a universal procedure pointer to a Text Services Manager post-update callback function. See Technote TE 27, "Inline Input for TextEdit with TSMTE" for a description of the TSMTEPostUpdateUPP type.

Data type retrieved or set: TSMTEPostUpdateUPP

kControlStaticTextTruncTag

Gets or sets how text is truncated at the end of a line for a static text control.

Data type retrieved or set: TruncCode; the value truncEnd indicates that characters are truncated off the end of the string; the value truncMiddle indicates that characters are truncated from the middle of the string. Default is a value of -1, which indicates that no truncation occurs and the text is instead wrapped.

kControlIconResourceIDTag

Gets or sets the resource ID of the icon to use.

Data type retrieved or set: SInt16

kControlIconContentTag

Gets or sets the type of content to be used in an icon control.

Data type retrieved or set: Control ButtonContentInfo; see *Mac OS 8 Control Manager Reference* for a description of this data type.

kControlBevelButtonScaleIconTag

Gets or sets whether, when the proper icon size is unavailable, an icon should be scaled for use with a given bevel button. This tag is only for use with icon suites or the

IconRef data type.

Data type retrieved or set: Boolean. If true, indicates that if an icon of the ideal size isn't available, a larger or smaller icon should be scaled to the ideal size. If false, no scaling should occur; instead, a smaller icon should be drawn or a larger icon clipped. Default is false.

kControlPushButtonCancelTag

Gets or sets whether a given push button in a dialog or alert should be drawn with the theme-specific adornments for a Cancel button.

Data type retrieved or set: Boolean; default is false.

kControlPopupButtonExtraHeightTag

Gets or sets the amount of extra vertical white space in a pop-up menu button.

Data type retrieved: SInt16; default is 0.

kControlGroupBoxTitleRectTag

Gets the rectangle that contains the title of a group box (and any associated control, such as a checkbox or other button). Data type retrieved: Rect

### **Control Definition Feature Constants**

With the Mac OS 8.5 Control Manager, your control definition function may report the following new feature flags to reflect the features that your control supports. For other control definition feature flags, see "Defining Your Own Control Definition Function" in *Mac OS 8 Control Manager Reference*.

#### **Constant descriptions**

kControlAutoToggles

If the bit specified by this mask is set, the control definition function supports automatically changing among various states (on, off, mixed) in response to user actions.

kControlSupportsGetRegion

If the bit specified by this mask is set, the control definition

function supports the kControlMsgGetRegion message, described in "Control Definition Message Constants" (page 42).

### Control Definition IDs

The Mac OS 8.5 Control Manager defines the following new control definition IDs. For details on other standard control definition IDs, see *Mac OS 8 Control Manager Reference*.

### **Constant descriptions**

kControlEditTextInlineInputProc

Identifies the inline input variant of the editable text control ('CDEF' resource ID 17), which supports 2-byte script systems. This variant cannot be combined with the password variant of the editable text box.

kControlIconRefProc

Identifies the variant of the icon control ('CDEF' resource ID 20) that supports all standard types of icon-based content. Note that you do not supply content for this control upon its creation with a call to the NewControl function. Rather, after the control's creation you can set or change its content at any time by passing the SetControlData function the kControlIconContentTag control data tag constant and a ControlButtonContentInfo structure containing any of the allowable data types. Supported data types for this icon control variant are specified with the following ControlContentType values: kControlContentIconSuiteRes, kControlContentClconRes (uses a black-and-white 'ICON' resource if the color resource isn't available),

kControlContentIconSuiteHandle, kControlContentIconRef. Note, too, that if you supply the kControlContentIconRef value, you must first use Icon Services functions to register your resources and generate IconRef values. See Mac OS 8 Control Manager Reference for a description of the ControlButtonContentInfo data type and the ControlContentType constants.

### kControlIconRefNoTrackProc

Identifies the non-tracking variant of the icon control ('CDEF' resource ID 20) that supports all standard types of icon-based content. This control immediately returns kControlIconPart as the part code hit without tracking. Note that you do not supply content for this control upon its creation with a call to the NewControl function. Rather, after the control's creation you can set or change its content at any time by passing the SetControlData function the kControlIconContentTag control data tag constant and a ControlButtonContentInfo structure containing any of the allowable data types. Supported data types for this icon control variant are specified with the following ControlContentType values: kControlContentIconSuiteRes, kControlContentClconRes (uses a black-and-white 'ICON' resource if the color resource isn't available),

kControlContentIconSuiteHandle.

kControlContentCIconHandle, and kControlContentIconRef. Note, too, that if you supply the kControlContentIconRef value, you must first use Icon Services functions to register your resources and generate IconRef values. See Mac OS 8 Control Manager Reference for a description of the ControlButtonContentInfo data type and the ControlContentType constants.

### kControlCheckBoxAutoToggleProc

Identifies a checkbox control ('CDEF' resource ID 23) that automatically changes among its various states (on, off, mixed) in response to user actions. Your application must only call the function <code>GetControl32BitValue</code> (page 16) to get the checkbox's new state—there is no need to manually change the control's value after tracking successfully.

kControlRadioButtonAutoToggleProc

Identifies a radio button control ('CDEF' resource ID 23) that automatically changes among its various states (on, off, mixed) in response to user actions. Your application must only call the function <code>GetControl32BitValue</code> (page 16) to get the radio button's new state—there is no need to manually change the control's value after tracking successfully.

kControlScrollTextBoxProc

Identifies the standard variant of the scrolling text box ('CDEF' resource ID 27), which contains a scroll bar. Your application can use the kControlScrollTextBoxProc ID to create a scrolling box of non-editable text, such as is used for an "About" box. You must pass the NewControl function the ID of a 'TEXT' resource—and, optionally, a 'styl' resource—to be used for the initial value of the control. The minimum and maximum values are reserved for the kControlScrollTextBoxProc variant and should be set to 0.

Identifies the auto-scrolling variant of the scrolling text box

kControlScrollTextBoxAutoScrollProc

('CDEF' resource ID 27); this variant does not contain a scroll bar. Your application can use the kControlScrollTextBoxAutoScrollProc ID to create a scrolling box of non-editable text, such as is used for an "About" box. You must pass the NewControl function the ID of a 'TEXT' resource—and, optionally, a 'styl' resource—to be used for the initial value of the control. For the minimum value of the control, pass a value equal to the delay, in ticks, before the control begins scrolling; this delay will also be used between when scrolling completes and when it begins again. For the maximum value of the control, pass a value equal to the delay, in ticks, between each unit of scrolling. The unit of scrolling for the auto-scrolling text box control is one pixel at a time, unless your application changes this value by calling the SetControlData function. Note that in order to advance the content of the text box—that is, to scroll the content—you must call the IdleControls function on a periodic basis, such as whenever you receive a null event.

## **Control Definition Message Constants**

The Mac OS 8.5 Control Manager may pass the following new constants in the message parameter of your control definition function to specify the actions that your function must perform. For other control definition message constants, see "Defining Your Own Control Definition Function" in *Mac OS 8 Control Manager Reference*.

```
enum {
    kControlMsgApplyTextColor = 30,
    kControlMsgGetRegion = 31
}:
```

### **Constant descriptions**

kControlMsgApplyTextColor

Set the foreground color to be consistent with the current drawing environment and suitable for display against the background color or pattern. To indicate that your control definition function supports this message, set the kControlHasSpecialBackground feature bit. When this message is sent, the Control Manager passes a pointer to a structure of type ControlApplyTextColorRec (page 32) in your control definition function's param parameter. The Control Manager sets the ControlApplyTextColorRec structure to contain data describing the current drawing environment. Your control definition function is responsible for using this data to apply a text color which is consistent with the current theme and optimally readable on the control's background. Your control definition function should return 0 as the function result.

kControlMsaGetRegion

Obtain the region occupied by the specified control part. To indicate that your control definition function supports this message, set the kControlSupportsGetRegion feature bit. When this message is sent, the Control Manager passes a pointer to a structure of type ControlGetRegionRec (page 33) in your control definition function's param parameter. Your control definition function is responsible for setting the region field of the ControlGetRegionRec structure to the region that contains the control part which the Control Manager specifies in the part field. Your control definition

function return a result code of type <code>OSStatus</code> as the function result.

# Control Font Style Flag Constant

With the Mac OS 8.5 Control Manager, you can pass the following new control font style flag constant in the flags field of the ControlFontStyleRec structure to specify the fields of the structure that should be applied to the control. For more details on control font style flag constants and the ControlFontStyleRec structure, see *Mac OS 8 Control Manager Reference*.

```
enum {
    kControlAddToMetaFontMask = 0x0200
}:
```

### **Constant description**

kControlAddToMetaFontMask

If the bit specified by this mask is set, the control may use a meta-font while also adding other attributes to the font. If the bit specified by this mask is not set, but a meta-font is specified for the control, any additional attributes set for the font are ignored.

## **Control Key Script Behavior Constants**

With the Mac OS 8.5 Control Manager, you can use the following constants of type Control KeyScriptBehavior to specify the kind of behavior to be used in an editable text control with respect to changing and locking the keyboard menu as the field is focused. The Control KeyScriptBehavior constants are set and retrieved with the kControlEditTextKeyScriptBehaviorTag control data tag constant; for details on kControlEditTextKeyScriptBehaviorTag, see "Control Data Tag Constants" (page 34).

```
enum {
    kControlKeyScriptBehaviorAllowAnyScript = 'any ',
    kControlKeyScriptBehaviorPrefersRoman = 'prmn',
    kControlKeyScriptBehaviorRequiresRoman = 'rrmn'
};
typedef UInt32 ControlKeyScriptBehavior;
```

### **Constant descriptions**

kControlKeyScriptBehaviorAllowAnyScript

Does not change the current keyboard and allows the user to change the keyboard at will. This is the default for non-password fields.

kControlKeyScriptBehaviorPrefersRoman

Changes the current keyboard to Roman whenever the editable text field receives focus but allows the user to change the keyboard at will. This is the default for password fields.

kControlKeyScriptBehaviorReguiresRoman

Changes the current keyboard to Roman whenever the editable text field receives focus and does not allow the user to change the keyboard.

### **Control Part Code Constants**

The Mac OS 8.5 Control Manager defines the following new control part code constants. You can use control part codes with various functions to identify control parts. For details on other control part code constants, see *Mac OS 8 Control Manager Reference*.

#### **Constant descriptions**

kControlClockHourDayPart

Identifies the part of a clock control that contains the hour or the day.

kControlClockMinuteMonthPart

Identifies the part of a clock control that contains the minute or the month.

kControlClockSecondYearPart

Identifies the part of a clock control that contains the second or the year.

kControlClockAMPMPart

Identifies the part of a clock control that contains the AM/PM information.

kControlStructureMetaPart

Identifies the entire region occupied by a control. The kControlStructureMetaPart constant is for use only with GetControlRegion (page 29).

kControlContentMetaPart

Identifies the area of a control in which other controls may be embedded; this region is only defined for controls that can be embedders. The kControlContentMetaPart constant is for use only with GetControlRegion (page 29).

# Result Codes for the Mac OS 8.5 Control Manager

The new result codes returned by the Mac OS 8.5 Control Manager are listed below.

controlPropertyInvalid	-5603	'macs' property signature not allowed
controlPropertyNotFoundErr	-5604	Specified property does not exist
$\verb controlInvalidDataVersionErr  \\$	-30597	Incorrect version of data passed
controlHandleInvalidErr	-30599	Invalid control handle

### CHAPTER 2

Mac OS 8.5 Control Manager Reference

# **Document Version History**

This document has had the following releases:

 Table A-1
 Programming With the Mac OS 8.5 Control Manager Revision History

Version	Notes
Jan. 12, 1999	Initial public release. The following changes were made from the prior version:
	Changed "Control Manager 2.0" to "Mac OS 8.5 Control Manager" throughout to reflect final versioning.
	"Control Definition IDs" (page 39). Added descriptions of kControlIconRefProc and kControlIconRefNoTrackProc.
	"Result Codes for the Mac OS 8.5 Control Manager" (page 45). Changed the controlPropertyInvalidErr constant to controlPropertyInvalid.
	Added "Using the Mac OS 8.5 Control Manager" chapter to contain code listings moved from "Mac OS 8.5 Control Manager Reference" chapter.

Jul. 23, 1998 First seed draft release.

### APPENDIX

Document Version History

# Index

A	G
associating data with controls 20	gestaltControlMgrAttr constant 13 gestaltControlMgrPresent constant 14 GetControl32BitMaximum function 15 GetControl32BitMinimum function 15 GetControl32BitValue function 16 GetControlProperty function 21 GetControlPropertySize function 22 GetControlRegion function 29 GetControlViewSize function 26
С	
changing control settings 14 ControlApplyTextColorRec type 32 control data tag constants 34 control definition feature constants 38 control definition IDs 39 ControlEditTextValidationProcPtr type 33 ControlEditTextValidationUPP type 31 control font style flag constant 43 ControlGetRegionRec type 34 controlHandleInvalidErr result code 45 controlInvalidDataVersionErr result code 45 control key script behavior constants 43 ControlKeyScriptBehavior type 43 control part code constants 44 controlPropertyInvalid result code 45 controlPropertyInvalid result code 45 controlPropertyNotFoundErr result code 45 control settings, changing 14	
	К
	kControlAddToMetaFontMask constant 43 kControlAutoToggles constant 38 kControlBevelButtonScaleIconTag constant 37 kControlCheckBoxAutoToggleProc constant 40
	D
displaying controls 25	
E	kControlEditTextInlineInputProc constant 39
editable text, validating 8	kControlEditTextInlinePostUpdateProcTag constant 37
	kControlEditTextInlinePreUpdateProcTag constant 37

kControlEditTextKeyScriptBehaviorTag 0 constant 36 kControlEditTextLockedTag constant 36 obtaining control part regions 29 kControlEditTextValidationProcTag constant 36 kControlGroupBoxTitleRectTag constant 38 Р kControlIconContentTag constant 37 kControlIconRefNoTrackProc constant 40 proportional scroll boxes 7 kControlIconRefProc constant 39 kControlIconResourceIDTag constant 37 kControlKeyScriptBehaviorAllowAnyScript constant 44 R kControlKeyScriptBehaviorPrefersRoman constant 44 RemoveControlProperty function 23 kControlKeyScriptBehaviorRequiresRoman result codes 45 constant 44 kControlMsgApplyTextColor constant 42 kControlMsqGetRegion constant 42 S kControlPopupButtonExtraHeightTag constant 38 scroll boxes, proportional 7 kControlPushButtonCancelTag constant 38 kControlRadioButtonAutoToggleProc SetControl32BitMaximum function 17 SetControl32BitMinimum function 18 constant 41 kControlScrollTextBoxAutoScrollAmountTag SetControl32BitValue function 19 constant 36 SetControlProperty function 24 SetControlViewSize function 26 kControlScrollTextBoxAutoScrollProc SetUpControlTextColor function 27 constant 41 "Smart Scrolling" 7 kControlScrollTextBoxContentsTag constant 36 kControlScrollTextBoxDelayBeforeAutoScrol 1Tag constant 35 V kControlScrollTextBoxDelayBetweenAutoScro 11Tag constant 36 validating controls 28 kControlScrollTextBoxProc constant 41 kControlStaticTextTruncTag constant 37 kControlStructureMetaPart constant 45 kControlSupportsGetRegion constant 38

 $\begin{array}{c} {\tt MyControlEditTextValidationProc}\\ {\tt function} \ \ 30 \end{array}$ 

This Apple manual was written, edited, and composed on a desktop publishing system using Apple Macintosh computers and FrameMaker software. Line art was created using  $Adobe^{TM}$  Illustrator and Adobe Photoshop.

Text type is Palatino<sup>®</sup> and display type is Helvetica<sup>®</sup>. Bullets are ITC Zapf Dingbats<sup>®</sup>. Some elements, such as program listings, are set in Adobe Letter Gothic.

WRITER
Donna S. Lee
PRODUCTION EDITOR
Glen Frank

Acknowledgments to Guy Fullerton, Pete Gontier, and Chris Thomas.