This chapter describes how text-processing applications can communicate flexibly and efficiently with utilities that provide services to those applications. Applications that need input methods, spell-checking, hyphenation, and so forth can use the Text Services Manager to search for, obtain information about, and communicate with those utilities. Utilities can use the Text Services Manager to request actions and information from applications, and to send data to them.

Read this chapter if you are developing or enhancing an application to use text services. In particular, if you want your application to support text input in a 2-byte script system, you should use the Text Services Manager. Your application will then work with multiple script systems and many input methods.

Read this chapter if you are writing or adapting a utility that provides a text service such as text input. Utilities that work with the Text Services Manager are called *text service components*. If your utility is a text service component, it will be able to communicate with a wide range of applications.

Before reading this chapter, read the chapter "Introduction to Text on the Macintosh" in this book. To use this chapter, you should also be familiar with the Apple Event Manager and the Component Manager. For details on the Apple Event Manager, see *Inside Macintosh: Interapplication Communication*. For more on the Component Manager, see *Inside Macintosh: More Macintosh Toolbox*.

This chapter refers to routines, constants, and data structures from QuickDraw, the Event Manager, the Window Manager, the Menu Manager, and the Process Manager. For details on QuickDraw, see *Inside Macintosh: Imaging*. For more on the Event Manager, Window Manager, and Menu Manager, see *Inside Macintosh: Macintosh Toolbox Essentials*. For information on the Process Manager, see *Inside Macintosh: Processes*.

This chapter first provides a brief introduction to text services in general, input methods in particular, and the Text Services Manager itself. If you are writing an application, it then discusses how you can

- use the Text Services Manager routines for client applications, to send information to text service components
- implement the text-service Apple event handlers in your client application, to receive information from text service components
- communicate directly with the Component Manager and text service components, if your application's special needs require you to bypass the Text Services Manager

If you are writing a text service component, this chapter discusses how you can

- implement the text service component routines, so that the Text Services Manager and client applications can request the text services you provide
- use the Text Services Manager routines for text service components, to send information to client applications and the Text Services Manager

About Text Services

The Text Services Manager is the part of Macintosh system software that maintains communication between applications that need text services and utility programs that provide them. The Text Services Manager exists so that these two types of programs can work together without needing to know anything about each others' internal structures or identities.

A **text service** is a specific text-handling task such as spell-checking, hyphenation, and handling input of complex text. A **text service component** is a utility program that uses the Text Services Manager to provide a text service to an application. Text service components are registered components with the Component Manager, as described in the Component Manager chapter of *Inside Macintosh: More Macintosh Toolbox*.

A **client application** is a text-processing program that uses the Text Services Manager to request a service from a text service component. To accomplish this, a client application needs to make the Text Services Manager aware of its existence and needs to make specific Text Services Manager calls during execution.

In principle, text services can include many different types of tasks. However, only one type of text service is currently defined: text input. This chapter describes how to work with any type of text service component, and how to create any type of text service component, but it emphasizes input methods. It also points out the ways in which input methods are handled differently from other types of text service components.

About Input Methods


An **input method** is a facility that automatically converts phonetic or syllabic characters into ideographic or other complex representations. It permits use of a standard keyboard to generate the thousands to tens of thousands of different characters needed by some languages. Text input in Japanese, Chinese, and Korean usually requires an input method.

For example, text input in the Japanese script system requires software for transcribing Romaji (phonetic Japanese using Roman characters) or Hiragana (syllabic Japanese) into ideographic Kanji (Chinese characters). Each Kanji character may correspond to more than one possible Hiragana sequence, and vice versa. The input method must grammatically parse sentences or clauses of Hiragana text (which has no word separations) and select the best combination of Kanji and Hiragana characters to represent that text.

Chinese text input is similar to Japanese, in that a conversion from Pinyin (Roman) or Zhuyinfuhao (phonetic) to ideographic Hanzi (Chinese characters) is required. Korean text input requires conversion from Jamo (phonetic) to non-ideographic Hangul (complex clusters of Jamo).


Bottomline input allows the user to type text into a special **floating input window**— usually displayed in the lower portion of the screen—where conversion is to take place. The floating input window typically appears whenever the user starts typing characters. See Figure 7-1.

Figure 7-1 Bottomline input with a floating input window



Inline input is an input method in which conversion of characters takes place at the current line position in the application where the text is intended to appear. This allows the user to type text directly into the application window and requires no separate input window. Inline input is the principal example of the kind of text service supported by the Text Services Manager. See Figure 7-2.

Figure 7-2 Inline input




About Input Methods 7-7

With either bottomline input or inline input, the user can usually type Roman characters or characters of another subscript. Figure 7-3 shows an example of a floating palette, with which the user can select whether text entry is to be in 1-byte or 2-byte Romaji, Katakana, or Hiragana. The user presses a key such as the Space bar to initiate conversion from the input characters to the final characters.

The input method is often extended so that characters may be converted in extremely precise ways. For example, in the Japanese script system, when Hiragana text is converted to Kanji, the user has the option of changing any individual phrase: lengthening it, shortening it, or selecting different possible interpretations. Figure 7-3 shows a scrolling list of additional conversion options displayed next to the converted text in a floating input window. Only after the user is satisfied with the conversion and presses the Return key is the text actually sent to the application.

Figure 7-3 Displaying conversion options for bottomline input



Input methods commonly rely upon one or more dictionaries to perform conversion. The main dictionary lists all standard conversion options for any valid syllabic or phonetic input. Besides using the main dictionary, users can add specialized dictionaries, such as legal or medical dictionaries, to extend the range of the input method. See the chapter "Dictionary Manager" in this book for more information.

About the Text Services Manager

The Text Services Manager links text service components to client applications that use text services. When a client application requests a service from the Text Services Manager, the Text Services Manager routes the request to a text service component associated with that application. The text service component processes the request and may send text or other information back to the Text Services Manager, which passes it on to the client application through an Apple event.

An application that explicitly uses the Text Services Manager is called a **TSM-aware application**. An application that does not make calls to the Text Services Manager is called non-TSM-aware. A non-TSM-aware application can still make indirect use of some services of the Text Services Manager; see "Floating Input Windows" on page 7-13.

The Text Services Environment

The text services environment is a structure for the efficient flow of information between client applications and text service components. It allows client applications to obtain text services without having to know anything about the specific text service components performing them. Likewise, it allows text service components to perform their services without having to know anything about the specific client applications making the requests.

The text services environment consists of a client application, a text service component, the Apple Event Manager, the Component Manager, and the Text Services Manager. For a client application to work within the text services environment, it must

- call the routines of the Text Services Manager application interface described under "Text Services Manager Routines for Client Applications" on page 7-48. By using these application-level routines, a client application becomes TSM-aware and communicates with other parts of the environment.
- implement handlers for the Apple events described under "Apple Event Handlers Supplied by Client Applications" on page 7-65. A client application receives text and other information from a text service component through Apple events.


For a text service component to work within the text services environment, it must

- register as a component with the Component Manager
- call the routines of the Text Services Manager component interface described under "Text Services Manager Routines for Components" on page 7-77
- implement the component-level text service component routines described under "Text Service Component Routines" on page 7-84

Figure 7-4 shows some of the flow of information in the text services environment when a TSM-aware application uses a text service component. Application-level calls that an application makes to the Text Services Manager application interface are converted to component-level calls that are passed to an individual text service component. The text service component in turn makes calls to the Text Services Manager component interface; those calls are converted to Apple events that are passed on to the application.

The Text Services Manager controls the overall process by keeping track of which text service components are available to a given application and which application is to receive data from a given text service component. The Text Services Manager communicates with text service components through the Component Manager; applications that have special needs can likewise communicate directly with individual text service components by calling the text service component routines.

Figure 7-4 How a TSM-aware client application uses the Text Services Manager



IMPORTANT

The event-handling structure of the Text Services Manager requires that the low-memory global variable Sevtend be nonzero. If your application sets Sevtend to 0 to force the Event Manager function SystemEvent to always return a value of FALSE, text service components do not function correctly. See *Inside Macintosh: Macintosh Toolbox Essentials* for more information on the SystemEvent function and the Sevtend global variable. \blacktriangle

The Text Services Manager and Input Methods

Although the Text Services Manager can work with any type of text service component, it provides several features specific to input methods for 2-byte script systems. The Text Services Manager synchronizes the current input method with the current keyboard script. For example, if the user changes from a Japanese to a Chinese font, the application changes the keyboard script to Chinese and the Text Services Manager then switches the current input method from Japanese to Chinese as well. Unlike with other text services, the Text Services Manager opens and closes input methods, and takes care of their menu handling.

Inline Input

A principal feature of the Text Services Manager is its support for inline input. Figure 7-4 shows how information flows through the Text Services Manager when a TSM-aware application uses it for inline input. The application passes key-down events to the text service component; the text service component sends text and messages back to the application with Apple events. Events, messages, and requests for service between the application and the text service component all pass through the Text Services Manager.


For inline input, the Text Services Manager offers routines that let client applications and text service components communicate about what happens in the **active input area**—the portion of the screen in which the user enters text and where the text service component displays converted text. The client application and the text service component share control over the active input area.

The active input area is almost like a small window with invisible borders inside of the application's document window. It replaces the insertion point in the document, but it can be any width; it can even occupy more than one entire line of text. Text within the active input area can have its own font and size, different from that of body text. Text within the active input area can even scroll out of sight if there is more text than can fit in the space allotted for it in the active input area.

The application is responsible for determining the location and size of the active input area, and for drawing and highlighting all text within it. The text service component is responsible for accepting user input (as key-down events), for converting input text to final text, and for telling the application what characters to draw—and what characters to accept as confirmed—at every step of the way. The text service component can also instruct the application to scroll certain parts of the active input area into view, if necessary.

The text service component processes the user input, called **raw text**, as it is entered. The text service component first has the application draw the text on the screen as entered. Then it **converts** the raw text, translating it from phonetic or syllabic to ideographic or complex syllabic characters. Finally, it **confirms** the converted text upon user approval of the conversion. By convention in some script systems, a text service component converts text when the user presses the Space bar after entering a sequence of characters, and confirms the converted text when the user presses Return to accept the conversion. See Figure 7-5. (In Korean, conversion happens continuously and automatically, and confirmation happens by convention when the user presses either Return or the Space bar.)

Figure 7-5 Entering, converting, and confirming text in an active input area



User presses Return; converted text is confirmed (no underline). Active input area closes.

New active input area opens when user enters more raw text.

The text service component continually removes the confirmed input from the active input area and sends it to the application for storage in its text buffer. The text service component uses Apple events for this purpose, and for notifying the application of every character (raw, converted, or confirmed) that needs to be drawn or highlighted within the active input area.

In a number of situations, a client application may need to initiate the confirmation of input in progress. For example, if a user switches input methods, makes a menu selection, or selects text outside the active input area, the user has implicitly requested confirmation of the existing text. The client application needs to inform the text service component so it can confirm all text, whether raw or converted, in the active input area. The client application can make that request through a call to the Text Services Manager.


Floating Input Windows

The Text Services Manager also provides a service to facilitate the use of an input window for text entry and conversion when inline input is not supported by the application or not desired by the user. This floating input window is a standard bottomline input window: it usually appears in the lower portion of the screen, although the user can drag it to any location. Once the user's text has been converted correctly in the window, it is sent to the application.

The Text Services Manager's floating input window is mainly for use with applications that are not TSM-aware. See Figure 7-4. The input window uses the **floating window service**, a part of the Text Services Manager. It works this way:

- 1. The Process Manager intercepts key-down events and passes them to the Text Services Manager.
- 2. The Text Services Manager passes them to the appropriate input method for processing.
- 3. The input method then passes the processed text back to the Text Services Manager. The floating window service displays the text in a floating input window.
- 4. When the user is finished with the text, the floating window service passes the processed text back to the client application through standard key-down events (not Apple events).

Figure 7-6 How a non-TSM-aware application uses the Text Services Manager



In this way the Text Services Manager can provide an input method text service component for applications that have no knowledge of the text services environment.


TSM-aware applications should normally use inline input. However, the Text Services Manager does allow TSM-aware applications to use a floating input window. Users may prefer bottomline input if the size of the text displayed in the document makes reading the characters difficult.

Floating Utility Windows

Floating windows are useful for more than just text entry. Input methods can use the Text Services Manager floating window service to create utility windows—floating windows that display palettes or present lists of choices to the user. For example, most Japanese input methods let a user set the input mode to either 2-byte Hiragana, 1-byte Hiragana, 2-byte Romaji, or 1-byte Romaji. In the past, users selected these modes from controls inside the input method's input window. Now, since the system provides a standard floating input window for non-TSM-aware applications as well as for TSM-aware applications that request it, input methods should offer mode selection in a separate floating palette. Figure 7-3 on page 7-8 shows an example of a floating palette window used with bottomline input; Figure 7-9 on page 7-33 shows the same palette used with inline input.

Figure 7-7 illustrates the window-layer organization provided by the Text Services Manager. A floating window, whether an input window or a utility window, is always in front of all application windows but behind any help balloons.

Figure 7-7 Floating window service layer



About Text Service Components

Text service components are components as defined and used by the Component Manager. They have a specific structure, interface, and manner of execution. For more information on components, see the chapter "Component Manager" in *Inside Macintosh: More Macintosh Toolbox*. This section briefly describes the component description record, a data structure associated with a text service component.

The *component description record*, maintained by the Component Manager for each registered component, identifies the characteristics of the component, including the nature of services provided by the component and the manufacturer of the component. It is filled out by the text service component at initialization.

The ComponentDescription data type defines the format of the component description record:

```
TYPE ComponentDescription =
   RECORD
      componentType:
                            OSType;
                                      {command set ID}
                                      {specifies flavor}
      componentSubType:
                            OSType;
      componentManufacturer:
                            OSType;
                                      {vendor ID}
                                      {control flags}
      componentFlags:
                            OSType;
                                      {mask for control flags}
      componentFlagsMask:
                            OSType;
   END;
```

Field descriptions

componentType

For text service components, this field contains the interface type. The **interface type** specifies the set of Apple events and component commands associated with the text service component. Currently, all text service components have the same interface type, kTextService, whose associated 4-character tag is 'tsvc'. To obtain a list of all available text service components, a client application can specify the value kTextServices in the componentType field when calling the Component Manager routine GetServiceList.

componentSubType

For text service components, this field contains the text service component type. The **text service component type** specifies the function and optionally a set of additional routines and data structures associated with that particular kind of text service component. Currently, only one text service component type is defined, 'inpm', specifying an inline input method.

component Manufacturer

The identification number of the manufacturer of this particular text service component.

componentFlags Four bytes that contain component-specific information. See Figure 7-8:


Bits 0–7 contain the language code (as unsigned 8 bits).

Bits 8–14 contain the script code (as unsigned 7 bits).

Bit 15 indicates whether the text service component takes active events. When bit 15 = 1, the text service component is interactive and accepts user events. When bit 15 = 0, the text service component is not interactive—that is, it only supplies batch services. Apple has reserved bits 16–23, so text services must set them to 0.

The Component Manager defines bits 24–31.

Figure 7-8 The format of the componentFlags field of the component description record



componentFlagsMask

Four bytes that contain values used to affect the componentFlags field. This field should be 0 in the component description record for any text service component.

For example, an input method for the Japanese script system might assign the following values to the componentType, componentSubType, and componentFlags fields of component description record.

Using the Text Services Manager (for Client Applications)

This section describes how your client application can use the Text Services Manager application interface to communicate with text service components, how it can use Apple event handlers to receive information from text service components, and how it can communicate directly with text service components—bypassing the Text Services Manager altogether—for special purposes.

Testing for the Availability of the Text Services Manager

Use the Gestalt environmental selector gestaltTSMgrVersion to determine whether the Text Services Manager is available. The Gestalt function returns a 32-bit value indicating which version of the Text Services Manager is installed.

For more information on the Gestalt function, see the Gestalt Manager chapter in *Inside Macintosh: Operating System Utilities*.

Calling the Text Services Manager

The application interface to the Text Services Manager consists of application-level calls that your client application uses to send information to text service components by way of the Text Services Manager. They are documented in detail under "Text Services Manager Routines for Client Applications" on page 7-48. The Text Services Manager maps many of those calls to equivalent component-level calls to text service components. Those text service component routines are described under "Text Service Component Routines" on page 7-84.

This section describes how your client application can use the application interface to the Text Services Manager to

- prepare for communication with the Text Services Manager
- create an internal record called a TSM document
- make text services other than text input available to the user
- activate and deactivate a TSM document
- give text service components a chance to handle events, respond to menu selections, and set the shape of the cursor
- explicitly confirm text within the active input area
- terminate communication with the Text Services Manager

Initializing as a TSM-Aware Application

If your client application plans to use any of the Text Services Manager application-interface routines, it must call InitTSMAwareApplication at startup, immediately after calling the rest of the Toolbox initialization routines. See Listing 7-1.

Listing 7-1 Initializing as a TSM-aware application

```
FUNCTION Initialize: OSErr;
VAR
   myErr:
            OSErr;
BEGIN
   InitGraf(@thePort);
   InitFonts;
   InitWindows;
   InitMenus;
   TEInit;
   InitDialogs(NIL);
   InitCursor;
   IF (InitTSMAwareApplication = noErr) THEN
      Initialize := DoNew;
                                   {application routine that }
                                   { creates window & TSM document}
END;
```

The Text Services Manager records the fact that your client application is TSM-aware, and allocates any private data storage as necessary.

Creating a TSM Document

Your client application needs to create an internal record called a **TSM document** (defined by the TSMDocument data type) before it can use any services provided through the Text Services Manager. A TSM document is a private data structure that is associated with each of your application's documents that use a text service. You cannot access the TSM document record directly. You call the NewTSMDocument function to instruct the Text Services Manager to create the TSM document. The Text Services Manager returns a TSM document ID, an identifier that you supply in subsequent calls to the Text Services Manager.

Typically, you create a TSM document for each window that your application uses. Use the supportedInterfaceTypes array to indicate which text service interfaces you support. Currently only one interface is defined—'tsvc', the component type for text services components. Pass any data you like in the refcon parameter to the call. The Text Services Manager returns the refcon value in the keyAETSMDocumentRefcon parameter of any Apple event sent to your application. You can then use the refcon value to determine which TSM document and window the Apple event belongs to.

Listing 7-2 shows the sample application's DoNew function, which is called from the initialization routine presented in Listing 7-1. The call to NewTSMDocument specifies that the application supports one interface type (kTextService). NewTSMDocument opens the default input method for the current keyboard script, assigns it to this document, and returns the TSM document ID in the idocID parameter. The routine makes use of a modified window record (type MyWindowRecord) that is a standard window record with an additional field for holding the TSM document ID.

Listing 7-2 Creating a new TSM document and associating it with a window

```
FUNCTION DoNew: OSErr;
VAR
   wRecordPtr:
                     myWindowPtr;
   window:
                     WindowPtr;
                     InterfaceTypeList;
   supportedTypes:
  myErr:
                     OSErr;
BEGIN
   supportedTypes[0] := kTextService;
                               {allocate storage for window record}
   wRecordPtr := myWindowPtr(NewPtr(sizeof(myWindowRecord)));
   IF wRecordPtr <> NIL THEN
   BEGIN
      IF qColorQDAvailable THEN
         window := GetNewCWindow(kWINDResID, Ptr(wRecordPtr),
                                  WindowPtr(-1))
      ELSE
         window := GetNewWindow(kWINDResID, Ptr(wRecordPtr),
                                  WindowPtr(-1));
      IF window = NIL THEN
                                              {couldn't get window}
      BEGIN
         DisposePtr(Ptr(wRecordPtr));
                                                        {clean up}
         DoNew := kWindowFailed;
         Exit(DoNew);
      END;
      myErr := NewTSMDocument(1, supportedTypes,
                               wRecordPtr^.idocID,
                               LongInt(wRecordPtr));
   END;
   {do other window intialization, like creating scroll bars}
   DoNew := myErr;
END;
```

Making Text Services Available to the User

Text services that are input methods are always displayed in the keyboard menu. System software takes care of that; your application does not need to list input methods. However, your application may wish to provide a menu or scrolling list to display other types of available text services. (Note that, currently, no text services other than input methods are available. This capability is provided for future extensibility.)

To obtain a list of the available text services on the user's system, call the GetServiceList function. You pass it an array of interface types (to indicate the types of services you want returned in the list) and a pointer to a data structure (to hold the list). The function returns the number of available components, and a name and component identifier for each one.

Because text service components can be registered or unregistered at any time, your client application should periodically call either GetServiceList or the Component Manager function GetComponentListModSeed to see if the list of registered text service components may have changed.

IMPORTANT

If your client application displays a list or menu of text service components, do not show input methods. They are already displayed in the Keyboard menu. To show them in two places would be confusing to users. \blacktriangle

The Text Services Manager automatically opens input methods; your client application does not have to open them. You do have to explicitly open all other types of text services, however. If the user chooses a text service from a menu or list that you have displayed, you need to open that text service.

You call the OpenTextService function to associate the text service component with the current TSM document. OpenTextService then returns a valid component instance to indicate that the text service component has been opened and initialized.

Whenever a user wishes to close a text service component that you have opened, call the CloseTextService function.

Activating and Deactivating a TSM Document

To notify the Text Services Manager that a window in your client application associated with a TSM document has been activated, and that you are ready to use a text service component, use the ActivateTSMDocument function.

Listing 7-3 shows how to handle activating and deactivating a TSM document. You specify the document using the ID assigned to it when it was created (with the NewTSMDocument function). This routine, like the previous samples, assumes that the application has an extended window record with a field, idocID, that contains the TSM document ID.

Listing 7-3 Activating and deactivating a TSM document

```
PROCEDURE DoActivate(window: WindowPtr; becomingActive: Boolean);
VAR
   myErr: OSErr;
BEGIN
   IF becomingActive THEN
       myErr := ActivateTSMDocument(MyWindowPtr(window)^.idocID)
   ELSE
       myErr := DeactivateTSMDocument(MyWindowPtr(window)^.idocID);
END;
```

When the Text Services Manager receives an ActivateTSMDocument call, it deactivates the currently active TSM document (if it hasn't already been explicitly deactivated) and stores the new document as the currently active TSM document. If the specified text service component for the document has a menu, the Text Services Manager inserts the menu into the menu bar as an application or system menu.

When a window in your client application associated with a TSM document has been deactivated, you should call the DeactivateTSMDocument function. The Text Services Manager in turn calls the text service component function DeactivateTextService for any text service components associated with the TSM document being deactivated.

Input-method text services are handled in a special way: the identity of the input method of the deactivated document is retained by the Text Services Manager, and compared with the input method used by the next *activated* document. If the newly active document uses the same input method, the Text Services Manager will simply activate the new instance of the same input method. If the documents use different input methods, the previous input method is then closed, and any windows belonging to it are closed and menus are removed. The new input method is then activated. Not closing an input method until it is actually unneeded avoids extra removal and immediate redisplay of input method palettes and menus.

Passing Events, Menu Selections, and Cursor Setting

Whenever your client application receives an event from the Event Manager function WaitNextEvent, you need to give each text service component an opportunity to handle that event, if appropriate. Use the TSMEvent function to let the Text Services Manager dispatch the events to the correct text service component. You provide a pointer to the event record containing the event. The Text Services Manager passes the event in turn to each component associated with the currently active TSM document, starting with input methods. If the event is handled by a component, TSMEvent returns TRUE and the event is changed to a null event. If the event is not handled, TSMEvent returns FALSE and you are responsible for handling the event.

Listing 7-4 is a partial example of an event handler in which the application passes events to the Text Services Manager for routing to text service components. If no text service component handles an event, the application handles it. The global variable

gusingTSM is TRUE if the Text Services Manager is present and the application is making use of it.

Listing 7-4 Passing events to a text service component

```
PROCEDURE MyDoEvent(event: eventRecord);
VAR
   handledByTS:
                  Boolean;
   gotEvent:
                  Boolean;
BEGIN
   WHILE TRUE DO
   BEGIN
      IF gHasWaitNextEvent THEN
      BEGIN
         gotEvent := WaitNextEvent(everyEvent, event,
                                     kSleep, NIL);
         handledByTS := FALSE;
         IF (qUsingTSM AND gotEvent) THEN
            handledByTS := TSMEvent(event);
      END;
      IF gotEvent AND (NOT handledByTS) THEN
         {process event in normal way}
   END;
END;
```

Whenever a user chooses a menu item, it may be from a text service component's menu; your application must therefore give the text service component a chance to respond. (This situation occurs only with text service components that are not input methods.) To do this, use the TSMMenuSelect function with the result from the Menu Manager function MenuSelect in the menuResult parameter. If TSMMenuSelect returns TRUE, then the text service component has handled the menu selection, so your client application does not need to do so. However, your application is still responsible for removing the highlighting from the menu title after the selection has been handled.

Your client application is generally responsible for setting the cursor to an appropriate shape. However, the text service component may have its own cursor requirements when the cursor is within the boundaries of its windows or palettes. To allow a text service component to set the cursor, use the SettsMCursor function. Call it whenever you would normally set the cursor yourself. If SettsMCursor returns TRUE, the cursor is either on a text service component window or on the active input area and a text service component has set the cursor. In this case, you should not set the cursor.

Confirming Active Text Within a TSM Document

Normally, an input method text service component ejects finished input from the active input area continually as it processes user events, sending the confirmed text to your application with the Update Active Input Area Apple event.

Circumstances may arise in which you need to confirm input in progress before the text service component ejects it (that is, before the user presses Return). If, for example, the user clicks the mouse in text outside the active input area, that constitutes an implicit user acceptance of the text in the active input area. You should explicitly terminate any active input and save the text that is in the active input area by calling the FixTSMDocument function. The text service component sends the confirmed text to your application and empties the active input area.

Listing 7-5 shows what happens when the user clicks the go-away box of the active document window after entering some text in the active input area. The global variable gidocid represents the ID of the active TSM document.

Listing 7-5 Confirming text in an active input area

```
PROCEDURE DoMouseDown (event: EventRecord);
VAR
   part:
               Integer;
   theWindow:
               WindowPtr;
               OSErr;
   myErr:
BEGIN
   part := FindWindow(event.where, theWindow);
   CASE part OF
      inContent:
         DoContentClick(theWindow, event);
      inDrag:
         DragWindow(theWindow, event.where,
                               theWindow^.portRect);
      inGoAway:
         IF TrackGoAway(theWindow, event.where) THEN
         BEGIN
            myErr := FixTSMDocument(gIDocID);
                                                  {confirm text}
            DoActivate(theWindow, FALSE);
                                               {deactivate window}
            HideWindow(theWindow);
                                                  {put it away}
            qVisible := FALSE;
         END;
   END;
END;
```

Deleting a TSM Document

When your client application closes a document window and no longer needs its associated TSM document, it needs to call the DeleteTSMDocument function to inform the Text Services Manager that the TSM document should be deleted.

The Text Services Manager closes the text service components for the specified TSM document by calling the Component Manager CloseComponent function for each open text service component. It then disposes of the internal TSM document record for the specified TSM document.

Closing Down as a TSM-Aware Application

To let the Text Services Manager perform needed housekeeping chores when your application has closed, your client application needs to call CloseTSMAwareApplication just before quitting, as shown in Listing 7-6.

Listing 7-6 Closing a TSM-aware application

```
FUNCTION DoQuitApplication: OSErr;
VAR
   myErr: OSErr;
BEGIN

   {app-specific clean up}

   myErr := CloseTSMAwareApplication; {ignore the error}
   ExitToShell;
END;
```

Requesting a Floating Input Window for Text Entry

Your client application may need to provide for users who prefer to enter text using a floating input window instead of entering text directly in the line of a document. For example, when the text font size is too small for reading ideographic characters, too big for convenient entry directly into the document window, or is being greeked, users may prefer a floating input window.

Your client application calls the UseInputWindow function with the useInputWindow parameter set to TRUE to display a floating input window for the TSM document you specify in the idocID parameter to the call. To display floating input windows for all documents associated with your application, you set the idocID parameter to NIL and the useInputWindow parameter to TRUE. To return to inline input, call UseInputWindow with the useInputWindow parameter set to FALSE.

Associating Input Methods With Scripts and Languages

If you use the application-interface routines, the Text Services Manager automatically associates a default input method with your TSM document every time the current script and language change. Although it is unlikely that it would ever need to, your client application can use Text Services Manager routines to control that automatic association.

The Operating System uses the GetDefaultInputMethod and SetDefaultInputMethod functions to associate an input method with a given script and language. When the user uses the Keyboard menu, Keyboard control panel, or other device for controlling input method preferences, these functions establish permanent associations (they last across restarts).

The Text Services Manager maintains a current text service language that it uses to synchronize input methods to the current script system and language. The Operating System calls the SetTextServiceLanguage function when the user switches the keyboard script, and the floating window service calls the GetTextServiceLanguage function to determine the text service language.

These routines make use of the script-language record, described under "Identifying the Supported Scripts and Languages" on page 7-42.

If your client application uses the Text Services Manager application-interface routines, the Text Services Manager automatically synchronizes the input method to the current text service language and there is no need to make the calls described here. If your client application bypasses the Text Services Manager and uses the text service component routines, the Text Services Manager does not provide automatic input method synchronization and you may have to make some of these calls yourself. See "Direct Access to Text Service Components" on page 7-36 for more information on the Component Manager and on how to communicate directly with text service components.

Handling Text Service Apple Events

Text service components send information to your client application through Apple events. To communicate with an input method text service component, you need to implement Apple event handlers that

- receive raw, converted, or confirmed text from the input method, update the active input area, and highlight text appropriately
- convert screen location (in global coordinates) to text offset (in the active input area or in the application's text buffer), so that the input method can, for example, adjust the caret position or cursor display to reflect the text beneath the cursor
- convert text offset to screen location, so that the input method can, for example, place a list of conversion options next to a particular section of raw text
- respond to the input method's request to show or hide a floating input window

Each Apple event contains two required parameters:

- The keyAETSMDocumentRefcon parameter is filled in by the Text Services Manager. It tells the application which TSM document is affected by the Apple event.
- The keyAEServerInstance parameter is filled in by the text service component, and identifies the component that is sending the Apple event.

Other parameters are specific to each Apple event, and are described under "Apple Event Handlers Supplied by Client Applications" on page 7-65.

For general rules for writing Apple event handlers, see the discussion of the Apple Event Manager in *Inside Macintosh: Interapplication Communication*.

Receiving Text and Updating the Active Input Area

The text service component uses the Update Active Input Area Apple event to request that your client application create and update an active input area, including drawing text in the active input area, and accepting confirmed text. For details on active input areas, see "Inline Input" on page 7-11. This Apple event also asks the client application to update a range of text in the active input area and highlight appropriately.

Because your application is responsible for all drawing in the active input area, it receives an Update Active Input Area Apple event whenever the user enters raw text (for example, Romaji for Japanese input), whenever that raw text is converted to an intermediate form (for example, Hiragana), whenever the text is converted (for example, to Kanji), and whenever the converted text is confirmed. The input method also uses this Apple event to instruct your application in how to highlight the various types of text (raw, converted, and so on) within the active input area.

The input method uses the Update Active Input Area Apple event to send additional information to your application, such as current caret position, a range of text that should be scrolled into view if it is not visible, and boundaries of clauses (language-specific groupings of text) that may exist in the active input area.

Listing 7-7 shows a sample handler for the Update Active Input Area Apple event. The handler first receives the input parameters, including the text and the ranges of text to highlight and update. The handler then puts any confirmed text into the application's text buffer.

Listing 7-7 A sample handler for the Update Active Input Area Apple event

```
FUNCTION MyHandleUpdateActive(theAppleEvent: AppleEvent;
reply: AppleEvent;
handlerRefCon: LongInt): OSErr;

VAR
theHiliteDesc: AEDesc;
theUpdateDesc: AEDesc;
theTextDesc: AEDesc;
myErr: OSErr;
```

```
returnedType: DescType;
   script:
                  ScriptLanguageRecord;
   fixLength:
                  LongInt;
   refcon:
                  LongInt;
   textSize:
                  LongInt;
   actualSize:
                  LongInt;
   thePinRange:
                  TextRange;
BEGIN
   {Get the required parameter keyAETSMDocumentRefcon}
   myErr := AEGetParamPtr(theAppleEvent, keyAETSMDocumentRefcon,
                           typeLongInteger, returnedType, @refcon,
                           sizeof(refcon), actualSize);
   IF myErr = noErr THEN
   BEGIN
      {Get the required parameter keyAETheData}
      theTextDesc.dataHandle := NIL;
      myErr := AEGetParamDesc(theAppleEvent, keyAETheData,
                              typeChar, theTextDesc);
   END;
   IF myErr <> noErr THEN
   BEGIN
      MyHandleUpdateActive := myErr;
      Exit(MyHandleUpdateActive);
   END;
   {Get the required parameter keyAEScriptTag}
   myErr := AEGetParamPtr(theAppleEvent, keyAEScriptTag,
                           typeIntlWritingCode, returnedType,
                           @script, sizeof(script), actualSize);
   IF myErr = noErr THEN
      {Get the required parameter keyAEFixLength}
      myErr := AEGetParamPtr(theAppleEvent, keyAEFixLength,
                              typeLongInteger, returnedType,
                              @fixLength, sizeof(fixlength),
                              actualSize);
   IF myErr = noErr THEN
   BEGIN
      {Get the optional parameter keyAEHiliteRange}
      theHiliteDesc.dataHandle := NIL;
      myErr := AEGetParamDesc(theAppleEvent, keyAEHiliteRange,
                              typeTextRangeArray, theHiliteDesc);
   END;
```

```
IF myErr <> noErr THEN
BEGIN
   MyHandleUpdateActive := myErr;
   myErr := AEDisposeDesc(theTextDesc);
                                          {ignore the error}
   Exit(MyHandleUpdateActive);
END;
{Get the optional parameter keyAEUpdateRange}
theUpdateDesc.dataHandle := NIL;
myErr := AEGetParamDesc(theAppleEvent, keyAEUpdateRange,
                        typeTextRangeArray, theUpdateDesc);
IF myErr <> noErr THEN
BEGIN
   MyHandleUpdateActive := myErr;
   myErr := AEDisposeDesc(theTextDesc);
                                          {ignore the error}
   myErr := AEDisposeDesc(theHiliteDesc);
   Exit(MyHandleUpdateActive);
END;
{Get the optional parameter keyAEPinRange}
myErr := AEGetParamPtr(theAppleEvent, keyAEPinRange,
                        typeTextRange, returnedType,
                        @thePinRange, sizeof(thePinRange),
                        actualSize);
MyHandleUpdateActive := myErr;
IF myErr = noErr THEN
BEGIN
   textSize := GetHandleSize(theTextDesc.dataHandle);
   MyHandleUpdateActive := MemError;
   IF MemError = noErr THEN
   BEGIN
      {if the value of keyAEFixLength is -1, the text }
      { contained in the keyAETheData parameter should }
      { completely replace the active input area in }
      { the application window}
      IF fixLength = -1 THEN fixLength := textSize;
      {the application procedure SetNewText handles }
      { updating and confirming the text in the active }
      { input area, highlighting, and scrolling the }
      { specified offsets into view}
```

Converting Screen Position to Text Offset

An input method text service component uses the Position To Offset Apple event when it needs to know the byte offset in a text buffer (usually the buffer corresponding to the active input area) corresponding to a given screen position. An input method typically sends the Position To Offset Apple event to your application in response to a mouse-down event. If the event location is in the application window (including the active input area), the input method may want to know which character the event corresponds to, in order to locate the caret or define highlighting.

An input method may also send Position To Offset in response to SetTSMCursor, so that it can modify the appearance of the cursor depending on the type of text the cursor passes over.

Your application's handler returns a byte offset and a value indicating whether the screen position is within the active input area. If it is, the offset is measured from the start of the active input area (the leading edge of the first character on the first line). If it is not, the offset is measured from the beginning of the application's body text. The definition of *body text* and the significance of measurements within it are specific to your application; here it means any application text outside of the active input area.

To help the input method more specifically define individual characters, your application can optionally return an indication as to whether the position corresponds to the leading edge or the trailing edge of the glyph corresponding to the character at the indicated offset.

The Position To Offset Apple event is similar in function to the QuickDraw PixelToChar function, and returns similar results. Your handler may use PixelToChar to get the information it returns to the text service component, or it may use a TextEdit call, as shown in the following code sample.

Listing 7-8 shows a sample handler for the Position To Offset Apple event. The handler first receives the input parameters, then uses the TextEdit function TEGetOffset to convert a screen location to text offset. The TEGetOffset function is described in the chapter "TextEdit" in this book.

Listing 7-8 A sample handler for the Position To Offset Apple event

```
FUNCTION MyHandlePos2Offset(theAppleEvent: AppleEvent;
                              reply: AppleEvent;
                              handlerRefCon: LongInt): OSErr;
VAR
   myErr:
                  OSErr;
   returnedType: DescType;
   refcon:
                  LongInt;
   currentPoint: Point;
   clickWindow:
                  WindowPtr;
   where, part:
                  Integer;
   oldPort:
                  GrafPtr;
   offset:
                  LongInt;
   te:
                  TEHandle;
   actualSize:
                  LongInt;
   bodyRect:
                  Rect;
   dragging:
                  Boolean;
   isMatch:
                  Boolean;
BEGIN
   {Get the required parameter TSMDocumentRefcon}
   myErr := AEGetParamPtr (theAppleEvent, keyAETSMDocumentRefcon,
                           typeLongInteger, returnedType, @refcon,
                           sizeof(refcon), actualSize);
   IF myErr = noErr THEN
      {Get the required parameter keyAECurrentPoint}
      myErr := AEGetParamPtr (theAppleEvent, keyAECurrentPoint,
                               typeQDPoint, returnedType,
                              @currentPoint,
                               sizeof(currentPoint), actualSize);
   IF myErr <> noErr THEN
   BEGIN
      MyHandlePos2Offset := myErr;
      Exit(MyHandlePos2Offset);
   END;
   where := kTSMOutsideOfBody;
   part := FindWindow(currentPoint, clickWindow);
   {the application function IsWindowForTheAE returns TRUE}
   {if the refcon is associated with the window}
   isMatch := IsWindowForTheAE(refcon, clickWindow);
```

```
IF ((clickWindow = FrontWindow) AND
      isMatch AND (part = inContent)) THEN
BEGIN
   GetPort(oldPort);
   SetPort(clickWindow);
   {convert currentPoint into the local }
   { coordinates of the current grafport}
   GlobalToLocal(currentPoint);
   {the application function GetTheBodyRect returns the}
   {body rect of the window}
   bodyRect := GetTheBodyRect(clickWindow);
   IF PtInRect(currentPoint, bodyRect) THEN
   BEGIN
      where := kTSMInsideOfBody;
   {the application function FindTheTEHandle returns the }
   { window's TEHandle. Then the TextEdit function }
   { TEGetOffset returns the offset corresponding to the point}
      te := FindTheTEHandle (clickWindow);
      offset := TEGetOffset(currentPoint, te);
      {The application function IsInsideInputArea returns }
      { TRUE if offset is within the active input area. }
      { It is application's responsibility to remember }
      { the range of the input area.}
      IF IsInsideInputArea(offset, clickWindow) THEN
         where := kTSMInsideOfActiveInputArea;
   END;
   {get the optional parameter: keyAEDragging}
   dragging := FALSE;
   myErr := AEGetParamPtr (theAppleEvent, keyAEDragging,
                           typeBoolean, returnedType,
                           @dragging, sizeof(dragging),
                           actualSize);
END;
IF myErr <> noErr THEN
```


```
BEGIN
      MyHandlePos2Offset := myErr;
      Exit(MyHandlePos2Offset);
  END;
   {if the parameter keyAEdragging is TRUE and the mouse}
   { position is outside the body text, the application }
   { can scroll the text within the active input area, }
   { rather than returning kTSMOutsideOfBody. The application }
   { procedure HandleScroll is handling the scrolling.}
  IF (dragging = TRUE) AND (where = kTSMOutsideOfBody) THEN
  BEGIN
      HandleScroll(te, offset);
      where := kTSMInsideOfActiveInputArea;
  END;
   SetPort(oldPort);
   {Construct the return parameter keyAEOffset}
  myErr := AEPutParamPtr(reply, keyAEOffset, typeLongInteger,
                           @offset, sizeof(offset));
   IF myErr = noErr THEN
      {Construct the return parameter keyAERegionClass}
      MyHandlePos2Offset := AEPutParamPtr(reply, keyAERegionClass,
                                    typeShortInteger,
                                    @where, sizeof(where))
  ELSE MyHandlePos2Offset := myErr;
END;
```

Converting Text Offset to Screen Position

An input method text service component uses the Offset To Position Apple event when it needs to know the screen position corresponding to a given byte offset in the text buffer for the active input area. An input method typically sends the Offset To Position Apple event to your application when it needs to draw something in a specific spatial relationship with a given character in the active input area. For example, it may need to draw a floating window containing suggested conversion options beside a particular range of raw or converted text. See Figure 7-9.

The text service component supplies a byte offset, measured from the character at the start of the active input area. The application returns a point designating the global coordinates of the caret position corresponding to that offset. Your application may optionally return information about the font, size, and other measurements of the text in the active input area, so that the text service component can more precisely locate the elements it is to draw.

Figure 7-9 Drawing a window with conversion options next to the active input area



The Offset To Position Apple event is similar in function to the QuickDraw CharToPixel function, and it returns similar results. Your handler may use CharToPixel to get the information it returns to the text service component, or it may use a TextEdit call, as shown in the following code sample.

Listing 7-9 shows a sample handler for the Offset To Position Apple event. The handler first receives the input parameters, then uses the TextEdit function TEGetPoint to convert a text offset to a screen location. The TEGetPoint function is described in the chapter "TextEdit" in this book.

Listing 7-9 A sample handler for the Offset To Position Apple event

```
FUNCTION MyHandleOffset2Pos(theAppleEvent: AppleEvent;
                                reply: AppleEvent;
                                handlerRefCon: LongInt): OSErr;
VAR
   myErr:
                   OSErr;
   rtErr:
                   OSErr;
   returnedType:
                   DescType;
   offSet:
                   LongInt;
   refcon:
                   LongInt;
   actualSize:
                   LongInt;
   theWindow:
                   WindowPtr;
   te:
                   TEHandle;
   oldPort:
                   GrafPtr;
   thePoint:
                   Point;
   theFixed:
                   Fixed;
BEGIN
```

```
{Get the required parameter keyAEOffset}
myErr := AEGetParamPtr(theAppleEvent, keyAEOffset,
                        typeLongInteger, returnedType, @offSet,
                        sizeof(offSet), actualSize);
IF myErr = noErr THEN
   {Get the required parameter TSMDocumentRefcon}
   myErr := AEGetParamPtr(theAppleEvent,
                           keyAETSMDocumentRefcon,
                            typeLongInteger, returnedType,
                            @refcon, sizeof(refcon),
                           actualSize);
IF myErr <> noErr THEN
BEGIN
   MyHandleOffset2Pos := myErr;
   Exit(MyHandleOffset2Pos);
{the application function GetWindowFromRefcon returns the }
{ window which is associated with the refcon}
rtErr := noErr;
                                              {initialize rtErr}
theWindow := GetWindowFromRefcon(refcon);
IF theWindow = NIL THEN
   rtErr := errOffsetInvalid
ELSE
BEGIN
   {the application function FindTheTEHandle returns the }
   { TEHandle for the window}
   te := FindTheTEHandle(theWindow);
   {the TextEdit function TEGetPoint returns the point }
   { corresponding to the given offset}
   thePoint := TEGetPoint(offSet, te);
   IF (offSet > te^^.teLength) OR (offSet < 0) THEN</pre>
      rtErr := errOffsetInvalid
   ELSE IF(PtInRect(thePoint,theWindow^.portRect) = FALSE) THEN
      rtErr := errOffsetIsOutsideOfView
   ELSE
   BEGIN
      GetPort(oldPort);
      SetPort(theWindow);
```

```
{Convert the Point into global coordinates}
   LocalToGlobal(thePoint);
   SetPort(oldPort);
END;
{construct the return parameter keyAEPoint}
myErr := AEPutParamPtr(reply, keyAEPoint, typeQDPoint,
                        @thePoint, sizeof(thePoint));
IF myErr = noErr THEN
   {construct the optional return parameter keyAETextFont}
   myErr := AEPutParamPtr(reply, keyAETextFont,
                        typeLongInteger, @te^^.txFont,
                        sizeof(longInt));
IF myErr = noErr THEN
BEGIN
   {construct optional return parameter keyAETextPointSize}
   theFixed := BSL(Fixed(te^^.txSize), 16);
   myErr := AEPutParamPtr(reply, keyAETextPointSize,
                        typeFixed, @theFixed,
                        sizeof(theFixed));
END;
IF myErr = noErr THEN
   {construct optional return parameter keyAETextLineHeight}
   myErr := AEPutParamPtr(reply, keyAETextLineHeight,
                        typeShortInteger, @te^^.lineHeight,
                        sizeof(Integer));
IF myErr = noErr THEN
   {construct optional return parameter keyAETextLineAscent}
   myErr := AEPutParamPtr(reply, keyAETextLineAscent,
                        typeShortInteger, @te^^.fontAscent,
                        sizeof(Integer));
IF myErr = noErr THEN
BEGIN
   {construct the optional return parameter keyAEAngle-- }
   {90 = horizontal direction, 180 = vertical direction}
   theFixed := Fixed(90);
   myErr := AEPutParamPtr(reply, keyAETextPointSize,
                        typeFixed, @theFixed,
                        sizeof(Fixed));
END;
IF myErr <> noErr THEN
BEGIN
```

Showing or Hiding the Input Window

Input methods that work with a floating input window often offer options to the user for either (1) continually displaying the input window, (2) displaying it only as text is being typed in and hiding it immediately after the user confirms it, or (3) leaving the window up for a specified amount of time after confirmation. The Show/Hide Input Window Apple event requests that your client application make the bottomline floating input window either visible or not visible. An input method text service component sends this Apple event whenever it needs to know or change the current state of the window.

This Apple event is for use only by applications that display their own input windows. If your application does not itself control the display of a floating input window, you can ignore this Apple event. If your application uses the Text Services Manager floating window service for bottomline input (by calling UseInputWindow), you do not receive this Apple event because it is handled by the Text Sevices Manager.

Direct Access to Text Service Components

Your client application can bypass the Text Services Manager and communicate with text service components directly. Many of the text service component routines correspond in function to the Text Services Manager application-interface routines. It is therefore possible for a client application to use the text service component routines if it needs to exert finer control over its interaction with text service components or if it requires specific kinds of text services or server-specific knowledge. It is not recommended in most cases, because the Text Services Manager is not available to help with dispatching and housekeeping chores.

Calling the Component Manager

If your client application does not use the Text Services Manager, it has to communicate with the Component Manager directly to identify and initialize individual text service components. You can use Component Manager calls to find components, set a default component, get information about components, and open components. See the chapter "Component Manager" in *Inside Macintosh: More Macintosh Toolbox* for more information.

Calling Text Service Components

If your client application calls text service components directly, it uses the text service component routines, a component-level interface described under "Text Service Component Routines" on page 7-84.

After opening a text service component with the OpenComponent or OpenDefaultComponent function, your client application calls InitiateTextService function to instruct the text service component to commence its operations.

To inform a text service component that its associated document window is becoming active or inactive, call the ActivateTextService or DeactivateTextService function.

You are responsible for adding the text service component menu to your application's menu bar. Furthermore, you are responsible for either disabling the menu or removing it from your menu bar when the text service component becomes inactive. Call the GetTextServiceMenu function to obtain menus from each open text service component.

To pass events to text service components, call the TextServiceEvent function. You are also responsible for allowing the text service components to control the cursor. Use the SetTextServiceCursor function to give the text service component a chance to set the cursor.

When a user makes a selection from the menu for a text service component, call the TextServiceMenuSelect function. You should call TextServiceMenuSelect right after the Menu Manager routines MenuSelect or MenuKey.

Before closing the component, call the TerminateTextService function to tell the text service component to finish its operations. You should remove the text service component's menu from the menu bar when the text service component is deactivated.

Using the Text Services Manager (for Text Service Components)

This chapter does not describe how to write a text service component. It describes only the interface between text service components and the Text Services Manager. Each text service component has several functions; it must be able to

- perform the tasks for which it was created
- communicate with the Component Manager
- receive calls from the Text Services Manager (or client applications), through the Component Manager
- send calls to the Text Services Manager

How components perform their specific text-handling tasks is beyond the scope of *Inside Macintosh*. How components communicate with the Component Manager is described in the chapter "Component Manager" in *Inside Macintosh*: More Macintosh Toolbox.

How text service components communicate with the Text Services Manager is described in this section.

The text service component routines are the component-level calls that the Text Services Manager makes to text service components through the Component Manager. See "Text Service Component Routines" on page 7-84 for detailed descriptions of the calls. If you are writing a text service component, it must implement the text service component routines.

Text service components also make calls to the Text Services Manager, to send Apple events to client applications and to request the use of a floating window when needed. See "Text Services Manager Routines for Components" on page 7-77 for detailed descriptions of those component-interface calls.

For a brief discussion of some of the data types associated with text service components, see "About Text Service Components" beginning on page 7-14.

Providing Menus and Icons

If you are writing a text service component, you can have it display its own menu, provide an icon for the title of that menu, and provide icons for the Keyboard menu.

Providing a Text Service Component Menu

Although most user selections and configurations are best made with floating palettes, a text service component may put one menu into the menu bar. For input-method text service components, the menu cannot be hierarchical. Input-method menus appear on the right (system) side of the menu bar, between the Help menu and the Keyboard menu. Menus for non-input-method text service components appear on the left (application) side of the menu bar. See Figure 7-10 on page 7-40.

To create the menu, follow the standard procedures as described in the Menu Manager chapter of *Inside Macintosh: Macintosh Toolbox Essentials*. The Text Services Manager installs the menu in the menu bar whenever your component is opened or activated. The application (through the Text Services Manager) passes the menu commands to you for handling when appropriate.

All instances of an input-method text service component must share one menu handle. Therefore, make sure to allocate the handle in the System heap. You can store the menu handle in your component's refcon field. See the discussion of the Component Manager SetComponentRefcon routine in *Inside Macintosh: More Macintosh Toolbox*.

IMPORTANT

An input-method text service component should never dispose of its menu handle in response to a TerminateTextService call (see page 7-86). Any other kind of text service component should always dispose of its menu handle in response to a TerminateTextService call.

Using an icon for the menu title

If you wish to have an icon instead of text as the title of your text service component menu, first create a small-icon suite (such as 'kcs#', 'kcs4', and 'kcs8') to represent your menu title. Then, in your menu resource, make the menu title a 5-byte Pascal string (6 bytes total size), with this format:

Byte	Value
0	\$05 (length byte for menu string)
1	\$01 (invalid character code)
2–5	Handle to icon suite

When the menu is created, the menu bar definition procedure knows from the values of the first 2 bytes that the final 4 bytes are a handle to an icon suite, and the procedure will put the icon in the menu bar. For more on creating icon suites and drawing icons, see the Finder Interface chapter of *Inside Macintosh: Macintosh Toolbox Essentials*. See also *Macintosh Human Interface Guidelines* for design suggestions for color icon families. •

Remember these limitations when considering an input-method menu: an input method can put up only one menu, the menu cannot be hierarchical, and the menu can be removed from the menu bar if there is insufficient room for it (on a small screen). It may be more appropriate to use palettes.

Providing Input Method Icons for the Keyboard Menu

Any text service component that provides an input method must supply the following keyboard icon resources to display an icon for the input method in the Keyboard menu: 'kcs#', 'kcs4', and 'kcs8'. The resource ID number of the keyboard icon resources must equal the script code of the script system that the input method supports. If your input method supports more than one script system, you can have more than one icon suite, each with the appropriate resource IDs.

Figure 7-10 shows a Keyboard menu displaying a Japanese input method and a Korean input method, as well as keyboard layouts from several other script systems. The Japanese input method is active; its icon is checked in the menu and appears highlighted on the menu bar.

Figure 7-10 Input method icons in the Keyboard menu and menu bar



The pencil icon between the Keyboard menu and the Help menu in Figure 7-10 is the title for the menu belonging to the active input method.

For more information on keyboard icon suites, see the appendix "Keyboard Resources" in this book. For information on script codes, see the chapter "Script Manager" in this book.

Responding to Calls

When a client application makes certain calls to the Text Services Manager application interface, the Text Services Manager in turn calls your text service component. Your text service component responds to these calls by initiating or closing a text service, manipulating text service windows, responding to events or menu commands, and confirming text input.

Initiating a Text Service

When your text service component receives the InitiateTextService call, it can commence its operations to provide its text service. That may include opening windows or palettes, initializing data structures, communicating with the user or application, or otherwise getting started with its tasks.

The Text Services Manager may call InitiateTextService on its own or in response to receiving the application-interface call OpenTextService.

Activating Text Service Component Windows

If a window associated with a TSM document associated with your text service is being activated, your text service component receives the ActivateTextService call. You should show floating windows associated with your component instance and prepare to receive and handle events.

If the window is being deactivated, your text service component receives the <code>DeactivateTextService</code> call. You should perform any necessary cleanup or other tasks associated with deactivating your current component instance. If your text service component is not an input method, you should also hide all floating windows associated with the document being deactivated. If your text service component is an input method and if the newly activated document does <code>not</code> use your text services, you will receive the <code>HidePaletteWindows</code> call. At that point you should hide all floating windows associated with the component instance being deactivated.

The Text Services Manager calls ActivateTextService and DeactivateTextService in response to receiving the application-interface calls ActivateTSMDocument and DeactivateTSMDocument, respectively.

Responding to Events and Updating the Cursor and Menu

The Text Services Manager (or a client application) is responsible for adding your text service component's menu to the menu bar. When your text service component receives a GetTextServiceMenu call, it needs to return a menu handle. The section "Providing Menus and Icons" on page 7-38 gives instructions for creating text service menus and icons.

When your text service component receives the call TextServiceEvent, TextServiceMenuSelect, or SetTextServiceCursor, it should handle the event, menu command, or cursor-drawing if appropriate. For example, when the user enters text, you receive and handle the key-down events; you in turn inform the application what characters to draw in the active input area. When the user makes a menu selection, you are given an opportunity to check whether it is from your menu and then to act on it. You are regularly given the opportunity to redraw the cursor, in case it may be over an area under your control (such as a palette window or the active input area).

The Text Services Manager may call GetTextServiceMenu on its own or in response to receiving the application-interface call OpenTextService. The Text Services Manager calls TextServiceEvent, TextServiceMenuSelect, and SetTextServiceCursor in response to receiving the application-interface calls TSMEvent, TSMMenuSelect, and SetTSMCursor, respectively.

Confirming Active Text Input

A client application may need your input method text service component to terminate input immediately and confirm any text currently in the active input area. When your text service component receives the call FixTextService, it should confirm all text in the active input area, just as if the user had pressed Return. It should send the confirmed text to the client application through the Update Active Input Area Apple event.

The Text Services Manager calls FixTextService in response to receiving the application-interface call FixTSMDocument.

Closing a Text Service

When your text service is no longer needed, the Text Services Manager calls your text service component's TerminateTextService function before calling the Component Manager to close the component. Your text service component should use this time to confirm any active input in progress and then dispose of memory as needed.

The Text Services Manager may call TerminateTextService on its own or in response to receiving the application-interface call CloseTextService.

Identifying the Supported Scripts and Languages

The Operating System, the Text Services Manager, or a client application may need to determine which scripts and languages your text service component supports. When you receive the GetScriptLanguageSupport call, you return that information in a script-language support record.

The GetScriptLanguageSupport function and several Text Services Manager application-interface routines use the **script-language record**—and the **script-language support record**—to pass information about the scripts and languages associated with text service components.

The script-language record provides a script code and language code for the script system and the language associated with a given text service component. The script-language record is defined by the ScriptLanguageRecord data type as follows:

```
TYPE ScriptLanguageRecord =
   RECORD
        fScript: ScriptCode;
        fLanguage: LangCode;
   END;
```

Field descriptions

fScript The number that identifies a script system supported by the text

service component

fLanguage The number that identifies a language associated with the script

supported by the text service component

For a list of constants for all defined script and language codes, see the chapter "Script Manager" in this book.

The script-language support record consists of an array of script-language records. It is defined by the ScriptLanguageSupport data type as follows:

```
TYPE ScriptLanguageSupport =
    RECORD
    fScriptLanguageCount: Integer;
    fScriptLanguageArray: ARRAY[0..0] of ScriptLanguageRecord;
END;
```

Field descriptions

fScriptLanguageCount

The number of script-language records in this script-language support record.

fScriptLanguageArray

A variable-length array of script-language records.

The Text Services Manager can call GetScriptLanguageSupport on its own or in response to receiving the application-interface call GetTextServiceLanguage.

Listing 7-10 gives an example of the response to the GetScriptLanguageSupport call by a Chinese input method.

Listing 7-10 Determining the script and language for a text service component

```
TYPE
scriptHandlePtr= ^ScriptLanguageSupportHandle;

VAR
scriptHdlPtr:scriptHandlePtr;

{The following is part of the case statement that dispatches }
{ text service component routines. It is the component's }
{ response to receiving a GetScriptLanguageSupport call}

kCMGetScriptLangSupport:
BEGIN
scriptHdlPtr := (scriptHandlePtr) @(cmParams^.params[0]);
IF scriptHdlPtr^ = NIL THEN
```

Making Calls

Your text service component needs to make two kinds of calls to the Text Services Manager: calls that cause the sending of an Apple event to a client application, and calls that request a floating window from the Text Services Manager.

Sending Apple Events to Client Applications

Apple events allow text service components to send information to and request specific services of client applications. It is the responsibility of the client application to install Apple event handlers for these Apple events. Using these events, the text service component controls the text services environment by requesting a variety of services from the client application.

Your text service component can send Apple events to request that a client application perform the following actions:

- create or update text in an active input area
- help you track cursor movements by converting global coordinates to the byte offset of characters in the active input area
- help you position items on the screen by converting the byte offset of characters in the active input area to global coordinates
- show or hide a floating input window

Note

Your text service component must always use the kCurrentProcess constant as the target address when it creates an Apple event to send to the Text Services Manager. •

To send Apple events to a client application, your text service component calls the Text Services Manager SendAEFromTSMComponent function. The Text Services Manager then completes the Apple event and sends it to the application. For general information on constructing and sending Apple events, see the discussion of the Apple Event Manager in *Inside Macintosh: Interapplication Communication*.

Listing 7-11 shows an example of a text service component preparing and sending an Update Active Input Area Apple event. The component creates the Apple event and constructs the required parameters, including the text to be sent to the application. It also constructs the optional parameters that specify highlighting and update ranges in the text. It then calls SendAefromTSMComponent to send the Apple event. In this listing, globalHandle is a handle to a data structure in which the text service component maintains all information about the text in the active input area.

Listing 7-11 Constructing and sending an Update Active Input Area Apple event

```
FUNCTION MyCreateUpdateInlineAreaAE(globalHandle: TglobalHandle)
: OSErr;
VAR
                            ProcessSerialNumber;
   psnRecord:
   myErr:
                            OSErr;
                            AEAddressDesc;
   addrDescriptor:
   theAEvent:
                            AppleEvent;
   theReply:
                            AppleEvent;
                            ScriptLanguageRecord;
   slRecord:
   theRangeTableSize:
                           LongInt;
   theTextData:
                           Handle;
   theUpdateRangeTable:
                           TextRangeArray;
   theHiliteRangeTable:
                           TextRangeArray;
BEGIN
   {Apple event must go to the current process }
   psnRecord.highLongOfPSN := 0;
   psnRecord.lowLongOfPSN := kCurrentProcess;
   myErr := AECreateDesc(typeProcessSerialNumber, @psnRecord,
                            sizeof(psnRecord), addrDescriptor);
   IF myErr <> noErr THEN
   BEGIN
      MyCreateUpdateInlineAreaAE := myErr;
      Exit(MyCreateUpdateInlineAreaAE);
   END;
```

```
{create the Apple event record}
myErr := AECreateAppleEvent(kTextServiceClass,
                           kUpdateActiveInputArea,
                           addrDescriptor,
                           kAutoGenerateReturnID,
                           kAnyTransactionID, theAEvent);
IF myErr <> noErr THEN
BEGIN
   MyCreateUpdateInlineAreaAE := myErr;
   myErr := AEDisposeDesc(addrDescriptor);
                                            {ignore the error}
   Exit(MyCreateUpdateInlineAreaAE);
END;
{construct the required parameter keyAEServerInstance-- }
{ globalHandle^^.fSelf = global containing component instance}
myErr := AEPutParamPtr(theAEvent, keyAEServerInstance,
                        typeComponentInstance,
                        @globalHandle^^.fSelf,
                        sizeof(ComponentInstance));
IF myErr = noErr THEN
BEGIN
   {construct required parameter keyAEScriptTag }
   { --Korean in this case}
   slRecord.fScript := smKorean;
   slRecord.fLanguage := langKorean;
   myErr := AEPutParamPtr(theAEvent, keyAEScriptTag,
                           typeIntlWritingCode,
                           @slRecord, sizeof(slRecord));
END;
IF myErr = noErr THEN
BEGIN
   {construct required parameter keyAETheData. globalHandle }
   { is a handle to component's data structure describing }
   { all text in the active inline area}
   theTextData := globalHandle^^.fTextData;
   HLock(theTextData);
   myErr := AEPutParamPtr(theAEvent, keyAETheData, typeChar,
                        theTextData^,
                        globalHandle^^.fTextDataLength);
   HUnlock(theTextData);
END;
```

```
IF myErr = noErr THEN
   {construct the required parameter keyAEFixLength}
   myErr := AEPutParamPtr(theAEvent, keyAEFixLength,
                        typeInteger,
                        @globalHandle^^.fFixedLength,
                        sizeof(LongInt));
IF myErr = noErr THEN
BEGIN
   {construct the optional parameter UpdateRangeTable}
   theUpdateRangeTable := globalHandle^^.fUpdateRangeTable;
   theRangeTableSize := sizeof(TextRangeArray)
                        + the Update Range Table. f Num Of Ranges
                        * sizeof(TextRange);
   myErr := AEPutParamPtr(theAEvent, keyAEFixLength,
                        typeInteger,
                        @theUpdateRangeTable,
                        theRangeTableSize);
END;
IF myErr = noErr THEN
BEGIN
   {construct the optional parameter HiliteRangeTable}
   theHiliteRangeTable := globalHandle^^.fHiliteRangeTable;
   theRangeTableSize := sizeof(TextRangeArray)
                        + theHiliteRangeTable.fNumOfRanges
                        * sizeof(TextRange);
   myErr := AEPutParamPtr(theAEvent, keyAEFixLength,
                        typeInteger,
                        @theHiliteRangeTable,
                        theRangeTableSize)
END;
IF myErr <> noErr THEN
BEGIN
   MyCreateUpdateInlineAreaAE := myErr;
   myErr := AEDisposeDesc(theAEvent);
                                           {ignore the errors}
   myErr := AEDisposeDesc(addrDescriptor);
  Exit(MyCreateUpdateInlineAreaAE);
END;
{send the Apple event}
myErr := SendAEFromTSMComponent(theAEvent, theReply,
                           kAEWaitReply + kAENeverInteract,
                           kAENormalPriority, 120, NIL, NIL);
MyCreateUpdateInlineAreaAE := myErr;
```

```
myErr := AEDisposeDesc(theAEvent); {ignore the errors}
myErr := AEDisposeDesc(addrDescriptor);
myErr := AEDisposeDesc(theReply);
END;
```

Opening Floating Utility Windows

To open a floating utility window in front of the current client application, you use the NewServiceWindow function. If the call is successful, NewServiceWindow allocates a floating window in the floating window service layer, and returns a pointer to the window. See "Floating Input Windows" on page 7-13 and "Floating Utility Windows" on page 7-14 for a discussion of the Text Services Manager floating window service and the floating window service layer.

Your text service component can open multiple floating windows. When your component receives an event, you must determine if the event belongs to one of your text service floating windows. To get a pointer to the frontmost window in the floating window service layer, call the GetFrontServiceWindow function. To find out which part of your floating window an event occurred in, call the FindServiceWindow function. Your text service component can close the floating window you originally allocated by using the CloseServiceWindow function.

Text Services Manager Reference

This section describes four categories of routines and handlers, and their related constants and data structures:

- Text Services Manager routines called by client applications (the application interface to the Text Services Manager)
- application-supplied handlers for Apple events initiated by text service components
- Text Services Manager routines called by text service components (the component interface to the Text Services Manager)
- text service component routines, called by the Text Services Manager and possibly by client applications

Text Services Manager Routines for Client Applications

The Text Services Manager provides an application interface that allows client applications to use text service components independently of any specific knowledge of those components. Your client application makes these application-level calls to the Text Services Manager, which in turn calls the text service component using the component-level routines described in the section "Text Service Component Routines" on page 7-84.

The routines in the application interface let you

- initialize and close your TSM-aware application
- use TSM documents
- pass events, menu items, and cursor control to text service components
- confirm active input in TSM documents that use input methods
- provide text services to the user
- request a floating input window instead of inline input
- associate scripts and languages with text service components

Initializing and Closing as a TSM-Aware Application

If your client application uses any of the application-level Text Services Manager routines, call the InitTSMAwareApplication function immediately after you have called the other Toolbox initialization routines.

The Text Services Manager needs to perform some housekeeping when your client application is closed. To expedite this process, call the CloseTSMAwareApplication function when you quit.

InitTSMAwareApplication

The InitTSMAwareApplication function informs the Text Services Manager that your application is TSM-aware.

FUNCTION InitTSMAwareApplication: OSErr;

DESCRIPTION

The Text Services Manager notes that your application is TSM-aware by allocating the necessary data in its internal data structures.

RESULT CODES

noErr No error memFullErr Insufficier

memFullErr Insufficient memory to initialize tsmAlreadyRegisteredErr Application is already TSM-initialized tsmNotAnAppErr The caller is not an application

SEE ALSO

For sample code that uses the InitTSMAwareApplication function, see Listing 7-1 on page 7-18.

CloseTSMAwareApplication

The CloseTSMAwareApplication function informs the Text Services Manager that you have closed your application.

FUNCTION CloseTSMAwareApplication: OSErr;

DESCRIPTION

The Text Services Manager performs necessary housekeeping when your application closes.

Before you call the CloseTSMAwareApplication function, be sure that your application disposes of all open TSM documents by calling the DeleteTSMDocument function (see page 7-53).

RESULT CODES

noErr No error

tsmNeverRegisteredErr Application was never TSM-initialized

SEE ALSO

For sample code that uses the CloseTSMAwareApplication function, see Listing 7-6 on page 7-24.

Creating and Activating TSM Documents

This section describes the functions that let you create, activate, deactivate, and dispose of a TSM document (for details on the contents of a TSM document, see the section "Creating a TSM Document" on page 7-18).

NewTSMDocument

The NewTSMDocument function creates a TSM document and returns a handle to the document's ID.

FUNCTION NewTSMDocument (numOfInterface: Integer;

VAR supportedInterfaceTypes:

InterfaceTypeList;

VAR idocID: TSMDocumentID;
refCon: LongInt): OSErr;

numOfInterface

The number of supported text service interface types. Currently, this number must be 1.

supportedInterfaceTypes

A list of supported interface types. This list helps the Text Services Manager to locate the text services that have the correct interface type. Currently, the Text Services Manager has defined one interface type: kTextService (= 'tsvc'). The data type InterfaceTypeList is a

simple array of 4-character (OSType) tags.

idocID Upon successful completion of the call, contains the document

identification number of the TSM document created.

refCon A reference constant to store in the TSM document record. It may have

any value you wish.

DESCRIPTION

Each time your client application calls the NewTSMDocument function, the Text Services Manager creates an internal record called a TSM document and returns its ID.

If the call is successful, NewTSMDocument opens the default input method text service component of the current keyboard script and assigns it to this document. If NewTSMDocument returns tsmScriptHasNoIMErr, it has still created a valid TSM document, but has not associated an input method with it.

If NewTSMDocument fails to create a new TSM document, it returns an error and sets idocID to NIL.

RESULT CODES

noErr No e memFullErr Insu tsmUnsupportedTypeErr Supp tsmNeverRegisteredErr App

tsmNeverRegisteredErr tsmScriptHasNoIMErr tsmCantOpenComponentErr No error

Insufficient memory to open document Supported type was not 'tsvc' Application is not TSM-aware

Current script does not use input methods Cannot open default input of current script

SEE ALSO

For sample code that uses the NewTSMDocument function, see Listing 7-2 on page 7-19.

ActivateTSMDocument

The ActivateTSMDocument function instructs the Text Services Manager to mark the TSM document associated with a newly active window as active.

FUNCTION ActivateTSMDocument (idocID: TSMDocumentID): OSErr;

idocID A TSM document identification number created by a prior call to the

NewTSMDocument function (see page 7-50).

DESCRIPTION

When a window that has an associated TSM document becomes active, your client application must call the ActivateTSMDocument function to inform the Text Services Manager that the document is activated and is ready to use text service components.

ActivateTSMDocument calls the equivalent text service component routine ActivateTextService (see page 7-85) for all open text service components associated with the TSM document.

If a text service component has a menu, the Text Services Manager inserts the menu into the menu bar.

RESULT CODES

noerr No error

tsmInvalidDocIDErr Document is not a valid TSM document

SEE ALSO

For sample code that uses the ActivateTSMDocument function, see Listing 7-3 on page 7-21.

DeactivateTSMDocument

The DeactivateTSMDocument function instructs the Text Services Manager to mark the TSM document as inactive.

FUNCTION DeactivateTSMDocument (idocID: TSMDocumentID): OSErr;

idocID A TSM document identification number created by a prior call to the NewTSMDocument function (see page 7-50).

DESCRIPTION

The DeactivateTSMDocument function lets you inform the Text Services Manager that a TSM document in your client application is no longer active and must temporarily stop using text service components.

The Text Services Manager calls the equivalent text service component function DeactivateTextService (see page 7-85) for any text service component associated with the TSM document being deactivated.

IMPORTANT

Once your application is initialized as a TSM-aware application, at least one TSM document must always be active when your application is active. If a situation arises in which you are a TSM-aware application but all of your TSM documents are inactive, any text service component that has a menu or palette windows will be unable to communicate with the user. The best policy is to always create a TSM document, even if only a dummy document, immediately after initializing as a TSM-aware application. \blacktriangle

RESULT CODES

noerr No error

tsmInvalidDocIDErr Document is not a valid TSM document

SEE ALSO

For sample code that uses the DeactivateTSMDocument function, see Listing 7-3 on page 7-21.

DeleteTSMDocument

The DeleteTSMDocument function closes all opened text service components for the TSM document.

FUNCTION DeleteTSMDocument (idocID: TSMDocumentID): OSErr;

idocID A TSM document identification number created by a prior call to the

NewTSMDocument function (see page 7-50).

DESCRIPTION

When your application disposes of a TSM document, it must call the DeleteTSMDocument function to inform the Text Services Manager that the document is no longer using text service components. DeleteTSMDocument invokes the Component Manager CloseComponent function for each open text service component associated with this document. It also disposes of the internal data structure for the TSM document.

RESULT CODES

noErr No error

tsmInvalidDocIDErr Document is not a valid TSM document

tsmNeverRegisteredErr Application is not TSM-aware

Passing Events to Text Service Components

This section describes a function that lets you instruct the Text Services Manager to pass certain events to the appropriate text service component.

TSMEvent

The TSMEvent function passes all events obtained from the WaitNextEvent function, including null events, to the Text Services Manager.

```
FUNCTION TSMEvent (VAR event: EventRecord): Boolean;
```

event The event record for the event that has been obtained from

WaitNextEvent.

DESCRIPTION

Your client application regularly obtains events such as key-down events from the Toolbox Event Manager function WaitNextEvent. Some of these events may need to be handled by text service components. The TSMEvent function lets you pass those events to the Text Services Manager. The Text Services Manager dispatches the passed events to the appropriate text service components by calling the TextServiceEvent function for each component (see page 7-87).

If TSMEvent returns FALSE, you need to process the event as you normally do. If TSMEvent returns TRUE, the event has been handled by a text service component and is now a null event. You should process the null event as you normally do.

Note

The way the Text Services Manager uses and dispatches Apple events creates the potential for a reentrance situation that your client application should know about and be prepared to handle. When your application calls TSMEvent, the Text Services Manager uses the Apple Event Manager function AESend to pass data to your application through an Apple event. Your Apple event handler is thus invoked before the TSMEvent trap has returned. •

SEE ALSO

The WaitNextEvent function is described in the Event Manager chapter of *Inside Macintosh: Macintosh Toolbox Essentials.*

For sample code that uses the TSMEvent function, see Listing 7-4 on page 7-22.

Passing Menu Selections and Cursor Setting

This section describes two functions, TSMMenuSelect and SetTSMCursor, that let you instruct the Text Services Manager to pass menu commands and cursor control to the appropriate text service component.

TSMMenuSelect

The TSMMenuSelect function gives the specified text service component a chance to reply to a menu selection.

```
FUNCTION TSMMenuSelect (menuResult: LongInt): Boolean;
menuResult
```

The result from the Menu Manager MenuSelect function.

DESCRIPTION

When the user chooses a menu item, the item may belong to a text service component's menu. To provide an opportunity for the text service component to reply to its menu selections, your application should call TSMMenuSelect with the result from the Menu Manager MenuSelect function.

TSMMenuSelect returns FALSE if a text service component did not handle the menu selection. In this case, your client application should process the menu selection normally. TSMMenuSelect returns TRUE when a text service component handled the menu selection. In this case, you should take no action.

After TSMMenuSelect returns, your application should—as usual—call the Menu Manager function HiliteMenu with the menuID parameter set to 0 to remove the highlighting from the menu title.

SEE ALSO

The Menu Manager is described in *Inside Macintosh: Macintosh Toolbox Essentials*.

SetTSMCursor

The SetTSMCursor function provides an opportunity for the text service component to set the shape of the cursor. If the text service component does not respond, your application may set the cursor.

```
FUNCTION SetTSMCursor (mousePos: Point): Boolean;
```

mousePos

A QuickDraw point indicating the position (in global coordinates) of the cursor in your application.

DESCRIPTION

Your client application is responsible for setting the cursor to an appropriate shape as it passes over your various user interface elements. It is also necessary to provide an opportunity for a text service component to set the cursor over its own user interface elements. The SettsmCursor function allows the text service component to control the shape of the cursor if appropriate.

Call SetTSMCursor whenever you would normally call the QuickDraw SetCursor procedure. When SetTSMCursor returns TRUE, the cursor is positioned in a text service component window or in the active input area and it has been set by a text service component. Your client application should not set the cursor in this case. When SetTSMCursor returns FALSE, the cursor has not been set, and your client application may set it.

SetTSMCursor calls the equivalent text service component function
SetTextServiceCursor (page 7-88) for each open text service component to
provide an opportunity for each one to set shape of the cursor. If a text service
component actually changes the shape of the cursor, the Text Services Manager does not
call SetTextServiceCursor for the rest of the text service components and returns
TRUE. If none of the text service components sets the cursor, then SetTSMCursor
returns FALSE.

SEE ALSO

The SetCursor procedure is described in the QuickDraw chapters of *Inside Macintosh: Imaging*.

Confirming Active Input in a TSM Document

This section describes the FixTSMDocument function, which allows you to explicitly confirm text in the active input area.

FixTSMDocument

The FixTSMDocument function informs the Text Services Manager that input in the active input area of a specified TSM document has been interrupted, and that the text service component must confirm the text and terminate user input.

FUNCTION FixTSMDocument (idocID: TSMDocumentID): OSErr;

idocID The identification number of a TSM document created by a prior call to the NewTSMDocument function (see page 7-50).

DESCRIPTION

Typically, an inline input text service component removes confirmed input from the active input area each time the user presses the Return key, and passes the confirmed text to your application through an Apple event.

In certain situations, however, your client application may need to inform the text service component that there has been an interruption in user input for a specific TSM document. In this case you call the FixTSMDocument function to give the input method text service component the opportunity to confirm any input in progress.

For instance, if the user clicks in the close box of the window in which active input is taking place, call FixTSMDocument before you close the window. The text service component will pass you the current contents (both converted and unconverted) of the active input area as confirmed text.

For simple activating and deactivating of your application's window, it is not necessary to confirm the text in the active inline area. The input method saves the text and restores it when your window is reactivated.

RESULT CODES

noErr No error

tsmInvalidDocIDErr The document is not a valid TSM document

tsmDocNotActiveErr The TSM document is not active tsmTSNotOpenErr The default input method is not open

SEE ALSO

For sample code that uses the FixTSMDocument function, see Listing 7-5 on page 7-23.

Making Text Services Available to the User

This section describes functions that let you provide ways for the user to choose, open, and close text service components that are not input methods.

Your client application is responsible for providing a way—usually a menu—for the user to choose from among all available text service components. To get a list of available text service components to display in a menu, call the <code>GetServiceList</code> function. Be sure to filter out input methods, because the Keyboard menu already displays them.

When the user chooses a text service component that is not an input method, call the OpenTextService function to add the text service component to the TSM document. The OpenTextService and CloseTextService functions let you inform the Text Services Manager that a user of your client application has chosen to open or close a text service component. The Text Services Manager then opens or closes the component and associates it with a TSM document or ends the association as appropriate.

GetServiceList

The GetServiceList function obtains a complete list of text service components of a given kind available to the user of your client application.

FUNCTION GetServiceList (numOfInterfaceTypes: Integer;
supportedInterfaceTypes:
InterfaceTypeList;
VAR serviceInfo: TextServiceListHandle;
VAR seedValue: LongInt): OSErr;

numOfInterfaceTypes

The number of interface types supported by your client application.

supportedInterfaceTypes

A list of the interface types supported by your client application. The data type InterfaceTypeList is a simple list of 4-character (OSType) tags.

serviceInfo

A handle to the text service component list data structure. If the handle is NIL, the Text Services Manager allocates the handle; otherwise, it assumes the handle is a valid text service component list handle, as defined by the TextServiceListHandle data type.

seedValue

A value that indicates whether the list of text service components returned by GetServiceList may have been modified. This value is returned in this parameter after the Text Services Manager calls the Component Manager GetComponentListModSeed function.

DESCRIPTION

When your client application calls GetServiceList, the Text Services Manager locates all the text service components that support the specified interface and text service component types and creates a text service component list, defined by the TextServiceList data type, that contains an entry for each of the text service components.

It is possible to register text service components or withdraw them from registration at any time. Once it has compiled a list of text services, the Text Services Manager invokes the GetComponentListModSeed function and returns the value in the modseed parameter. You can save that value and, the next time you need to draw or regenerate the list of services, call the Component Manager GetComponentListModSeed function. If the seed value differs from the one you received from your last call to GetServiceList, you need to call GetServiceList once more to update the information. Alternatively, you can simply call GetServiceList each time you need to update the list, although that may be less efficient.

GetServiceList uses the text service component information record, defined by the TextServiceInfo data type, and the text service component list record, defined by the TextServiceList data type.

```
TYPE TextServiceInfo =
   RECORD
      fComponent: Component;
   fItemName: Str255;
END;
TextServicesInfoPtr = ^TextServiceInfo;
```

Field descriptions

fComponent A component identifier for this text service component. You can use

the component identifier in Text Services Manager functions that open or obtain information about a text service component.

itemName A Pascal string with the name of a text service component. (The

script system to use for displaying the string is specified in the componentFlags field of the component description record. See

page 7-15.)

TYPE TextServiceList = RECORD

fTextServiceCount: Integer;

fServices: ARRAY[0..0] of TextServiceInfo;

END;

TextServiceListPtr = ^TextServiceList;

TextServiceListHandle = ^TextServiceListPtr;

Field descriptions

fTextServiceCount

An integer that provides the number of text service components in

the text service component list.

fServices A variable-length array of text service component information

records.

RESULT CODES

noErr No error

memFullErr Insufficient memory

tsmUnsupportedTypeErr Supported type was not 'tsvc'

OpenTextService

The OpenTextService function instructs the Text Services Manager to open a text service component that a user has chosen and to associate it with a TSM document.

idocID The identification number of a TSM document created by a prior call to the NewTSMDocument function (see page 7-50).

aComponent

A component identifier for this text service component.

aComponentInstance

Upon completion of the call, contains a component instance. This value identifies your application's connection to a text service component. You must supply this value whenever you call the text service functions provided by the component directly.

DESCRIPTION

You can obtain the component identifier to pass in aComponent by comparing the menu item name selected by the user with the component item names in the TextServiceList record obtained by calling GetServiceList.

The Text Services Manager opens the requested component by calling the Component Manager OpenComponent function.

If the specified text service component is already open, the Text Services Manager does not open it again and the tsmComponentAlreadyOpenErr error message is returned as a result code. Whether or not the text service is open, the Text Services Manager calls the functions InitiateTextService (see page 7-84) and ActivateTextService (see page 7-85) for the given text service and returns a valid component instance. Upon completion of the OpenTextService call, the selected text service component is initialized and active.

Note

This function is for opening text service components other than input methods. Your application does not need to open or close input methods. ◆

RESULT CODES

noErr tsmInvalidDocIDErr tsmComponentAlreadyOpenErr tsmCantOpenComponentErr No error
The document is not a valid TSM document
Component is already open for this document

Component is already open for this document Component doesn't exist or won't open

CloseTextService

The CloseTextService function deactivates the active TSM document's association with the specified text service and closes the service component.

idocID The identification number of a TSM document created by a prior call to the NewTSMDocument function (see page 7-50).

aComponentInstance

The component instance created by a prior call to OpenTextService.

DESCRIPTION

When a user wants to close an opened text service component, your client application should call CloseTextService.

If the text service component displays a menu, the Text Services Manager removes the menu from the menu bar.

Note

This function is for closing text service components other than input methods. Your application does not need to open or close input methods. ◆

RESULT CODES

noErr No error

tsmInvalidDocIDErr The document is not a valid TSM document tsmNoOpenTSErr The component for this document is not open

Requesting a Floating Input Window

In certain situations, bottomline input with a floating input window is preferable to inline input for text input users. The Text Services Manager provides two ways to control how the floating input window is used: with a single specified TSM document or with all documents of a given application.

UseInputWindow

The UseInputWindow function associates a floating input window with a particular TSM document or with all TSM documents of an application.

FUNCTION UseInputWindow (idocID: TSMDocumentID;

useWindow: Boolean): OSErr;

idocID The TSM document ID of the particular TSM document to be associated

with the floating input window. If NIL, this call affects all your

application's TSM documents.

useWindow A Boolean value that indicates whether to use the floating input window.

Set it to TRUE if you want to use a floating window; set it to FALSE if you

do not want to use a floating window.

DESCRIPTION

The Text Services Manager provides a floating input window for your application's use if you call UseInputWindow with a value of TRUE in the useWindow parameter. To specify inline input instead, call UseInputWindow with a value of FALSE in the useWindow parameter.

The default value for useWindow is FALSE; if you do not call UseInputWindow, the Text Services Manager assumes that your application wants to use inline input. If your application wants to save the user's choice, it can put the last-used value for useWindow in a preferences file before quitting.

If you pass a valid TSM document ID for the idocID parameter, the useWindow parameter affects only that TSM document. If you pass NIL for the idocID parameter, the useWindow parameter affects all your application's TSM documents, including documents you create after making this call.

RESULT CODES

noErr No error

tsmInvalidDocIDErr The document is not a valid TSM document

tsmNeverRegisteredErr Application is not TSM-aware

Associating Scripts and Languages With Components

The utility routines described in this section allow you to

- assign a particular text service component as the default component to be associated with a given script system and language
- determine which text service component is the default component associated with a given script system and language

- determine the script system and language combination for the currently active text service component
- assign a script system and language combination to the currently active text service component

In addition to these routines, you can use the text service component function GetScriptLanguageSupport (described on page 7-90) to determine which additional scripts and languages a text service component supports.

These routines make use of the script-language record, described under "Identifying the Supported Scripts and Languages" on page 7-42.

SetDefaultInputMethod

The operating system uses the SetDefaultInputMethod function to assign a default (input method) text service component to a given script and language.

FUNCTION SetDefaultInputMethod (ts: Component;

VAR slRecord: ScriptLanguageRecord):

OSErr;

ts The component identifier of the input method text service component to

be associated with the script and language combination given in the

slRecord parameter.

slRecord A script-language record that describes the script and language

combination to be associated with the input method text service

component specified in the ts parameter.

DESCRIPTION

The operating system uses SetDefaultInputMethod to associate an input method text service component with a given script and language. The operating system calls this function when the user expresses input method preferences through the Keyboard menu, Keyboard control panel, or other device. The associations made with this function are permanent; that is, they persist after restart.

If the script code and language code specified in the script-language record are incompatible, SetDefaultInputMethod returns the error parametr.

RESULT CODES

noErr No error

paramErr The script does not match the language tsmScriptHasNoIMErr Current script does not use input methods tsmCantOpenComponentErr Cannot open default input of current script

GetDefaultInputMethod

The GetDefaultInputMethod function returns the default (input method) text service component for a given script and language.

FUNCTION GetDefaultInputMethod (VAR ts: Component;

VAR slRecord: ScriptLanguageRecord):

OSErr;

ts The component identifier of the input method text service component

that is associated with the script and language combination given in the

slRecord parameter.

slRecord A script-language record that describes the script and language

combination that is associated with the input method text service

specified in the ts parameter.

DESCRIPTION

The operating system uses GetDefaultInputMethod to find out which input method to activate when the user selects a new keyboard script from the Keyboard menu or by Command-key combination, or when an application calls KeyScript to change keyboard scripts.

In versions of Japanese system software starting with KanjiTalk 7.0, if the default input method is an old (pre-KanjiTalk 7.0) non-TSM-aware method,

GetDefaultInputMethod returns the error tsmInputMethodIsOldErr. In that case the ts parameter contains the script code of the old input method in its high-order word, and the reference ID of the old input method in its low-order word.

RESULT CODES

noerr No error

paramErr The script does not match the language tsmScriptHasNoIMErr The script does not use input methods tsmInputMethodIsOldErr The default input method is old-style

SetTextServiceLanguage

The SetTextServiceLanguage function changes the current input script and language.

FUNCTION SetTextServiceLanguage (VAR slRecord:

ScriptLanguageRecord): OSErr;

slRecord A script-language record for the current text service component.

DESCRIPTION

The operating system calls this Text Services Manager function when the user switches the keyboard script, so that the Text Services Manager can synchronize the input method with the current keyboard script.

RESULT CODES

noErr No error

paramErr The script does not match the language tsmCantOpenComponentErr Cannot open default input of the script

GetTextServiceLanguage

The GetTextServiceLanguage function returns the language supported by the default (current) input method text service component for the current keyboard script.

FUNCTION GetTextServiceLanguage (VAR slRecord:

ScriptLanguageRecord): OSErr;

slRecord A script-language record that, upon completion of the call, describes the

language supported by the current text service component.

RESULT CODES

noErr No error

Apple Event Handlers Supplied by Client Applications

This section describes the Apple events for which client applications must install handlers. Text service components request action from and send information to client applications through these Apple events.

Your application uses these Apple events to receive text from text service components, to show or hide input windows, and to convert screen positions to text offsets—and vice versa—for text service components. The conversion operations are used to track mouse events and determine screen locations of text in the active input area.

The Apple events described in this section are all organized under the kTextServiceClass constant with a value of 'tsvc'.

lists the Apple event ID constants for the Apple events described in this section.

Table 7-1 Apple event ID constants

Constant	Value	Explanation
kUpdateActiveInputArea	'updt'	Update Active Input Area
kPos2Offset	'p2st'	Position To Offset
kOffset2Pos	'st2p'	Offset To Position
kShowHideInputWindow	'shiw'	Show/Hide Input Window

Table 7-2 shows the Apple event keyword constants used in the Apple events described in this section.

 Table 7-2
 Apple event keyword constants

/ ppic over new constants		
Constant	Value	Meaning
keyAETSMDocumentRefcon	'refc'	TSM document reference constant
keyAEServerInstance	'srvi'	Component instance
keyAETheData	'kdat'	Text from active input area
keyAEScriptTag	'sclg'	Script-language record
keyAEFixLength	'fixl'	Length of confirmed text
keyAEHiliteRange	'hrng'	Highlight range in text
keyAEUpdateRange	'udng'	Update range in text
keyAEClauseOffsets	'clau'	Clause offsets array
keyAECurrentPoint	'cpos'	Current point
keyAEDragging	'bool'	Dragging flag
keyAEOffset	'ofst'	Byte offset in text
keyAERegionClass	'rgnc'	Region class
keyAEPoint	'gpos'	Calculated point
optional keyword for Update Active	optional keyword for Update Active Input Area	
keyAEPinRange	'pnrg'	Range for scrolling
optional keywords for Offset To Pos	optional keywords for Offset To Position	
keyAETextFont	'ktxf'	Text font
keyAETextPointSize	'ktps'	Text size
keyAETextLineHeight	'ktlh'	Text line height
keyAETextLineAscent	'ktas'	Font ascent

Table 7-2 Apple event keyword constants (continued)

Constant	Value	Meaning
keyAEAngle	'kang'	Text angle
optional keyword for Position To Offse	et	
keyAELeadingEdge	'klef'	Leading-edge Boolean

Table 7-3 lists the Apple event descriptor types discussed in this section.

 Table 7-3
 Apple event descriptor types

Constant	Value	Meaning
typeComponentInstance	'cmpi'	Server instance
typeTextRangeArray	'tray'	Text range array
typeOffsetArray	'ofay'	Offset array
typeIntlWritingCode	'intl'	Script-language record
typeQDPoint	'QDpt'	QuickDraw point
typeAEText	'tTXT'	Apple event text
typeText	'TEXT'	Plain text
typeTextRange	'txrn'	A text range record
typeTSMDocumentRefcon	'refc'	TSM document reference constant
typeFixed	'fixd'	Fixed 16.16 format

Table 7-4 lists the Apple event descriptor type constants for region class discussed in this section.

Table 7-4 Apple event descriptor type constants for the Apple event region class

Constant	Value
kTSMOutsideOfBody	1
kTSMInsideOfBody	2
kTSMInsideOfActiveInputArea	3

For the values of standard Apple event constants used in the following section not listed in these tables, see the *Apple Event Registry: Standard Suites*.

Creating and Updating an Active Input Area

The text service component uses the Update Active Input Area Apple event to request that your client application create and update an active input area, and accept confirmed text. For details on active input areas, see "Inline Input" on page 7-11.

Update Active Input Area—Creating and Updating an Active Input Area

Event class kTextServiceClass

Event ID kUpdateActiveInputArea

Requested action Update a range of text. Specify any necessary highlighting with

offsets in the optional keyAEHiliteRange parameter.

Required parameters

Keyword: keyAETSMDocumentRefcon

Descriptor type: typeLongInteger

Data: A TSM document specifier (reference constant) supplied by the

application in a prior call to the NewTSMDocument function (see page 7-50). This value is associated with the TSM document

whose active input area is to be updated.

Keyword: keyAEServerInstance
Descriptor type: typeComponentInstance

Data: A component instance value created by a prior call to the

Component Manager OpenComponent function. This value

identifies the text service component.

Keyword: keyAETheData

Descriptor type: typeChar

Data: Text data that has been processed in some way by a text service

component.

Keyword: keyAEScriptTag

Descriptor type: typeIntlWritingCode

Data: The script code and language code associated with the text

returned in the keyAETheData parameter. The information is passed in a script-language record, as defined on page 7-42.

Update Active Input Area—Creating and Updating an Active Input Area (continued)

Required parameters

Keyword: keyAEFixLength
Descriptor type: typeLongInteger

Data: The length of the confirmed text in the active inline area.

If the value of keyAEFixLength is -1, the text contained in the keyAETheData parameter is to completely replace the current selection in the application window. In this case, there is to be no active input area, the text is all considered to be confirmed, and is to be made part of the body text of the client application.

If the value is 0, an active input area is in process, but there is no completely confirmed text being sent.

If the value is greater than 0, the text specified in the keyAETheData parameter up to the indicated offset is confirmed data and should be consumed by the application. The

Text Services Manager considers any text beyond the offset specified by the keyAEFixLength parameter to be inside the active input area with the starting point of the active input area at

that offset. This is illustrated in Figure 7-11.

Figure 7-11 Updating text in an active input area

Τηε ωινε δαρκ σεα

keyAEFixLength = -1 (no conversion needed)

The wine dark sea

keyAEFixLength = 0 (no confirmed text)

Τηε wine dark sea

keyAEFixLength = 5 (first 5 characters are confirmed)

Update Active Input Area—Creating and Updating an Active Input Area (continued)

Optional parameters

Keyword: keyAEHiliteRange
Descriptor type: typeTextRangeArray

Data: An array that specifies the ranges of text to be highlighted in

the active input area. It also specifies caret position. There are

5 types of highlighting:

Constant Applies to

kCaretPosition The caret position only
kRawText All of the unconverted text
kSelectedRawText Part of the unconverted text
kConvertedText All of the converted text
kSelectedConvertedText Part of the converted text

For instance, the input method may have the application highlight all raw text with a gray underline; but if it needs to further highlight a selection within that raw text, it may specify a different underline for the selected raw text. The text range array is an array of

text-range records, each of which has this form:

```
TYPE TextRange =
  RECORD
  fStart: LongInt;
  fEnd: LongInt;
  fHiliteStyle: Integer;
  END;
```

For the text-range record whose highlight style is

kCaretPosition, both fStart and fEnd are the same and denote the position of the caret.

Negative values for a text range mean that the specified range only adds to, rather than replaces, any current highlighting for the specified type of text.

Update Active Input Area—Creating and Updating an Active Input Area (continued)

Optional parameters

Keyword: keyAEUpdateRange
Descriptor type: typeTextRangeArray

Data: An array of text-range records that indicates the update range of the

active input area (in many circumstances, not all of the active input area needs updating). Update Active Input Area always uses the text-range records in the text range array in pairs. The first record (0) specifies a range of old text (text in the inline buffer) to be updated; the second record (1) specifies the range of text in keyAETheData that is to replace that old text. In general, the record n ($n \ge 0$, n is an even number) specifies the range of old text to be updated and the

record n + 1 specifies the range of new text to replace the corresponding old text. (The fHiliteStyle field is ignored.)

Keyword: keyAEPinRange
Descriptor type: typeTextRange

Data: A text range record that specifies a start offset and and an end offset

that should be scrolled into view if the text specified by these offsets

is not already in view. (The fHiliteStyle field is ignored.)

Keyword: keyAEClauseOffsets
Descriptor type: typeOffsetArray

Data: An offset array (defined by the OffsetArray data type) that

specifies offsets of word or clause boundaries of the new text. Offsets are from the start of the active input area. Applications can

use this information for word selection or other purposes.

TYPE OffsetArray =
 RECORD

fNumOfOffsets: Integer;

fOffset: ARRAY[0..0] of LongInt;

END;

The numOfOffsets field contains an integer that specifies the number of offsets in the offset array. The fOffset field is an array

of long integers with the number of entries specified in the

numOfOffsets field.

Return parameter

Keyword: keyErrorNumber

Descriptor type: typeShortInteger

Data: Any errors that the application needs to return to the text service

component. The application must pass Memory Manager, TextEdit, or other errors that it receives through to the component; otherwise,

it should pass 0 (noErr).

The text range array data structure used in the keyAEHiliteRange and keyAEUpadateRange parameters described above is defined by the TextRangeArray data type:

```
TYPE TextRangeArray =
   RECORD
      fNumOfRanges: Integer;
      fRange: ARRAY[0..0] of TextRange;
END;
```

The fNumOfRanges field contains an integer that indicates how many text ranges this array holds. The fRange field contains a series of text-range records. (If the array consists of more than one text-range record, the size of the array must be calculated as fNumOfRanges * SizeOf(fRange).)

For sample code that handles the Update Active Input Area Apple event, see Listing 7-7 on page 7-26.

Converting Global Coordinates to Text Offsets

The Position To Offset Apple event requests a client application to convert specified global coordinates to byte offsets in text. The text service component uses this Apple event for mouse tracking, in order to draw the caret, highlight text, or adjust the cursor appearance.

Position To Offset—Converting Global Coordinates to Text Offset

Event class kTextServiceClass

Event ID kPos2Offset

Requested action Convert global coordinates specified in the keyAECurrentPoint

parameter to a byte offset. If the click is within the limits of the active input area, the offset is relative to the start of the active input area. Otherwise, the offset is relative to the start of the application's body text. The client application specifies the classification of the location of the offset in the keyAERegionClass return parameter.

Required parameters

Keyword: keyAETSMDocumentRefcon

Descriptor type: typeLongInteger

Data: A TSM document specifier (reference constant) supplied by the

application in a prior call to the NewTSMDocument function (see page 7-50). This value is associated with the TSM document

affected by this event.

Position To Offset—Converting Global Coordinates to Text Offset (continued)

Required parameters

Keyword: keyAEServerInstance
Descriptor type: typeComponentInstance

Data: A component instance value created by a prior call to the

Component Manager OpenComponent function. This value

identifies the text service component.

Keyword: keyAECurrentPoint

Descriptor type: typePoint

Data: A point that contains the global coordinates that describe the

current mouse position.

Optional parameter

Keyword: keyAEdragging
Descriptor type: typeBoolean

Data: A Boolean value that indicates whether the input method is

currently tracking the mouse—that is, whether the user is dragging the current selection. If it is TRUE, the application should pin the cursor to the limits of the active input area (to avoid highlighting

beyond the limits of the active input area).

Return parameters

Keyword: keyAEOffset
Descriptor type: typeLongInteger

Data: A byte offset that specifies the character corresponding to the

current mouse position (keyAECurrentPoint). If the click is within the limits of the active input area, the offset is relative to the start of the active input area. Otherwise, the offset is relative to the

start of the application's body text.

Keyword: keyAERegionClass
Descriptor type: typeShortInteger

Data: The classification of the position specified in the keyAEOffset

parameter. Three constants define the classification:

Constant e
kTSMOutsideOfBody 1
kTSMInsideOfBody 2
kTSMInsideOfActiveInputArea 3

A value of kTSMOutsideOfBody means that the offset is

outside the application's body text. A value of

kTSMInsideOfBody means that the offset is inside the body text. kTSMInsideOfActiveInputArea means that the offset is inside

the active input area.

continued

Position To Offset—Converting Global Coordinates to Text Offset (continued)

Return parameters

Keyword: keyErrorNumber

Descriptor type: typeShortInteger

Data: Any errors that the application needs to return to the text service

component. The application must pass Memory Manager, TextEdit,

or other errors that it receives through to the component;

otherwise, it should pass 0 (noErr).

Optional return parameter

Keyword: keyAELeadingEdge

Descriptor type: typeBoolean

Data: A Boolean value that is equivalent to the leadingEdge parameter

of the QuickDraw PixelToChar function. It is TRUE if the specified point corresponds to the leading edge of the character whose offset is returned; it is FALSE if the specified point

corresponds to the trailing edge of the character.

For sample code that handles the Position To Offset Apple event, see Listing 7-8 on page 7-30.

Converting Text Offsets to Global Coordinates

The Offset To Position Apple event requests that a client application convert byte offsets in text to global coordinates. The text service component uses this Apple event to determine where in the active input area to draw an element (such as the caret or a palette of conversion choices) that relates to a particular character.

Offset To Position—Converting Text Offsets to Global Coordinates

Event class kTextServiceClass

Event ID kOffset2Pos

Requested action Convert a specified byte offset into global coordinates. The offset

value passed to the client application is relative to the start of the active input area. If there is no active input area, the offset is relative

to the start of the current text body.

Required parameters

Keyword: keyAETSMDocumentRefcon

Descriptor type: typeLongInteger

Data: A TSM document specifier (reference constant) supplied by the

application in a prior call to the NewTSMDocument function (see page 7-50). This value is associated with the TSM document

affected by this event.

Offset To Position—Converting Text Offsets to Global Coordinates (continued)

Required parameters

Keyword: keyAEServerInstance
Descriptor type: typeComponentInstance

Data: A component instance value returned by a prior call to the

Component Manager OpenComponent function. This value

identifies the text service component.

Keyword: keyAEOffset

Descriptor type: typeLongInteger

Data: The text offset to be converted into a global point. Offset is in terms

of bytes from the start of the active input area.

Return parameters

Keyword: keyAEPoint
Descriptor type: typePoint

Data: A point that contains the global coordinates obtained by converting

the byte offset passed in the keyAEOffset parameter.

Keyword: keyErrorNumber

Descriptor type: typeShortInteger

Data: errOffsetInvalid indicates that there is no text at the offset.

errOffsetIsOutsideOfView indicates that the text offset is out

of view.

The application must pass Memory Manager, TextEdit, or other errors that it receives through to the component; otherwise, it

should pass 0 (noErr).

Optional return parameters

Keyword: keyAETextFont
Descriptor type: typeLongInteger

Data: The font of the text in the active input area. The application can

send this information to the input method to help the input method

position the active input area.

Keyword: keyAETextPointSize

Descriptor type: typeFixed

Data: The size of the text in the active input area. The application can

send this information to the input method to help the input method

position the active input area.

Keyword: keyAETextLineHeight
Descriptor type: typeShortInteger

Data: The line height of the text in the active input area. The application

can send this information to the input method to help the input

method position the active input area.

continued

Offset To Position—Converting Text Offsets to Global Coordinates (continued)

Optional return parameters

Keyword: keyAETextLineAscent
Descriptor type: typeShortInteger

Data: The ascent height of the text in the active input area. The

application can send this information to the input method to help

the input method position the active input area.

Keyword: keyAEAngle
Descriptor type: typeFixed

Data: The orientation of the text in the active input area. The value 90

specifies a horizontal line direction and 180 specifies a vertical line direction. The application can send this information to the input method to help the input method position the active input area.

For sample code that handles the Offset To Position Apple event, see Listing 7-9 on page 7-33.

Showing or Hiding the Floating Input Window

Input methods that supply floating input windows for bottomline input may need to show or hide the input window at various times. The Show/Hide Input Window Apple event requests the client application to make the floating input window either visible or not visible, so that an input method can offer any of the above options.

Note

If your application is not displaying its own floating input window, you can ignore this Apple event. ◆

Show/Hide Input Window—Showing or Hiding the Floating Input Window

Event class kTextServiceClass
Event ID kShowHideInputWindow

Requested action Make the bottomline floating input window either visible or not

visible, depending on the value of the keyAEShowHideInputWindow parameter.

Required parameters

Keyword: keyAETSMDocumentRefcon

Descriptor type: typeLongInteger

Data: A TSM document specifier (reference constant) supplied by the

application in a prior call to the NewTSMDocument function (see page 7-50). This value is associated with the TSM document for the

window being shown or hidden.

Keyword: keyAEServerInstance
Descriptor type: typeComponentInstance

Show/Hide Input Window—Showing or Hiding the Floating Input Window (continued)

Data: A component instance value returned by a prior call to the

Component Manager OpenComponent function. This value

identifies the text service component.

Optional parameter

Keyword: keyAEShowHideInputWindow

Descriptor type: typeBoolean

Data: If TRUE, the bottomline input window should be shown; if FALSE, it

should be hidden. This parameter is not needed if the input method

is simply inquiring about the state of the input window.

Return parameter

Keyword: keyAEShowHideInputWindow

Descriptor type: typeBoolean

Data: The current state of the input window: TRUE if the window is

shown; FALSE if it is hidden. If the optional parameter

keyAEShowHideInputWindow is included, this return parameter should show the state of the window *before* it was set to the state

requested in the optional parameter.

Text Services Manager Routines for Components

This section describes the Text Services Manager component interface—the routines and related data structures that are for the use of text service components. These functions let your text service component

- send Apple events to a client application to request specific information about the active input area in a TSM document
- put up a floating window for various purposes

Sending Apple Events to a Client Application

This section describes the SendAEFromTSMComponent function, with which your text service component sends Apple events to a client application.

SendAEFromTSMComponent

The SendAEFromTSMComponent function sends Apple events from a text service component to a client application.

FUNCTION SendAEFromTSMComponent (VAR theAppleEvent: AppleEvent;

VAR reply: AppleEvent;
sendMode: AESendMode;

sendPriority: AESendPriority;
timeOutInTicks: LongInt;

idleProc: IdleProcPtr;

filterProc: EventFilterProcPtr):

OSErr;

theAppleEvent

The Apple event to be sent.

reply The reply Apple event returned by SendAEFromTSMComponent.

sendMode The value that lets you specify one of the following modes specified by

corresponding constants: the reply mode for the Apple event, the interaction level, the application switch mode, the reconnection mode, and the return receipt mode. To obtain the value for this parameter, add the appropriate constants. Comprehensive details about these constants are provided in the description of the Apple Event Manager AESend

function in *Inside Macintosh*: *Interapplication Communication*.

sendPriority

The value that specifies whether to put the Apple event at the back of the event queue (set with the kAENormalPriority flag) or at the front of the queue (kAEHighPriority flag).

timeOutInTicks

The length of time (in ticks) that the client application is willing to wait for the reply or return receipt from the server application before it times out. If the value of this parameter is kNoTimeOut, the Apple event never times out.

idleProc

A pointer to a function for any tasks (such as displaying a globe, a wristwatch, or a spinning beach ball cursor) that the application performs while waiting for a reply or a return receipt.

filterProc

A pointer to a routine that accepts certain incoming Apple events that are received while the handler waits for a reply or a return receipt and filters out the rest.

DESCRIPTION

The SendAEFromTSMComponent function is essentially a wrapper routine for the Apple Event Manager function AESend. See the description of AESend for additional necessary information, including constants for the sendMode parameter and result codes.

SendAEFromTSMComponent identifies your text service component from the keyAEServerInstance parameter in the Apple event specified in the theAppleEvent parameter. If a reference constant (refcon) in a TSM document that corresponds to this parameter is found in the internal data structures of the Text Services Manager, SendAEFromTSMComponent adds the reference constant as the keyAETSMDocumentRefcon parameter to the given Apple event before sending it to the application.

If the client application is not TSM-aware, SendAEFromTSMComponent routes the Apple events to the floating input window to allow bottomline input.

IMPORTANT

If your text service component changes the environment in any way—such as by modifying the A5 world or changing the current zone—while constructing an Apple event, it must restore the previous settings before sending the Apple event. ▲

Note

Your text service component should always use the kCurrentProcess constant as the target address when it creates an Apple event to send to the Text Services Manager. ◆

SEE ALSO

The AESend function is described with the Apple Event Manager in *Inside Macintosh: Interapplication Communication*.

The kCurrentProcess constant is described in *Inside Macintosh: Processes*.

For sample code showing how a text service component calls the SendAEFromTSMComponent function, see Listing 7-11 on page 7-45.

Opening Floating Utility Windows

In conjunction with the Process Manager, the Text Services Manager maintains the floating window service, whose windows occupy a special layer called the floating window service layer. See Figure 7-7 on page 7-14.

The Text Services Manager uses the floating window service to provide a standard floating input window when needed. Text service components can use the service to create, close, and find floating windows used for various other user-interface purposes. You can manipulate the service windows with these calls:

- The NewServiceWindow function lets you open a floating window in front of the current application.
- The CloseServiceWindow function lets you close a previously allocated floating window.
- The GetFrontServiceWindow function helps you find out which is the frontmost window in the floating window service layer.
- The FindServiceWindow function helps you find out which part of a text service component's floating window a mouse-down event has occurred in.

Client applications

These calls may be made by client applications also. See the following description of NewServiceWindow for special instructions for client applications. ◆

NewServiceWindow

The NewServiceWindow function opens a floating utility window in the floating window service layer, in front of the current application. The text service component may use the window for interaction with the user or other purposes.

FUNCTION NewServiceWindow (wStorage: Ptr; boundsRect: Rect;

title: Str255; visible: Boolean;
theProc: Integer; behind: WindowPtr;
goAwayFlag: Boolean;
ts: ComponentInstance;

VAR window: WindowPtr): OSErr;

wStorage A pointer to the location in memory of the window record. Do not

allocate the window record on the stack. Always be sure to allocate the

window in the heap, or else pass NIL for this parameter.

boundsRect

A rectangle given in global coordinates that determines the size and location of the new floating window. This rectangle becomes the portRect field of the graphics port record (defined by the QuickDraw

GrafPort data type) for this window.

title A Pascal string that contains the title of the window.

visible A Boolean value to determine whether the window is to be drawn. If

TRUE, NewServiceWindow draws the window. First it calls the window definition procedure defined in the theProc parameter to draw the window frame. Then it generates an update event for the entire window

contents.

the Proc The window definition procedure for the floating window.

behind A window pointer (defined by the Window Manager WindowPtr data

type) that determines the plane of the floating window.

NewServiceWindow inserts the new window behind the window pointed to by this parameter. To put the new window behind all other windows, use behind = NIL. To place it in front of all other windows,

use behind = POINTER(-1).

goAwayFlag

A Boolean value that determines whether the go-away region should be drawn in the window. If this parameter is TRUE and the window is frontmost (as specified by the behind parameter), NewServiceWindow

draws a go-away region in the frame.

A component instance returned by a prior call to the Component

Manager OpenComponent function. This value is stored in the refcon field of the window record; text service components should not change

the value of the window's refcon field.

Client applications

If you are a client application making this call, pass the Process Manager constant kCurrentProcess in this parameter so that events in the new window will be forwarded to you. After you have created the window, you can use its ref con field for private storage as usual. •

window A pointer to the newly allocated floating window.

DESCRIPTION

This function calls the Window Manager NewWindow function. If a floating window is successfully allocated, NewServiceWindow returns a pointer to that window as the function result. Otherwise, it returns NIL.

A text service component can open multiple windows in this layer. When a text service component receives an event, it determines whether the event belongs to one of its text service component windows by calling FindServiceWindow.

If you are an application that uses NewServiceWindow to open a floating window, be sure to hide the floating window when you are switched out; that is, when another application's windows become active.

Balloon Help

If you are writing a text service component and want the service window to have custom Balloon Help, place an 'hwin' resource (with references to 'hcrt' and 'STR#' resources) in your component resource fork, with a name equal to the window title. The Text Services Manager will then open the resources automatically when needed. If you are writing a client application, you need not follow anything other than normal procedures to have Balloon Help. •

RESULT CODES

noErr No error

memFullErr Insufficient memory to open the window

SEE ALSO

Window definition procedures and the NewWindow function are described in the Window Manager chapter of *Inside Macintosh: Macintosh Toolbox Essentials*.

Balloon Help is described in the Help Manager chapter of *Inside Macintosh: More Macintosh Toolbox*.

CloseServiceWindow

The CloseServiceWindow function closes a previously allocated floating input window.

FUNCTION CloseServiceWindow (window: WindowPtr): OSErr;

window A pointer to the service window to close. This function calls the Window

Manager CloseWindow procedure.

DESCRIPTION

If the window pointer is NIL or if it points to a non-floating window, CloseServiceWindow returns paramErr.

RESULT CODES

noErr No error paramErr Parameter error

SEE ALSO

The CloseWindow procedure is described in the Window Manager chapter of *Inside Macintosh: Macintosh Toolbox Essentials*.

GetFrontServiceWindow

The GetFrontServiceWindow function determines which is the frontmost window in the floating window service layer.

FUNCTION GetFrontServiceWindow (VAR window: WindowPtr): OSErr;

window A pointer to the frontmost window in the service layer.

DESCRIPTION

This function calls the Window Manager FrontWindow function. The GetFrontServiceWindow function returns a pointer to the frontmost window in the service layer. If there is no window in the service layer, it returns NIL.

SEE ALSO

The FrontWindow function is described in the Window Manager chapter of *Inside Macintosh: Macintosh Toolbox Essentials*.

FindServiceWindow

The FindServiceWindow function determines which part of a text service component's floating window a mouse-down event has occurred in.

```
FUNCTION FindServiceWindow (thePoint: Point;

VAR theWindow: WindowPtr): Integer;

thePoint The point where the mouse button was pressed (in global coordinates, as stored in the where field of the Event Manager event record).

theWindow A pointer to a Window Manager window pointer (defined by the WindowPtr data type) that identifies the floating window in which the mouse-down event occurred. If the mouse-down event did not occur in a text service component floating window, this parameter is set to NIL.
```

DESCRIPTION

The FindServiceWindow function is similar to the Window Manager FindWindow function, except that FindServiceWindow searches the floating window service layer only.

FindServiceWindow calls the Window Manager FindWindow function. It returns one of the following predefined constants to identify the location of the mouse-down event.

Constant	Value	Explanation
inDesk	0	None of the following
inMenuBar	1	In menu bar
inSysWindow	2	In system window
inContent	3	In content region (except grow, if active)
inDrag	4	In drag region
inGrow	5	In grow region (active window only)
inGoAway	6	In go-away region (active window only)
inZoomIn	7	In zoom-in region
inZoomOut	8	In zoom-out region

It the mouse position is not over a floating window, FindServiceWindow returns inDesk (0) as its function result, and sets the return parameter theWindow to NIL.

SEE ALSO

The FindWindow function is described in the Window Manager chapter of *Inside Macintosh: Macintosh Toolbox Essentials*.

Event records are described in the Event Manager chapter of *Inside Macintosh: Macintosh Toolbox Essentials*.

The Process Manager is described in *Inside Macintosh: Processes*.

Text Service Component Routines

This section describes the component-level routines and related data structures and constants through which the Text Services Manager communicates with text service components. The Text Services Manager uses the Component Manager to dispatch the text service component routines to specific text service components.

Client applications also may make the calls described in this section, but the Text Services Manager does not play a role in the connection between the client application making the call and the text service component receiving it. If you are an application making these calls, you need to know the component instance of the component whose routine you are calling.

If you are writing a text service component, it must implement routines for the calls described in this section. With these routines, your component

- provides a text service
- accepts events and updates its cursor and menu (if any)
- confirms active input when requested (if it is an input method)
- identifies the scripts and languages it supports

Providing a Text Service

This section describes the functions a text service component supports to initiate, activate, deactivate, and terminate a text service. The Text Services Manager makes these calls to components either on its own or in response to application-interface calls it receives from client applications.

InitiateTextService

The InitiateTextService function instructs a specified text service component to do whatever it needs to set up its operations and commence its performance.

A component instance created by a prior call to the Component Manager OpenComponent function.

DESCRIPTION

The Text Services Manager can call InitiateTextService to any component that it has already opened with the Component Manager OpenComponent or OpenDefaultComponent functions. Text service components should be prepared to handle InitiateTextService calls at any time.

Any text service component can receive multiple InitiateTextService calls. The Text Services Manager calls InitiateTextService each time the user adds a text service to a TSM document, even if the text service component has already been opened. This provides an opportunity for the component to restart or to display user interface elements that the user may have closed.

This function should return a ComponentResult value of zero if there is no error, and an error code if there is one.

ActivateTextService

The ActivateTextService function notifies a text service component that its associated document window is becoming active. This allows the text service component to display any associated floating windows.

A component instance created by a prior call to the Component Manager OpenComponent function.

DESCRIPTION

The appropriate response to ActivateTextService is for the text service component to restore its active state, including displaying all floating windows if they have been hidden. If it is an input method, it should specify the redisplay of any unconfirmed text currently in the active input area.

DeactivateTextService

The DeactivateTextService function lets a text service component know that its associated document window is becoming inactive. This allows time for the text service component to prepare for deactivation.

```
\begin{tabular}{ll} FUNCTION & DeactivateTextService (ts: ComponentInstance): \\ & ComponentResult; \end{tabular}
```

A component instance created by a prior call to the Component Manager OpenComponent function.

DESCRIPTION

When it receives a DeactivateTextService call, the text service component is responsible for saving whatever state information it needs to save, so that it can restore the proper information when it becomes active again. A component other than an input method should also hide all its floating windows and menus. However, an input-method component should *not* hide its windows in response to this call. If the subsequent document being activated is using the same component's service, it would be irritating to the user to hide and then immediately redisplay the same windows. An input-method component should hide its windows only in response to a HidePaletteWindows call.

An input method should not confirm any unconfirmed text in the active input area, but should save it until reactivated.

HidePaletteWindows

The HidePaletteWindows function instructs an input method to hide its floating windows because another input method is becoming active.

A component instance created by a prior call to the Component Manager OpenComponent function.

DESCRIPTION

The HidePaletteWindows function is not called every time a component's document becomes inactive; it is called by the Text Services Manager only if the new document that is becoming active does not use the same text service component as the document last deactivated. When it receives a HidePaletteWindows call, the text service component should hide all its floating and nonfloating windows. Its menus, if any, will be removed from the menu bar by the Text Services Manager.

If the text service component has no palettes, it should return a ComponentResult value of noErr.

TerminateTextService

The TerminateTextService function terminates the operations of a text service in preparation for closing the text service component.

A component instance created by a prior call to the Component Manager OpenComponent function.

DESCRIPTION

The Text Services Manager calls TerminateTextService before closing the component instance. A text service component must use this opportunity to confirm any inline input in progress.

If the text service component needs to remain open, it should return an OSErr value in the component result return value. This could happen, for example, if the user chooses Cancel in response to a text service component dialog box.

If this call is made to the *last* open instance of a text service component, the component should hide any open palette windows. If it is an input method, the component should *not* dispose of its menu handle if it has a menu.

Responding to Events and Updating the Cursor and Menu

To pass events to text service components, the Text Services Manager calls the TextServiceEvent function. To allow components to handle menu commands, it calls TextServiceMenuSelect. To allow components to set the shape of the cursor, it calls SetTextServiceCursor. To allow components to add their menus to the menu bar, it calls GetTextServiceMenu.

TextServiceEvent

The TextServiceEvent function routes an event to a specified text service component.

A component instance created by a prior call to the Component Manager OpenComponent function.

numOfEvents

event

The number of events being passed.

The Event Manager event record (defined by the EventRecord data

type) for the event being passed.

DESCRIPTION

If the text service component handles the event, it should return a nonzero value for componentResult and it should change the event to a null event. If it does not handle the event, it should return 0.

TextServiceMenuSelect

The TextServiceMenuSelect function lets a text service component handle commands from its menus.

```
FUNCTION TextServiceMenuSelect (ts: ComponentInstance; serviceMenu: MenuHandle; item: Integer): ComponentResult;
```

A component instance created by a prior call to the Component Manager OpenComponent function.

serviceMenu

A Menu Manager menu handle (defined by the MenuHandle data type) to a specific text service component menu.

item The text service component menu item that the user has selected.

DESCRIPTION

When the user makes a menu selection, the client application calls TSMMenuSelect; the Text Services Manager in turn calls TextServiceMenuSelect to all active components. The text service component receiving this call should return 0 for componentResult if it did not handle the menu selection, and 1 if it did.

After the text service component performs the chosen task, it is not responsible for removing the highlighting from the menu title.

SetTextServiceCursor

The ${\tt SetTextServiceCursor}$ function lets the text service component control the shape of the cursor.

```
FUNCTION SetTextServiceCursor (ts: ComponentInstance; mousePos: Point): ComponentResult;
```

A component instance created by a prior call to the Component Manager OpenComponent function.

mousePos

A location (specified as a QuickDraw point) that specifies the global coordinates for the vertical and horizontal position of the mouse.

DESCRIPTION

The text service component must return a nonzero value for ComponentResult if it has set the cursor, and 0 if it has not.

GetTextServiceMenu

The GetTextServiceMenu function returns a handle to a menu belonging to a text service component.

```
FUNCTION GetTextServiceMenu (ts: ComponentInstance;

VAR serviceMenu: MenuHandle):

ComponentResult;
```

A component instance created by a prior call to the Component Manager OpenComponent function.

serviceMenu

A menu handle (defined by the Menu Manager MenuHandle data type) for the text service component that is to be updated.

DESCRIPTION

The Text Services Manager calls GetTextServiceMenu to a text service component when the component is opened or activated, so that it can put the component's menu on the menu bar.

The menu handle passed in serviceMenu may be preallocated or it may be NIL. If the menu handle is NIL, the text service component should allocate a new menu and return it.

Note

All instances of an input-method component must share a single menu handle, allocated in the system heap. ◆

If the text service component does not have a menu, it should return a ComponentResult value of TSMHasNoMenuErr.

Confirming Active Input in a TSM Document

To stop active input in a text service component, the Text Services Manager calls the FixTextService function described in this section.

FixTextService

The FixTextService function explicitly terminates any input that is in progress in a specified text service component.

```
FUNCTION FixTextService (ts: ComponentInstance): ComponentResult;
```

A component instance created by a prior call to the Component Manager OpenComponent function.

DESCRIPTION

This function is equivalent to the user explicitly confirming text, but the request comes instead from the application or from the Text Services Manager. The text service component must stop accepting further input and confirm the current input, as appropriate.

Identifying the Supported Scripts and Languages

The Text Services Manager or a client application may call the GetScriptLanguageSupport function to find out all the scripts and languages supported by your text service component.

Get Script Language Support

The GetScriptLanguageSupport function determines which languages and scripts a specified text service component supports, including its primary language and script.

```
FUNCTION GetScriptLanguageSupport (ts: ComponentInstance;

VAR scriptHandle:

ScriptLanguageSupportHandle):

ComponentResult;
```

A component instance created by a prior call to the Component Manager OpenComponent function.

scriptHandle

A handle to a script-language support record. The handle must be either NIL or a valid handle. If it is NIL, the text service component allocates a new handle. If it is already a valid handle, the text service component resizes it as necessary.

DESCRIPTION

The GetScriptLanguageSupport function lets a caller find out all scripts and languages that your text service component supports. GetScriptLanguageSupport should return a list of scripts and languages in the scriptHandle return parameter. The ComponentResult return value should contain 0 if the list is correct, or an error value if an error occurred.

The component should list all its supported scripts and languages, starting with the primary script and language as specified in the componentFlags field of its component description record. See page 7-15.

The result is returned in a handle to a script-language support record. See "Identifying the Supported Scripts and Languages" on page 7-42 for a description of the script-language support record.

SEE ALSO

For sample code that shows a text service component responding to the GetScriptLanguageSupport function, see Listing 7-10 on page 7-43.

Summary of the Text Services Manager

Pascal Summary

Constants

CONST

```
kTSMVersion = 1;
                                 {Version of Text Services Manager}
                                 {Component type for component description}
  kTextService = 'tsvc';
  kInputMethodService = 'inpm'; {Component subtype for component desc.}
  bTakeActiveEvent = 15;
                                 {Bit set if component takes activate events}
                                                                {Bits 8 - 14}
  bScriptMask = $00007F00;
  bLanguageMask = $000000FF;
                                                                {Bits 0 - 7}
                                                                {Bits 0 - 14}
  bScriptLanguageMask = ScriptMask + bLanguageMask;
{Hilite styles}
  kCaretPosition = 1;
                                 {specify caret position}
  kRawText = 2;
                                 {specify range of raw text}
  kSelectedRawText = 3;
                                 {specify range of selected raw text}
  kConvertedText = 4;
                                 {specify range of converted text}
  kSelectedConvertedText = 5;
                                 {specify range of selected converted text}
{Apple Event constants}
  kTextServiceClass = kTextService;
                                       {Event class}
  kUpdateActiveInputArea = 'updt';
                                        {Update active inline area}
  kPos2Offset = 'p2st';
                                        {Convert global coordinates to }
                                        { character position}
  kOffset2Pos = 'st2p';
                                        {Convert character position to }
                                        { global coordinate}
  kShowHideInputWindow = 'shiw';
                                       {show or hide the input window}
  {Event keywords}
  keyAETSMDocumentRefcon = 'refc'; {TSM document refcon}
  keyAEServerInstance = 'srvi'; {Server instance}
                                 {typeText}
  keyAETheData = 'kdat';
```

```
keyAEScriptTag = 'sclg';
                                 {Script tag}
  keyAEFixLength = 'fixl';
  keyAEHiliteRange = 'hrng';
                                 {Hilite range array}
  keyAEUpdateRange = 'udng';
                                 {Update range array}
  keyAEClauseOffsets = 'clau';
                                 {Clause offsets array}
  keyAECurrentPoint = 'cpos';
                                 {Current point}
  keyAEDragging = 'bool';
                                 {Dragging flag}
  keyAEOffset = 'ofst';
                                 {Offset}
  keyAERegionClass = 'rgnc';
                                 {Region class}
  kevAEPoint = 'qpos';
                                 {Current point}
  keyAEBufferSize = 'buff';
                                 {Buffer size to get the text}
  keyAERequestedType = 'rtyp';
                                 {Requested text type}
  keyAEMoveView = 'mvvw';
                                 {Move view flag}
  keyAELength = 'leng';
                                 {Length}
  keyAENextBody = 'nxbd';
                                 {Next or previous body}
{optional keywords for Offset2Pos}
  keyAETextFont = 'ktxf';
  keyAETextPointSize = 'ktps';
  keyAETextLineHeight = 'ktlh';
  keyAETextLineAscent = 'ktas';
  keyAEAngle = 'kang';
{optional keyword for Pos2Offset}
  keyAELeftSide = 'klef';
                                 {type Boolean}
{optional keyword for kShowHideInputWindow}
  keyAEShowHideInputWindow = 'shiw'; {type Boolean}
{keyword for PinRange}
  keyAEPinRange = 'pnrg';
{Desc type ...}
  typeComponentInstance = 'cmpi'; {component instance}
  typeTextRange = 'txrn';
                                     {text range}
  typeTextRangeArray = 'tray';
                                    {text range array}
  typeOffsetArray = 'ofay';
                                    {offset array}
  typeIntlWritingCode = 'intl';
                                    {script code}
  typeQDPoint = 'QDpt';
                                    {QuickDraw point}
  typeAEText = 'tTXT';
                                     {Apple event text}
  typeText = 'TEXT';
                                     {plain text}
{Apple event descriptor type constants}
  kTSMOutsideOfBody = 1;
  kTSMInsideOfBody = 2;
```

```
kTSMInsideOfActiveInputArea = 3;
kNextBody = 1;
kPreviousBody = 2;

{Apple event error constants}
errOffsetInvalid = -1800;
errOffsetIsOutsideOfView = -1801;
errTopOfDocument = -1810;
errTopOfBody = -1811;
errEndOfDocument = -1812;
errEndOfBody = -1813;
```

Data Types

```
TYPE TextRange =
   RECORD
      fStart:
                     LongInt;
      fEnd:
                     LongInt;
      fHiliteStyle: Integer;
   END;
  TextRangePtr = ^TextRange;
   TextRangeHandle = ^TextRangePtr;
   TextRangeArray =
   RECORD
      fNumOfRanges: Integer;
                     ARRAY [0..0] of TextRange;
      fRange:
   END;
   TextRangeArrayPtr = ^TextRangeArray;
  TextRangeArrayHandle = ^TextRangeArrayPtr;
  OffsetArray =
   RECORD
      fNumOfOffsets: Integer;
      fOffset: ARRAY [0..0] of LongInt;
   END;
   OffsetArrayPtr = ^OffsetArray;
   OffsetArrayHandle = ^OffsetArrayPtr;
   TextServiceInfo =
   RECORD
      fComponent: Component;
```

```
fItemName: Str255;
END;
TextServicesInfoPtr = ^TextServiceInfo;
TextServiceList =
RECORD
   fTextServiceCount: Integer;
   fServices:
                        ARRAY [0..0] of TextServiceInfo;
END;
TextServiceListPtr = ^TextServiceList;
TextServiceListHandle = ^TextServiceListPtr;
ScriptLanguageRecord =
RECORD
   fScript:
               ScriptCode;
   fLanguage: LangCode;
END;
ScriptLanguageSupport =
RECORD
   fScriptLanguageCount:
                          Integer;
   fScriptLanguageArray: ARRAY [0..0] of ScriptLanguageRecord;
END;
ScriptLanguageSupportPtr = ^ScriptLanguageSupport;
ScriptLanguageSupportHandle = ^ScriptLanguageSupportPtr;
InterfaceTypeList = ARRAY [0..0] of OSType;
TSMDocumentID = Ptr;
```

Text Services Manager Routines for Client Applications

Initializing and Closing as a TSM-Aware Application

```
FUNCTION InitTSMAwareApplication: OSErr; FUNCTION CloseTSMAwareApplication: OSErr;
```

Creating and Activating TSM Documents

```
FUNCTION NewTSMDocument (numOfInterface: Integer;

VAR supportedInterfaceTypes: InterfaceTypeList;

VAR idocID: TSMDocumentID;

refCon: LongInt): OSErr;

FUNCTION ActivateTSMDocument

(idocID: TSMDocumentID): OSErr;
```

FUNCTION DeactivateTSMDocument

FUNCTION DeleteTSMDocument

(idocID: TSMDocumentID): OSErr;
(idocID: TSMDocumentID): OSErr;

Passing Events to Text Service Components

FUNCTION TSMEvent (VAR event: EventRecord): Boolean;

Passing Menu Selections and Cursor Setting

FUNCTION TSMMenuSelect (menuResult: LongInt): Boolean;
FUNCTION SetTSMCursor (mousePos: Point): Boolean;

Confirming Active Input in a TSM Document

FUNCTION FixTSMDocument (idocID: TSMDocumentID): OSErr;

Making Text Services Available to the User

FUNCTION GetServiceList (numOfInterfaceTypes: Integer;

supportedInterfaceTypes: InterfaceTypeList;
VAR serviceInfo: TextServiceListHandle;

VAR seedValue: LongInt): OSErr;

FUNCTION OpenTextService (idocID: TSMDocumentID; aComponent: Component;

VAR aComponentInstance: ComponentInstance):

OSErr;

FUNCTION CloseTextService (idocID: TSMDocumentID; aComponentInstance:

ComponentInstance): OSErr;

Requesting a Floating Input Window

FUNCTION UseInputWindow (idocID: TSMDocumentID; useWindow: Boolean):
OSErr;

Associating Scripts and Languages With Components

FUNCTION SetDefaultInputMethod

(ts: Component;

VAR slRecord: ScriptLanguageRecord): OSErr;

 ${\tt FUNCTION} \ \ {\tt GetDefaultInputMethod}$

(VAR ts: Component;

VAR slRecord: ScriptLanguageRecord): OSErr;

FUNCTION SetTextServiceLanguage

(VAR slRecord: ScriptLanguageRecord): OSErr;

FUNCTION GetTextServiceLanguage

(VAR slRecord: ScriptLanguageRecord): OSErr;

Text Services Manager Routines for Components

Sending Apple Events to a Client Application

```
FUNCTION SendAEFromTSMComponent

(VAR theAppleEvent: AppleEvent;

VAR reply: AppleEvent; sendMode: AESendMode; sendPriority: AESendPriority; timeOutInTicks: LongInt; idleProc: IdleProcPtr; filterProc: EventFilterProcPtr): OSErr;
```

Opening Floating Utility Windows

```
FUNCTION NewServiceWindow (wStorage: Ptr; boundsRect: Rect; title: Str255; visible: Boolean; theProc: Integer; behind: WindowPtr; goAwayFlag: Boolean; ts: ComponentInstance; VAR window: WindowPtr): OSErr;

FUNCTION CloseServiceWindow (window: WindowPtr): OSErr;

FUNCTION GetFrontServiceWindow (VAR window: WindowPtr): OSErr;

FUNCTION FindServiceWindow (thePoint: Point; VAR theWindow: WindowPtr): Integer;
```

Text Service Component Routines

Providing a Text Service

```
FUNCTION InitiateTextService
(ts: ComponentInstance): ComponentResult;

FUNCTION ActivateTextService
(ts: ComponentInstance): ComponentResult;

FUNCTION DeactivateTextService
(ts: ComponentInstance): ComponentResult;

FUNCTION HidePaletteWindows (ts: ComponentInstance): ComponentResult;

FUNCTION TerminateTextService
(ts: ComponentInstance): ComponentResult;
```

Responding to Events and Updating the Cursor and Menu

```
FUNCTION TextServiceEvent (ts: ComponentInstance; numOfEvents: Integer; VAR event: EventRecord): ComponentResult;
```

Confirming Active Input in a TSM Document

```
FUNCTION FixTextService (ts: ComponentInstance): ComponentResult;
```

Identifying the Supported Scripts and Languages

```
FUNCTION GetScriptLanguageSupport
```

(ts: ComponentInstance; VAR scriptHandle:
 ScriptLanguageSupportHandle): ComponentResult;

C Summary

Constants

```
#define kTSMVersion
                                            /* Version of the
                                               Text Services Manager */
#define kTextService
                              'tsvc'
                                            /* component type for
                                               the component description */
                                            /* component subtype for
#define kInputMethodService 'inpm'
                                               the component description */
#define bTakeActiveEvent
                                            /* bit set if the component
                             15
                                                takes active event */
#define bScriptMask
                             0x00007F00
                                            /* bit 8 - 14 */
#define bLanguageMask
                                            /* bit 0 - 7 */
                             0x000000FF
#define bScriptLanguageMask bScriptMask+bLanguageMask
                                                         /* bit 0 - 14 */
/* Hilite styles ... */
typedef enum {
  kCaretPosition
                                  /* specify caret position */
                          = 1,
  kRawText
                          = 2,
                                   /* specify range of raw text */
  kSelectedRawText
                          = 3,
                                   /* specify range of selected raw text */
  kConvertedText
                          = 4,
                                   /* specify range of converted text */
```

```
kSelectedConvertedText = 5
                                   /* specify range of selected
                                       converted text */
} HiliteStyleType;
/* Apple Event constants ... */
/* Event class ... */
#define
            kTextServiceClass
                                    kTextService
/* event ID ... */
#define
            kUpdateActiveInputArea 'updt'
                                              /* update active Inline area */
#define
            kPos2Offset
                                             /* converting global coordinates
                                    'p2st'
                                                 to char position */
#define
            kOffset2Pos
                                    'st2p'
                                              /* converting char position
                                                 to global coordinates */
#define
            kShowHideInputWindow
                                    'shiw'
                                              /* show or hide bottomline
                                                 input window */
/* Event keywords ... */
                                             /* TSM document refcon */
#define keyTSMDocumentRefcon
                                 'refc'
                                              /* component instance */
#define keyAEServerInstance
                                 'srvi'
                                              /* typeText */
#define keyAETheData
                                 'kdat'
#define keyAEScriptTag
                                 'sclg'
                                              /* script tag */
#define keyAEFixLength
                                 'fixl'
                                              /* fix len ?? */
#define keyAEHiliteRange
                                              /* hilite range array */
                                 'hrng'
#define keyAEUpdateRange
                                  'udng'
                                              /* update range array */
                                              /* Clause Offsets array */
#define keyAEClauseOffsets
                                 'clau'
#define keyAECurrentPoint
                                              /* current point */
                                 'cpos'
#define keyAEDragging
                                              /* dragging flag */
                                  'bool'
#define keyAEOffset
                                 'ofst'
                                              /* offset */
                                              /* region class */
#define keyAERegionClass
                                 'rgnc'
#define keyAEPoint
                                              /* current point */
                                  'apos'
#define keyAEBufferSize
                                 'buff'
                                              /* buffer size to get text */
                                              /* requested text type */
#define keyAERequestedType
                                 'rtyp'
#define keyAEMoveView
                                  'mvvw'
                                              /* move view flag */
#define keyAELength
                                              /* length */
                                  'leng'
#define keyAENextBody
                                              /* next or previous body */
                                 'nxbd'
/* optional keyword for UpdateActiveInputArea */
#define keyAEPinRange
/* optional keywords for Offset2Pos */
#define keyAETextFont
                                 'ktxf'
#define keyAETextPointSize
                                 'ktps'
```

```
#define keyAETextLineHeight
                                 'ktlh'
#define keyAETextLineAscent
                                 'ktas'
#define keyAEAngle
                                 'kang'
/* optional keywords for Pos2Offset */
#define keyAELeadingEdge
                                 'klef'
/* Apple event descriptor type ... */
#define typeComponentInstance
                                             /* server instance */
                                 'cmpi'
#define typeTextRange
                                 'txrn'
                                             /* text range record */
#define typeTextRangeArray
                                 'tray'
                                             /* text range array */
#define typeOffsetArray
                                 'ofay'
                                             /* offset array */
#define typeIntlWritingCode
                                             /* script code */
                                 'intl'
#define typeQDPoint
                                             /* OuickDraw Point */
                                 'ODpt'
#define typeAEText
                                 'tTXT'
                                             /* Apple Event text */
#define typeText
                                             /* Plain text */
                                 'TEXT'
#define typeFixed
                                 'fixd'
                                             /* Fixed number 16.16 */
/* Apple event descriptor type constants */
typedef enum {
   kTSMOutsideOfBody
                                 = 1,
  kTSMInsideOfBody
                                 = 2,
  kTSMInsideOfActiveInputArea
                                 = 3
} AERegionClassType;
typedef enum {
  kNextBody
                                 = 1,
  kPreviousBody
                                 = 2
} AENextBodyType;
/* Apple Event error definitions */
typedef enum {
   errOffsetInvalid
                             = -1800,
   errOffsetIsOutsideOfView = -1801,
   errTopOfDocument
                             = -1810,
   errTopOfBody
                              = -1811,
   errEndOfDocument
                              = -1812,
   errEndOfBody
                              = -1813
} AppleEventErrorType;
```

Data Types

```
struct TextRange {
                                   /* typeTextRange 'txrn' */
   long fStart;
  long fEnd;
   short fHiliteStyle;
typedef struct TextRange
                              TextRange;
typedef
               TextRange
                              *TextRangePtr;
typedef
               TextRangePtr
                              *TextRangeHandle;
                                 /* typeTextRangeArray
                                                        'txra' */
struct TextRangeArray {
               fNumOfRanges;
                                 /* specify the size of the fRange array */
   short
   TextRange
               fRange[1];
                                 /* when fNumOfRanges > 1, the size of this
                                    array has to be calculated */
};
typedef struct TextRangeArray
                                 TextRangeArray;
typedef
               TextRangeArray
                                 *TextRangeArrayPtr;
typedef
               TextRangeArrayPtr *TextRangeArrayHandle;
struct OffsetArray {
                                 /* typeOffsetArray'offa' */
   short fNumOfOffsets;
                                 /* specify the size of the fOffset array */
   long fOffset[1];
                                 /* when fNumOfOffsets > 1, the size of
                                    this array has to be calculated */
};
typedef struct OffsetArray
                              OffsetArray;
typedef
               OffsetArray
                              *OffsetArrayPtr;
               OffsetArrayPtr *OffsetArrayHandle;
typedef
/* extract Script/Language code from Component flag ... */
#define mGetScriptCode(cdRec) ((ScriptCode) (cdRec.componentFlags &
                                                      bScriptMask) >> 8)
                                                cdRec.componentFlags &
#define mGetLanguageCode(cdRec) ((LangCode)
                                                         bLanguageMask)
typedef void *TSMDocumentID;
/* text service component information list */
struct TextServiceInfo {
  Component
               fComponent;
   Str255
               fItemName;
};
                                 TextServiceInfo;
typedef struct TextServiceInfo
typedef
               TextServiceInfo *TextServiceInfoPtr;
```

```
/*text service component list*/
struct TextServiceList {
                     fTextServiceCount;
                                          /* number of entries in the
   short
                                              'fServices' array */
   TextServiceInfo fServices[1];
                                          /* Note: array of 'TextServiceInfo'
                                             records follows */
};
typedef struct TextServiceList
                                    TextServiceList;
typedef
               TextServiceList
                                    *TextServiceListPtr;
               TextServiceListPtr
                                    *TextServiceListHandle;
typedef
/*script and language record*/
struct ScriptLanguageRecord {
   ScriptCode fScript;
   LangCode
               fLanguage;
};
typedef struct ScriptLanguageRecord ScriptLanguageRecord;
/*script and language support record*/
struct ScriptLanguageSupport {
                        fScriptLanguageCount; /* number of entries in the
 short
                                                 'fScriptLanguageArray'
                                                array */
 ScriptLanguageRecord fScriptLanguageArray[1]; /* Note: array of
                                                    'ScriptLanguageRecord'
                                                   records follows */
};
typedef struct ScriptLanguageSupport
                                          ScriptLanguageSupport;
               ScriptLanguageSupport
                                          *ScriptLanguageSupportPtr;
typedef
typedef
               ScriptLanguageSupportPtr
                                          *ScriptLanguageSupportHandle;
```

Text Services Manager Routines for Client Applications

Initializing and Closing as a TSM-Aware Application

```
pascal OSErr InitTSMAwareApplication ();
pascal OSErr CloseTSMAwareApplication ();
```

Creating and Activating TSM Documents

```
pascal OSErr ActivateTSMDocument
                             (TSMDocumentID idocID);
pascal OSErr DeactivateTSMDocument
                             (TSMDocumentID idocID);
pascal OSErr DeleteTSMDocument
                             (TSMDocumentID idocID);
Passing Events to Text Service Components
pascal Boolean TSMEvent
                             (EventRecord *event);
Passing Menu Selections and Cursor Setting
pascal Boolean TSMMenuSelect(long menuResult);
pascal Boolean SetTSMCursor (Point mousePos);
Confirming Active Input in a TSM Document
pascal OSErr FixTSMDocument (TSMDocumentID idocID);
Making Text Services Available to the User
pascal OSErr GetServiceList (short numOfInterfaceTypes,
                              OSType supportedInterfaceTypes[],
                              TextServiceListHandle *serviceInfo,
                              long *seedValue);
pascal OSErr OpenTextService
                             (TSMDocumentID idocID, Component aComponent,
                               ComponentInstance *aComponentInstance);
pascal OSErr CloseTextService
                             (TSMDocumentID idocID,
                              ComponentInstance aComponentInstance)
Requesting a Floating Input Window
pascal OSErr UseInputWindow (TSMDocumentID idocID, Boolean useWindow);
Associating Scripts and Languages With Components
pascal OSErr SetDefaultInputMethod
                             (Component
                              ScriptLanguageRecord *slRecordPtr);
pascal OSErr GetDefaultInputMethod
                             (Component *ts,
                              ScriptLanguageRecord *slRecordPtr);
```

Text Services Manager Routines for Components

Sending Apple Events to a Client Application

Opening Floating Utility Windows

Text Service Component Routines

Providing a Text Service

Responding to Events and Updating the Cursor and Menu

Confirming Active Input in a TSM Document

Identifying the Supported Scripts and Languages

Assembly-Language Summary

Trap Macros

Trap Macro Names for Text Services Manager Routines

Pascal name	Trap macro name
NewTSMDocument	_NewTSMDocument
DeleteTSMDocument	_DeleteTSMDocument
ActivateTSMDocument	_ActivateTSMDocument
DeactivateTSMDocument	_DeactivateTSMDocument
TSMEvent	_TSMEvent
TSMMenuSelect	_TSMMenuSelect

Pascal name	Trap macro name
SetTSMCursor	_SetTSMCursor
FixTSMDocument	_FixTSMDocument
GetServiceList	_GetServiceList
OpenTextService	_OpenTextService
CloseTextService	_CloseTextService
SendAEFromTSMComponent	_SendAEFromTSMComponent
SetDefaultInputMethod	_SetDefaultInputMethod
${\tt GetDefaultInputMethod}$	_GetDefaultInputMethod
SetTextServiceLanguage	_SetTextServiceLanguage
GetTextServiceLanguage	_GetTextServiceLanguage
UseInputWindow	_UseInputWindow
NewServiceWindow	_NewServiceWindow
CloseServiceWindow	_CloseServiceWindow
GetFrontServiceWindow	_GetFrontServiceWindow
${\tt InitTSMAwareApplication}$	$_$ InitTSMAwareApplication
CloseTSMAwareApplication	_CloseTSMAwareApplication
FindServiceWindow	_FindServiceWindow

Trap Macro Names for Text Service Component Routines

Trap macro name
_GetScriptLanguageSupport
_InitiateTextService
_TerminateTextService
_ActivateTextService
_DeactivateTextService
_TextServiceEvent
_GetTextServiceMenu
_TextServiceMenuSelect
_FixTextService
_SetTextServiceCursor
_HidePaletteWindows

Result Codes

tsmComponentNoErr	0	Component result: no error
tsmUnsupScriptLanguageErr	-2500	Specified script and language are not supported
tsmInputMethodNotFoundErr	-2501	Specified input method cannot be found
tsmNotAnAppErr	-2502	The caller was not an application
tsmAlreadyRegisteredErr	-2503	The caller is already TSM-initialized
tsmNeverRegisteredErr	-2504	The caller is not TSM-aware
tsmInvalidDocIDErr	-2505	Invalid TSM document ID
tsmTSMDocBusyErr	-2506	Document is still active
tsmDocNotActiveErr	-2507	Document is not active
tsmNoOpenTSErr	-2508	There is no open text service component
tsmCantOpenComponentErr	-2509	Can't open the component
tsmTextServiceNotFoundErr	-2510	No text service component found
tsmDocumentOpenErr	-2511	There are open documents
tsmUseInputWindowErr	-2512	An input window is being used
tsmTSHasNoMenuErr	-2513	The text service component has no menu
tsmTSNotOpenErr	-2514	Text service component is not open
tsmComponentAlreadyOpenErr	-2515	Text service component already open for document
tsmInputMethodIsOldErr	-2516	The default input method is old-style
tsmScriptHasNoIMErr	-2517	Script has no (or old) input method
tsmUnsupportedTypeErr	-2518	Unsupported interface type
tsmUnknownErr	-2519	Any other error