

IBM ECM System Monitor Field Guides

Incident Forwarding via Email

February 06th, 2026
CENIT AG
Michael Wohland

Content

Introduction	3
Overview	3
Disclaimer	3
Purpose of this guide.....	4
Requirements.....	4
Step by Step setup	5
1. Prepare the mail server configuration in ESM.....	5
2. Preparing the MailExportIncident.....	8
3. Test of the Task.....	10
4. Automate the sending of mails	12
Contact Information	15

Introduction

Overview

This guide describes in detail how IBM ECM System Monitor (ESM) can be integrated with Mail to forward ESM incidents.

Disclaimer

The content of this document is based on ESM Version 5.7.0.0-000. The descriptions and guidelines in this document are for informational purposes only. Up-to-dateness, content completeness, appropriateness and validity for all possible scenarios cannot be guaranteed. All information is provided on an as-is basis. The author is not liable for any errors or omissions in this document or any losses, injuries and damages arising from its use.

If you are planning to set up or configure ESM or to adjust an existing installation, it is absolutely necessary to consider current security whitepapers, release notes and announcements from the official IBM ECM System Monitor product documentation website.

Purpose of this guide

This guide provides a step-by-step setup for using a mail server in combination with ESM to forward incidents to mail accounts.


Requirements

- ESM Version 5.7.0.0-000 or later (already installed)
- Availability of a mail server


Step by Step setup

1. Prepare the mail server configuration in ESM

ESM offers two mail server possibilities. It is possible to configure either a standard smtp server or to integrate with an Azure server instead. For both options you need to switch into the Cconfiguration console and select Administration dashboard from the top. In the menu on the left, you find an entry for the mail server administration which you need to select.



After selecting it, you can click on the drop-down next to the +. In the drop-down you will find the two options. Select the one that works for you.



Example for SMTP Server:

*Server Name:	MySmtServerAlias
*Host:	SMTPServerHostname
*Port:	25
*From Address:	MySenderAddress@MyDomain.com
Authentication:	☒
* Username:	MyUserNamemyDomain
* Password:	

 [Additional Parameters](#)

The Server Name is just an alias, like a configuration name. You can specify whatever you want here. For the other parameters please specify your relevant information.

Authentication might be required but, in some cases, it is not necessary.

There is also an option for additional parameters. They are usually not required.

Save your setup by clicking on the check icon above the configuration.

Example for Azure Server:


 	
*Server Name:	MyAzureServerAlias
*From Address:	MySenderAddress@MyDomain.com
*Tenant ID:	532ef83b-73ff-4909-abfc-2e161f50253d
*Client ID:	d7cbdd40-4579-4320-a5ed-b6aa397fa1bd
Secret:	*****
Private Key Path:	
Certificate Path:	

The Server Name is just an alias, like a configuration name. You can specify whatever you want here. For the other parameters please specify your relevant information.

Private Key Path and Certificate Path might be required but usually this is not necessary.


Save your setup by clicking on the check icon above the configuration.

After saving you should see your mail server on the list.



2. Preparing the MailExportIncident

Open the Configuration console and switch to the configuration dashboard. Select the task in the menu on the left and click on the + next to MailExportIncident to create a new task:



The configuration for the task will open. Please adjust the setup as required .

✕
◀ ▶ ✓ ↻

⚙️ Task Configuration

Select the type of the task and enter its configuration data.

*Name:

active ☐

Task:

Subject Template:

Body Template:

Mail Server Name:

Recipients:

👤 Agent

Select the location where the Task should run.

📅 Schedule

If active when and how often should the Task be executed?

☒ Interval ☐ Cron

Start:

End:

Interval:

Specify a name for the task – make sure you will be able to easily identify it later.

Keep “active” unchecked, as the task will be triggered by criterias of the incident.

You can adjust Subject Template and Body Template – see the configuration help that is offered on the right side of the setup.

For Mail Server Name select your mail server that should be used from the drop-down.

In Recipients you can specify one recipient or a comma separated list of recipients.


As Agent please specify [Run on Server].

The Schedule is only relevant if a task is set to active.


Save your setup by clicking on the check icon above the configuration – the configuration editor will close.

3. Test of the Task


Open the task configuration again by double clicking on it. It is available below the MailExportIncident task in the sidebar.




You can now execute the task manually as a test:



You should see a task result in the console:



If you have specified yourself in the recipients, you should also receive an email that looks like this – as this was a test execution the content will just show the template information:



4. Automate the sending of mails

To automatically forward incidents by task there are two possible setup procedures available.

You can either set up the forwarding per Probe configuration individually, or you can set up conditions in the task itself which are more global.

Example for automation in the Probe configuration:

As example I will use a simple CPU Probe here.

Open your Probe configuration. In the Configuration console you can do that via the configuration dashboard by double clicking on the situation. In the Operating console you can select the Probe from the Probe sidebar and click on “Edit” button above the information.

In the Configuration console switch to page 3 (Automation) of the setup, in the Operating console select the Automation tab.

The screenshot shows the 'Automation' configuration page for a 'Cpu @ Server_Agent' probe. At the top, there's a navigation bar with a 'Back' button and three status indicators. Below the navigation bar, the 'Automation' tab is selected, showing a description: 'Trigger tasks automatically by occurrence of certain incidents.' A table with columns 'Condition', 'Mode', and 'Tasks' is present, but it is empty. Below the table, there's a section titled 'Cpu @ Server_Agent' with a sub-header 'Automation'. This section contains a progress bar with five steps: 'Probe', 'Schedule', 'Evaluation', 'Tags', and 'Automation'. The 'Automation' step is currently active. Below the progress bar, a message states: 'No task triggers configured. To add a new task trigger please press the add button.' At the bottom of this section, there is a button labeled '+ Add task trigger'.

Click on + / + Add task trigger to add a condition.

Add your condition as desired:

The screenshot shows the 'Automation' configuration console. At the top, there are navigation icons (back, forward, search, etc.) and a status bar with three circles. Below the title 'Automation', a subtitle reads 'Trigger tasks automatically by occurrence of certain incidents.' A table lists the configured automation rules:

Condition	Mode	Tasks
All of: Severity >= Critical Situation == Cpu @ Server_Agent	Always	ForwardIncidentByMail

The screenshot shows the configuration console for the 'Cpu @ Server_Agent' probe. The 'Automation' tab is selected in the top navigation bar. Below the probe name, there is a section titled 'Tasks triggered by incidents from this probe:'. It contains a table with the same configuration as the previous screenshot:

Condition	Mode	Task
Severity >= Critical Situation == Cpu @ Server_Agent	Always	ForwardIncidentByMail

In the Configuration console setup you can see that the probe itself is mentioned in the condition. In the Operating console setup the probe is not explicitly listed (but used).

The Mode is either Always (whenever the condition matches) or First (only on the change of the severity – when the condition matches).

As Task select the Task for Mail that was just created.


Save the setup.

Example for automation in the task configuration:

This option is more global than the other setup, as the condition does not require the probe itself. E.g. it can be used to forward any Critical information as shown in this example.

The configuration for this is currently only available in the Configuration console via the task itself.

Open the task configuration as done during the task setup and switch to the second page (Automation).



You can see the condition that was created in the Probe for the automation in here as well.

Click on the + to add an additional condition. For this one the Situation is not required, and it can be removed once the condition is shown - Example:



Save the setup.

No matter which of the two options you select, you should now receive an email whenever the condition matches.

Cpu @ Server_Agent - HARMLESS



_Testuser examples.jar <LeeG@r6hg.onmicrosoft.com>

To ● Wohland, Michael

2026-02-06T09:16:23.716Z: HARMLESS: 41.6 | 41,6% CPU usage (average).
Measured values: 21%, 42%, 49%, 46%, 50% | null

Contact Information

If you have any questions, please contact us at ECM.SystemMonitor@cenit.com.

CENIT AG

Phone: +49 711 7825 30

Email: ECM.SystemMonitor@cenit.com