

# **Portico™ Integration Instructions**

6/10/2013

e2Value®, Inc. P.O. Box 3518 Stamford, CT 06905

Voice: 203.975.7990 Fax: 203.975.7861

Email: support@e2value.com

## **Table of Contents**

Please note: This is NOT OUR XML product. If you are attempting to do an XML integration, please login to e2Value and click on the XML Integration link located at the top of the page.

1	Pro	duct Description	3
2	Pro	duct Requirements	3
3	Por	tico™ Integration Types	4
	3.1	Basic	4
	3.2	Advanced	
4	Def	initions	5
	4.1	Integration Definitions	5
	4.2	Estimator Definitions	
5	Use	er Setup	7
6	Esti	mator Links	8
	6.1	Residential	8
	6.2	Commercial	8
	6.3	Farm and Ranch	8
	6.4	Pronto ™	8
	6.5	InVision	8
	6.6	InQuest	8
	6.7	AV3	8
	6.8	Smart Data Warehouse/Retrieving Past Estimates	8
7	Bas	ic Portico™ Integration	9
	7.1	Authentication	9
	7.2	Example - Basic Authentication Routine	11
	7.3	Quickstart Example - Full Working Example ASP Page and Code	12
	7.4	After Authenticating – Special Note on JavaScript Popup Windows	15
	7.5	Special Note for Farm and Ranch, Homestead and Quick Commercial	
		s - Popup Itemizer Window	17
8	PHF	P Instructions:	
	8.1	Example - Basic Authentication Routine	
	8.2	Quickstart Example - Full Working Example ASP Page and Code	
9		anced Portico™ Integration	
	9.1	CA DOI Regulation 2010.00001 Compliance	21
	9.2	Data Parameters	
	9.3	Commercial Variable Lists	
	9.4	Residential Variable Lists	
	9.5	Streaming PDF Return	41

## 1 **Product Description**

Please note: This is NOT OUR XML product. If you are attempting to do an XML integration, please login to e2Value and click on the XML Integration link located at the top of the page.

Portico™ provides customers with a seamless login and the ability to quickly integrate with our system without having to develop screens and design their own database for the estimator as they do with XML. Portico™ is a great option when a company wants to provide quick estimator access for their customers with no hassles.

Portico™ is capable of receiving known property data (i.e. address, square footage, year built) and returning it to the customer's system, but this is not a requirement in order to use the product. We store everything so there is no demand placed on the customer's network and resources other than the initial integration which typically takes 1-2 days.

## 2 Product Requirements

Portico™, as with all e2Value® applications, requires Internet Explorer 5.0 or higher. Please make sure you communicate this to your clients.

## 3 Portico™ Integration Types

Be sure you find out which Portico product your company purchased prior to integration.

#### 3.1 Basic

The Basic Portico™ option allows users to seamlessly log into e2Value® via their website by clicking on a link. This typically takes place through the agents-only area on the carrier/vendor website. The carrier/vendor internal staff will usually access via the company Intranet. This option eliminates the need for the end user to enter one username and password for their site and a separate one for the e2Value® site. The end user only needs to enter their existing username and password that was provided to them (from the carrier) to enter the agent-only area or the company Intranet. Then when the user clicks on the estimator that they wish to use, the system sends e2Value® the company's username and password and a unique identifier (virtual name) for the user accessing the site. This option is available for all programs that we offer. Minimal programming is typically required of a company's IT staff.

- The company sets up 1 link per estimator.
- Setup is typically 1 day.
- All Estimators, including Pronto<sup>™</sup>, are available for this option.

### 3.2 Advanced

The Advanced Portico™ option allows customers to integrate portions of their proprietary rating, quoting or policy issuing systems with the e2Value® system by sending URL parameters for additional data fields along with the link to the estimator. This option eliminates the need for duplicate entry of the name, address, city, zip code, year built, sq. ft., etc. Additionally a customer can provide us a return path so that output data can be sent back to the company once the estimate has been completed.

Once the basic information is entered in the customer's system, they could click a button that typically reads "Valuation". They are then seamlessly logged into the e2Value® estimator where they could enter the remaining information. Once they've completely filled out the property information and they click the "Calculate" button, the replacement cost is displayed. They will also see a button that reads "return to XXXX" (the name of their program). This will transfer the replacement cost back to their system via URL parameters.

- The company sets up 1 link per estimator. The documentation provides a link specific to each estimator (BPR, BPA, EXR, etc.). The customer's developer must then create a menu of our estimators on their end.
- Setup is typically 2 days.
- This option is available for all Residential and Manufactured Home estimators, including Pronto™.
- The customer can choose what data they want returned from our system.
- If a customer wants additional data that we do not currently provide, we typically charge for any development time necessary to include these additional fields.
- As with all our estimators, we store all of the data in the SDW even though we return it to their system.

## 4 **Definitions**

## 4.1 Integration Definitions

**Username:** YOUR USERNAME – provided to you by e2Value.

Password: YOUR\_PASSWORD - provided to you by e2Value.

**Virtual User Name:** This is the unique identifier that you give your users. This may be the username that they logged into your site with or an agency code, a company name, etc.

## 4.2 Estimator Definitions

**Pronto™ Residential:** Pronto™ is a virtual inspection system that combines our Residential estimator with 3<sup>rd</sup> party property data along with Geo-Imagery sources to produce an instant inspection from just an address.

**ProntoLite™ Residential:** Pronto™ is a virtual inspection system that combines our Residential estimator with Geo-Imagery sources to produce an instant inspection from just an address and 3 basic questions about the property.

**Residential:** The Residential estimator is our coverage quoting estimator for residential homes. This estimator is the estimator most typically used for integration into agency sites.

**Exterior Residential:** The Exterior Residential estimator is known as either an Exterior or "Driveby" inspection estimator. It includes the same information as the Residential plus additional information that could be acquired by visiting the home.

**Full Residential:** The Full Residential estimator is known as an Interior and Exterior inspection. This is a very comprehensive estimator detailing all interior and exterior features and typically only used by inspection professionals.

**A&A:** The A&A (Additions & Alterations) estimator is used only for Condos and Co-ops. This estimator is typically used by agents in major metropolitan areas for the purposes of quoting coverage.

**Full A&A:** Full A&A (Additions & Alterations) estimator is used only for Condos and Co-ops. This is a very comprehensive estimator that details all interior features and is typically only used by inspection professionals.

**Additional Structures:** The Additional Structures estimator is used for quoting coverage of detached structures such as swimming pools, garages and tennis courts. All other estimators have additional structures quoting capabilities. This is to be used only when a customer wants to determine the value of just the additional structure.

**Pronto™ Commercial:** Pronto™ is a virtual inspection system that combines our commercial estimator with 3<sup>rd</sup> party property data along with Geo-Imagery sources to produce an instant inspection from just an address.

**ProntoLite™ Commercial:** Pronto™ is a virtual inspection system that combines our commercial estimator with Geo-Imagery sources to produce an instant inspection from just an address and 2 basic questions about the property.

**Quick Commercial Estimator (QCE):** The Quick Commercial Estimator is our commercial structure quoting system. This estimator is typically used by agents and underwriters to determine coverage.

**QCE Pro Estimator:** The QCE Pro Estimator is our commercial structure quoting system. This estimator is typically used by inspectors to determine coverage.

**Farm and Ranch Estimator:** The Farm and Ranch Estimator is our agricultural structure estimating system. This estimator is typically used by agents and underwriters to determine coverage.

**Homestead Estimator:** The Homestead Estimator combines our Farm and Ranch Estimator and our Residential estimator so that customers can determine coverage quotes for family farms or farms with residential structures. This estimator is typically used by agents and underwriters.

**InQuest:** The InQuest product is for customers who want 3<sup>rd</sup> party public data but without the EVS valuator or Geo-Imagery. InQuest allows a customer to choose 1-3 data providers and get the public data in a side by side format.

**InVision:** The InVision product is for customers who want the Geo-Imagery but without the EVS estimator or 3<sup>rd</sup> party data. InVision provides the Geo-Imagery section and Riskmeter section, if they want it, so that customers can get a visual inspection without having to pay for the estimator or 3<sup>rd</sup> party data.

**AV3:** AV3 is an Automated Valuation Model (AVM) that calculates the three standard approaches to valuation automatically and includes them in a single report. AV3 is a USPAP compliant product that follows the FDIC guidelines for AVM's for use in monitoring Collateral Values and for Home Equity Lines of Credit (HELOC). AV3 May not be used for origination.

## 5 User Setup

1. User hierarchies are based on the IDs that we provide the customer. We typically provide an internal and external ID. The internal has rights over the external one. If a client has more robust needs we can work with them to create more IDs, but the premise will be the same.

#### 2. Carrier

- a. Internal User Typically underwriters, but may also be claims and inspection staff. The virtual user identifies specific individuals once they log into the system.
- External User Typically agents, but may also be outside claims adjusters and inspection companies. The virtual user identifies specific individuals once they log into the system.

## 3. Portal/Inspection Vendor

- a. Company's Users
  - i. Internal Typically customer support, internal staff or inspection staff.
  - ii. External Inspectors and, in some cases, other carriers if the client is an insurance portal.

#### b. Client's Users

- i. Internal We can provide access to their portal clients so that they have rights over their agents. Just like the carriers setup above, a client can associate user IDs with our passwords to give access to a specific company's underwriters and allow privileges over their agents.
- ii. External As with the internal, we can provide IDs that the portal or company assigns to their customers within their database to allow access by their client's agents.

## 6 Estimator Links.

Make sure you find out which e2Value estimators your company purchased prior to integration.

### 6.1 Residential

Residential Estimates: https://evs.e2value.com/evs/est/bpr/default.asp
Residential Pro Estimates: https://evs.e2value.com/evs/est/bpp/default.asp
A&A Estimates: https://evs.e2value.com/evs/est/bpa/default.asp
A&A Pro Estimates: https://evs.e2value.com/evs/est/bap/default.asp
Exterior Estimates: https://evs.e2value.com/evs/est/exr/default.asp
Full Residential Estimates: https://evs.e2value.com/evs/est/flr/default.asp
Full A&A Estimates: https://evs.e2value.com/evs/est/fla/default.asp

Additional Structures Estimates: https://evs.e2value.com/evs/est/ada/default.asp

## 6.2 Commercial

Quick Commercial Structures Estimates: https://evs.e2value.com/evs/est/qce/default.asp QCE Pro Structures Estimates: https://evs.e2value.com/evs/est/cmm/default.asp

### 6.3 Farm and Ranch

Farm and Ranch Structures Estimates: https://evs.e2value.com/evs/est/fnr/default.asp Homestead Structures Estimates: https://evs.e2value.com/evs/est/hsd/default.asp

### 6.4 Pronto ™

Pronto Residential: https://evs.e2value.com/evs/est/pronto\_res\_In/default.aspx
ProntoLite TM Residential: https://evs.e2value.com/evs/est/pronto\_res/default.aspx
Pronto Commercial: https://evs.e2value.com/evs/est/pronto\_cmm/default.aspx
ProntoLite TM Commercial: https://evs.e2value.com/evs/est/pronto\_cmm 3/default.aspx

## 6.5 InVision

InVision Estimates: https://evs.e2value.com/evs/est/invision/default.aspx

## 6.6 InQuest

InQuest Estimates: https://evs.e2value.com/evs/est/inquest/default.aspx

### 6.7 AV3

Residential Banking: https://evs.e2value.com/evs/est/av3/default.aspx

## 6.8 Smart Data Warehouse/Retrieving Past Estimates

The Smart Data Warehouse is where all saved estimates are stored. There is no archiving so all work is live and can be rerun through the estimator at any time.

To directly access the Smart Data Warehouse: https://evs.e2value.com/evs/sdw.asp

## 7 Basic Portico<sup>TM</sup> Integration

### 7.1 Authentication

Authentication is achieved by sending your username, password and virtual username to the following URL:

https://evs.e2value.com/evs/remote\_auth.asp

In the following format:

https://evs.e2value.com/evs/remote\_auth.asp?username=YOUR\_USERNAME&password=YOU R\_PASSWORD&vusername=YOUR\_VIRTUALUSERNAME

The *vusername* parameter allows the "virtual user" access only to his or her own estimates in the Smart Data Warehouse (SDW)<sup>TM</sup>, not access to all properties run by that Portico user. Virtual usernames are not provided by e2Value and instead are freeform data that you choose (e.g. ABCAgency). No setup is required. Once a login occurs with a *vusername* that was not previously in the system, it will automatically become part of the system and will be visible in the SDW.

Note that the value for *vusername* must be URL encoded (to prevent problems if spaces and special characters are used). In general, spaces and special characters should be avoided.

Please post the to URL via a server-side connection, so that your username/password is not available to the end user. Please also ensure that if you have a firewall, outbound connections on Port 80 are allowed.

This page will return an XML formatted response. A successful result looks like:

Unsuccessful results look like:

Where the "<message>" contains the error.

When the response indicates a success, you must take the <authid> and <authcode> parameters to form your link URL, which will look like this:

https://evs.e2value.com/evs/est/bpr/default.asp?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59Ivw3C9r1GS81&ad=1663 (Residential)

or

https://evs.e2value.com/evs/est/bpp/default.asp?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59 lvw3C9r1GS81&ad=1663 (Residential Pro)

or

https://evs.e2value.com/evs/est/exr/default.asp?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59Ivw3C9r1GS81&ad=1663 (Exterior Residential)

or

https://evs.e2value.com/evs/est/flr/default.asp?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59lvw3C9r1GS81&ad=1663 (Full Residential)

or

https://evs.e2value.com/evs/est/ada/default.asp?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59 lvw3C9r1GS81&ad=1663 (Additional Structures)

or

https://evs.e2value.com/evs/est/bpa/default.asp?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59 lvw3C9r1GS81&ad=1663 (A&A)

or

https://evs.e2value.com/evs/est/bap/default.asp?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59 lvw3C9r1GS81&ad=1663 (A&A Pro)

or

https://evs.e2value.com/evs/est/fla/default.asp?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59lvw3C9r1GS81&ad=1663 (Full A&A)

or

https://evs.e2value.com/evs/est/qce/default.asp?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59 lvw3C9r1GS81&ad=1663 (Quick Commercial)

or

https://evs.e2value.com/evs/est/cmm/default.asp?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59Ivw3C9r1GS81&ad=1663 (QCE Pro)

or

https://evs.e2value.com/evs/est/fnr/default.asp?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59Ivw3C9r1GS81&ad=1663 (Farm and Ranch)

or

https://evs.e2value.com/evs/est/hsd/default.asp?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59 lvw3C9r1GS81&ad=1663 (Homestead)

or

https://evs.e2value.com/evs/est/pronto\_res\_In/default.aspx?ac=kHAnhBkdgF6vgT2EYe16NgEb mkXgUyV59Ivw3C9r1GS81&ad=1663 (Pronto™ Residential)

or

https://evs.e2value.com/evs/est/pronto\_res/default.aspx?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59Ivw3C9r1GS81&ad=1663 (Pronto Lite™ Residential)

OI

https://evs.e2value.com/evs/est/pronto\_cmm/default.aspx?ac=kHAnhBkdgF6vgT2EYe16NgEbmk XgUyV59Ivw3C9r1GS81&ad=1663 (Pronto™ Commercial)

or

https://evs.e2value.com/evs/est/pronto\_cmm\_3/default.aspx?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59Ivw3C9r1GS81&ad=1663 (Pronto Lite™ Commercial)

or

https://evs.e2value.com/evs/est/invision/default.aspx?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59lvw3C9r1GS81&ad=1663 (InVision™)

or

https://evs.e2value.com/evs/est/inquest/default.aspx?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59lvw3C9r1GS81&ad=1663 (InQuest™)

or

https://evs.e2value.com/evs/est/av3/default.aspx?ac=kHAnhBkdgF6vgT2EYe16NgEbmkXgUyV59Ivw3C9r1GS81&ad=1663 (AV3 Residential Banking)

Where ac is the <authcode> and ad is the <authid>. NOTE: You must generate an <authcode> and <authid> for each user you send into the system. If you reuse the same authcode/authid, user sessions will be overwritten.

## 7.2 Example - Basic Authentication Routine

The following is sample ASP code that shows how to obtain an <authorde> and <authid> from the server-side:

<%

Dim XMLhttp

Dim XMLResponse

Dim oXML

Dim bResponseOK

Dim oResponseNode

Dim strResponse

Dim authResult

Dim sErrMsg

Dim sAuthCode

Dim sAuthID

sErrMsg = ""

```
Set XMLhttp = Server.CreateObject("MSXML2.ServerXMLHTTP")
XMLhttp.Open "GET",
"https://evs.e2value.com/evs/remote_auth.asp?username=YOUR_USERNAME&password=YOU
R_PASSWORD&vusername=ABCAgency", False
XMLhttp.send
If XMLhttp.Status = 200 Then
       strResponse = XMLhttp.responseText
       Set oXML = Server.CreateObject("Microsoft.XMLDOM")
       oXML.async = False
       bResponseOK = oXML.loadXML(strResponse)
       If bResponseOK Then
              Set oResponseNode = oXML.selectSingleNode("response")
              authResult = oResponseNode.getAttribute("status")
              If authResult = "success" Then
                      sAuthCode = oResponseNode.selectSingleNode("authcode").text
                      sAuthID = oResponseNode.selectSingleNode("authid").text
              Else
                      sErrMsg = oResponseNode.selectSingleNode("message").text
              End If
       Else
              sErrMsg = "Error: Bad response format."
       Fnd If
       Set oXML = Nothing
Else
       sErrMsg = "Error: Connection timeout."
End If
Set XMLhttp = nothing
If sErrMsg = "" Then
       Response.write "AuthCode = " & sAuthCode
       Response.write "<br>"
       Response.write "AuthID = " & sAuthID
Else
       Response.write sErrMsg
End If
%>
This yields:
AuthCode = kHAnhBkqgF6vgT2EYe16NgEbmkXgUyV59Ivw3C9r1GS81
AuthID = 1663
```

https://evs.e2value.com/evs/est/bpr/default.asp?ac=kHAnhBkqgF6vgT2EYe16NgEbmkXgUyV59Ivw3C9r1GS81&ad=1663

# 7.3 Quickstart Example - Full Working Example ASP Page and Code

Which is used to form this link:

Save the following code to an .asp file, change the username and password constants and direct your users to it. No additional work is required, but the HTML output can be custom-tailored to your needs.

```
< @ Language=VBScript %>
Dim e2Value_Link_URL, e2Value_sAuthCode, e2Value_sAuthID, e2Value_sErrMsg,
sVirtualUsername
Const e2Value_Username = "yourusername"
Const e2Value_Password = "yourpassword"
sVirtualUsername = Request("yourvirtualusername")
Call authLinkTo()
If e2Value sErrMsg <> "" Then
       e2Value_Link_URL = "javascript:void(0)"" onclick=""alert('Temporarily unavailable.
Please try refreshing this page. If problem continues, contact technical support.')"
Else
       e2Value Link URL = "https://evs.e2value.com/evs/appselect.asp?ac=" &
e2Value_sAuthCode & "&ad=" & e2Value_sAuthID & """ target=""e2valuewindow"""
End If
Sub authLinkTo()
       Dim XMLhttp, XMLResponse, oXML, bResponseOK, oResponseNode, strResponse
       Dim authResult
       e2Value_sErrMsg = ""
       Set XMLhttp = Server.CreateObject("MSXML2.ServerXMLHTTP")
       XMLhttp.Open "GET", "https://evs.e2value.com/evs/remote_auth.asp?username=" &
e2Value Username & "&password=" & e2Value Password & "&vusername=" &
Server.URLEncode(sVirtualUsername), False
       XMLhttp.send
       If XMLhttp.Status = 200 Then
              strResponse = XMLhttp.responseText
               Set oXML = Server.CreateObject("Microsoft.XMLDOM")
              oXML.async = False
              bResponseOK = oXML.loadXML(strResponse)
              If bResponseOK Then
                      Set oResponseNode = oXML.selectSingleNode("response")
                      authResult = oResponseNode.getAttribute("status")
                      If authResult = "success" Then
                             e2Value sAuthCode =
oResponseNode.selectSingleNode("authcode").text
                             e2Value sAuthID =
oResponseNode.selectSingleNode("authid").text
                      Else
                             e2Value sErrMsg =
oResponseNode.selectSingleNode("message").text
                      End If
               Else
                      e2Value_sErrMsg = "Error: Bad response format."
               End If
               Set oXML = Nothing
       Else
              e2Value_sErrMsg = "Error: Connection timeout."
```

```
End If
    Set XMLhttp = nothing
End Sub
%>
<html>
<head>
    <title>e2Value Link-To</title>
</head>
<body bgcolor="#FFFFF" link="#0000FF" vlink="#0000FF" alink="#0000FF">
<div align="center"><center>
<img
src="https://evs.e2value.com/evs/img/logo_a_162x36.gif" width="162"
 height="36">
 <b><font face="Verdana"
size="2">Expert Valuation System</font></b>
<img
src="https://evs.e2value.com/evs/img/logo_b_162x4.gif" width="162" height="4">
 <img
src="https://evs.e2value.com/evs/img/logo_c_162x3.gif" width="162" height="3">
 >
 <img
src="https://evs.e2value.com/evs/img/logo_d_162x24.gif" width="162"
 height="24">
 <p
align="center"><small><strong></small>
<img
src="https://evs.e2value.com/evs/img/spacer.gif" width="1" height="1">
<img
src="https://evs.e2value.com/evs/img/spacer.gif" width="1" height="1">
 
<img src="https://evs.e2value.com/evs/img/solutions2_181x278.jpg"
    width="181" height="278">
    <div align="center"><center><font face="Arial" size="3"
color="#880000"><b>Click <a href="<% = e2Value_Link_URL %>">here</a> to enter the<font
size="5"><br>e2Value Resource Center</font>
```

```
</b></font>
       </center></div>
        
<div align=center><center>
<img src="./img/spacer.gif" width="1"
height="1">
  
</center></div>
</center></div>
</body>
</html>
```

The sVirtualUsername parameter should come from a form, querystring, or any other source from which the user entered their own virtual username.

If implementing this feature for Farm and Ranch and/or Homestead users, replace appselect.asp with fnrselect.asp and save the file as a new asp page.

If implementing this feature for users of the Quick Commercial estimator, replace appselect.asp with cmmselect.asp and save the file as a new asp page.

## 7.4 After Authenticating – Special Note on JavaScript Popup Windows

If you've designed your system to link to the e2 Value forms via a popup window, the following may be helpful.

Some users have difficulty launching popup windows with the latest versions of Internet Explorer (which include a built-in popup-blocker) and / or third-party popup-blocking software. Consider the following example code to encapsulate your window opening statements:

```
<script language="JavaScript">
<!--
function openWindow(url) {
   var newwin =
window.open(url,'popupwindow1','scrollbars=yes,resizable=yes,width=650,scrollbars=no,height=4
50,location=yes,toolbar=no,status=no,directories=no,menubar=no');

if (newwin == null) {
   alert("\nYour web browser just prevented a pop-up window from opening. Try holding
   down the 'Ctrl' key and clicking the button or link you just clicked.\n\nlf you are interested
   in configuring your popup blocker to avoid this message next time, please visit
   http://www.e2value.com/popupblocker/.\n");</pre>
```

# 7.5 Special Note for Farm and Ranch, Homestead and Quick Commercial Users - Popup Itemizer Window

If you choose to itemize the Equipment/Contents of a structure, a pop up "Itemizer" window is opened. The itemized list is customized based on the structure type that has been selected. It allows the user to select the Items List and then an Item from within the list.

For instance, for "Barn, Bank", the user can select one of three lists – Cattle Equipment, Hog Equipment or Sheep Equipment. If Cattle Equipment is selected, the user is presented a second list consisting of items such as "6" concrete flatwork", "crossing guard" and "hay shelter".

For each item picked from this second list, the user can override the default Unit Price that is presented and also enter a Quantity of that item.

Some users have difficulty launching popup windows with the latest versions of Internet Explorer (which include a built-in popup-blocker) and / or third-party popup-blocking software. You will usually be able to get around this problem by holding down the ctrl button while you try again.

More than one user can be logged into the system using the same username at the same time. The popup Itemizer has been designed to properly handle the Itemizer inputs in such cases.

## 8 PHP Instructions:

## 8.1 Example - Basic Authentication Routine

```
$out = "GET
/evs/remote_auth.asp?username=YOUR_USERNAME&password=YOUR_PASSWORD&vusern
ame=VIRTUAL_USERNAME HTTP/1.0\r\n\r\n";
```

Passing the "vusername" parameter logs the user in under that virtual username.

# 8.2 Quickstart Example - Full Working Example ASP Page and Code

Save the following code to a .php file, change the username and password constants and direct your users to it. No additional work is required, but the HTML output can be custom-tailored to your needs.

```
<?php
$e2Value_Username = "yourusername";
$e2Value_Password = "yourpassword";
$VirtualUsername = "yourvirtualusername";
$e2Value_Link_URL = "";
$authcode = "";
$authid = "";
$err = "":
n = "";
$fp = fsockopen("evs.e2value.com", 80, $errno, $errstr, 30);
// As of PHP 4.3.0, if you have compiled in OpenSSL support, you
// should prefix the hostname with 'ssl://' and use port 443 instead of
// 80 (the second argument) to use an SSL connection over TCP/IP
// to connect to the remote host:
// $fp = fsockopen("ssl://evs.e2value.com", 443, $errno, $errstr, 30);
if (!$fp) {
  $err = "Error: Connection timeout.";
} else {
  $out = "GET /evs/remote_auth.asp?username=" . $e2Value_Username . "&password=" .
$e2Value_Password. "&vusername=" . $VirtualUsername . " HTTP/1.0\r\n\r\n";
  fwrite($fp, $out);
  $body = false;
  while (!feof($fp)) {
    s = fgets(fp, 1024);
    if ($body)
       sin .= ss:
    if ($s == "\n")
       $body = true:
  if(strpos($in,"success")!==false){
```

```
$authcode = substr($in,strpos($in,"<authcode>")+strlen("<authcode>"),
strpos($in,"</authcode>")-strlen("<authcode>")-strpos($in,"<authcode>"));
   $authid = substr($in,strpos($in,"<authid>")+strlen("<authid>"), strpos($in,"</authid>")-
strlen("<authid>")-strpos($in,"<authid>"));
 } else {
   $err = substr($in,strpos($in,"<message>")+strlen("<message>"), strpos($in,"</message>")-
strlen("<message>")-strpos($in,"<message>"));
 }
fclose($fp);
if ($err == "") {
  $e2Value_Link_URL = "https://evs.e2value.com/evs/appselect.asp?ac=" . $authcode . "&ad="
. $authid . "\" target=\"e2valuewindow";
} else {
  $e2Value_Link_URL = "javascript:void(0)\" onclick=\"alert('Temporarily unavailable. Please
try refreshing this page. If problem continues, contact technical support.')";
?>
<html>
<head>
     <title>e2Value Link-To</title>
</head>
<body bgcolor="#FFFFF" link="#0000FF" vlink="#0000FF" alink="#0000FF">
<div align="center"><center>
<img
src="https://evs.e2value.com/evs/img/logo_a_162x36.gif" width="162"
 height="36">
 <b><font face="Verdana"
size="2">Expert Valuation System</font></b>
>
 <img
src="https://evs.e2value.com/evs/img/logo_b_162x4.gif" width="162" height="4">
 >
 <img
src="https://evs.e2value.com/evs/img/logo_c_162x3.gif" width="162" height="3">
 <img
src="https://evs.e2value.com/evs/img/logo_d_162x24.gif" width="162"
 height="24">
 <p
align="center"><small><strong><small>
<img
src="https://evs.e2value.com/evs/img/spacer.gif" width="1" height="1">
```

```
<img
src="https://evs.e2value.com/evs/img/spacer.gif" width="1" height="1">
 
<img src="https://evs.e2value.com/evs/img/solutions2_181x278.jpg"
    width="181" height="278">
    <div align="center"><center><font face="Arial" size="3"
color="#880000"><b>Click <a href="<?php print($e2Value_Link_URL); ?>">here</a> to enter
the<font size="5"><br>e2Value Resource Center</font>
        </b></font>
        </center></div>
         
<div align=center><center>
<img src="./img/spacer.gif" width="1"
height="1">
  
</center></div>
</center></div>
</body>
</html>
```

The \$VirtualUsername parameter should come from a form, querystring, or any other source from which the user entered their own virtual username.

If implementing this feature for Farm and Ranch and/or Homestead users, replace appselect.asp with fnrselect.asp and save the file as a new asp page.

If implementing this feature for users of the Quick Commercial estimator, replace appselect.asp with cmmselect.asp and save the file as a new asp page.

## 9 Advanced Portico™ Integration

When forming your link URL, you may supply additional parameters to your URL. Doing so allows the "client info" and "policy info" section to be pre-populated.

The list of parameters is as follow:

### **Estimator Types:**

BPR - Residential

BPP - Residential Pro

EXR - Exterior Residential

FLR - Full Residential

**BPA - A & A** 

BAP - A & A Pro

ADA - Additional Structures

QCE - Quick Commercial

CMM - QCE Pro

P1C - Pronto Commercial

P3C - Pronto Lite Commercial (3 Question)

P1R - Pronto Residential

P3R – Pronto Lite Residential (3 Question)

FNR – Farm and Ranch

HSD - Homestead

INV - InVision

INQ - InQuest

AV3 - Residential Banking

## 9.1 CA DOI Regulation 2010.00001 Compliance

California Department of Insurance regulation, REG-2010-00001: Standards and Training for Estimating Replacement Value on Homeowners' Insurance went into effect 6/27/2011. In order for your integration to comply with the new regulation you must include the following fields in the data return:

- ArchtectFeesAndPermits
- HouseMaterialsAndLabor
- Overhead
- Profit
- ReplacementCostWithoutDebrisRemoval

These fields and their descriptions are listed on page 27.

### 9.2 Data Parameters

Note: All parameter values should be url-encoded.

\*Not supported by P1R, P3R, P1C, P3C INV and INQ. \*\*Not supported by INQ

Parameter Name	Est. Type	Require d	Max length	Description	Requirements
preload	ALL	Υ	1	Value must be 1	Value must be 1
clientisbusiness	ALL	N	1	Value must be 1 or 0, default is 1	If value is 1 then the business entity name will be the value specified in cln1
cfn1	ALL	N	100	Client First Name	

cmi1	ALL	N	1	Client Middle Initial	
cln1	ALL	N	100	Client Last Name	
cfn2	BPR	N	100	Client First Name 2	
cmi2	BPR	N	1	Client Middle Initial 2	
cln2	BPR	N	100	Client Last Name 2	
ccova	ALL **, †	N	30	Coverage	Must be numeric
ccova	ALL**, †	N	70	Origin of Coverage A	Must be one of the
					following (Previous Coverage, Agent's Estimate, Builder's Estimate, Claims Estimate, Insured's Estimate, Market Value, Purchase Price, Unknown)
paddr1	ALL	N	150	Client Address 1	
paddr2	ALL	N	150	Client Address 2	
pcity	ALL	N	100	Client City	
pstate	ALL	N	2	Client State	
pzip	ALL	N	5	Client Zip	
pi_number	ALL**, †	N	100	Policy Number	
pi carrier	ALL**, †	N	100	Carrier	
pi_agent	ALL**, †	N	100	Agent	
pi_requestor	ALL*,†	N	100	Requestor	
pi_interviewed	ALL*, †	N	100	Person Interviewed	
pi_inspdate	ALL*, †	N	50	Inspection Date	Must be valid date
pi_inspby	ALL*, †	N	100	Inspected By	
pi effdate	ALL**, †	N	50	Effective Date	Must be valid date
pi_agencycode	ALL**, †	N	100	Agency Code	
pi_agencyName	ALL**, †	N	100	Agency Name	
pi add1	ALL**, †	N	100	Agency Address 1	
pi add2	ALL**, †	N	100	Agency Address 2	
pi_city	ALL**, †	N	100	Agency City	
pi_state	ALL**, †	N	2	Agency State	
pi_zip	ALL**, †	N	5	Agency Zip	
pi_phone	ALL**, †	N	10	Agency Phone	
id	ALL	N	100	An unique ID provided by the	
				partner to identify the submitted order. If this field is provided during the initial request, a fieldname called "return_id" will be appended to the return URL along with its unique ID which was provide by the partner.	
u	ALL	N	7000	A return URL provided by the partner. If this field is provided during the initial request, there will be a link created at the final calculation page with the URL provided by the partner.	If no custom fieldnames were used in the return URL, partner should append a character "?" to the end of the URL. (e.g. http://www.returnh ere.com/index.asp

		T		1	?)
postback_rt_aut opostbackurl	BPR EXR	N	5000	A return URL provided by the partner. If this field is provided during the initial request, system will automatically call the provided URL behind the scene.	If no custom fieldnames were used in the return URL, partner should append a character "?" to the end of the URL. (e.g. http://www.returnh ere.com/index.asp ?)
bname	ALL, †	N	50	This is the text of the return URL link that will be display on the final calculation page. If this is not provided during the initial request, a default name will be used.	
propid	ALL	N	10	PropertyID.  If the PropertyID is specified, the user will immediately be taken to the estimator for editing the corresponding property.	The PropertyID value is generated by e2Value and may be returned to the user using the 'rt_propid' value below. If the id entered cannot be found the parameter will be ignored.
yrblt	BPR BPP BPA BAP FLR EXR QCE CMM HSD P3R	N	4	Year Built	Value must be a valid year.
consttype	BPR BPP BPA BAP FLR EXR QCE CMM HSD P3R	N	100	Construction Type	Value must be a valid construction type from those selectable in the e2Value EVS estimator.
sqft	BPR BPP BPA BAP FLR EXR QCE CMM	N	10	Square Feet	Must be a valid numeric value.

	HSD P3R				
rooftype	BPR BPP FLR EXR HSD P3R	N	100	Roof Type	Value must be a valid roof type from those selectable in the e2Value EVS estimator.
roofcov	QCE CMM	N	100	Roof Covering	Value must be a valid roof covering from those selectable in the e2Value EVS estimator.
structtype	QCE CMM	N	100	Structure Type	Value must be a valid structure type from those selectable in the e2Value EVS estimator.
numfloors	QCE CMM	N	4	Number Of Floors	Value must be a valid integer.
ovrlcondition	QCE CMM	N	100	Overall Condition	Value must be a valid overall condition from those selectable in the e2Value EVS estimator.
extwall	QCE CMM	N	100	Exterior Wall	Value must be a valid exterior wall from those selectable in the e2Value EVS estimator.
locale	BPR	N	100	Locale	Values must be valid e2Value locales. Multiple locales can be specify by using   as a separator.  e.g. beachfront suburb an rural
archstyle	BPR P3R	N	100	Architectural Style	Value must be a valid architectural style from those selectable in the e2Value EVS estimator.
constquality	BPR P3R	N	100	Construction Quality	Value must be a valid construction quality from those selectable in the e2Value EVS

					estimator.
shape	BPR P3R	N	100	Physical Shape	Value must be a valid physical shape from those selectable in the e2Value EVS estimator.
exterior1	BPR P3R	N	100	Primary Exterior	Value must be a valid primary exterior from those selectable in the e2Value EVS estimator.
rt_propid	ALL	N	1	Returns the unique Property ID of this property in the return URL specified by the user. Value will be returned as rt_propid= <pre>rt_propid=<pre>cproperty id&gt;</pre> where <pre>cproperty id&gt; is the actual unique</pre> Property ID value of this property.</pre>	The PropertyID value is generated by e2Value. See 'propid' parameter above for further description. Value must be 1 or 0, default is 1
rt_yrblt	BPR BPP BPA BAP FLR EXR P1R P3R P1C P3C QCE CMM FNR HSD	N	1	Returns the Year Built in the return URL specified by the user. Value will be returned as rt_yrblt= <year> where <year> is the actual Year Built value of this property. In QCE, CMM, FNR, and HSD, returns the year built of each structure in the property separated by a " " character in the return URL specified by the user. Value will be returned as rt_yrblt=<yrblt1 yrblt2 yrblt3 etc< td=""><td>Value must be 1 or 0, default is 1</td></yrblt1 yrblt2 yrblt3 etc<></year></year>	Value must be 1 or 0, default is 1
rt_consttype	BPR BPP BPA BAP FLR EXR P1R P3R P1C P3C QCE CMM FNR HSD	N	1	Returns the Construction Type in the return URL specified by the user. Value will be returned as rt_consttype= <construction type=""> where <construction type=""> is the actual Construction Type value of this property.  In QCE, CMM, FNR, and HSD, returns the construction type of each structure in the property separated by a " " character in the return URL specified by the user. Value will be returned as rt_consttype=<consttype1 consttype2 consttype3 etc></consttype1 consttype2 consttype3 etc></construction></construction>	Value must be 1 or 0, default is 1
rt_sqft	BPR BPP BPA BAP FLR EXR	N	1	Returns the Square Feet in the return URL specified by the user.  Value will be returned as  rt_sqft= <square feet=""> where  <square feet=""> is the actual  Square Feet value of this</square></square>	Value must be 1 or 0, default is 1

	DAD				
rt_rooftype	P1R P3R P1C P3C QCE CMM FNR HSD	N	1	property. In QCE, CMM, FNR, and HSD, returns the square feet of each structure in the property separated by a " " character in the return URL specified by the user. Value will be returned as rt_sqft= <sqft1 sqft2 sqft3 etc> Returns the Roof Type in the</sqft1 sqft2 sqft3 etc>	Value must be 1 or
Т_тоокуро	BPP FLR EXR P1R P3R P1C P3C			return URL specified by the user. Value will be returned as rt_rooftype= <roof type=""> where <roof type=""> is the actual Roof Type value of this property.</roof></roof>	0, default is 1
rt_numStories	P1R P3R P1C	N	1	Returns the number of stories in the return URL specified by the user. Value will be returned as rt_numStories= <number of="" stores=""></number>	Value must be 1 or 0, default is 1
rt_structtype	QCE CMM FNR HSD	N	1	Returns the structure type of each structure in the property separated by a " " character in the return URL specified by the user. Value will be returned as rt_structtype= <structtype1 structty pe2 structtype3 etc=""></structtype1 structty>	Value must be 1 or 0, default is 1
rt_roofcov	QCE CMM FNR HSD	N	1	Returns the roof covering of each structure in the property separated by a " " character in the return URL specified by the user. Value will be returned as rt_roofcov= <roofcov1 roofcov2 roofcov3 etc></roofcov1 roofcov2 roofcov3 etc>	Value must be 1 or 0, default is 1
rt_numfloors	QCE CMM FNR HSD	N	1	Returns the number of floors of each structure in the property separated by a " " character in the return URL specified by the user. Value will be returned as rt_numfloors= <numfloors1 numfloors2 numfloors3 etc></numfloors1 numfloors2 numfloors3 etc>	Value must be 1 or 0, default is 1
rt_ovrlcondition	QCE CMM FNR HSD	N	1	Returns the overall condition of each structure in the property separated by a " " character in the return URL specified by the user. Value will be returned as rt_ovrlcondition= <ovrlcondition1 ovrlcondition2 ovrlcondition3 etc></ovrlcondition1 ovrlcondition2 ovrlcondition3 etc>	Value must be 1 or 0, default is 1
rt_extwall	QCE CMM FNR	N	1	Returns the exterior wall type of each structure in the property separated by a " " character in the	Value must be 1 or 0, default is 1

	HSD			return URL specified by the user.	
				Value will be returned as rt_extwall= <extwall1 extwall2 ext wall3 etc=""></extwall1 extwall2 ext>	
rt_locale	BPR	N	1	Specify if you want locales to be returned.	Value must be 1 or 0, default is 0
rt_archstyle	BPR P3R	N	1	Specify if you want architectural style to be returned.	Value must be 1 or 0, default is 0
rt_constquality	BPR P3R	N	1	Specify if you want construction quality to be returned.	Value must be 1 or 0, default is 0
rt_shape	BPR P3R	N	1	Specify if you want physical shape to be returned.	Value must be 1 or 0, default is 0
rt_exterior1	BPR P3R	N	1	Specify if you want primary exterior to be returned.	Value must be 1 or 0, default is 0
nopopup	ALL	N	1	If the <i>nopopup</i> parameter is specified and set to 1, the return URL will open in the same browser window as the estimate rather than in a popup window which is the default behavior.	Value must be 1 or 0, default is 0.
goToSDW	ALL	N	1	If the <i>goToSDW</i> parameter is specified and set to 1, the system will bypass the estimator and any other specified CML parameters and take the user directly to the Smart Data Warehouse. If the <i>u</i> parameter was also specified, then a return button will appear in the SDW pointing back to the URL that the user specified. The <i>bname</i> and <i>nopopup</i> parameters can also be used in this case to control the settings of the return button.	Value must be 1 or 0, default is 0.
rt_rpctype	BPR BPP BPA BAP FLR EXR BPA P1R P3R P1C P3C QCE CMM FNR HSD	N	1	Returns the Replacement Cost Type in the return URL specified by the user. Value will be returned as rt_rpctype= <re>replacement cost type&gt; where &lt; replacement cost type&gt; is the actual Replacement Cost Type value of this property. Possible return values for the Replacement Cost Type are "full", "func" (for "functional"), or an empty value if none exists for this property.</re>	Value must be 1 or 0, default is 0.

rt_areas	P1R P3R	N	1	Returns the additional areas in the return URL specified by user. Value will be returned as rt_areas= <areas>. For <areas>, Columns are separated by   and rows are separated by a line break.</areas></areas>	Value must be 1 or 0, default is 0.
				For example: garage, attached 1997 500 1/2 Story 1997 600	
				Note: Column 1 = area name Column 2 = year built Column 3 = sqft	

#### Examples:

https://evs.e2value.com/evs/est/bpr/default.asp?ac=hE5ke7hnCC0RdQyBVAxZkdB6jhUCRvSZ3f stY92oxDP2X&ad=406767&preload=1&cfn1=test&cmi1=t&cln1=riskmetertest&cfn2=test2&cmi2=2&cln2=riskmetertest2&ccova=%24750%2C0000%2E00&ccovao=Previous+Coverage&paddr1=123+test&paddr2=apt+%23+2&pcity=bay+shore&pstate=ny&pzip=11706&pi\_carrier=carrier&pi\_n umber=12345678&pi\_requestor=requestor&pi\_interviewed=interviewed&pi\_effdate=8%2F1%2F2006&pi\_inspdate=8%2F10%2F2006&pi\_inspby=inspectby&pi\_agencyName=agency+name&pi\_add1=add1&pi\_add2=add2&pi\_city=bay+shore&pi\_state=ny&pi\_zip=11706&pi\_phone=1111111111&pi\_agencycode=1234567&pi\_agent=agent&id=12345&u=http%3A%2F%2Fwww%2Ee2value%2Ecom%2Flinkto%2Fcml%2Findex%2Easp%3F&bname=Return+to+System (Residential)

or

https://evs.e2value.com/evs/est/qce/default.asp?ac=3zs9Yt3CXxPHXgNwlvnp9XwS73kxhKiprZH lourDMyfQn&ad=406764&preload=1&cfn1=test&cmi1=t&cln1=riskmetertest&cfn2=test2&cmi2=2 &cln2=riskmetertest2&ccova=%24750%2C0000%2E00&ccovao=Previous+Coverage&paddr1=1 23+test&paddr2=apt+%23+2&pcity=bay+shore&pstate=ny&pzip=11706&pi\_carrier=carrier&pi\_nu mber=12345678&pi\_requestor=requestor&pi\_interviewed=interviewed&pi\_effdate=8%2F1%2F20 06&pi\_inspdate=8%2F10%2F2006&pi\_inspby=inspectby&pi\_agencyName=agency+name&pi\_ad d1=add1&pi\_add2=add2&pi\_city=bay+shore&pi\_state=ny&pi\_zip=11706&pi\_phone=1111111111 &pi\_agencycode=1234567&pi\_agent=agent&id=12345&u=http%3A%2F%2Fwww%2Ee2value%2 Ecom%2Flinkto%2Fcml%2Findex%2Easp%3F&bname=Return+to+System (Quick Commercial)

or

https://evs.e2value.com/evs/est/cmm/default.asp?ac=72uB1v7EzzRjZiPyMxOrBZyUA7mzjMkrt3J KqwSfO0hsp&ad=406766&preload=1&cfn1=test&cmi1=t&cln1=cmlcmmtest&cfn2=test2&cmi2=2 &cln2=cmlcmmtest2&ccova=%24750%2C0000%2E00&ccovao=Previous+Coverage&paddr1=12 3+test&paddr2=apt+%23+2&pcity=bay+shore&pstate=ny&pzip=11706&pi\_carrier=carrier&pi\_nu mber=12345678&pi\_requestor=requestor&pi\_interviewed=interviewed&pi\_effdate=8%2F1%2F20 06&pi\_inspdate=8%2F10%2F2006&pi\_inspby=inspectby&pi\_agencyName=agency+name&pi\_ad d1=add1&pi\_add2=add2&pi\_city=bay+shore&pi\_state=ny&pi\_zip=11706&pi\_phone=1111111111 &pi\_agencycode=1234567&pi\_agent=agent&id=12345&u=http%3A%2F%2Fwww%2Ee2value%2 Ecom%2Flinkto%2Fcml%2Findex%2Easp%3F&clientisbusiness=1&bname=Return+to+System

## (QCE Pro)

If a return URL was provided by the partner using the 'u' parameter during the initial request, there will be a link created at the final calculation page with the URL provided by the partner. Several return parameters will be appended to this URL and are listed as follows:

	T-4	
Parameter Name	Est.	Description
	Type	Description
return_ad	ALL†	Returns the authid value used during the initial request.
return_rpc**	ALL†	Returns the calculated replacement cost value.
FinalRCVInclusiveOfDebri	ALL†	Returns "Final RCV Inclusive of Debris Removal" if
sRemoval**		property is located in California.
DebrisRemoval**	ALL†	Returns "Debris Removal" if property is located in California.
ArchtectFeesAndPermits**	ALL†	Returns "Architect's Fees and Permits" if property is located in California.
HouseMaterialsAndLabor* *	ALL†	Returns "House Materials and Labor" if property is located in California.
Overhead**	ALL†	Returns "Overhead" if property is located in California.
Profit**	ALL†	Returns "Profit" if property is located in California.
ReplacementCostWithout DebrisRemoval**	ALL†	Returns "Replacement Cost WITHOUT Debris Removal" if property is located in California.
return_structuresrpc**	BPR BPP	Returns the calculated replacement cost value of other structures. For QCE, CMM, FNR, and HSD see
	FLR QCE CMM FNR HSD	note below.
return_unique**	BPR BPP FLR	Returns the total value of any unique items entered.
return_ACV**	BPR BPP FLR QCE CMM FNR HSD	Returns the ACV value. For QCE, CMM, FNR, and HSD see note below.
return_id	ALL	Returns the contents of the 'id' parameter if specified by the partner during the initial request.
av3_wv	AV3	AV3 Weighted Value
av3_rt	AV3	Report Type
av3_rd	AV3	Report Date
av3_ed	AV3	Effective Date
av3_tn	AV3	Tracking Number
av3_ln	AV3	Loan Number
av3_pt	AV3	Product Type
av3_bn	AV3	Borrower Name
av3_iusr	AV3	Intended User
av3_iu	AV3	Intended Use
av3_scah	AV3	Sales Comparable Approach (High)
av3_scal	AV3	Sales Comparable Approach (Low)
av3_scal	AV3	Sales Comparable Approach (Low)

av3_scac	AV3	Sales Comparable Approach (Confidence Score)
av3_cavh	AV3	Cost Approach to Value (High)
av3_cavl	AV3	Cost Approach to Value (Low)
av3_cavc	AV3	Cost Approach to Value (Confidence Score)
av3_iavh	AV3	Income Approach to Value (High)
av3_iavl	AV3	Income Approach to Value (Low)
av3_iavc	AV3	Income Approach to Value (Confidence Score)
av3_caprate	AV3	Cap Rate
av3_fico	AV3	FICO Score
av3_olv	AV3	Orderly Liquidation Value
av3_flv	AV3	Forced Liquidation Value

<sup>\*\*</sup> Not supported by INV and INQ

## Note: When using return parameters in QCE, CMM, FNR, and HSD:

- The **return\_structuresrpc** parameter will include the replacement cost for each structure in the property separated by a "|" (pipe) character.
- The return\_ACV parameter will include the ACV range for each structure in the property separated by a "|" (pipe) character.

## 9.3 Commercial Variable Lists

consttype (Construction Type)
A - frame fireproof structural steel frame foam form concrete framing, steel framing, wood framing, wood with elevated slab hoop arch masonry bearing walls masonry, block masonry, brick masonry, stone metal frame metal frame (slant) milled timbers pole frame post and beam prefabricated quonset reinforced concrete frame stucco on masonry veneer, brick veneer, brick with wood frame veneer, stone wood frame, modular
roofcov (Roof Covering)
acrvlic

<sup>†</sup> Not supported by AV3

bituthene, self-seal

built-up composition, high rise, 3 ply

built-up composition, low rise, 3 ply

built-up tar and gravel

copper clad stainless steel

copper, standing seam

corrugated aluminum

corrugated composition

corrugated fiberglass

corrugated galvanized iron

Dibiten

earth covered

glass panels

metal other than standing seam

metal, standing seam

plastic, elastomeric membrane

plastic, elastomeric membrane, loose, trocal

plastic, elastomeric membrane, neoprene

polycarbonate panels

polyethylene film

rubber

shakes, cedar

shakes, wood

shingles, aluminum tab

shingles, architectural

shingles, asbestos replacement

shingles, asphalt

shingles, cedar

shingles, composition

shingles, composition asphalt

shingles, dimensional asphalt

shingles, fiberglass tabs

shingles, Minera

shingles, porcelain enamel

shingles, wood

silicone, 3 ply, rolled

steel

tile, barrel

tile, clay, flat bed

tile, clay, glazed, interlock

tile, clay, Spanish

tile, concrete, flat

tile, concrete, interlock

tile, concrete, premium

tile, Ludowici

tile, slate

tile, slate, graduated

tile, slate, patterned

tile, slate, red

tile, slate, synthetic

urethane foam, silicone cover

### structtype (Structure Type)

-----

Apartment

Auditorium

Auto, mini-lube

Auto, sales/showroom

Auto, service center

Auto, service repair

Bank, branch

Bar/Tavern

Beauty Salon/Barber Shop

Bowling alley

Car wash

Church

Cold storage facility

College, dormitory

Community center

Concession stand

Condominium

Convenience market

Country club

Courthouse

Day care center

Dispensary/urgent care

Dressing and shower facility

Fire station, paid

Fire station, volunteer

Fraternal building

Funeral home

Garage, parking

Garage, underground parking

Government building

Greenhouse

Handball/racquetball club

Hangar, aircraft

Health club

Home improvement center

Hospital, convalescent

Hospital, general

Hospital, veterinary

Hotel

Indoor tennis club

Jail

Laboratory

Laundromat

Library, public

Manufacturing, heavy

Manufacturing, light

Medical office

Motel

Multi-family residence

Multiple residence, elderly

Office

Pavilion, open

Post office, branch

Post office, main

Prison

Restaurant

Restaurant, fast food

Restroom building

Rink, hockey

School, elementary

School, gymnasium

School, secondary

School, vocational

Shopping center, strip

Social club

Store, department

Store, discount

Store, retail

Supermarket

Surgical center

Swimming pool, enclosed

Terminal, airport

Terminal, bus

Theater, movie

Warehouse

Warehouse, mini storage

Warehouse, self storage

## ovrlcondition (Overall Condition)

\_\_\_\_\_

excellent

above average

average

below average

poor

## extwall (Exterior Wall)

brick veneer, face brick

brick veneer, glazed

brick veneer, jumbo

brick veneer, large

brick veneer, norman

brick veneer, roman

brick veneer, standard

brick wall, cavity

brick wall, reinforced

concrete block

concrete block, glazed

concrete block, slumpstone

concrete block, split face

concrete wall, cast in place

metal siding, aluminum, simulated wood

metal siding, baked enamel

metal siding, corrugated aluminum

metal siding, corrugated aluminum, painted

metal siding, corrugated composition

metal siding, corrugated fiberglass

metal siding, corrugated galvanized iron

metal siding, porcelain

panels, brick

panels, cement fiber

panels, concrete block

panels, fiberglass

panels, glass and aluminum

panels, glass and metal

panels, polycarbonate (greenhouse)

panels, rubble

panels, sandwich

panels, stone

panels, stucco

polyethylene film (greenhouse)

precast concrete panel

precast concrete panel, granite finish

siding, barn board

siding, board and batten

siding, cedar beveled

siding, cedar shingles

siding, glasweld

siding, hardboard

siding, lap board

siding, plywood

siding, redwood beveled

siding, spaced board

siding, tongue and grove

siding, vinyl

stone veneer, arizona stone

stone veneer, granite

stone veneer, lava stone

stone veneer, limestone

stone veneer, rubble

stone veneer, sandstone

stucco

tilt-up, concrete wall

tilt-up, concrete wall, with pilasters

## 9.4 Residential Variable Lists

architectural style (non-manufactured homes)

2 - Family Home

3 - Family Home

4 - Family Home

A - Frame

Adirondack

Adobe

American 4-Square

Architecturally Unique

Art Deco

Art Moderne

Arts and Crafts Style

**Basic** 

Beaux Arts

Bi - level

Brownstone

Brownstone, Bowfront Victorian

Brownstone, Bowfront Victorian - End Unit

Brownstone, End Unit

Brownstone, Victorian

Brownstone, Victorian - End Unit

Bungalow

California Ranch

Cape Cod

Castle - like

Chalet

Charleston

Chateau

City House

City House, Art Deco

City House, Art Deco - End Unit

City House, Art Moderne City House, Art Moderne - End Unit

City House, Beaux Arts Classical

City House, Beaux Arts Classical - End Unit

City House, End Unit

City House, Gothic

City House, Gothic - End Unit

City House, International Style

City House, International Style - End Unit

City House, Itallianate

City House, Itallianate - End Unit

City House, Neo-Classical

City House, Neo-Classical - End Unit

City House, Renaissance Revival

City House, Renaissance Revival - End Unit

City House, Romanesque

City House, Romanesque - End Unit

City House, Second Empire

City House, Second Empire - End Unit

City House, Sullivanesque

City House, Sullivanesque - End Unit

Classical Revival

Colonial

Colonial, Dutch

Colonial, Eclectic

Colonial, French

Colonial, New England Style

Colonial, Revival

Colonial, Southern

Colonial, Spanish

Colonial, Tract

Conch

Contemporary

Contemporary, California

Contemporary, English

Contemporary, French

Contemporary, Tudor

Contractor Modern

Converted Barn

Cottage

Country Style

Craftsman Style

Deconstruction

Designed by a Famous Architect

Duplex

Earth Shelter, Bermed

Earth Shelter, Hillside

Earth Shelter, Underground

English Style

European Influenced

Farmhouse

Federal

Fourplex

French Provincial

French Style

Georgian

Georgian Revival

German Stone

Gingerbread

Gothic Revival

Greek Revival

Gulf Coast Style

High Ranch

International Style

Italian Villa

Italianate

Key West Style

Log

Mansion

Mediterranean

Mission Style

Moderne

Monterey Style

Normandy Style

Octagon

One - of - a - Kind

Palatial

Period

Post Modern

Prairie Style

Public Building-like

Pueblo

Queen Anne

Raised Cape

Raised Ranch

Rambler

Ranch

Regency

Richardsonian Romanesque

Santa Barbara

Santa Fe Style

Second Empire

Shingle Style

Shotgun Style

Southampton Style

Spanish Mission

Spanish Revival

Spanish Style

Split entry

Split level

Stick, Eastern

Stick, Western

Townhouse

Townhouse, End Unit

Townhouse, Federal Style

Townhouse, Federal Style - End Unit

Townhouse, Georgian Style

Townhouse, Georgian Style - End Unit

Tract home

Tri - level

Triplex

Tudor

Vernacular/Folk

Victorian

Wrightian

### construction\_quality (non-manufactured homes)

-----

above average / upgraded

average / standard

basic / economic

expensive / custom

modest / fair

opulent / museum quality

very expensive / luxury

### physical\_shape

-----

angular (few to no right angles)

complicated

contemporary

curvy (extensive curves)

H - shaped

I - shaped

L - shaped

octagonal

rectangular

rectangular with angled wing

rounded

square

T - shaped

U - shaped

unique

## construction\_type (non-manufactured homes)

A - frame

autoclaved aerated concrete

foam form concrete

framing, steel

framing, wood

framing, wood with elevated slab

log

masonry, block

masonry, brick

masonry, stone

modular, wood frame poured concrete rammed earth stick structural insulated panel stucco on frame

stucco on masonry

timber/post & beam

veneer, brick

veneer, brick with wood frame

veneer, stone

### primary\_exterior / secondary\_exterior

-----

adobe

aluminum siding

asbestos replacement, cement fiber

asphalt

autoclaved aerated concrete, exposed

autoclaved aerated concrete, painted

board and batten

brick masonry

brick w/block backup

brownstone

cedar siding

cement fiber

clapboard

clay tile

concrete block

concrete block, painted

concrete, reinforced

decorative wood shingle

Drivit/EIFS

glass block

glass panels

half log siding

hardboard

limestone

local stone

log (<11"diameter)

log (>11"diameter)

Masonite

metal siding

paint

plywood with batts

precast concrete

precast stone

rammed earth

redwood siding

siding, log

solid stone

steel siding

stone rubble

stucco

stucco over masonry

stucco with half timbering

stucco, slick finish

stucco, smooth coat

stucco, Tuscan finish

T1-11 siding

Tabby siding

veneer, common brick

veneer, face brick

veneer, rubble

veneer, stone

vinyl siding

wood shake/shingle

wood siding

wood stresskin panels

### primary\_roof\_covering / secondary\_roof\_covering (n/a for geodesic domes)

-----

aluminum

architectural shingle

asbestos shingle replacement

asphalt shingle

barrel tile

cedar shingle/shake

cement fiber

clay tile

composition roll

composition shingle

composition, built-up

concrete tile

Dibiten

dimensional asphalt shingle

earth covered

Elastomeric

**EPDM** membrane

fiberglass shingle

glass panel

glazed tile

hail proof shingle

Lamarite shingle

Ludowici tile

metal other than standing seam

metal, corrugated

metal, ribbed

Minera shingle

polyurethane foam

PVC membrane

red slate

rubber

slate

slate, graduated

slate, patterned

slate, synthetic

Spanish tile

standing seam copper

standing seam metal

steel

tar and gravel

TPO membrane wood shake wood shingle

### locale

\_\_\_\_\_

beachfront city, large city, medium city, small coastal

exclusive pocket gated community

island, accessible by boat only island, accessible by bridge

remote, moderate remote, slight remote, very resort rural suburban

town urban waterfront

#### state

\_\_\_\_\_

Alabama

Alaska Arizona

Arkansas

California

Colorado

Connecticut

Delaware

District of Columbia

Florida Georgia

Hawaii

Idaho

Illinois

Indiana

Iowa

Kansas

Kentucky

Louisiana

Maine

Maryland

Massachusetts

Michigan

Minnesota

Mississippi

Missouri

Montana

Nebraska

Nevada

New Hampshire

**New Jersey** 

New Mexico

New York

North Carolina

North Dakota

Ohio

Oklahoma

Oregon

Pennsylvania

Rhode Island

South Carolina

South Dakota

Tennessee

Texas

Utah

Vermont

Virginia

Washington

West Virginia

Wisconsin

Wyoming

## 9.5 Streaming PDF Return

Please visit the XML Integration Center at <a href="https://evs.e2value.com/evs/xml">https://evs.e2value.com/evs/xml</a> for information related to receiving the appraisal output in a PDF format. All the information is listed under "Streaming PDF Return."