Universidad de San Carlos de Guatemala Facultad de Ingeniería Escuela de Ciencias y Sistemas Redes de Computadoras 2

<u>Práctica 1</u> <u>MANUAL TECNICO</u>

Leonardo Roney Martínez Maldonado - 201780044 Cesar Leonel Chamale Sican - 201700634 Julio Enrique Wu Chiu - 201906180

Marcos Enrique Curtidor Sagui – 201900874

MANUAL TECNICO

subredes resultantes

| Subred | Nº de Hosts | IP de red | Máscara Primer Host | | Último Host | Broadcast | |
|----------|-------------|--------------------|---------------------|----------------|----------------|----------------|--|
| Subred 1 | 62 | 192.168.88.0 /26 | 255.255.255.192 | 192.168.88.1 | 192.168.88.62 | 192.168.88.63 | |
| Subred 2 | 62 | 192.168.88.64 /26 | 255.255.255.192 | 192.168.88.65 | 192.168.88.126 | 192.168.88.127 | |
| Subred 3 | 62 | 192.168.88.128 /26 | 255.255.255.192 | 192.168.88.129 | 192.168.88.190 | 192.168.88.191 | |
| Subred 4 | 62 | 192.168.88.192 /26 | 255.255.255.192 | 192.168.88.193 | 192.168.88.254 | 192.168.88.255 | |

Configuración:

| | <u>Configuración</u> | | | |
|---|--|--|--|--|
| 1 | Switch0 | | | |
| | Configuracion de vtp server enable config t vtp domain grupo8 vtp password grupo8 vtp mode server | | | |
| | VLAN | | | |
| | enable config t vlan 18 name Ventas vlan 28 name Distribucion exit vlan 38 name Administracion exit vlan 48 name Servidores exit vlan 99 name Management&Native exit | | | |

vlan 999 name BlackHole exit

MODO TRONCAL

enable config t interface range fa0/1-2 switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005

InterVLAN

config t
int vlan18
ip address 192.168.88.62 255.255.255.192
exit
int vlan28
ip address 192.168.88.126 255.255.255.192
exit
int vlan38
ip address 192.168.88.190 255.255.255.192
exit
int vlan48
ip address 192.168.88.254 255.255.255.192
ip routing

STP

enable configure terminal spanning-tree mode rapid-pvst end

configure terminal spanning-tree mode pvst end

sh spanning-tree summary

• BLACKHOLE (SEGURIDAD)

//show interface status configure terminal interface range fa0/3-24 switchport mode access switchport access vlan 999 end configure terminal interface range gig0/1-2 switchport mode access switchport access vlan 999 exit

VLAN NATIVA 99 (SEGURIDAD)

configure terminal interface range fa0/1-2show switchport trunk native vlan 99

DESACTIVAR DTP (SEGURIDAD)

configure terminal interface range fa0/1-2 switchport nonegotiate

2 Switch1

• Configuracion de vtp client

enable config t vtp domain grupo8 vtp password grupo8 vtp mode client

MODO TRONCAL

enable config t interface fa0/1 switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005

exit interface fa0/6 switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 exit

MODO ACCESO

enable config t interface fa0/7 switchport mode access switchport access vlan 18 exit interface fa0/8 switchport mode access switchport access vlan 28

PORT CHANEL /*LACP*/

enable config t interface range fa0/2-3 channel-protocol lacp channel-group 1 mode active exit interface range fa0/4-5 channel-protocol lacp channel-group 3 mode active exit interface port-channel 1 switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 exit interface port-channel 3 switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005

/*DESACTIVAR LAGP O PAGP*/

enable conf t interface range fa0/2-3 no channel-protocol no channel-group exit no interface port-channel 1 interface range fa0/4-5 no channel-protocol no channel-group exit no interface port-channel 3 end

/*PAGP*/

enable config t interface range fa0/2-3 channel-protocol pagp channel-group 1 mode desirable exit interface range fa0/4-5 channel-protocol pagp channel-group 3 mode desirable

STP

enable configure terminal spanning-tree mode rapid-pvst end

sh spanning-tree summary

• BLACKHOLE (SEGURIDAD)

configure terminal interface range fa0/9-24 switchport mode access switchport access vlan 999 end configure terminal interface range gig0/1-2 switchport mode access switchport access vlan 999 exit

VLAN NATIVA 99 (SEGURIDAD)

--show interface trunk configure terminal interface fa0/1 switchport trunk native vlan 99 exit interface fa0/6 switchport trunk native vlan 99 exit interface port-channel 1 switchport trunk native vlan 99 exit interface port-channel 3 switchport trunk native vlan 99 exit

DESACTIVAR DTP (SEGURIDAD)

configure terminal interface fa0/1-6 switchport nonegotiate exit

PORT SECURITY (SEGURIDAD)

configure terminal interface range fa0/7

switchport port-security switchport port-security maximum 5 switchport port-security violation shutdown switchport port-security mac-address sticky exit interface range fa0/8 switchport port-security switchport port-security maximum 1 switchport port-security violation shutdown switchport port-security mac-address sticky exit 3 Switch2 Configuracion de vtp client enable config t vtp domain grupo8 vtp password grupo8 vtp mode client MODO TRONCAL enable config t interface fa0/3 switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 exit interface fa0/8 switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 exit PORT CHANEL /*LACP*/ enable config t interface range fa0/1-2 channel-protocol lacp channel-group 1 mode active exit

interface range fa0/6-7 channel-protocol lacp channel-group 2 mode active exit interface range fa0/4-5 channel-protocol lacp channel-group 5 mode active exit interface port-channel 1 switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 exit interface port-channel 2 switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 exit interface port-channel 5 switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005

/*DESACTIVAR LAGP O PAGP*/

conf t interface range fa0/1-2 no channel-protocol no channel-group exit no interface port-channel 1 interface range fa0/6-7 no channel-protocol no channel-group exit no interface port-channel 2 interface range fa0/4-5 no channel-protocol no channel-group exit no interface port-channel 5 end

enable

/*PAGP*/

enable config t interface range fa0/1-2 channel-protocol pagp channel-group 1 mode desirable exit interface range fa0/6-7 channel-protocol pagp channel-group 2 mode desirable exit interface range fa0/4-5 channel-protocol pagp channel-group 5 mode desirable

STP

enable configure terminal spanning-tree mode rapid-pvst end

sh spanning-tree summary

• BLACKHOLE (SEGURIDAD)

//show interface status configure terminal interface range fa0/9-24 switchport mode access switchport access vlan 999 end configure terminal interface range gig0/1-2 switchport mode access switchport access vlan 999 exit

• VLAN NATIVA 99 (SEGURIDAD)

--show interface trunk configure terminal interface fa0/3 switchport trunk native vlan 99 exit interface fa0/8 switchport trunk native vlan 99 exit interface port-channel 1 switchport trunk native vlan 99 exit interface port-channel 2 switchport trunk native vlan 99 exit interface port-channel 5 switchport trunk native vlan 99 exit

DESACTIVAR DTP (SEGURIDAD)

configure terminal interface range fa0/1-8 switchport nonegotiate exit

| 4 | Switch3 | | | | |
|---|-----------------------------|--|--|--|--|
| | Configuracion de vtp client | | | | |
| | enable | | | | |
| | config t | | | | |
| | vtp domain grupo8 | | | | |
| | vtp password grupo8 | | | | |
| | vtp mode client | | | | |
| | | | | | |
| | MODO TRONCAL | | | | |
| | enable | | | | |
| | config t | | | | |
| | interface range fa0/1-2 | | | | |

switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 exit

MODO ACCESO

enable config t interface fa0/8 switchport mode access switchport access vlan 28 exit interface fa0/7 switchport mode access switchport access vlan 38

PORT CHANEL /*LACP*/

enable config t interface range fa0/3-4 channel-protocol lacp channel-group 2 mode active exit interface range fa0/5-6 channel-protocol lacp channel-group 4 mode active exit interface port-channel 2 switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 exit interface port-channel 4 switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 exit

/*DESACTIVAR LAGP O PAGP*/

enable conf t interface range fa0/3-4 no channel-protocol no channel-group exit no interface port-channel 2 interface range fa0/5-6 no channel-protocol no channel-group exit no interface port-channel 4 end

/*PAGP*/

enable config t interface range fa0/3-4 channel-protocol pagp channel-group 2 mode desirable exit interface range fa0/5-6 channel-protocol pagp channel-group 4 mode desirable

STP

enable configure terminal spanning-tree mode rapid-pvst end

sh spanning-tree summary

• BLACKHOLE (SEGURIDAD)

//show interface status configure terminal interface range fa0/9-24 switchport mode access switchport access vlan 999 end configure terminal interface range gig0/1-2 switchport mode access switchport access vlan 999 exit

VLAN NATIVA 99 (SEGURIDAD)

configure terminal interface range fa0/1-2 switchport trunk native vlan 99 interface port-channel 2 switchport trunk native vlan 99 exit interface port-channel 4 switchport trunk native vlan 99 exit

DESACTIVAR DTP (SEGURIDAD)

configure terminal interface range fa0/1-6 switchport nonegotiate exit

PORT SUCURITY (SEGURIDAD)

configure terminal interface range fa0/7 switchport port-security switchport port-security maximum 1 switchport port-security violation shutdown switchport port-security mac-address 0009.7C28.DDC8 exit interface range fa0/8

switchport port-security
switchport port-security maximum 1
switchport port-security violation shutdown
switchport port-security mac-address sticky
exit
switchport port-security

| 5 | Switch4 |
|---|---|
| | Configuracion de vtp client enable config t vtp domain grupo8 vtp password grupo8 vtp mode client |
| | MODO TRONCAL enable config t interface range fa0/1-3 switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 |
| | enable config t interface fa0/4 switchport mode access switchport access vlan 48 exit interface fa0/5 switchport mode access switchport mode access switchport access vlan 18 |

STP

enable configure terminal spanning-tree mode rapid-pvst end

sh spanning-tree summary

• MANDAR AL HOYO NEGRO (SEGURIDAD)

//show interface status configure terminal interface range fa0/6-24 switchport mode access switchport access vlan 999 end configure terminal interface range gig0/1-2 switchport mode access switchport access vlan 999 exit

• DESACTIVAR DTP (SEGURIDAD)

configure terminal interface range fa0/1-3 switchport nonegotiate exit

• VLAN NATIVA 99 (SEGURIDAD)

configure terminal interface range fa0/1-3 switchport trunk native vlan 99

PORT SUCURITY (SEGURIDAD) conf t interface range fa0/5 switchport port-security switchport port-security maximum 5 switchport port-security violation shutdown switchport port-security mac-address sticky exit

| 6 | Switch5 | | | | |
|---|---|--|--|--|--|
| | Configuracion de vtp client enable config t vtp domain grupo8 vtp password grupo8 vtp mode client | | | | |
| | MODO TRONCAL | | | | |
| | enable config t interface fa0/3 switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 exit interface fa0/6 switchport mode trunk switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 exit | | | | |
| | MODO ACCESO | | | | |
| | enable config t interface fa0/9 switchport mode access switchport access vlan 28 exit interface fa0/10 | | | | |

switchport mode access switchport access vlan 38

PORT CHANEL /*LACP*/

enable config t interface range fa0/4-5 channel-protocol lacp channel-group 5 mode active exit interface range fa0/1-2

channel-protocol lacp channel-group 3 mode active

exit

interface range fa0/7-8 channel-protocol lacp

channel-group 4 mode active

exit

interface port-channel 3 switchport mode trunk

switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 exit

interface port-channel 4 switchport mode trunk

switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 exit

interface port-channel 5 switchport mode trunk

switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 end

/*DESACTIVAR LAGP O PAGP*/

enable conf t interface range fa0/4-5 no channel-protocol no channel-group exit no interface port-channel 5 interface range fa0/1-2 no channel-protocol no channel-group exit no interface port-channel 3 interface range fa0/7-8 no channel-protocol no channel-group exit no interface port-channel 4 end /*PAGP*/ enable config t interface range fa0/4-5 channel-protocol pagp channel-group 5 mode desirable exit interface range fa0/1-2 channel-protocol pagp channel-group 3 mode desirable exit interface range fa0/7-8 channel-protocol pagp channel-group 4 mode desirable end STP enable configure terminal spanning-tree mode rapid-pvst end sh spanning-tree summary BLACKHOLE (SEGURIDAD) //show interface status configure terminal interface range fa0/11-24 switchport mode access switchport access vlan 999 end

configure terminal interface range gig0/1-2 switchport mode access switchport access vlan 999 exit

DESACTIVAR DTP (SEGURIDAD)

configure terminal interface range fa0/1-8 switchport nonegotiate exit

• VLAN NATIVA 99 (SEGURIDAD)

configure terminal interface fa0/3 switchport trunk native vlan 99 exit interface fa0/6 switchport trunk native vlan 99 exit interface port-channel 3 switchport trunk native vlan 99 exit interface port-channel 4 switchport trunk native vlan 99 exit interface port-channel 5 switchport trunk native vlan 99 exit

PORT SUCURITY (SEGURIDAD)

conf t
interface range fa0/9
switchport port-security
switchport port-security maximum 1
switchport port-security violation shutdown
switchport port-security mac-address sticky
exit

interface range fa0/10
switchport port-security
switchport port-security maximum 1
switchport port-security violation shutdown
switchport port-security mac-address 000A.4189.A6A3
exit

| 7 | Switch6 | | | | |
|---|--|--|--|--|--|
| | Configuracion de vtp client enable | | | | |
| | config t | | | | |
| | vtp domain grupo8 | | | | |
| | vtp password grupo8 | | | | |
| | vtp mode client | | | | |
| | end | | | | |
| | MODO TRONCAL | | | | |
| | enable config t | | | | |
| | interface range fa0/1-3 | | | | |
| | switchport mode trunk | | | | |
| | switchport trunk allowed vlan 1,18,28,38,48,99,999,1002-1005 | | | | |
| | exit | | | | |
| | MODO ACCESO | | | | |
| | enable config t | | | | |
| | config t interface fa0/4 | | | | |
| | switchport mode access | | | | |
| | switchport access vlan 18 | | | | |
| | exit | | | | |
| | interface fa0/5 | | | | |
| | switchport mode access | | | | |
| | switchport access vlan 48 end | | | | |
| | STP RAPID PVST | | | | |
| | enable | | | | |
| | configure terminal | | | | |
| | spanning-tree mode rapid-pvst | | | | |
| | end | | | | |
| | | | | | |

STP PVST

enable configure terminal spanning-tree mode pvst end

sh spanning-tree summary

• BLACKHOLE (SEGURIDAD)

//show interface status configure terminal interface range fa0/6-24 switchport mode access switchport access vlan 999 end configure terminal interface range gig0/1-2 switchport mode access switchport access vlan 999 exit

DESACTIVAR DTP (SEGURIDAD)

configure terminal interface range fa0/1-3 switchport nonegotiate exit

VLAN NATIVA 99 (SEGURIDAD)

configure terminal interface range fa0/1-3 switchport trunk native vlan 99

• PORT SUCURITY (SEGURIDAD)

conf t interface range fa0/4 switchport port-security switchport port-security maximum 5 switchport port-security violation shutdown switchport port-security mac-address sticky exit

• Para limpiar la tabla de mac

clear port-security all

| 8 | CONFIGURACION DE IP's | | | | |
|---|--|--|--|--|--|
| | | | | | |
| | • VENTAS - 192.168.88.0 | | | | |
| | PC0 | | | | |
| | ipconfig 192.168.88.1 255.255.255.192 192.168.88.62 | | | | |
| | PC2 | | | | |
| | ipconfig 192.168.88.2 255.255.255.192 192.168.88.62 | | | | |
| | 1p001111g 102.100.00.2 200.200.102 102.100.00.02 | | | | |
| | PC5 | | | | |
| | ipconfig 192.168.88.3 255.255.255.192 192.168.88.62 | | | | |
| | DISTRIBUIO/ON 400 400 00 64 | | | | |
| | DISTRIBUCION - 192.168.88.64 PC1 | | | | |
| | ipconfig 192.168.88.65 255.255.255.192 192.168.88.126 | | | | |
| | The same and the s | | | | |
| | PC3 | | | | |
| | ipconfig 192.168.88.66 255.255.255.192 192.168.88.126 | | | | |
| | PC7 | | | | |
| | ipconfig 192.168.88.67 255.255.255.192 192.168.88.126 | | | | |
| | peering realisation and an arrangement of the property of the | | | | |
| | ADMINISTRACION - 192.168.88.128 | | | | |
| | PC4 | | | | |
| | ipconfig 192.168.88.129 255.255.255.192 192.168.88.190 | | | | |
| | PC6 | | | | |
| | ipconfig 192.168.88.130 255.255.255.192 192.168.88.190 | | | | |
| | | | | | |
| | | | | | |
| | | | | | |
| | | | | | |

• SERVIDOR - 192.168.88.192 SERVER1

--- ipconfig 192.168.88.193 255.255.255.192 192.168.88.254

SERVER2

--- ipconfig 192.168.88.194 255.255.255.192 192.168.88.254

ANEXO:







DIAGRAMA DE TOPOLOGIA:





IP's



Vlan's

| F | Vlan1 | | Down | 1 | <not set=""></not> | <not set=""></not> | 0002.17E1.8AD5 |
|---|------------|----------|-----------|--------|--------------------|----------------------|------------------------------------|
| 1 | Vlan18 | | Up | 18 | 192.168.88.62/26 | <not set=""></not> | 0002.17E1.8A01 |
| | Vlan28 | | Up | 28 | 192.168.88.126/26 | <not set=""></not> | 0002.17E1.8A02 |
| | Vlan38 | | Up . | 38 | 192.168.88.190/26 | <not set=""></not> | 0002.17E1.8A03 |
| | Vlan48 | | Up | 48 | 192.168.88.254/26 | <not set=""></not> | 0002.17E1.8A04 |
| | Physical L | ocation: | Intercity | > Home | City > Corporate | Office > Main Wiring | Closet > Rack > Multilayer Switch0 |

Blackhole

