Template Type Deduction

C++模板类型推导

对于如下的C++模板类型推导

```
1 template<typename T>
2 void f(ParamType param);
3 f(expr);// 根据expr推导T和ParamType
```

要分三钟情况:

Case 1 ParamType是引用或指针,且不是Universal Reference

- 首先,如果expr是引用类型,则C++模板类型推导时会忽略参数expr 的reference-ness。
- 然后,对ParamType的推导决定对T的推导

正常情况下,expr的constness会被保留,但是下面代码中函数f(const T¶m)参数型中已经有const关键字时,则T只就不再含有constness。

```
1 #include <iostream>
2 using namespace std;
3 template<typename T>
4 void f(const T& param) // 此时T被推导为int, param的类型为
    const int &
        cout << param << endl;</pre>
        T tmp = 2019; // 正常运行
       tmp += 1;
9
        cout << tmp << endl;</pre>
10 }
11
   void g(T& param) // 此时T被推导为const int, param的类型为
    const int &
13 {
14
        cout << param << endl;</pre>
        T tmp = 2019; // error, 无法编译
16
       tmp += 1;
17
        cout << tmp << endl;</pre>
18 }
19
20 int main()
21 {
22
        int x = 27; // as before
23
        const int& rx = x; // as before
```

```
24  f(rx); // T is int
25  g(rx); // T is const int
26  return 0;
27 }
```

指针型的推导类似。

Case 2 ParamType是Universal Reference

Universal Reference翻译成通用引用?

这种情况,没那么明显直观了。模板类型的声明有点像右值引用(rvalue references, T&&)。但是当expr是左值(lvaue)时,推导行为有点"怪异"。

- 如果expr是一个左值(lvalue),则T和ParamType都被推导为lvaue references。这很不常见。首先,在模板类型推导中,这是唯一一个 把T推导为引用的场景。其次,尽管ParamType是用rvalue reference 的语法来声明的,但是其推导出来的类型是lvalue reference。
- 如果expr是一个rvalue,则应用普通的推导规则(如, Case 1的规则)

举例:

```
1 template<typename T>
2 void f(T&& param); // param is now a universal
    reference
3 int x = 27; // as before
4 const int cx = x; // as before
5 const int& rx = x; // as before
6 f(x); // x is lvalue, so T is int&,
7 // param's type is also int&
8 f(cx); // cx is lvalue, so T is const int&,
9 // param's type is also const int&
10 f(rx); // rx is lvalue, so T is const int&,
11 // param's type is also const int&
12 f(27); // 27 is rvalue, so T is int,
13 // param's type is therefore int&&, 右值(rvalue)
```

Case 3 ParamType既不是指针也不是引用

当ParamType即不是指针也不是引用时,则按值传递(pass-by-value):

```
1 template<typename T>
2 void f(T param); // param is now passed by value
```

这意味着无论传进来的是什么,param都是一份copy,一个全新的object。

- 和之前一样,如果expr是引用类型,则忽略referenceness
- 如果忽略过referenceness后,expr是const的,则也忽略constness。 如果expr是volatile的,则也忽略。

因此:

```
int x = 27; // as before
const int cx = x; // as before
const int& rx = x; // as before
f(x); // T's and param's types are both int
f(cx); // T's and param's types are again both int
f(rx); // T's and param's types are still both int
```

注意尽管上面的cx和rx是const的,但param却不是const的。expr是const的,即不能修改,并不意味着它的copy也是不能修改的。

只有在按值传递时const(和volatile)才会被忽略。对于引用或指针类的 parameters, constness是要保留的。

```
template<typename T>
void f(T param); // param is still passed by value
const char* const ptr = // ptr is const pointer to
const object
"Fun with pointers";
f(ptr);
```

注意上面的代码中ptr是按值传递的,param的类型是const char*。

总结:

- 在模板类型推导时, 忽略reference-ness
- 在推导universal references类型的paramterer时,lvalue类型的 arguments要特殊对待
- 当推导按值传递的parameters时,const和volatile类型的arguments 被当作non-const和non-volatile处理
- 在模板类型推导时,数组或函数作为arguments时,它们会退化为 pointers。(除非它们用于初始化引用)

参考:

Effective Modern C++