

Loadscope User Guide

Precision rifle load development for Mac & Windows

Version 1.15.0 · [loadscope.app](#)

ONCE PER RIFLE

Create New Load — set up your rifle

Click Create New Load in the left sidebar. Step 1 is your rifle and setup. Loadscope writes it into your workbook for you — no typing into spreadsheet cells.

Rifle & Setup

LOAD NAME

Load name: 6.5 Creedmoor - 140gr

RIFLE

Rifle: 6.5 Creedmoor

Cartridge: 6.5 Creedmoor

Barrel: Pick or type a barrel

Round count: 0 Total rounds through this barrel. Loadscope adds each imported session automatically; use + Add for rounds you didn't import.

Optic: Pick or type an optic

Chrono: Pick or type yours

Scope click (turret): 0.1 Mil

Sight height (in):

Barrel twist:

LOAD COMPONENTS

Bullet: .264 / 6.5 mm Hornady 140gr ELD-M (.264) .326 G7

Projectile length (in):

Powder: H4350

Primer: Choose your primer...

Brass: Pick or type a brand

TEST SESSION

Test: Powder ladder Seating depth Barrel tuner Factory ammo

CBTO (in): what you seated them all at

Date: 08/25/26

Typical distance (yd): 100

Next: Plan your ladder →

Just save for now

- 1 Load a saved setup — pick a previous setup from this dropdown to fill everything in, or start a new one by filling in the fields below. Loadscope saves what you enter, so it's in this dropdown next time.
- 2 Rifle & Shooter — rifle, optic, cartridge, scope-click. Set once; pick it from the dropdown next time.
- 3 Load Components — bullet, powder, primer, brass. The bullet picker also feeds the ballistic solver.
- 4 Projectile length — optional, and you can usually leave it alone. Picking your bullet fills this in from the maker's published figure where there is one, and Loadscope estimates it otherwise. The box tells you which you are getting. Type a number only if you have measured the bullets in front of you with calipers — makers publish an approximate length and it can differ from the lot you actually bought, so your own measurement wins. This is the length of the bullet on its own, not a loaded round.
- 5 Click Next → to move on to planning your ladder.

PLAN YOUR LADDER

Plan your ladder

Enter your ladder one time and Loadscope lists every load to make.

Then shoot them in order — lowest charge to highest, or highest to lowest if you set the plan to High → Low. Shooting in order is how Loadscope matches each string to the right charge. This is the key to the whole process.

Record by hand at the range? Tools → Print Ladder Sheet prints your planned charges in shooting order, with blank spaces for speeds and conditions (powder and seating-depth ladders).

Want an earlier load back? Click Past Loads... on the Import Data screen (next to the Working on: name at the top) or on the Loads tab in Libraries. It lists every load you have filed away, including ones you never saved to the Library.

Reworking a load? Use Rework a Saved Load on the Home screen — it opens here with that load's rifle already filled in.

- 1 Powder ladder, Seating depth or Barrel tuner — pick which test this is. A powder ladder steps the charge; a seating test steps the seating depth, entered either as a CBTO (2.780 in) or as a jump off the lands (0.020 in) — whichever way you think about it; a tuner test steps the setting on your tuner dial and leaves your load alone.
- 2 Enter it once: your starting charge, the step between charges, and how many. Loadscope lists every load below so you know exactly what to load.

The screenshot shows the 'Create New Load' screen in the Loadscope app. The interface is dark-themed with orange accents. On the left is a sidebar menu with options: Home, Rifle & Setup, Measure Target, Import Data, Results, Range & DOPE, DOPE Card, Recipe Card, Libraries, and Compare Loads. The main area is titled 'Create New Load' and 'STEP 2 OF 2 - PLAN YOUR LADDER'. It specifies 'Loading for: 6.5 Creedmoor · H4350'. There are three test type buttons: 'Powder ladder' (selected), 'Seating depth', and 'Barrel tuner'. Below, it says 'Powder (set in Rifle & Setup): H4350'. The 'Charges' section has 'Even increments' selected, with an 'Enter my charges' button. It features three sliders: 'Start charge (gr)' set to 41.0, 'Step (gr)' set to 0.2, and 'Number of steps' set to 8. A 'Shots per string' slider is set to 5. A note states: 'Under 5 shots per charge, a ladder can rarely tell one charge from the next. Loadscope tells you either way on Results.' Below this, 'Your loads:' are listed as a sequence: P1 41.0, P2 41.2, P3 41.4, P4 41.6, P5 41.8, P6 42.0, P7 42.2, P8 42.4. A summary line reads '8 loads - 41.0 to 42.4 gr'. At the bottom, there is a 'Back' button and a 'Measure Target' button. The footer of the app shows 'Phone Sync - Off', 'Phone targets (3)', and 'User Guide'.

TRACK BARREL LIFE

Track rounds per barrel

Loadscope keeps a running round count for every barrel — set it once and it stays current on its own.

The screenshot shows the 'Rifle & Setup' section of the Loadscope application. The interface is divided into several sections: 'LOAD NAME', 'RIFLE & SHOOTER', 'LOAD COMPONENTS', and 'TEST SESSION'. The 'Rifle & Setup' section is currently active, showing fields for 'Load name', 'Rifle', 'Shooter', 'Cartridge', 'Barrel', 'Round count', 'Optic', 'Chrono', and 'Scope click (turret)'. The 'Round count' field is set to 0, and there is a '+ Add' button next to it. The 'LOAD COMPONENTS' section includes fields for 'Bullet', 'Powder', 'Primer', 'Brass', and 'Distance (yd)'. The 'TEST SESSION' section includes a 'Test' dropdown menu with options 'Powder ladder', 'Seating depth', and 'Factory ammo', and a 'Powder test CBTO (in)' field. At the bottom, there is a 'Next: Plan your ladder' button and a 'Just save for now' link.

Rifle & Setup
Loadscope writes this straight into your workbook.

LOAD NAME

Load name: 6.5 Creedmoor - 140gr

RIFLE & SHOOTER

Rifle: 6.5 Creedmoor

Shooter: Type the shooter's name

Cartridge: 6.5 Creedmoor

Barrel: Pick or type a barrel

Round count: 0 [+ Add](#) Total rounds through this barrel. Loadscope adds each imported session automatically; use + Add for rounds you didn't import.

Optic: Pick or type an optic

Chrono: Pick or type yours

Scope click (turret): 0.1 Mil

LOAD COMPONENTS

Bullet: Other (type it)

140gr ELD-M

Powder: H4350

Primer: Choose your primer...

Brass: Pick or type a brand

Distance (yd): 100

TEST SESSION

Test: Powder ladder Seating depth Factory ammo

Powder test CBTO (in): Powder-only test (no seating)

Date: 08/13/26

[Next: Plan your ladder →](#)

[Just save for now](#)

Round count lives right on Rifle & Setup, tied to the barrel you entered.

Set a starting number once — every import adds that session's rounds automatically.


Shot rounds you didn't import (practice, matches)? Click + Add and type how many.

Switch barrels and the count follows — each barrel keeps its own total.

EVERY RANGE DAY

Shoot, then drop your files

Back from the range? Drop the files your chronograph and target app export onto the drop zone — or click Browse — then Run Import.




- 1 Drop zone — bring in your chronograph file (and a target app's export too, if you use one). The Chronograph and Target app chips show where each kind goes.
- 2 Click Run Import. Loadscope backs up your workbook first, matches everything to your ladder, and shows your results right inside the app.

FASTER IMPORTS

Import a whole folder

Point Loadscope at a whole range-day folder and it imports everything inside — no file-by-file dragging.



Drag a whole range-day folder onto Loadscope, or click Browse folder.

It pulls every chronograph file inside — and your target app's exports too, if you use one — including subfolders, in one shot. It doesn't care what the files are called or what format they're in.


Each file's format is auto-detected, so you never sort them by hand.

Individual files still work the same way — point it at a folder when that's faster.

NO TARGET APP NEEDED

Measure your target groups from a photo

Don't run a target app? The Measure Target page measures your group right in Loadscope and scores it like any import.



- 1 Bring in your groups — Import from phone pulls groups you measured on the Loadscope app. Choose target photos lets you measure on the desktop.

- 2 Set the scale — drag a line across a known length (a 1-inch grid square) and type what it measures. Work in inches, mm, MOA or mil, whichever your target is printed in — many shooters run a mil-dot scope and a mil grid. That turns pixels into real measurements, so every number is honest.

- 3 Set your aiming point — click Move aim and drop the crosshair on your point of aim. Loadscope then measures how far the group sits off that aim — elevation and windage — not just its size.

- 4 Mark shots — tap each bullet hole. Loadscope works out group size, mean radius and vertical, and scores it under its charge.


- 5 It saves itself — once you've marked the number of shots your ladder plan expects, Loadscope saves that target for you. There's no Save button to remember. When every group sits on its own photo it stays put afterwards, so you can drag the result and recipe boxes clear of your group before you move on; the button you press next is the one that's lit.

- 6 Powder ladder / Seating depth / Barrel tuner — three buttons that set what each bull is: a powder charge, a seating depth or a tuner setting. Measure a whole ladder on one sheet

THE ANSWER

Your best powder charge

The Results screen leads with your winner. The gold BEST LOAD bar at the top is the suggested charge — picked from the loads you tested. Three per-winner buttons sit right under the numbers.



Three buttons under the numbers — Save this load to Library, Generate Recipe Card (printable recipe in your browser), and Save as PDF.

- 1 BEST LOAD — the winning charge weight, scored across velocity flat-spot, SD, mean radius and vertical SD. Need at least 3 charges (plan 5–8 in a ladder).
- 2 Powder Charges — your real worksheet, right in the app. Composite Score: lower is better.
- 3 Winner column — 1st / 2nd / 3rd ranking so you can see the runners-up.

HOW THE SCORE IS BUILT

Scoring — why this charge won

The Scoring sub-tab shows the scoring math — exactly why a charge won, and lets you tune what matters to you.

Four things are scored: velocity flat-spot, velocity SD, mean radius and vertical SD. Each is put on the same scale, then blended into one composite score — lowest wins.

The four are NOT weighted equally, and the mix is not a fixed table — Loadscope sets it from the distance you tested at. Up close, mean radius leads and velocity barely counts. At distance, velocity SD takes over, because that is what opens your groups up vertically the further you shoot.

A powder ladder at 100 yards comes out at mean radius 40%, vertical SD 35%, velocity SD 20% and flat-spot 5%. By 1000 yards velocity SD has climbed to 50% and mean radius has dropped to 25%. A seating test is weighted differently again: velocity barely counts at all (10%), mean radius carries it up close at 65%, and vertical SD grows to 40% by 1000 yards.

Tune what matters to you — every weight is yours to set on the Scoring tab. Nudge one and re-score. Use recommended weights hands the dial back to Loadscope.

The screenshot shows the 'Results' tab in the Loadscope application. The interface is dark-themed with orange accents. On the left is a sidebar with navigation options: Home, Rifle & Setup, Measure Target, Import Data, Results (highlighted), Range & DOPE, Pocket Card, Load Card, Libraries, Compare Loads, and a '+ Create New Load' button. The main content area displays the 'BEST LOAD' and 'POWDER LADDER' results. At the top, it shows '57.8 gr' as the winning charge. Below this, a message states: 'Your winner: 57.8 gr - with 58 right there with it. At 10 shots a charge there's nothing between them. That's two good loads, not one doubtful one.' The 'SCORED ON THESE 4 METRICS' section lists: AVG VELOCITY (2763 fps, Flat-spot ✓), VELOCITY SD (3.5 fps, SD ✓), MEAN RADIUS (0.112 in, MR ✓), and VERTICAL SD (0.067 in, Vert ✓). The 'LOAD' section shows 'POWDER: H4350' and 'BEST CHARGE: 57.8 gr'. A 'TEST CBTO' button is labeled 'Not set - Open Setup ->'. A large box contains the instruction: 'Next: Create New Load, switch it to Seating depth, and test seating depth at the winning charge.' Below this are buttons for 'Save this load to Library', 'Generate Load Card', and 'Save as PDF...'. The bottom section, 'POWDER LADDER WEIGHTS', shows sliders for: FLAT-SPOT (5%), VELOCITY SD (20%), MEAN RADIUS (40%), and VERTICAL SD (35%), totaling 100%. A 'Re-score with these weights' button is present. A text box explains: 'Set from your test distance. Near 100 yd, mean radius leads — 5 / 20 / 40 / 35 (flat-spot / velocity SD / mean radius / vertical). By 1000 yd velocity SD takes over — 5 / 50 / 25 / 20 — because the charge turns into vertical downrange. Every weight is a slider — tune it and re-score. How did we land on these weights? ->'. At the very bottom, it says 'SCORE FOR ANOTHER DISTANCE'.

READ THE FLAT-SPOT

Charts with ± 1 SD error bars

The charts live on the sub-tab where the data is: open Powder Charges for the velocity and velocity-SD charts, Seating Depths for the mean-radius and vertical-SD charts. Every charge is graphed with ± 1 SD error bars so your velocity flat-spot is obvious at a glance.



Every charge is plotted with ± 1 SD error bars on each point.

A flat run of points with short whiskers is your velocity flat-spot — it pops right out.

The winning charge is highlighted on the curve.

Hit Save chart image for a clean PNG to keep or share.

THE SEATING ANSWER

Your best seating depth

The Seating Depth view — same logic, but the bar at the top picks the winning CBTO instead of the winning charge.

Results: Your best load from everything you tested — winning charge and seating depth, scored across all four metrics. [Copy summary](#) [Refresh](#) [View worksheet in Excel](#)

BEST LOAD · POWDER LADDER

57.8 gr [Why this WON](#)

Your winner: 57.8 gr - with 58 right there with it.
At 10 shots a charge there's nothing between them. That's two good loads, not one doubtful one.
6.5 Creedmoor · Hornady 140gr ELD-M · H4350

SCORED ON THESE 4 METRICS

AVG VELOCITY	VELOCITY SD	MEAN RADIUS	VERTICAL SD
2763 fps	3.5 fps	0.112 in	0.067 in
Flat-spot ✓	SD ✓	MR ✓	Vert ✓

LOAD: POWDER: H4350

BEST CHARGE: 57.8 gr

TEST CBTO: Not set · [Open Setup](#)

→ Next: Create New Load, switch it to Seating depth, and test seating depth at the winning charge.

[Save this load to Library](#) [Generate Load Card](#) [Save as PDF...](#)

Powder Charges Scoring Seating Depths

Powder Charge Log — your real worksheet

Why your winning charge won. The trophy row shows that charge's performance during the powder ladder test — measured at the seating depth you used for the ladder, NOT your final load's seating depth. Your final load's actual numbers live on Seating Depth Log > Best Load here.

[Edit charges](#)

	A	B	C	D	E	F	G	H	I	J	K	L	M	N	O
1	6.5 Creedmoor - 140gr — POWDER CHARGE LOG														
2	Winning charge: 57.8 gr														
3	Best in: All metrics ✓														
4															
5	Load	Charge	Shot 1	Shot 2	Shot 3	Shot 4	Shot 5	Avg Vel	ES	SD	MR (in)	Vertical (in)	VertSD (in)	Comp.	Pos.
6	1	57.0	2685	2690	2693	2697	2699	2700	28	9.0	0.260	0.617	0.156	0.765	
7	2	57.2	2709	2713	2716	2719	2721	2722	25	8.0	0.220	0.522	0.132	0.582	
8	3	57.4	2732	2736	2739	2742	2743	2744	22	7.0	0.180	0.427	0.108	0.392	
9	4	57.6	2751	2755	2757	2759	2760	2760	17	6.0	0.128	0.304	0.077	0.092	3rd

Phone Sync — Off

User Guide

- 1 BEST CBTO — the winning seating depth, scored across the same four factors. Shown the way you entered the ladder: a CBTO (base to bullet ogive) or a jump off the lands. Plan at least 3; 5–7 is plenty.
- 2 CBTO (in) — each row's tested seating depth. Loadscope fills these from your seating-depth strings, matched in order by your ladder plan (nothing to name).
- 3 Winner column — 1st / 2nd / 3rd by composite score. Save to Library to keep your confirmed load.

THE TUNER ANSWER

Your best tuner setting

Running a barrel tuner? Loadscope scores each setting you shoot on group height and mean radius, then names your best setting and the plateau of good settings beside it. Your powder charge and seating depth stay where they are — only the dial changes.

Pick Barrel tuner on the Plan your ladder screen, then enter your start setting, the step in marks, and how many settings you want to shoot. Enter Marks per turn as well — how many marks make one full turn of your tuner, 50 on a Cortina V3. That is what tells Loadscope the last setting on the dial sits next to the first.

Shoot one group at each setting, in the order listed, and measure them the way you measure any target. Loadscope pairs each group to its setting by position, so there is nothing to name.

Velocity is deliberately left out of a tuner score. It barely moves with tuner position, so scoring it would be measuring your ammunition and calling it a tuner result.

Settings too close together to tell apart are reported as too close to call rather than ranked — three-shot groups will do that often. You set how the score splits between group height and mean radius on the Scoring screen.

BEFORE YOU SHOOT

Range & DOPE

From your winning load and the measured muzzle velocity, Loadscope predicts your full DOPE table — 100 to 1000 yards.

Loadscope

Home

Rifle & Setup

Measure Target

Import Data

Results

Range & DOPE

Pocket Card

Load Card

Libraries

Compare Loads

+ Create New Load

Phone Sync — Off

Quick Guide

Range Session & DOPE

Grey = predicted. Type what you dialed (in Mils) and the cell turns solid = confirmed.

Predicted from — BC Drag model

Temp F Read from Press inHg DA

Latitude Where you shoot — feeds Corolls (tick Show Corolls). Leave blank to skip it.

Predicted from BC 0.326 G7 (database (Hornady G7)).

Sg 1.88 · SpnD 0.2 Mils at 1000 yd · Aero Jump -0.35 MOA in a 10 mph full value · hCor 0.1 Mils at 1000 yd

Session date: Distances — first: step: Apply View: Target mph:

Range in yd · holds in Mils · ToF in seconds	10 mph full value	windage	target speed
Range Elev Clicks Wind SpnD * hCor * ToF Lead *			
100 0.0 0 0.1 0.0 0.0 0.11 2.2 predicted			
200 0.5 5 0.3 0.0 0.0 0.23 2.2 predicted			
300 1.1 11 0.5 0.1 R 0.0 0.35 2.3 predicted			
400 1.9 19 0.6 0.1 R 0.0 0.48 2.4 predicted			
500 2.8 28 0.8 0.1 R 0.0 0.62 2.4 predicted			
600 3.7 37 1.0 0.1 R 0.0 0.77 2.5 predicted			
700 4.7 47 1.2 0.1 R 0.1 R 0.93 2.6 predicted			
800 5.8 58 1.4 0.1 R 0.1 R 1.09 2.7 predicted			
900 7.1 71 1.6 0.2 R 0.1 R 1.27 2.8 predicted			
1000 8.4 84 1.8 0.2 R 0.1 R 1.46 2.9 predicted			

Wind is a 10 mph full value — halve it for 5, double it for 20, and take the crosswind component for anything off 3 or 9 o'clock. Lead is for the target speed you set. * = not applied to the solution. SpnD and hCor push RIGHT, so ADD them to a left-to-right wind and SUBTRACT them from a right-to-left wind. Lead depends on which way the target is moving.

Save DOPE

- 1 Predicted from your bullet's BC and drag model (G7/G1 solver, checked against published Applied Ballistics figures). Adjust BC / temp / pressure, hit Update to re-solve.
- 2 Grey, italic = predicted. Type what you actually dialed at the range and the cell turns solid = confirmed. Type two of them and Loadscope fills in the ranges between, and carries your correction a little further out — to 600 yards, no further. Past that it goes back to a plain prediction rather than guessing.
- 3 Click Save DOPE to write it back. Always confirm by live fire at known distance before you trust it.

TAKE IT WITH YOU

DOPE Card

A 4×6 range card you can print or save as PDF. Predicted to start; the numbers you dialed replace them as you shoot.

Loadscope

Home

Rifle & Setup

Measure Target

Import Data

Results

Range & DOPE

Pocket Card

Load Card

Libraries

Compare Loads

+ Create New Load

Pocket Range Card

Your printable 4x6 DOPE card. Predicted to start; your confirmed numbers replace them at the range.

This card is showing predicted dials. Open Range & DOPE and click Save DOPE to keep them — then confirm each value at the range.

Loadscope™

POCKET RANGE CARD

6.5 Creedmoor • Hornady 140gr ELD-M • 57.8gr • 2763 fps

Scope: — Click: — Zero: 100 yd Sight Ht: 1.75 in Twist: 1:8 RH

PREDICTED DOPE (italic rows) - estimated from your bullet, velocity & atmosphere. VERIFY AT THE RANGE before relying on these values.

Range (yd)	Elevation (Mils)		Wind 10 mph (Mils)		SpnD (Mils)	hCor (Mils)	Lead 4 mph (Mils)	Drop (in)	Vel (fps)	Energy (ft-lb)	TOF (s)
	Hold	Clicks	Hold	Clicks							
100	0	0	0.1	1	0.0	0.0	2.2	0	2621	2136	0.11
200	0.5	5	0.3	3	0.0	0.0	2.2	3	2483	1918	0.23
300	1.1	11	0.5	5	0.1	0.0	2.3	12	2350	1717	0.35
400	1.9	19	0.6	6	0.1	0.0	2.4	28	2220	1533	0.48
500	2.8	28	0.8	8	0.1	0.0	2.4	50	2095	1365	0.62
600	3.7	37	1	10	0.1	0.0	2.5	80	1974	1212	0.77
700	4.7	47	1.2	12	0.1	0.1	2.6	119	1857	1072	0.93
800	5.8	58	1.4	14	0.1	0.1	2.7	169	1743	945	1.09
900	7.1	71	1.6	16	0.2	0.1	2.8	229	1632	828	1.27
1000	8.4	84	1.8	18	0.2	0.1	2.9	303	1524	723	1.46

Generated Aug 13, 2026

Print layout: Field - two 4x6 cards per page

Open Print Card

The print layout above only changes what comes out of your printer — this preview stays the same. Opens the card in your browser, use the browser's Print to print on card stock, or Save as PDF.

- 1

Header — the load, scope, zero, sight height, twist. Everything you need on a card glanced at in the field.
- 2

Dial table — elevation and clicks in your turret's own units (mil or MOA — Loadscope reads which from your scope-click setting), a fixed 10 mph wind reference, drop, velocity, energy, and time of flight per 100 yards. Print the 4×6 card or Save as PDF.
- 3

Whose number is it — grey italic is our prediction, solid is what you dialed, and a shaded row is worked out from two of your own. A line under the table says how many ranges you have confirmed and where the projection stops.

KEEP THE RECIPE

Print your Recipe Card

The Recipe Card is the one-page printable recipe you produce with the buttons on Results (Generate Recipe Card and Save as PDF...). Bullet, powder, charge, primer, brass, CBTO, plus the performance numbers that won — everything you'd need to load it again next season, on a single sheet.

Loadscope

Load Card
The build sheet for your current winning load -- components, charge, seating depth, and its velocity and group numbers. Print it or save it with the load.

6.5 Creedmoor
6.5 CREEDMOOR · LOADSCOPE LOAD CARD

SUGGESTED WINNING LOAD - POWDER LADDER

POWDER CHARGE	CBTO	POWDER TYPE
57.8 gr	— in	H4350

COMPONENTS

Bullet	Bullet weight	Powder
Hornady 140gr ELD-M	140 gr	H4350
Primer	Brass	CBTO
—	—	—

RIFLE & SETUP

Rifle	Barrel	Cartridge
6.5 Creedmoor	—	6.5 Creedmoor
Optic	Chrono	Distance tested
—	—	100 yd

PERFORMANCE AT SUGGESTED LOAD

Avg velocity	SD	Group	Mean radius
2763 fps	3.5 fps	0.280 in (0.27 MOA)	0.112 in (0.11 MOA)
Vertical SD			
0.067 in (0.06 MOA)			

Generated by Loadscope from 6.5 Creedmoor - 140gr on August 13, 2026 at 07:36 AM - Always cross-check loads against published reloading manuals.

Phone Sync — Off

Quick Guide

Open the card in your browser, use the browser's Print to print it, or Save as PDF to keep it with the load.


Open Print Card

- 1 Print button — right on the page. One click sends the recipe to your printer for the binder on your bench.
- 2 Suggested winning load — the same charge, CBTO, and powder from your Results screen, restated for a printed header.
- 3 Components + Rifle setup — every part of the recipe and the rifle it ran on.
- 4 Performance at suggested load — the avg velocity, SD, group, and mean radius the winning load actually produced.

LOADS OVER TIME

Your Load Library

Every load you save with the Save this load to Library button ends up in your Load Library — across cartridges, rifles, and seasons. Right-click any row for the actions you'll use most.




The Library lives inside the same workbook as your Results — your saved loads travel with the file, with no extra cloud account to manage.

- 1 Saved loads — one row per load you confirmed. Click any row, then right-click for the actions menu.
- 2 Right-click actions — Copy load summary (paste into a text or email), Enter your actual dials... (reopens that load on Range & DOPE so you can type what you came up at each range, even on a load you already finished), Print this load as a Recipe Card... (same recipe as Results, but for a saved load), Save this load as PDF... (same native save dialog as Results), Open in Excel at this row (jump straight to the workbook), Delete this load... (confirm before anything goes).

The Help tab — column meanings & formulas

The Help tab lives at the right end of the bottom tab bar. It replaces the old cell hover-comments (which Excel-for-Mac was clipping). The full text is always visible.




When a label or number isn't self-explanatory, this is the place to look — no scrolling through PDFs, no hover-popup guesswork. It's part of the workbook itself.

- 1 **HELP MENU sidebar** — click any section name to jump straight to that tab's help. The menu stays visible while you scroll the body.
- 2 **Section banner** — names which workbook tab the items below are about (Powder Charge Log, Charts, Seating Depth Log, and so on).
- 3 **Each item:** bold header (the concept), the cell reference (e.g. Cell G15), and a plain-language explanation of what it means or how it's calculated.

TO YOUR PHONE

Send a load to your phone

Loadscope syncs straight to the Loadscope Ballistics app on your iPhone or iPad over your local Wi-Fi — no cables, no cloud, no account. Your dial goes where you actually shoot.



On the computer: turn on Phone Sync — the Phone Sync button at the bottom of the sidebar, or Support → Phone Sync. Your computer becomes discoverable on the Wi-Fi by name (it uses your Loadscope license, so only your own devices can connect).

On the phone: open Loadscope Ballistics, tap Sync, pick your computer, and pull the load — the recipe and predicted DOPE land on your phone for the field. Keep both devices on the same Wi-Fi.

On a guest or corporate network that hides devices? Tap Connect by address on the phone and type the address the computer shows.

YOUR UNITS

Imperial or metric

Open Settings and find Units. Pick Imperial or Metric to set everything in one click, or choose each measurement on its own — velocity in m/s with group size in inches is fine. The choices cover velocity, distance to target, group size, cartridge lengths (CBTO, OAL, jump), sight height, temperature, pressure, altitude and wind. Powder and bullet weights stay in grains.

Units only change what you see and type. Your saved loads, your scores and your workbook are stored the same way whatever you pick, so you can switch back and forth freely. The Excel workbook itself stays in inches, yards and fps.

Files from a European-set computer import as they are: m/s from a Garmin, mm group sizes, decimal commas and semicolon-separated columns all read correctly.

OTHER SETUPS

If your gear isn't on the list

Loadscope reads Garmin Xero (plugged in over USB, or a ShotView export), LabRadar, MagnetoSpeed and Athlon Velocity Pro. For targets it reads ShotMarker, BallisticX, OnTarget and Silver Mountain — or you can skip the target app and measure your groups from a photo right in Loadscope.

No file from your chronograph? Type the velocities in. On the Import screen, next to Browse folder, click Enter data by hand and put in the velocities for each charge in the order you shot them — straight off the chronograph's screen or your range log. They are scored exactly the same as an imported file.

Shooting factory ammo? Save each box as its own load and leave the powder and charge blank — those are the things a box doesn't tell you. What's written on the box goes in as the bullet. Compare Loads then ranks boxes against each other on mean radius and group size.

Using a chronograph or target app that isn't listed? Send a sample export to support@loadscope.app and we'll add it — the file readers are pluggable, so a new one is quick.