

Red Hat Openshift Container Storage 3.10

Operations Guide

Configuring and Managing Red Hat Openshift Container Storage.

Last Updated: 2018-12-21

Red Hat Openshift Container Storage 3.10 Operations Guide

Configuring and Managing Red Hat Openshift Container Storage.

Bhavana Mohan Customer Content Services Red Hat bmohanra@redhat.com

Legal Notice

Copyright © 2018 Red Hat, Inc.

This document is licensed by Red Hat under the <u>Creative Commons Attribution-ShareAlike 3.0</u> <u>Unported License</u>. If you distribute this document, or a modified version of it, you must provide attribution to Red Hat, Inc. and provide a link to the original. If the document is modified, all Red Hat trademarks must be removed.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java ® is a registered trademark of Oracle and/or its affiliates.

XFS ® is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat Software Collections is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack ® Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This guide provides information about operating your Container Storage deployment.

Table of Contents

PART I. MANAGE	. 4
CHAPTER 1. MANAGING CLUSTERS 1.1. INCREASING STORAGE CAPACITY 1.2. REDUCING STORAGE CAPACITY	. 5 5
CHAPTER 2. OPERATIONS ON A RED HAT GLUSTER STORAGE POD IN AN OPENSHIFT ENVIRONMENT	25
PART II. OPERATIONS	31
CHAPTER 3. CREATING PERSISTENT VOLUMES 3.1. FILE STORAGE 3.2. BLOCK STORAGE	32 32 53
CHAPTER 4. SHUTTING DOWN GLUSTER-BLOCK CLIENT NODES	69
CHAPTER 5. S3 COMPATIBLE OBJECT STORE IN A RED HAT OPENSHIFT CONTAINER STORAGE ENVIRONMENT 5.1. SETTING UP S3 COMPATIBLE OBJECT STORE FOR RED HAT OPENSHIFT CONTAINER STORAGE	70
5.2. OBJECT OPERATIONS	73
CHAPTER 6. CLUSTER ADMINISTRATOR SETUP	75
 CHAPTER 7. GLUSTER BLOCK STORAGE AS BACKEND FOR LOGGING AND METRICS 7.1. PREREQUISITES 7.2. ENABLING GLUSTER BLOCK STORAGE AS BACKEND FOR LOGGING 7.3. ENABLING GLUSTER BLOCK STORAGE AS BACKEND FOR METRICS 7.4. VERIFYING IF GLUSTER BLOCK IS SETUP AS BACKEND 	76 76 76 77 78
PART III. SECURITY	80
CHAPTER 8. ENABLING ENCRYPTION 8.1. PREREQUISITES 8.2. ENABLING ENCRYPTION FOR A NEW RED HAT OPENSHIFT CONTAINER STORAGE SETUP 8.3. ENABLING ENCRYPTION FOR AN EXISTING RED HAT OPENSHIFT CONTAINER STORAGE SETUP 8.4. DISABLING ENCRYPTION	81 81 81 84 86
PART IV. MIGRATION	89
CHAPTER 9. UPDATING THE REGISTRY WITH RED HAT OPENSHIFT CONTAINER STORAGE AS THE STORAGE BACK-END 9.1. VALIDATING THE OPENSHIFT CONTAINER PLATFORM REGISTRY DEPLOYMENT 9.2. CONVERTING THE OPENSHIFT CONTAINER PLATFORM REGISTRY WITH RED HAT OPENSHIFT CONTAINER STORAGE	90 90
PART V. MONITORING	97
CHAPTER 10. ENABLING VOLUME METRICS 10.1. ENABLING VOLUME METRICS FOR FILE STORAGE AND BLOCK STORAGE	98
PART VI. TROUBLESHOOT	101
CHAPTER 11. TROUBLESHOOTING	102

CHAPTER 12. CLIENT CONFIGURATION USING PORT FORWARDING	104
APPENDIX A. REVISION HISTORY	105
INDEX	106

PART I. MANAGE

CHAPTER 1. MANAGING CLUSTERS

Heketi allows administrators to add and remove storage capacity by managing either a single or multiple Red Hat Gluster Storage clusters.

1.1. INCREASING STORAGE CAPACITY

You can increase the storage capacity using any of the following ways:

- Adding devices
- Increasing cluster size
- Adding an entirely new cluster.

1.1.1. Adding New Devices

You can add more devices to existing nodes to increase storage capacity. When adding more devices, you must ensure to add devices as a set. For example, when expanding a distributed replicated volume with a replica count of replica 2, then one device should be added to at least two nodes. If using replica 3, then at least one device should be added to at least three nodes.

You can add a device either using CLI, or the API, or by updating the topology JSON file. The sections ahead describe using heketi CLI and updating topology JSON file. For information on adding new devices using API, see Heketi API https://github.com/heketi/heketi/wiki/API#device add

1.1.1.1. Using Heketi CLI

Register the specified device. The following example command shows how to add a device /dev/sde to node d6f2c22f2757bf67b1486d868dcb7794:

```
# heketi-cli device add --name=/dev/sde --
node=d6f2c22f2757bf67b1486d868dcb7794
OUTPUT:
Device added successfully
```

1.1.1.2. Updating Topology File

You can add the new device to the node description in your topology JSON file which is used to setup the cluster. Then re-run the command to load the topology.

Following is an example where a new /dev/sde drive added to the node:

In the file:

Load the topology file:

```
# heketi-cli topology load --json=topology-sample.json
    Found node 192.168.10.100 on cluster d6f2c22f2757bf67b1486d868dcb7794
        Found device /dev/sdb
        Found device /dev/sdc
        Found device /dev/sdd
        Adding device /dev/sde ... OK
    Found node 192.168.10.101 on cluster d6f2c22f2757bf67b1486d868dcb7794
        Found device /dev/sdb
        Found device /dev/sdc
        Found device /dev/sdd
    Found node 192.168.10.102 on cluster d6f2c22f2757bf67b1486d868dcb7794
        Found device /dev/sdb
        Found device /dev/sdc
        Found device /dev/sdd
    Found node 192.168.10.103 on cluster d6f2c22f2757bf67b1486d868dcb7794
        Found device /dev/sdb
        Found device /dev/sdc
        Found device /dev/sdd
```

1.1.2. Increasing Cluster Size

Another way to add storage to Heketi, is to add new nodes to the cluster. Like adding devices, you can add a new node to an existing cluster by either using CLI or API. When you add a new node to the cluster, you must register new devices to that node.

This section describes how to use Heketi CLI to increase the cluster size. For more information on adding new devices using API, see Heketi API: https://github.com/heketi/heketi/wiki/API#node_add



NOTE

For adding a node to be successful, ensure the ports are opened for glusterd communication. For more information about the ports, see https://access.redhat.com/documentation/en-us/red hat gluster storage/3.4/html/installation guide/port information

1.1.2.1. Adding a Node to OCP Cluster

 Scaleup the OCP cluster to add the new node. For more information see, https://access.redhat.com/documentation/en-us/openshift_container_platform/3.11/html-single/configuring_clusters/#adding-cluster-hosts_adding-hosts-to-cluster



NOTE

If the new node is already part of OCP cluster then skip this step and proceed with Step 2.

2. Configure the firewall rules:



NOTE

For adding a node to be successful, ensure the ports are opened for glusterd communication. For more information about the ports, see https://access.redhat.com/documentation/en-us/red_hat_gluster_storage/3.4/html/installation_guide/port_information

1. Add the following rules /etc/sysconfig/iptables file of the newly added glusterfs node:

```
-A OS_FIREWALL_ALLOW -p tcp -m state --state NEW -m tcp --dport 24007 -j ACCEPT
-A OS_FIREWALL_ALLOW -p tcp -m state --state NEW -m tcp --dport 24008 -j ACCEPT
-A OS_FIREWALL_ALLOW -p tcp -m state --state NEW -m tcp --dport 2222 -j ACCEPT
-A OS_FIREWALL_ALLOW -p tcp -m state --state NEW -m multiport --dports 49152:49664 -j ACCEPT
-A OS_FIREWALL_ALLOW -p tcp -m state --state NEW -m tcp --dport 24010 -j ACCEPT
-A OS_FIREWALL_ALLOW -p tcp -m state --state NEW -m tcp --dport 3260 -j ACCEPT
-A OS_FIREWALL_ALLOW -p tcp -m state --state NEW -m tcp --dport 111 -j ACCEPT
```

2. Reload/restart the iptables:

```
# systemctl restart iptables
```

- 3. Execute the following steps to add labels to the node where the RHGS Container will be deployed:
 - 1. Verify that Red Hat Openshift Container Storage is deployed and working as expected in the existing project by executing the following command:

```
# oc get ds
```

For example:

```
# oc get ds
NAME DESIRED CURRENT READY UP-TO-DATE
AVAILABLE NODE SELECTOR AGE
glusterfs-storage 3 3 3 3
3 glusterfs=storage-host 1d
```

2. Add the label for each node which is newly added, where the Red Hat Gluster Storage pods are to be added for the new cluster:

oc label node <NODE_NAME> glusterfs=<node_label>

where,

- NODE NAME: is the name of the newly created node.
- node_label: The name that is used in the existing daemonset. This is the value you get in the previous step when you execute oc get ds.

For example:

```
# oc label node 192.168.90.3 glusterfs=storage-host
node "192.168.90.3" labeled
```

3. Verify if the Red Hat Gluster Storage pods are running on the newly added node by executing the following command:

Observe additional Gluster Storage pods spawned on these new nodes

```
# oc get pods
```

For example:

READY	STATUS	RESTARTS	AGE
1/1	Running	0	30d
1/1	Running	0	30d
1/1	Running	0	30d
0/1	Running	0	1 m
	1/1 1/1 1/1	1/1 Running 1/1 Running 1/1 Running	1/1 Running 0 1/1 Running 0 1/1 Running 0

You should see additional Gluster Storage pods, in this example 4 gluster pods instead of just 3 as before. It will take 1-2 minutes for them to become healthy. (i.e. glusterfs-v759z 0/1 not healthy yet).

4. Verify if the Red Hat Gluster Storage pods are running

```
# oc get pods -o wide -l glusterfs=storage-pod
```

1.1.2.2. Using Heketi CLI

Following shows an example of how to add new node in **zone 1** to **597fceb5d6c876b899e48f599b988f54** cluster using the CLI:

```
# heketi-cli node add --zone=1 --cluster=597fceb5d6c876b899e48f599b988f54
--management-host-name=node4.example.com --storage-host-
name=192.168.10.104
```

OUTPUT:

Node information:

Id: 095d5f26b56dc6c64564a9bc17338cbf

State: online

Cluster Id: 597fceb5d6c876b899e48f599b988f54

```
Zone: 1
Management Hostname node4.example.com
Storage Hostname 192.168.10.104
```

The following example command shows how to register /dev/sdb and /dev/sdc devices for 095d5f26b56dc6c64564a9bc17338cbf node:

```
# heketi-cli device add --name=/dev/sdb --
node=095d5f26b56dc6c64564a9bc17338cbf
OUTPUT:
Device added successfully

# heketi-cli device add --name=/dev/sdc --
node=095d5f26b56dc6c64564a9bc17338cbf
OUTPUT:
Device added successfully
```

1.1.2.3. Updating Topology File

You can expand a cluster by adding a new node to your topology JSON file. When adding the new node you must add this node information **after** the existing ones so that the Heketi CLI identifies on which cluster this new node should be part of.

Following shows an example of how to add a new node and devices:

Load the topology file:

```
# heketi-cli topology load --json=topology-sample.json
Found node 192.168.10.100 on cluster d6f2c22f2757bf67b1486d868dcb7794
Found device /dev/sdb
Found device /dev/sdc
Found device /dev/sdd
Found device /dev/sde
Found node 192.168.10.101 on cluster d6f2c22f2757bf67b1486d868dcb7794
Found device /dev/sdb
Found device /dev/sdc
```

```
Found device /dev/sdd
Found node 192.168.10.102 on cluster d6f2c22f2757bf67b1486d868dcb7794
Found device /dev/sdb
Found device /dev/sdd
Found node 192.168.10.103 on cluster d6f2c22f2757bf67b1486d868dcb7794
Found device /dev/sdb
Found device /dev/sdc
Found device /dev/sdd
Creating node node4.example.com ... ID:

ff3375aca6d98ed8a004787ab823e293
Adding device /dev/sdb ... OK
Adding device /dev/sdc ... OK
```

1.1.3. Adding a New Cluster

Storage capacity can also be increased by adding new clusters of Red Hat Gluster Storage. New clusters can be added in the following two ways based on the requirement:

- Adding a new cluster to the existing Red Hat Openshift Container Storage
- Adding another Red Hat Openshift Container Storage cluster in a new project

1.1.3.1. Adding a New Cluster to the Existing Red Hat Openshift Container Storage

To add a new cluster to the existing Red Hat Openshift Container Storage, execute the following commands:

1. Verify that Red Hat Openshift Container Storage is deployed and working as expected in the existing project by executing the following command:

```
# oc get ds
```

For example:

```
# oc get ds
NAME DESIRED CURRENT READY UP-TO-DATE
AVAILABLE NODE SELECTOR AGE
glusterfs-storage 3 3 3 3 3
glusterfs=storage-host 1d
```

2. Verify if the Red Hat Gluster Storage pods are running by executing the following command:

Observe additional Gluster Storage pods spawned on these new nodes

```
# oc get pods
```

For example:

```
# oc get pods
NAME READY STATUS RESTARTS AGE
glusterfs-356cf 1/1 Running 0 30d
```

glusterfs-fh4gm	1/1	Running	0	30d
glusterfs-hg4tk	1/1	Running	0	30d
glusterfs-v759z	0/1	Running	0	1 m

You should see additional Gluster Storage pods, in this example 4 gluster pods instead of just 3 as before. It will take 1-2 minutes for them to become healthy. (i.e. glusterfs-v759z 0/1 not healthy yet).

3. Add the label for each node, where the Red Hat Gluster Storage pods are to be added for the new cluster to start by executing the following command:

```
# oc label node <NODE_NAME> glusterfs=<node_label>
```

where,

- NODE_NAME: is the name of the newly created node
- node_label: The name that is used in the existing daemonset.

For example:

```
# oc label node 192.168.90.3 glusterfs=storage-host
node "192.168.90.3" labeled
```

4. Verify if the Red Hat Gluster Storage pods are running by executing the following command:

```
# oc get ds
```

For example:

```
# oc get ds
NAME DESIRED CURRENT READY UP-TO-DATE
AVAILABLE NODE SELECTOR AGE
glusterfs-storage 3 3 3 3 3
glusterfs=storage-host 1d
```

5. Create a new topology file for the new cluster. You must provide a topology file for the new cluster which describes the topology of the Red Hat Gluster Storage nodes and their attached storage devices. As a sample, a formatted topology file (topology-sample.json) is installed with the 'heketi-client' package in the /usr/share/heketi/ directory.

For example:

```
"192.168.68.3"
             ]
        },
"zone": 1
    },
    "devices": [
        "/dev/sdb",
        "/dev/sdc",
        "/dev/sdd"
        "/dev/sde",
        "/dev/sdf",
        "/dev/sdg",
         "/dev/sdh",
         "/dev/sdi"
    ]
},
{
    "node": {
         "hostnames": {
             "manage": [
                 "node2.example.com"
             ],
             "storage": [
                 "192.168.68.2"
        },
        "zone": 2
    },
    "devices": [
        "/dev/sdb",
        "/dev/sdc",
        "/dev/sdd",
        "/dev/sde",
         "/dev/sdf"
        "/dev/sdg",
        "/dev/sdh"
         "/dev/sdi"
    ]
},
```

where,

o clusters: Array of clusters.

Each element on the array is a map which describes the cluster as follows.

- nodes: Array of OpenShift nodes that will host the Red Hat Gluster Storage container
 Each element on the array is a map which describes the node as follows
 - node: It is a map of the following elements:
 - zone: The value represents the zone number that the node belongs to; the zone number is used by heketi for choosing optimum position of bricks by having

replicas of bricks in different zones. Hence zone number is similar to a failure domain.

- hostnames: It is a map which lists the manage and storage addresses
 - manage: It is the hostname/IP Address that is used by Heketi to communicate with the node
 - storage: It is the IP address that is used by other OpenShift nodes to communicate with the node. Storage data traffic will use the interface attached to this IP. This must be the IP address and not the hostname because, in an OpenShift environment, Heketi considers this to be the endpoint too.
- devices: Name of each disk to be added

Edit the topology file based on the Red Hat Gluster Storage pod hostname under the **node.hostnames.manage** section and **node.hostnames.storage** section with the IP address. For simplicity, the /usr/share/heketi/topology-sample.json file only sets up 4 nodes with 8 drives each.

6. For the existing cluster, heketi-cli will be available to load the new topology. Run the command to add the new topology to heketi:

```
# heketi-cli topology load --json=<topology file path>
```

For example:

```
# heketi-cli topology load --json=topology.json
Creating cluster ... ID: 94877b3f72b79273e87c1e94201ecd58
 Creating node node4.example.com ... ID:
95cefa174c7210bd53072073c9c041a3
        Adding device /dev/sdb ... OK
        Adding device /dev/sdc ... OK
        Adding device /dev/sdd ... OK
        Adding device /dev/sde ... OK
    Creating node node5.example.com ... ID:
f9920995e580f0fe56fa269d3f3f8428
        Adding device /dev/sdb ... OK
        Adding device /dev/sdc ... OK
        Adding device /dev/sdd ... OK
        Adding device /dev/sde ... OK
    Creating node node6.example.com ... ID:
73fe4aa89ba35c51de4a51ecbf52544d
        Adding device /dev/sdb ... OK
        Adding device /dev/sdc ... OK
        Adding device /dev/sdd ... OK
        Adding device /dev/sde ... OK
```

1.1.3.2. Adding Another Red Hat Openshift Container Storage Cluster in a New Project

To add another Red Hat Openshift Container Storage in a new project to, execute the following commands:



NOTE

As Node label is global, there can be conflicts to start Red Hat Gluster Storage DaemonSets with the same label in two different projects. Node label is an argument to cns-deploy, thereby enabling deployment of multiple trusted storage pool by using a different label in a different project.

1. Create a new project by executing the following command:

```
# oc new-project <new_project_name>
```

For example:

```
# oc new-project storage-project-2
Now using project "storage-project-2" on server
"https://master.example.com:8443"
```

2. After the project is created, execute the following command on the master node to enable the deployment of the privileged containers as Red Hat Gluster Storage container can only run in the privileged mode.

```
# oc adm policy add-scc-to-user privileged -z storage-project-2
# oc adm policy add-scc-to-user privileged -z default
```

3. Create a new topology file for the new cluster. You must provide a topology file for the new cluster which describes the topology of the Red Hat Gluster Storage nodes and their attached storage devices. As a sample, a formatted topology file (topology-sample.json) is installed with the 'heketi-client' package in the /usr/share/heketi/ directory.

For example:

```
{
    "clusters": [
        {
             "nodes": [
                 {
                     "node": {
                          "hostnames": {
                              "manage": [
                                   "node1.example.com"
                              ],
                              "storage": [
                                   "192.168.68.3"
                          "zone": 1
                     "devices": [
                          "/dev/sdb",
                          "/dev/sdc",
                          "/dev/sdd",
                          "/dev/sde",
                          "/dev/sdf",
```

```
"/dev/sdg",
        "/dev/sdh",
        "/dev/sdi"
    1
},
{
    "node": {
         "hostnames": {
             "manage": [
                 "node2.example.com"
             ],
             "storage": [
                 "192.168.68.2"
         "zone": 2
    "devices": [
        "/dev/sdb",
        "/dev/sdc",
        "/dev/sdd",
        "/dev/sde",
         "/dev/sdf",
         "/dev/sdg",
        "/dev/sdh",
        "/dev/sdi"
    ]
},
```

where,

o clusters: Array of clusters.

Each element on the array is a map which describes the cluster as follows.

- nodes: Array of OpenShift nodes that will host the Red Hat Gluster Storage container
 Each element on the array is a map which describes the node as follows
 - node: It is a map of the following elements:
 - zone: The value represents the zone number that the node belongs to; the zone number is used by heketi for choosing optimum position of bricks by having replicas of bricks in different zones. Hence zone number is similar to a failure domain.
 - hostnames: It is a map which lists the manage and storage addresses
 - manage: It is the hostname/IP Address that is used by Heketi to communicate with the node
 - storage: It is the IP address that is used by other OpenShift nodes to communicate with the node. Storage data traffic will use the interface attached to this IP. This must be the IP address and not the hostname

because, in an OpenShift environment, Heketi considers this to be the endpoint too.

devices: Name of each disk to be added

Edit the topology file based on the Red Hat Gluster Storage pod hostname under the **node.hostnames.manage** section and **node.hostnames.storage** section with the IP address. For simplicity, the /usr/share/heketi/topology-sample.json file only sets up 4 nodes with 8 drives each.

4. Execute the following command on the client to deploy the heketi and Red Hat Gluster Storage pods:

```
# cns-deploy -n <namespace> --daemonset-label <NODE_LABEL> -g
topology.json
```

For example:

cns-deploy -n storage-project-2 --daemonset-label glusterfs2 -g
topology.json

Welcome to the deployment tool for GlusterFS on Kubernetes and OpenShift.

Before getting started, this script has some requirements of the execution

environment and of the container platform that you should verify.

The client machine that will run this script must have:

- * Administrative access to an existing Kubernetes or OpenShift cluster
 - * Access to a python interpreter 'python'
 - * Access to the heketi client 'heketi-cli'

Each of the nodes that will host GlusterFS must also have appropriate firewall

rules for the required GlusterFS ports:

- * 2222 sshd (if running GlusterFS in a pod)
- * 24007 GlusterFS Daemon
- * 24008 GlusterFS Management
- * 49152 to 49251 Each brick for every volume on the host requires

port. For every new brick, one new port will be used starting at 49152. We

recommend a default range of 49152-49251 on each host, though you can adjust

this to fit your needs.

In addition, for an OpenShift deployment you must:

- * Have 'cluster_admin' role on the administrative account doing the deployment
- * Add the 'default' and 'router' Service Accounts to the 'privileged' SCC
- * Have a router deployed that is configured to allow apps to access services

running in the cluster

```
Do you wish to proceed with deployment?
[Y]es, [N]o? [Default: Y]: Y
Using OpenShift CLI.
NAME
                    STATUS
                              AGE
storage-project-2
                    Active
                              2m
Using namespace "storage-project-2".
Checking that heketi pod is not running ... OK
template "deploy-heketi" created
serviceaccount "heketi-service-account" created
template "heketi" created
template "glusterfs" created
role "edit" added: "system:serviceaccount:storage-project-2:heketi-
service-account"
node "192.168.35.5" labeled
node "192.168.35.6" labeled
node "192.168.35.7" labeled
daemonset "glusterfs" created
Waiting for GlusterFS pods to start ... OK
service "deploy-heketi" created
route "deploy-heketi" created
deploymentconfig "deploy-heketi" created
Waiting for deploy-heketi pod to start ... OK
Creating cluster ... ID: fde139c21b0afcb6206bf272e0df1590
Creating node 192.168.35.5 ... ID: 0768a1ee35dce4cf707c7a1e9caa3d2a
Adding device /dev/vdc ... OK
Adding device /dev/vdd ... OK
Adding device /dev/vde ... OK
Adding device /dev/vdf ... OK
Creating node 192.168.35.6 ... ID: 63966f6ffd48c1980c4a2d03abeedd04
Adding device /dev/vdc ... OK
Adding device /dev/vdd ... OK
Adding device /dev/vde ... OK
Adding device /dev/vdf ... OK
Creating node 192.168.35.7 ... ID: de129c099193aaff2c64dca825f33558
Adding device /dev/vdc ... OK
Adding device /dev/vdd ... OK
Adding device /dev/vde ... OK
Adding device /dev/vdf ... OK
heketi topology loaded.
Saving heketi-storage.json
secret "heketi-storage-secret" created
endpoints "heketi-storage-endpoints" created
service "heketi-storage-endpoints" created
job "heketi-storage-copy-job" created
deploymentconfig "deploy-heketi" deleted
route "deploy-heketi" deleted
service "deploy-heketi" deleted
job "heketi-storage-copy-job" deleted
pod "deploy-heketi-1-d0grs" deleted
secret "heketi-storage-secret" deleted
service "heketi" created
route "heketi" created
deploymentconfig "heketi" created
```

Waiting for heketi pod to start ... OK heketi is now running. Ready to create and provide GlusterFS volumes.



NOTE

For more information on the cns-deploy commands, see to the man page of the cns-deploy.

5. Verify that Red Hat Openshift Container Storage is deployed and working as expected in the new project with the new daemonSet label by executing the following command:

For example:

# oc get ds	;			
NAME	DESIRED	CURRENT	READY	NODE-SELECTOR
AGE				
glusterfs 8m	3	3	3	storagenode=glusterfs2

1.2. REDUCING STORAGE CAPACITY

Heketi also supports the reduction of storage capacity. You can reduce storage by deleting devices, nodes, and clusters. These requests can only be performed by using the Heketi CLI or the API. For information on using command line API, see Heketi API https://github.com/heketi/heketi/wiki/API.



NOTE

- The IDs can be retrieved by executing the heketi-cli topology info command.
 - # heketi-cli topology info
- The heketidbstorage volume cannot be deleted as it contains the heketi database.

1.2.1. Deleting Volumes

You can delete the volume using the following Heketi CLI command:

heketi-cli volume delete <volume_id>

For example:

heketi-cli volume delete 12b2590191f571be9e896c7a483953c3 Volume 12b2590191f571be9e896c7a483953c3 deleted

1.2.2. Deleting Device

Deleting the device deletes devices from heketi's topology. Devices that have bricks cannot be deleted. You must ensure they are free of bricks by disabling and removing devices.

1.2.2.1. Disabling and Enabling a Device

Disabling devices stops further allocation of bricks onto the device. You can disable devices using the following Heketi CLI command:

heketi-cli device disable <device_id>

For example:

heketi-cli device disable f53b13b9de1b5125691ee77db8bb47f4
Device f53b13b9de1b5125691ee77db8bb47f4 is now offline

If you want to re-enable the device, execute the following command. Enabling the device allows allocation of bricks onto the device.

heketi-cli device enable <device_id>

For example:

heketi-cli device enable f53b13b9de1b5125691ee77db8bb47f4
Device f53b13b9de1b5125691ee77db8bb47f4 is now online

1.2.2.2. Removing and Deleting the Device

Removing devices moves existing bricks from the device to other devices. This helps in ensuring the device is free of bricks. A device can be removed only after disabling it.

1. Remove device using the following command:

heketi-cli device remove <device_id>

For example:

heketi-cli device remove e9ef1d9043ed3898227143add599e1f9 Device e9ef1d9043ed3898227143add599e1f9 is now removed

2. Delete the device using the following command:

heketi-cli device delete <device_id>

For example:

heketi-cli device delete 56912a57287d07fad0651ba0003cf9aa Device 56912a57287d07fad0651ba0003cf9aa deleted

The only way to reuse a deleted device is by adding the device to heketi's topology again.

1.2.2.3. Replacing a Device

Heketi does not allow one-to-one replacement of a device with another. However, in case of a failed device, follow the example below for the sequence of operations that are required to replace a failed device.

1. Locate the device that has failed using the following command:

```
# heketi-cli topology info

...

...

Nodes:
Node Id: 8faade64a9c8669de204b66bc083b10d

...

...

...

Id:a811261864ee190941b17c72809a5001 Name:/dev/vdc
State:online Size (GiB):499 Used (GiB):281 Free (GiB):218

Bricks:

Id:34c14120bef5621f287951bcdfa774fc Size (GiB):280 Path:
/var/lib/heketi/mounts/vg_a811261864ee190941b17c72809a5001/brick_34c
14120bef5621f287951bcdfa774fc/brick

...

...

...
```

The example below illustrates the sequence of operations that are required to replace a failed device. The example uses device ID a811261864ee190941b17c72809a5001 which belongs to node with id 8faade64a9c8669de204b66bc083b10das.

2. Add a new device preferably to the same node as the device being replaced.

```
# heketi-cli device add --name /dev/vdd --node
8faade64a9c8669de204b66bc083b10d
Device added successfully
```

3. Disable the failed device.

```
# heketi-cli device disable a811261864ee190941b17c72809a5001
Device a811261864ee190941b17c72809a5001 is now offline
```

4. Remove the failed device.

```
# heketi-cli device remove a811261864ee190941b17c72809a5001
Device a811261864ee190941b17c72809a5001 is now removed
```

At this stage, the bricks are migrated from the failed device. Heketi chooses a suitable device based on the brick allocation algorithm. As a result, there is a possibility that all the bricks might not be migrated to the new added device.

5. Delete the failed device.

heketi-cli device delete a811261864ee190941b17c72809a5001 Device a811261864ee190941b17c72809a5001 deleted

6. Before repeating the above sequence of steps on another device, you must wait for the self-heal operation to complete. You can verify that the self-heal operation completed when the Number of entries value returns a 0 value.

```
# oc rsh <any_gluster_pod_name>
for each in $(gluster volume list) ; do gluster vol heal $each info
| grep "Number of entries:" ; done
Number of entries: 0
Number of entries: 0
```

1.2.3. Deleting Node

Nodes that have devices added to it cannot be deleted. To delete the node, the devices that are associated with the node have to be deleted. Disabling and removing the node ensures all the underlying devices are removed too. Once the node is removed, all the devices in it can be deleted and finally the node can be deleted

1.2.3.1. Disabling and Enabling a Node

Disabling node stops further allocation of bricks to all the devices associated to the node. You can disable nodes using the following Heketi CLI command:

```
# heketi-cli node disable <node_id>
```

For example:

heketi-cli node disable 5f0af88b968ed1f01bf959fe4fe804dc Node 5f0af88b968ed1f01bf959fe4fe804dc is now offline

If you want to re-enable the node, execute the following command.

```
# heketi-cli node enable <node_id>
```

For example:

heketi-cli node enable 5f0af88b968ed1f01bf959fe4fe804dc Node 5f0af88b968ed1f01bf959fe4fe804dc is now online

1.2.3.2. Removing and Deleting the Node

Removing nodes moves existing bricks from all the devices in the node to other devices in the cluster. This helps in ensuring all the device in the node is free of bricks. A device can be removed only after disabling it.

1. To remove the node execute the following command:

```
# heketi-cli node remove <node_id>
```

For example:

heketi-cli node remove 5f0af88b968ed1f01bf959fe4fe804dc Node 5f0af88b968ed1f01bf959fe4fe804dc is now removed

2. Delete the devices associated with the node by executing the following command as the nodes that have devices associated with it cannot be deleted:

```
# heketi-cli device delete <device_id>
```

For example:

heketi-cli device delete 56912a57287d07fad0651ba0003cf9aa Device 56912a57287d07fad0651ba0003cf9aa deleted

Execute the command for every device on the node.

3. Delete the node using the following command:

```
# heketi-cli node delete <node_id>
```

For example:

```
heketi-cli node delete 5f0af88b968ed1f01bf959fe4fe804dc
Node 5f0af88b968ed1f01bf959fe4fe804dc deleted
```

Deleting the node deletes the node from the heketi topology. The only way to reuse a deleted node is by adding the node to heketi's topology again

1.2.3.3. Replacing a Node

Heketi does not allow one-to-one replacement of a node with another. However, in case of a failed node, follow the example below for the sequence of operations that are required to replace a failed node and its respective devices.

1. Locate the node that has failed using the following command:

```
# heketi-cli topology info
    Nodes:
Node Id: 8faade64a9c8669de204b66bc083b10d
. . .
                                                       Name:/dev/vdc
                Id:a811261864ee190941b17c72809a5001
State:online
                Size (GiB):499
                                   Used (GiB):281
                                                       Free (GiB):218
                        Bricks:
Id:34c14120bef5621f287951bcdfa774fc
                                      Size (GiB):280
                                                          Path:
/var/lib/heketi/mounts/vg_a811261864ee190941b17c72809a5001/brick_34c
14120bef5621f287951bcdfa774fc/brick
```

... ...

The example below illustrates the sequence of operations that are required to replace a failed node. The example uses node ID 8faade64a9c8669de204b66bc083b10d.

2. Add a new node, preferably that has the same devices as the node being replaced.

```
# heketi-cli node add --zone=1 --
cluster=597fceb5d6c876b899e48f599b988f54 --management-host-
name=node4.example.com --storage-host-name=192.168.10.104
# heketi-cli device add --name /dev/vdd --node
8faade64a9c8669de204b66bc083b10d
Node and device added successfully
```

3. Disable the failed node.

heketi-cli node disable 8faade64a9c8669de204b66bc083b10d Node 8faade64a9c8669de204b66bc083b10d is now offline

4. Remove the failed node.

```
# heketi-cli node remove 8faade64a9c8669de204b66bc083b10d
Node 8faade64a9c8669de204b66bc083b10d is now removed
```

At this stage, the bricks are migrated from the failed node. Heketi chooses a suitable device based on the brick allocation algorithm.

5. Delete the devices associated with the node by executing the following command as the nodes that have devices associated with it cannot be deleted:

```
# heketi-cli device delete <device_id>
```

For example:

heketi-cli device delete 56912a57287d07fad0651ba0003cf9aa Device 56912a57287d07fad0651ba0003cf9aa deleted

Execute the command for every device on the node.

6. Delete the failed node.

```
# heketi-cli node delete 8faade64a9c8669de204b66bc083b10d
Node 8faade64a9c8669de204b66bc083b10d deleted
```

1.2.4. Deleting Clusters

You can delete the cluster using the following Heketi CLI command:



NOTE

Before a cluster is deleted, ensure that all the nodes inside the cluster are deleted.

heketi-cli cluster delete <cluster_id>

For example:

 $\begin{array}{lll} \text{heketi-cli cluster delete 0e949d91c608d13fd3fc4e96f798a5b1} \\ \text{Cluster 0e949d91c608d13fd3fc4e96f798a5b1 deleted} \end{array}$

CHAPTER 2. OPERATIONS ON A RED HAT GLUSTER STORAGE POD IN AN OPENSHIFT ENVIRONMENT

This chapter lists out the various operations that can be performed on a Red Hat Gluster Storage pod (gluster pod):

1. To list the pods, execute the following command:

```
# oc get pods -n <storage_project_name>
```

For example:

	# oc aet	pods -n sto	orage-project	
ı	NAME			READY
ı	STATUS	RESTARTS	AGE	
ı	storage-p	roject-rout	ter-1-v89qc	1/1
ı	Running	0	1d	
ı	glusterfs	example.com	1/1	
ı	Running	0	1d	
glusterfs-dc-node2.example.com			example.com	1/1
ı	Running	1	1d	
ı	glusterfs-dc-node3.example.com			1/1
ı	Running	0	1d	
ı	heketi-1-	k1u14		1/1
	Running	0	23m	

Following are the gluster pods from the above example:

```
glusterfs-dc-node1.example.com
glusterfs-dc-node2.example.com
glusterfs-dc-node3.example.com
```



NOTE

The topology.json file will provide the details of the nodes in a given Trusted Storage Pool (TSP). In the above example all the 3 Red Hat Gluster Storage nodes are from the same TSP.

2. To enter the gluster pod shell, execute the following command:

```
# oc rsh <gluster_pod_name> -n <storage_project_name>
```

For example:

```
# oc rsh glusterfs-dc-node1.example.com -n storage-project
sh-4.2#
```

3. To get the peer status, execute the following command:

```
# gluster peer status
```

For example:

```
# gluster peer status

Number of Peers: 2

Hostname: node2.example.com
Uuid: 9f3f84d2-ef8e-4d6e-aa2c-5e0370a99620
State: Peer in Cluster (Connected)
Other names:
node1.example.com

Hostname: node3.example.com
Uuid: 38621acd-eb76-4bd8-8162-9c2374affbbd
State: Peer in Cluster (Connected)
```

4. To list the gluster volumes on the Trusted Storage Pool, execute the following command:

```
# gluster volume info
```

For example:

```
Volume Name: heketidbstorage
Type: Distributed-Replicate
Volume ID: 2fa53b28-121d-4842-9d2f-dce1b0458fda
Status: Started
Number of Bricks: 2 \times 3 = 6
Transport-type: tcp
Bricks:
Brick1:
192.168.121.172:/var/lib/heketi/mounts/vg_1be433737b71419dc9b395e221
255fb3/brick_c67fb97f74649d990c5743090e0c9176/brick
Brick2:
192.168.121.233:/var/lib/heketi/mounts/vg_0013ee200cdefaeb6dfedd28e5
Ofd261/brick_6ebf1ee62a8e9e7aOf88e4551d4b2386/brick
192.168.121.168:/var/lib/heketi/mounts/vq_e4b32535c55c88f9190da7b7ef
d1fcab/brick_df5db97aa002d572a0fec6bcf2101aad/brick
192.168.121.233:/var/lib/heketi/mounts/vg_0013ee200cdefaeb6dfedd28e5
Ofd261/brick_acc82e56236df912e9a1948f594415a7/brick
Brick5:
192.168.121.168:/var/lib/heketi/mounts/vg_e4b32535c55c88f9190da7b7ef
d1fcab/brick 65dceb1f749ec417533ddeae9535e8be/brick
Brick6:
192.168.121.172:/var/lib/heketi/mounts/vg_7ad961dbd24e16d62cabe10fd8
bf8909/brick_f258450fc6f025f99952a6edea203859/brick
Options Reconfigured:
performance.readdir-ahead: on
Volume Name: vol_9e86c0493f6b1be648c9deee1dc226a6
Type: Distributed-Replicate
Volume ID: 940177c3-d866-4e5e-9aa0-fc9be94fc0f4
Status: Started
Number of Bricks: 2 \times 3 = 6
```

Transport-type: tcp Bricks: Brick1: 192.168.121.168:/var/lib/heketi/mounts/vq_3fa141bf2d09d30b899f2f260c 494376/brick_9fb4a5206bdd8ac70170d00f304f99a5/brick 192.168.121.172:/var/lib/heketi/mounts/vg_7ad961dbd24e16d62cabe10fd8 bf8909/brick_dae2422d518915241f74fd90b426a379/brick 192.168.121.233:/var/lib/heketi/mounts/vg_5c6428c439eb6686c5e4cee565 32bacf/brick_b3768ba8e80863724c9ec42446ea4812/brick 192.168.121.172:/var/lib/heketi/mounts/vg_7ad961dbd24e16d62cabe10fd8 bf8909/brick_0a13958525c6343c4a7951acec199da0/brick Brick5: 192.168.121.168:/var/lib/heketi/mounts/vg_17fbc98d84df86756e7826326f b33aa4/brick_af42af87ad87ab4f01e8ca153abbbee9/brick Brick6: 192.168.121.233:/var/lib/heketi/mounts/vg_5c6428c439eb6686c5e4cee565 32bacf/brick_ef41e04ca648efaf04178e64d25dbdcb/brick Options Reconfigured: performance.readdir-ahead: on

- 5. To get the volume status, execute the following command:
 - # gluster volume status <volname>

For example:

<pre># gluster volume status vol_9e86c0493f6b1be</pre>	e648c9deee1	.dc226a6	
Status of volume: vol_9e86c0493f6b1be648c9	deee1dc226a	۱6	
Gluster process	TCP Port	RDMA Port	
Online Pid			
			-
Brick 192.168.121.168:/var/lib/heketi/mount			
g_3fa141bf2d09d30b899f2f260c494376/brick_9f		0	
b4a5206bdd8ac70170d00f304f99a5/brick 3462	49154	0	Υ
Brick 192.168.121.172:/var/lib/heketi/mount	-6/1/		
g_7ad961dbd24e16d62cabe10fd8bf8909/brick_da			
e2422d518915241f74fd90b426a379/brick	49154	Θ	Υ
115939	.0_0 .		•
Brick 192.168.121.233:/var/lib/heketi/mount	s/v		
g_5c6428c439eb6686c5e4cee56532bacf/brick_b3	3		
768ba8e80863724c9ec42446ea4812/brick	49154	0	Υ
116134			
Brick 192.168.121.172:/var/lib/heketi/mount			
g_7ad961dbd24e16d62cabe10fd8bf8909/brick_0a			
13958525c6343c4a7951acec199da0/brick	49155	0	Υ
115958	/		
Brick 192.168.121.168:/var/lib/heketi/mount			
<pre>g_17fbc98d84df86756e7826326fb33aa4/brick_at 42af87ad87ab4f01e8ca153abbbee9/brick</pre>	49155	0	Υ
42a107au07au4101coca133auuucca7u111ck	49100	U	ı

3481 Brick 192.168.121.233:/var/lib/heketi/mount g_5c6428c439eb6686c5e4cee56532bacf/brick_ef	s/v		
41e04ca648efaf04178e64d25dbdcb/brick 116153	49155	0	Υ
NFS Server on localhost 116173	2049	0	Υ
Self-heal Daemon on localhost 116181	N/A	N/A	Υ
NFS Server on node1.example.com 2049 0 Y 3501 Self-heal Daemon on node1.example.com N/A N/A Y 3509 NFS Server on 192.168.121.172 Y 115978 Self-heal Daemon on 192.168.121.172	2049 N/A	0 N/A	
Y 115986 Task Status of Volume vol_9e86c0493f6b1be64		.,,,,	
There are no active volume tasks			-

6. To use the snapshot feature, load the snapshot module using the following command on one of the nodes:

modprobe dm_snapshot



IMPORTANT

Restrictions for using Snapshot

 After a snapshot is created, it must be accessed through the user-serviceable snapshots feature only. This can be used to copy the old versions of files into the required location.

Reverting the volume to a snapshot state is not supported and should never be done as it might damage the consistency of the data.

- On a volume with snapshots, volume changing operations, such as volume expansion, must not be performed.
- 7. To take the snapshot of the gluster volume, execute the following command:
 - # gluster snapshot create <snapname> <volname>

For example:

gluster snapshot create snap1 vol_9e86c0493f6b1be648c9deee1dc226a6
snapshot create: success: Snap snap1_GMT-2016.07.29-13.05.46 created
successfully

8. To list the snapshots, execute the following command:

```
# gluster snapshot list
```

For example:

```
# gluster snapshot list

snap1_GMT-2016.07.29-13.05.46

snap2_GMT-2016.07.29-13.06.13

snap3_GMT-2016.07.29-13.06.18

snap4_GMT-2016.07.29-13.06.22

snap5_GMT-2016.07.29-13.06.26
```

9. To delete a snapshot, execute the following command:

```
# gluster snap delete <snapname>
```

For example:

```
# gluster snap delete snap1_GMT-2016.07.29-13.05.46

Deleting snap will erase all the information about the snap. Do you still want to continue? (y/n) y snapshot delete: snap1_GMT-2016.07.29-13.05.46: snap removed successfully
```

For more information about managing snapshots, see https://access.redhat.com/documentation/en-us/red_hat_gluster_storage/3.4/html-single/administration_guide/#chap-Managing_Snapshots.

10. You can set up Red Hat Openshift Container Storage volumes for geo-replication to a non-Red Hat Openshift Container Storage remote site. Geo-replication uses a master–slave model. Here, the Red Hat Openshift Container Storage volume acts as the master volume. To set up geo-replication, you must run the geo-replication commands on gluster pods. To enter the gluster pod shell, execute the following command:

```
# oc rsh <gluster_pod_name> -n <storage_project_name>
```

For more information about setting up geo-replication, see https://access.redhat.com/documentation/en-us/red_hat_gluster_storage/3.4/html/administration_guide/chap-managing_geo-replication.

11. Brick multiplexing is a feature that allows including multiple bricks into one process. This reduces resource consumption, allowing you to run more bricks than earlier with the same memory consumption.

Brick multiplexing is enabled by default from Container-Native Storage 3.6. If you want to turn it off, execute the following command:

```
# gluster volume set all cluster.brick-multiplex off
```

12. The **auto_unmount** option in glusterfs libfuse, when enabled, ensures that the file system is unmounted at FUSE server termination by running a separate monitor process that performs the unmount.

The GlusterFS plugin in Openshift enables the **auto_unmount** option for gluster mounts.

PART II. OPERATIONS

CHAPTER 3. CREATING PERSISTENT VOLUMES

OpenShift Container Platform clusters can be provisioned with persistent storage using GlusterFS.

Persistent volumes (PVs) and persistent volume claims (PVCs) can share volumes across a single project. While the GlusterFS-specific information contained in a PV definition could also be defined directly in a pod definition, doing so does not create the volume as a distinct cluster resource, making the volume more susceptible to conflicts.

Binding PVs by Labels and Selectors

Labels are an OpenShift Container Platform feature that support user-defined tags (key-value pairs) as part of an object's specification. Their primary purpose is to enable the arbitrary grouping of objects by defining identical labels among them. These labels can then be targeted by selectors to match all objects with specified label values. It is this functionality we will take advantage of to enable our PVC to bind to our PV.

You can use labels to identify common attributes or characteristics shared among volumes. For example, you can define the gluster volume to have a custom attribute (key) named **storage-tier** with a value of **gold** assigned. A claim will be able to select a PV with **storage-tier=gold** to match this PV.

More details for provisioning volumes in file-based storage is provided in Section 3.1, "File Storage". Similarly, further details for provisioning volumes in block-based storage is provided in Section 3.2, "Block Storage".

3.1. FILE STORAGE

File storage, also called file-level or file-based storage, stores data in a hierarchical structure. The data is saved in files and folders, and presented to both the system storing it and the system retrieving it in the same format. You can provision volumes either statically or dynamically for file-based storage.

3.1.1. Static Provisioning of Volumes

To enable persistent volume support in OpenShift and Kubernetes, few endpoints and a service must be created:

The sample glusterfs endpoint file (sample-gluster-endpoints.yaml) and the sample glusterfs service file (sample-gluster-service.yaml) are available at /usr/share/heketi/templates/ directory.

The sample endpoints and services file will not be available for ansible deployments since /usr/share/heketi/templates/ directory will not be created for such deployments.



NOTE

Ensure to copy the sample glusterfs endpoint file / glusterfs service file to a location of your choice and then edit the copied file. For example:

cp /usr/share/heketi/templates/sample-gluster-endpoints.yaml
/<path>/gluster-endpoints.yaml

 To specify the endpoints you want to create, update the copied sample-glusterendpoints.yaml file with the endpoints to be created based on the environment. Each Red Hat Gluster Storage trusted storage pool requires its own endpoint with the IP of the nodes in the trusted storage pool.

```
# cat sample-gluster-endpoints.yaml
apiVersion: v1
kind: Endpoints
metadata:
  name: glusterfs-cluster
subsets:
  - addresses:
      - ip: 192.168.10.100
    ports:
     - port: 1
  - addresses:
     - ip: 192.168.10.101
    ports:
     - port: 1
  - addresses:
      - ip: 192.168.10.102
    ports:
      - port: 1
```

name: is the name of the endpoint

ip: is the ip address of the Red Hat Gluster Storage nodes.

2. Execute the following command to create the endpoints:

```
# oc create -f <name_of_endpoint_file>
```

For example:

```
# oc create -f sample-gluster-endpoints.yaml
endpoints "glusterfs-cluster" created
```

3. To verify that the endpoints are created, execute the following command:

```
# oc get endpoints
```

For example:

```
# oc get endpoints
NAME ENDPOINTS
AGE
storage-project-router
192.168.121.233:80,192.168.121.233:443,192.168.121.233:1936 2d
glusterfs-cluster
192.168.121.168:1,192.168.121.172:1,192.168.121.233:1 3s
heketi 10.1.1.3:8080
2m
heketi-storage-endpoints
192.168.121.168:1,192.168.121.172:1,192.168.121.233:1 3m
```

4. Execute the following command to create a gluster service:

```
# oc create -f <name_of_service_file>
```

For example:

```
# cat sample-gluster-service.yaml
apiVersion: v1
kind: Service
metadata:
   name: glusterfs-cluster
spec:
   ports:
     - port: 1

# oc create -f sample-gluster-service.yaml
service "glusterfs-cluster" created
```

5. To verify that the service is created, execute the following command:

```
# oc get service
```

For example:

# oc get service NAME AGE	CLUSTER-IP	EXTERNAL-IP	PORT(S)
storage-project-router 80/TCP,443/TCP,1936/TCP	172.30.94.109 2d	<none></none>	
glusterfs-cluster	172.30.212.6	<none></none>	1/TCP
5s heketi	172.30.175.7	<none></none>	8080/TCP
2m heketi-storage-endpoints 3m	172.30.18.24	<none></none>	1/TCP



NOTE

The endpoints and the services must be created for each project that requires a persistent storage.

6. Create a 100G persistent volume with Replica 3 from GlusterFS and output a persistent volume specification describing this volume to the file pv001.json:

```
$ heketi-cli volume create --size=100 --persistent-volume-
file=pv001.json

cat pv001.json
{
    "kind": "PersistentVolume",
    "apiVersion": "v1",
    "metadata": {
        "name": "glusterfs-f8c612ee",
        "creationTimestamp": null
    },
    "spec": {
```

```
"capacity": {
    "storage": "100Gi"
},
    "glusterfs": {
        "endpoints": "TYPE ENDPOINT HERE",
        "path": "vol_f8c612eea57556197511f6b8c54b6070"
},
    "accessModes": [
        "ReadWriteMany"
],
    "persistentVolumeReclaimPolicy": "Retain"
},
    "status": {}
```



IMPORTANT

You must manually add the Labels information to the .json file.

Following is the example YAML file for reference:

```
apiVersion: v1
kind: PersistentVolume
metadata:
   name: pv-storage-project-glusterfs1
   labels:
     storage-tier: gold
spec:
   capacity:
     storage: 12Gi
accessModes:
     - ReadWriteMany
persistentVolumeReclaimPolicy: Retain
glusterfs:
   endpoints: TYPE END POINTS NAME HERE,
   path: vol_e6b77204ff54c779c042f570a71b1407
```

name: The name of the volume.

storage: The amount of storage allocated to this volume

glusterfs: The volume type being used, in this case the glusterfs plug-in

endpoints: The endpoints name that defines the trusted storage pool created

path: The Red Hat Gluster Storage volume that will be accessed from the Trusted Storage Pool.

accessModes: accessModes are used as labels to match a PV and a PVC. They currently do not define any form of access control.

labels: Use labels to identify common attributes or characteristics shared among volumes. In this case, we have defined the gluster volume to have a custom attribute (key) named **storage-tier** with a value of **gold** assigned. A claim will be able to select a PV with **storage-tier=gold** to match this PV.



NOTE

- heketi-cli also accepts the endpoint name on the command line (--persistent-volume-endpoint="TYPE ENDPOINT HERE"). This can then be piped to occreate -f to create the persistent volume immediately.
- o If there are multiple Red Hat Gluster Storage trusted storage pools in your environment, you can check on which trusted storage pool the volume is created using the heketi-cli volume list command. This command lists the cluster name. You can then update the endpoint information in the pv001.json file accordingly.
- When creating a Heketi volume with only two nodes with the replica count set to the default value of three (replica 3), an error "No space" is displayed by Heketi as there is no space to create a replica set of three disks on three different nodes.
- If all the heketi-cli write operations (ex: volume create, cluster create..etc) fails and the read operations (ex: topology info, volume info ..etc) are successful, then the possibility is that the gluster volume is operating in read-only mode.
- 7. Edit the pv001.json file and enter the name of the endpoint in the endpoint's section:

```
cat pv001.json
 "kind": "PersistentVolume",
 "apiVersion": "v1",
  "metadata": {
    "name": "glusterfs-f8c612ee",
    "creationTimestamp": null,
    "labels": {
      "storage-tier": "gold"
    }
 },
  "spec": {
    "capacity": {
      "storage": "12Gi"
    "glusterfs": {
      "endpoints": "glusterfs-cluster",
      "path": "vol_f8c612eea57556197511f6b8c54b6070"
    "accessModes": [
      "ReadWriteMany"
    "persistentVolumeReclaimPolicy": "Retain"
  "status": {}
```

8. Create a persistent volume by executing the following command:

```
# oc create -f pv001.json
```

```
# oc create -f pv001.json
persistentvolume "glusterfs-4fc22ff9" created
```

9. To verify that the persistent volume is created, execute the following command:

```
# oc get pv
```

For example:

```
# oc get pv

NAME CAPACITY ACCESSMODES STATUS CLAIM
REASON AGE
glusterfs-4fc22ff9 100Gi RWX Available
4s
```

10. Create a persistent volume claim file. For example:

```
# cat pvc.yaml
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
   name: glusterfs-claim
spec:
   accessModes:
    - ReadWriteMany
   resources:
     requests:
        storage: 100Gi
        selector:
        matchLabels:
        storage-tier: gold
```

11. Bind the persistent volume to the persistent volume claim by executing the following command:

```
# oc create -f pvc.yaml
```

For example:

```
# oc create -f pvc.yaml
persistentvolumeclaim"glusterfs-claim" created
```

12. To verify that the persistent volume and the persistent volume claim is bound, execute the following commands:

```
# oc get pv
# oc get pvc
```

```
# oc get pv
```

NAME CAPACITY ACCESSMODES STATUS CLAIM REASON AGE glusterfs-4fc22ff9 100Gi RWX Bound storageproject/glusterfs-claim 1m # oc get pvc NAME STATUS **VOLUME** CAPACITY ACCESSMODES AGE glusterfs-claim Bound glusterfs-4fc22ff9 100Gi **RWX** 11s

13. The claim can now be used in the application:

For example:

```
# cat app.yaml
apiVersion: v1
kind: Pod
metadata:
  name: busybox
spec:
  containers:
    - image: busybox
      command:
        - sleep
        - "3600"
      name: busybox
      volumeMounts:
        - mountPath: /usr/share/busybox
          name: mypvc
  volumes:
    - name: mypvc
      persistentVolumeClaim:
        claimName: glusterfs-claim
# oc create -f app.yaml
pod "busybox" created
```

For more information about using the glusterfs claim in the application see, https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html-single/configuring_clusters/#install-config-storage-examples-gluster-example.

14. To verify that the pod is created, execute the following command:

```
# oc get pods -n <storage_project_name>
```

```
# oc get pods -n storage-project

NAME READY STATUS RESTARTS
AGE
```

block-test-router-1-deploy 4h	0/1	Running	0
busybox 43s	1/1	Running	0
glusterblock-provisioner-1-bjpz4 4h	1/1	Running	0
glusterfs-7l5xf 4h	1/1	Running	0
glusterfs-hhxtk 4h	1/1	Running	3
glusterfs-m4rbc 4h	1/1	Running	0
heketi-1-3h9nb 4h	1/1	Running	Θ

15. To verify that the persistent volume is mounted inside the container, execute the following command:

oc rsh busybox

```
/ $ df -h
Filesystem
                                    Used Available Use% Mounted on
                          Size
/dev/mapper/docker-253:0-1310998-
81732b5fd87c197f627a24bcd2777f12eec4ee937cc2660656908b2fa6359129
                      100.0G
                                  34.1M
                                            99.9G
                                                    0% /
                                                      0% /dev
tmpfs
                          1.5G
                                        0
                                               1.5G
tmpfs
                          1.5G
                                        0
                                               1.5G
                                                      0%
/sys/fs/cgroup
192.168.121.168:vol_4fc22ff934e531dec3830cfbcad1eeae
                       99.9G
                                 66.1M
                                            99.9G
/usr/share/busybox
tmpfs
                          1.5G
                                        0
                                               1.5G
                                                      0%
/run/secrets
/dev/mapper/vg_vagrant-lv_root
                       37.7G
                                   3.8G
                                            32.0G
                                                  11%
/dev/termination-log
tmpfs
                          1.5G
                                    12.0K
                                                      0%
                                               1.5G
/var/run/secretgit s/kubernetes.io/serviceaccount
```



NOTE

If you encounter a permission denied error on the mount point, then refer to section Gluster Volume Security at: https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html-single/configuring_clusters/#install-configstorage-examples-gluster-example.

3.1.2. Dynamic Provisioning of Volumes

Dynamic provisioning enables you to provision a Red Hat Gluster Storage volume to a running application container without pre-creating the volume. The volume will be created dynamically as the claim request comes in, and a volume of exactly the same size will be provisioned to the application containers.

3.1.2.1. Configuring Dynamic Provisioning of Volumes

To configure dynamic provisioning of volumes, the administrator must define StorageClass objects that describe named "classes" of storage offered in a cluster. After creating a Storage Class, a secret for heketi authentication must be created before proceeding with the creation of persistent volume claim.

3.1.2.1.1. Creating Secret for Heketi Authentication

To create a secret for Heketi authentication, execute the following commands:



NOTE

If the **admin-key** value (secret to access heketi to get the volume details) was not set during the deployment of Red Hat Openshift Container Storage, then the following steps can be omitted.

1. Create an encoded value for the password by executing the following command:

```
# echo -n "<key>" | base64
```

where "key" is the value for "admin-key" that was created while deploying Red Hat Openshift Container Storage

For example:

```
# echo -n "mypassword" | base64
bXlwYXNzd29yZA==
```

2. Create a secret file. A sample secret file is provided below:

```
# cat glusterfs-secret.yaml

apiVersion: v1
kind: Secret
metadata:
   name: heketi-secret
   namespace: default
data:
   # base64 encoded password. E.g.: echo -n "mypassword" | base64
   key: bXlwYXNzd29yZA==
type: kubernetes.io/glusterfs
```

3. Register the secret on Openshift by executing the following command:

```
# oc create -f glusterfs-secret.yaml
secret "heketi-secret" created
```

3.1.2.1.2. Registering a Storage Class

When configuring a StorageClass object for persistent volume provisioning, the administrator must describe the type of provisioner to use and the parameters that will be used by the provisioner when it provisions a PersistentVolume belonging to the class.

1. To create a storage class execute the following command:

```
# cat > glusterfs-storageclass.yaml
apiVersion: storage.k8s.io/v1beta1
kind: StorageClass
metadata:
  name: gluster-container
provisioner: kubernetes.io/glusterfs
reclaimPolicy: Retain
parameters:
  resturl: "http://heketi-storage-project.cloudapps.mystorage.com"
  restuser: "admin"
  volumetype: "replicate:3"
  clusterid:
"630372ccdc720a92c681fb928f27b53f,796e6db1981f369ea0340913eeea4c9a"
  secretNamespace: "default"
  secretName: "heketi-secret"
  volumeoptions: "client.ssl on, server.ssl on"
  volumenameprefix: "test-vol"
allowVolumeExpansion: true
```

where,

resturl: Gluster REST service/Heketi service url which provision gluster volumes on demand. The general format must be IPaddress:Port and this is a mandatory parameter for GlusterFS dynamic provisioner. If Heketi service is exposed as a routable service in openshift/kubernetes setup, this can have a format similar to http://heketi-storage-project.cloudapps.mystorage.com where the fqdn is a resolvable heketi service url.

restuser: Gluster REST service/Heketi user who has access to create volumes in the trusted storage pool

volumetype: It specifies the volume type that is being used.



NOTE

Distributed-Three-way replication is the only supported volume type.

clusterid: It is the ID of the cluster which will be used by Heketi when provisioning the volume. It can also be a list of comma-separated cluster IDs. This is an optional parameter.



NOTE

To get the cluster ID, execute the following command:

heketi-cli cluster list

secretNamespace + secretName: Identification of Secret instance that contains the user password that is used when communicating with the Gluster REST service. These parameters are optional. Empty password will be used when both secretNamespace and secretName are

omitted.



NOTE

When the persistent volumes are dynamically provisioned, the Gluster plugin automatically creates an endpoint and a headless service in the name gluster-dynamic-<claimname>. This dynamic endpoint and service will be deleted automatically when the persistent volume claim is deleted.

volumeoptions: This is an optional parameter. It allows you to create glusterfs volumes with encryption enabled by setting the parameter to "client.ssl on, server.ssl on". For more information on enabling encryption, see Chapter 8, *Enabling Encryption*.



NOTE

Do not add this parameter in the storageclass if encryption is not enabled.

volumenameprefix: This is an optional parameter. It depicts the name of the volume created by heketi. For more information see Section 3.1.2.1.5, "(Optional) Providing a Custom Volume Name Prefix for Persistent Volumes"



NOTE

The value for this parameter cannot contain `_` in the storageclass.

allowVolumeExpansion: To increase the PV claim value, ensure to set the **allowVolumeExpansion** parameter in the storageclass file to **true**. For more information, see Section 3.1.2.1.7, "Expanding Persistent Volume Claim".

2. To register the storage class to Openshift, execute the following command:

```
# oc create -f glusterfs-storageclass.yaml
storageclass "gluster-container" created
```

3. To get the details of the storage class, execute the following command:

oc describe storageclass gluster-container

Name: gluster-container IsDefaultClass: No Annotations: <none>

Provisioner: kubernetes.io/glusterfs

Parameters: resturl=http://heketi-storage-

project.cloudapps.mystorage.com, restuser=admin, secretName=heketi-

secret, secretNamespace=default

No events.

3.1.2.1.3. Creating a Persistent Volume Claim

To create a persistent volume claim execute the following commands:

1. Create a Persistent Volume Claim file. A sample persistent volume claim is provided below:

```
# cat glusterfs-pvc-claim1.yam1
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
   name: claim1
   annotations:
    volume.beta.kubernetes.io/storage-class: gluster-container
spec:
   persistentVolumeReclaimPolicy: Retain
   accessModes:
        - ReadWriteOnce
   resources:
        requests:
        storage: 5Gi
```

persistentVolumeReclaimPolicy: This is an optional parameter. When this parameter is set to "Retain" the underlying persistent volume is retained even after the corresponding persistent volume claim is deleted.



NOTE

When PVC is deleted, the underlying heketi and gluster volumes are not deleted if "persistentVolumeReclaimPolicy:" is set to "Retain". To delete the volume, you must use heketi cli and then delete the PV.

2. Register the claim by executing the following command:

```
# oc create -f glusterfs-pvc-claim1.yaml
persistentvolumeclaim "claim1" created
```

3. To get the details of the claim, execute the following command:

```
# oc describe pvc <claim_name>
```

For example:

```
# oc describe pvc claim1

Name: claim1
Namespace: default
StorageClass: gluster-container
Status: Bound
Volume: pvc-54b88668-9da6-11e6-965e-54ee7551fd0c
Labels: <none>
Capacity: 4Gi
Access Modes: RWO
No events.
```

3.1.2.1.4. Verifying Claim Creation

To verify if the claim is created, execute the following commands:

1. To get the details of the persistent volume claim and persistent volume, execute the following command:

```
# oc get pv,pvc
NAME
                                              CAPACITY
              RECLAIMPOLICY
                              STATUS
                                         CLAIM
ACCESSMODES
REASON
         AGE
pv/pvc-962aa6d1-bddb-11e6-be23-5254009fc65b
                                                         RWO
Delete
                Bound
                           storage-project/claim1
                                                              3m
                       VOLUME
NAME
             STATUS
CAPACITY ACCESSMODES
                         AGE
pvc/claim1
             Bound
                       pvc-962aa6d1-bddb-11e6-be23-5254009fc65b
4Gi
           RWO
```

2. To validate if the endpoint and the services are created as part of claim creation, execute the following command:

```
# oc get endpoints, service
NAME
                               ENDPOINTS
AGE
ep/storage-project-router
192.168.68.3:443,192.168.68.3:1936,192.168.68.3:80
                                                      28d
ep/gluster-dynamic-claim1
192.168.68.2:1,192.168.68.3:1,192.168.68.4:1
                                                      5m
ep/heketi
                               10.130.0.21:8080
21d
ep/heketi-storage-endpoints
192.168.68.2:1,192.168.68.3:1,192.168.68.4:1
                                                      25d
NAME
                               CLUSTER-IP
                                                 EXTERNAL-IP
PORT(S)
                          AGE
svc/storage-project-router
                               172.30.166.64
                                                 <none>
80/TCP, 443/TCP, 1936/TCP
                          28d
svc/gluster-dynamic-claim1
                               172.30.52.17
                                                 <none>
                                                                1/TCP
5m
svc/heketi
                               172.30.129.113
                                                 <none>
                          21d
8080/TCP
svc/heketi-storage-endpoints
                               172.30.133.212
                                                 <none>
                                                                1/TCP
25d
```

3.1.2.1.5. (Optional) Providing a Custom Volume Name Prefix for Persistent Volumes

You can provide a custom volume name prefix to the persistent volume that is created. By providing a custom volume name prefix, users can now easily search/filter the volumes based on:

- Any string that was provided as the field value of "volnameprefix" in the storageclass file.
- Persistent volume claim name.
- Project / Namespace name.

To set the name, ensure that you have added the parameter **volumenameprefix** to the storage class file. For more information, see Section 3.1.2.1.2, "Registering a Storage Class"



NOTE

The value for this parameter cannot contain `_` in the storageclass.

To verify if the custom volume name prefix is set, execute the following command:

oc describe pv <pv_name>

For example:

oc describe pv pvc-f92e3065-25e8-11e8-8f17-005056a55501 Name: pvc-f92e3065-25e8-11e8-8f17-005056a55501

Labels: <none>

Annotations: Description=Gluster-Internal: Dynamically provisioned

PV

gluster.kubernetes.io/heketi-volume-

id=027c76b24b1a3ce3f94d162f843529c8

gluster.org/type=file

kubernetes.io/createdby=heketi-dynamic-provisioner

pv.beta.kubernetes.io/gid=2000

pv.kubernetes.io/bound-by-controller=yes

pv.kubernetes.io/provisioned-

by=kubernetes.io/glusterfs

volume.beta.kubernetes.io/mount-options=auto_unmount

StorageClass: gluster-container-prefix

Status: Bound

Claim: glusterfs/claim1

Reclaim Policy: Delete Access Modes: RWO Capacity: 1Gi

Message: Source:

Type: Glusterfs (a Glusterfs mount on the host that

shares a pod's lifetime)

EndpointsName: glusterfs-dynamic-claim1

Path: test-vol_glusterfs_claim1_f9352e4c-25e8-11e8-

b460-005056a55501

ReadOnly: false Events: <none>

The value for **Path** will have the custom volume name prefix attached to the namespace and the claim name, which is "test-vol" in this case.

3.1.2.1.6. Using the Claim in a Pod

Execute the following steps to use the claim in a pod.

1. To use the claim in the application, for example

cat app.yaml

```
apiVersion: v1
kind: Pod
metadata:
  name: busybox
spec:
  containers:
    - image: busybox
      command:
        - sleep
        - "3600"
      name: busybox
      volumeMounts:
        - mountPath: /usr/share/busybox
          name: mypvc
  volumes:
    - name: mypvc
      persistentVolumeClaim:
        claimName: claim1
# oc create -f app.yaml
pod "busybox" created
```

For more information about using the glusterfs claim in the application see, https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html-single/configuring_clusters/#install-config-storage-examples-gluster-example.

2. To verify that the pod is created, execute the following command:

```
# oc get pods -n storage-project
NAME
                                     READY
                                               STATUS
RESTARTS
           AGE
storage-project-router-1-at7tf
                                     1/1
                                               Running
                                                               0
13d
                                     1/1
busybox
                                               Running
                                                               0
8s
glusterfs-dc-192.168.68.2-1-hu28h
                                     1/1
                                               Running
                                                               0
glusterfs-dc-192.168.68.3-1-ytnlg
                                     1/1
                                               Running
glusterfs-dc-192.168.68.4-1-juqcq
                                     1/1
                                               Running
                                                               0
13d
heketi-1-9r47c
                                     1/1
                                                Running
                                                               0
13d
```

3. To verify that the persistent volume is mounted inside the container, execute the following command:

```
/ $ df -h
Filesystem Size Used Available Use% Mounted on
/dev/mapper/docker-253:0-666733-
38050a1d2cdb41dc00d60f25a7a295f6e89d4c529302fb2b93d8faa5a3205fb9
```

oc rsh busybox

	10.0G	33.8M	9.9G	0% /
tmpfs	23.5G	0	23.5G	0% /dev
tmpfs	23.5G	Θ	23.5G	0%
/sys/fs/cgroup				
/dev/mapper/rhgs-root				
3	17.5G	3.6G	13.8G	21%
/run/secrets				
/dev/mapper/rhgs-root				
, act,apper,ge 1 ee 2	17.5G	3.6G	13.8G	21%
/dev/termination-log	17.100	0.00	10.00	21/0
/dev/mapper/rhgs-root				
/ dev/ mapper// rigs root	17.5G	3.6G	13.8G	21%
/etc/resolv.conf	17.50	3.00	10.00	21/0
/dev/mapper/rhgs-root				
γαεν/ ιιαρρεί / Γίτιgs - Γουτ	17.5G	3.6G	13.8G	21%
/etc/hostname	17.56	3.00	13.00	21/0
/dev/mapper/rhgs-root				
/ dev/ iiiapper / r rigs - r oot	17.5G	3.6G	13.8G	21% /etc/hosts
shm	17.3G 64.0M	0	64.0M	0% /dev/shm
		•		0% /uev/Siiii
192.168.68.2:vol_5b05c1				40/
/ / a la a .a a / la la a	4.0G	32.6M	4.0G	1%
/usr/share/busybox				
tmpfs	23.5G	16.0K	23.5G	0%
/var/run/secrets/kuberr				
tmpfs	23.5G	Θ	23.5G	0%
/proc/kcore				
tmpfs	23.5G	Θ	23.5G	0%
/proc/timer_stats				

3.1.2.1.7. Expanding Persistent Volume Claim

To increase the PV claim value, ensure to set the **allowVolumeExpansion** parameter in the storageclass file to **true**. For more information refer, Section 3.1.2.1.2, "Registering a Storage Class"



NOTE

You can also resize a PV via the OpenShift Container Platform 3.11 Web Console.

To expand the persistent volume claim value, execute the following commands:

1. If the feature gates **ExpandPersistentVolumes**, and the admissionconfig **PersistentVolumeClaimResize** are not enabled, then edit the master.conf file located at /etc/origin/master/master-config.yaml on the master to enable them. For example:

To enable feature gates **ExpandPersistentVolumes**

apiServerArguments:
 runtime-config:

- apis/settings.k8s.io/v1alpha1=true storage-backend:
- etcd3

storage-media-type:

application/vnd.kubernetes.protobuf feature-gates:

```
    ExpandPersistentVolumes=true
controllerArguments:
        feature-gates:
        - ExpandPersistentVolumes=true
```

To enable admissionconfig **PersistentVolumeClaimResize** add the following under admission config in the master-config file.

```
admissionConfig:
   pluginConfig:
    PersistentVolumeClaimResize:
        configuration:
        apiVersion: v1
        disable: false
        kind: DefaultAdmissionConfig
```

1. Restart the OpenShift master by running the following commands:

```
# /usr/local/bin/master-restart api
# /usr/local/bin/master-restart controllers
```

2. To check the existing persistent volume size, execute the following command on the app pod:

```
# oc rsh busybox
# df -h
```

```
# oc rsh busybox
/ # df -h
Filesystem
                          Size
                                    Used Available Use% Mounted on
/dev/mapper/docker-253:0-100702042-
0fa327369e7708b67f0c632d83721cd9a5b39fd3a7b3218f3ff3c83ef4320ce7
                                   34.2M
                                                     0% /
                         10.0G
                                              9.9G
tmpfs
                                                     0% /dev
                         15.6G
                                       0
                                             15.6G
tmpfs
                         15.6G
                                       0
                                             15.6G
                                                     0%
/sys/fs/cgroup
/dev/mapper/rhel_dhcp47--150-root
                         50.0G
                                    7.4G
                                             42.6G 15%
/dev/termination-log
/dev/mapper/rhel_dhcp47--150-root
                                    7.4G
                                             42.6G 15%
                         50.0G
/run/secrets
/dev/mapper/rhel_dhcp47--150-root
                                    7.4G
                                             42.6G 15%
/etc/resolv.conf
/dev/mapper/rhel_dhcp47--150-root
                                    7.4G
                         50.0G
                                             42.6G 15%
/etc/hostname
/dev/mapper/rhel_dhcp47--150-root
                         50.0G
                                    7.4G
                                             42.6G 15% /etc/hosts
                         64.0M
                                             64.0M
                                                     0% /dev/shm
                                       0
10.70.46.177:test-vol_glusterfs_claim10_d3e15a8b-26b3-11e8-acdf-
```

005056a55501				
	2.0G	32.6M	2.0G	2%
/usr/share/busybox				
tmpfs	15.6G	16.0K	15.6G	0%
/var/run/secrets/kube	rnetes.io/s	erviceaccou	ınt	
tmpfs	15.6G	0	15.6G	0%
/proc/kcore				
tmpfs	15.6G	0	15.6G	0%
/proc/timer_list				
tmpfs	15.6G	Θ	15.6G	0%
/proc/timer_stats				
tmpfs	15.6G	Θ	15.6G	0%
/proc/sched_debug				
tmpfs	15.6G	0	15.6G	0% /proc/scsi
tmpfs	15.6G	0	15.6G	0%
/sys/firmware				

In this example the persistent volume size is 2Gi

3. To edit the persistent volume claim value, execute the following command and edit the following storage parameter:

```
resources:
    requests:
    storage: <storage_value>

# oc edit pvc <claim_name>
```

For example, to expand the storage value to 20Gi:

```
# oc edit pvc claim3
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
  annotations:
    pv.kubernetes.io/bind-completed: "yes"
    pv.kubernetes.io/bound-by-controller: "yes"
    volume.beta.kubernetes.io/storage-class: gluster-container2
    volume.beta.kubernetes.io/storage-provisioner:
kubernetes.io/glusterfs
  creationTimestamp: 2018-02-14T07:42:00Z
  name: claim3
  namespace: storage-project
  resourceVersion: "283924"
  selfLink: /api/v1/namespaces/storage-
project/persistentvolumeclaims/claim3
  uid: 8a9bb0df-115a-11e8-8cb3-005056a5a340
spec:
  accessModes:
  - ReadWriteOnce
  resources:
   requests:
      storage: 20Gi
  volumeName: pvc-8a9bb0df-115a-11e8-8cb3-005056a5a340
status:
```

accessModes:

- ReadWriteOnce

capacity:

storage: 2Gi phase: Bound

4. To verify, execute the following command on the app pod:

oc rsh busybox

/ # df -h

# oc rsh busybox # df -h					
Filesystem	Size	Used	Available	Use%	Mounted on
/dev/mapper/docker-253:0	9-10070204	2-			
0fa327369e7708b67f0c6320	d83721cd9a	5b39fd3a	a7b3218f3f1	f3c83e	ef4320ce7
	10.0G	34.2M	9.9G	0%	/
tmpfs	15.6G	0	15.6G	0%	/dev
tmpfs	15.6G	0	15.6G	0%	
/sys/fs/cgroup					
/dev/mapper/rhel_dhcp47					
	50.0G	7.4G	42.6G	15%	
/dev/termination-log					
/dev/mapper/rhel_dhcp47					
	50.0G	7.4G	42.6G	15%	
/run/secrets	450				
/dev/mapper/rhel_dhcp47			40.00	4 = 0 /	
	50.0G	7.4G	42.6G	15%	
/etc/resolv.conf	450				
/dev/mapper/rhel_dhcp47		7 40	40.00	4 = 0/	
/ata/baatnama	50.0G	7.4G	42.6G	15%	
/etc/hostname	150 root				
/dev/mapper/rhel_dhcp47	50.0G	7.4G	42.6G	150/	/etc/hosts
shm	64.0M	7.40	42.00 64.0M		/dev/shm
10.70.46.177:test-vol_g		•			
005056a55501		1a111110_0	13613800-20	703-1	ieo-acui-
	20.0G	65.3M	19.9G	1%	
/usr/share/busybox					
tmpfs	15.6G	16.0K	15.6G	0%	
/var/run/secrets/kuberne		_		•	
tmpfs	15.6G	0	15.6G	0%	
/proc/kcore	45.00		45.00	00/	
tmpfs	15.6G	0	15.6G	0%	
/proc/timer_list	15 66	0	15 66	00/	
tmpfs	15.6G	0	15.6G	0%	
/proc/timer_stats	15 60	0	1F 6C	00/	
tmpfs /proc/sched_debug	15.6G	0	15.6G	0%	
tmpfs	15.6G	O	15.6G	<u>۵</u> 0/	/nroc/sesi
tmpfs	15.6G 15.6G	0	15.6G	0%	/proc/scsi
/sys/firmware	T3.00	U	15.00	⊍%	
/ 3 y 3 / 1 II IIIWal C					

It is observed that the size is changed from 2Gi (earlier) to 20Gi.

3.1.2.1.8. Deleting a Persistent Volume Claim



NOTE

If the "persistentVolumeReclaimPolicy" parameter was set to "Retain" when registering the storageclass, the underlying PV and the corresponding volume remains even when a PVC is deleted.

1. To delete a claim, execute the following command:

```
# oc delete pvc <claim-name>
```

For example:

```
# oc delete pvc claim1
persistentvolumeclaim "claim1" deleted
```

2. To verify if the claim is deleted, execute the following command:

```
# oc get pvc <claim-name>
```

For example:

```
# oc get pvc claim1
No resources found.
```

When the user deletes a persistent volume claim that is bound to a persistent volume created by dynamic provisioning, apart from deleting the persistent volume claim, Kubernetes will also delete the persistent volume, endpoints, service, and the actual volume. Execute the following commands if this has to be verified:

• To verify if the persistent volume is deleted, execute the following command:

```
# oc get pv <pv-name>
```

For example:

```
\# oc get pv pvc-962aa6d1-bddb-11e6-be23-5254009fc65b No resources found.
```

To verify if the endpoints are deleted, execute the following command:

```
# oc get endpoints <endpointname>
```

```
# oc get endpoints gluster-dynamic-claim1
No resources found.
```

• To verify if the service is deleted, execute the following command:

```
# oc get service <servicename>
```

For example:

```
# oc get service gluster-dynamic-claim1
No resources found.
```

3.1.3. Volume Security

Volumes come with a UID/GID of 0 (root). For an application pod to write to the volume, it should also have a UID/GID of 0 (root). With the volume security feature the administrator can now create a volume with a unique GID and the application pod can write to the volume using this unique GID

Volume security for statically provisioned volumes

To create a statically provisioned volume with a GID, execute the following command:

```
$ heketi-cli volume create --size=100 --persistent-volume-file=pv001.json
--gid=590
```

In the above command, a 100G persistent volume with a GID of 590 is created and the output of the persistent volume specification describing this volume is added to the pv001.json file.

For more information about accessing the volume using this GID, see https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html/configuring_clusters/persistent-storage-examples#install-config-storage-examples-gluster-example.

Volume security for dynamically provisioned volumes

Two new parameters, gidMin and gidMax, are introduced with dynamic provisioner. These values allow the administrator to configure the GID range for the volume in the storage class. To set up the GID values and provide volume security for dynamically provisioned volumes, execute the following commands:

1. Create a storage class file with the GID values. For example:

```
# cat glusterfs-storageclass.yaml

apiVersion: storage.k8s.io/v1beta1
kind: StorageClass
metadata:
    name:gluster-container
provisioner: kubernetes.io/glusterfs
parameters:
    resturl: "http://heketi-storage-project.cloudapps.mystorage.com"
    restuser: "admin"
    secretNamespace: "default"
    secretName: "heketi-secret"
    gidMin: "2000"
    gidMax: "4000"
```



NOTE

If the gidMin and gidMax value are not provided, then the dynamic provisioned volumes will have the GID between 2000 and 2147483647.

- 2. Create a persistent volume claim. For more information see, Section 3.1.2.1.3, "Creating a Persistent Volume Claim"
- 3. Use the claim in the pod. Ensure that this pod is non-privileged. For more information see, Section 3.1.2.1.6, "Using the Claim in a Pod"
- 4. To verify if the GID is within the range specified, execute the following command:

```
# oc rsh busybox
```

\$ id

For example:

```
$ id
uid=1000060000 gid=0(root) groups=0(root),2001
```

where, 2001 in the above output is the allocated GID for the persistent volume, which is within the range specified in the storage class. You can write to this volume with the allocated GID.



NOTE

When the persistent volume claim is deleted, the GID of the persistent volume is released from the pool.

3.2. BLOCK STORAGE

Block storage allows the creation of high performance individual storage units. Unlike the traditional file storage capability that glusterfs supports, each storage volume/block device can be treated as an independent disk drive, so that each storage volume/block device can support an individual file system.

gluster-block is a distributed management framework for block devices. It aims to make Gluster-backed block storage creation and maintenance as simple as possible. gluster-block can provision block devices and export them as iSCSI LUN's across multiple nodes, and uses iSCSI protocol for data transfer as SCSI block/commands.



NOTE

Static provisioning of volumes is not supported for Block storage. Dynamic provisioning of volumes is the only method supported.

The recommended Red Hat Enterprise Linux (RHEL) version for block storage is RHEL-7.5.3.

Block volume expansion is not supported in Container-Native Storage 3.6.

3.2.1. Dynamic Provisioning of Volumes for Block Storage

Dynamic provisioning enables you to provision a Red Hat Gluster Storage volume to a running application container without pre-creating the volume. The volume will be created dynamically as the claim request comes in, and a volume of exactly the same size will be provisioned to the application containers.

3.2.1.1. Configuring Dynamic Provisioning of Volumes

To configure dynamic provisioning of volumes, the administrator must define StorageClass objects that describe named "classes" of storage offered in a cluster. After creating a Storage Class, a secret for heketi authentication must be created before proceeding with the creation of persistent volume claim.

3.2.1.1.1. Configuring Multipathing on all Initiators

To ensure the iSCSI initiator can communicate with the iSCSI targets and achieve HA using multipathing, execute the following steps on all the OpenShift nodes (iSCSI initiator) where the app pods are hosted:

1. To install initiator related packages on all the nodes where initiator has to be configured, execute the following command:

```
# yum install iscsi-initiator-utils device-mapper-multipath
```

2. To enable multipath, execute the following command:

```
# mpathconf --enable
```

3. Create and add the following content to the multipath.conf file:

```
# cat >> /etc/multipath.conf <<EOF</pre>
# LIO iSCSI
devices {
        device {
                 vendor "LIO-ORG"
                 user_friendly_names "yes" # names like mpatha
                 path_grouping_policy "failover" # one path per
group
                 hardware_handler "1 alua"
                 path_selector "round-robin 0"
                 failback immediate
                 path_checker "tur"
                 prio "alua"
                 no_path_retry 120
        }
}
EOF
```

4. Execute the following commands to start multipath daemon and [re]load the multipath configuration:

```
# systemctl start multipathd
# systemctl reload multipathd
```

3.2.1.1.2. Creating Secret for Heketi Authentication

To create a secret for Heketi authentication, execute the following commands:



NOTE

If the **admin-key** value (secret to access heketi to get the volume details) was not set during the deployment of Red Hat Openshift Container Storage, then the following steps can be omitted.

1. Create an encoded value for the password by executing the following command:

```
# echo -n "<key>" | base64
```

where "key" is the value for admin-key that was created while deploying CNS

For example:

```
# echo -n "mypassword" | base64
bXlwYXNzd29yZA==
```

2. Create a secret file. A sample secret file is provided below:

```
# cat glusterfs-secret.yaml

apiVersion: v1
kind: Secret
metadata:
   name: heketi-secret
   namespace: default
data:
   # base64 encoded password. E.g.: echo -n "mypassword" | base64
   key: bXlwYXNzd29yZA==
type: gluster.org/glusterblock
```

3. Register the secret on Openshift by executing the following command:

```
# oc create -f glusterfs-secret.yaml
secret "heketi-secret" created
```

3.2.1.1.3. Registering a Storage Class

When configuring a StorageClass object for persistent volume provisioning, the administrator must describe the type of provisioner to use and the parameters that will be used by the provisioner when it provisions a PersistentVolume belonging to the class.

1. Create a storage class. A sample storage class file is presented below:

```
# cat > glusterfs-block-storageclass.yaml
apiVersion: storage.k8s.io/v1
kind: StorageClass
metadata:
```

name: gluster-block

provisioner: gluster.org/glusterblock

reclaimPolicy: Retain

parameters:

resturl: "http://heketi-storage-project.cloudapps.mystorage.com"

restuser: "admin"

restsecretnamespace: "default" restsecretname: "heketi-secret"

hacount: "3" clusterids:

"630372ccdc720a92c681fb928f27b53f,796e6db1981f369ea0340913eeea4c9a"

chapauthenabled: "true"
volumenameprefix: "test-vol"

where,

resturl: Gluster REST service/Heketi service url which provision gluster volumes on demand. The general format must be IPaddress:Port and this is a mandatory parameter for GlusterFS dynamic provisioner. If Heketi service is exposed as a routable service in openshift/kubernetes setup, this can have a format similar to http://heketi-storage-project.cloudapps.mystorage.com where the fqdn is a resolvable heketi service url.

restuser: Gluster REST service/Heketi user who has access to create volumes in the trusted storage pool

restsecretnamespace + **restsecretname**: Identification of Secret instance that contains user password to use when talking to Gluster REST service. These parameters are optional. Empty password will be used when both **restsecretnamespace** and **restsecretname** are omitted.

hacount: It is the count of the number of paths to the block target server. **hacount** provides high availability via multipathing capability of iSCSI. If there is a path failure, the I/Os will not be interrupted and will be served via another available paths.

clusterids: It is the ID of the cluster which will be used by Heketi when provisioning the volume. It can also be a list of comma-separated cluster IDs. This is an optional parameter.



NOTE

To get the cluster ID, execute the following command:

heketi-cli cluster list

chapauthenabled: If you want to provision block volume with CHAP authentication enabled, this value has to be set to true. This is an optional parameter.

volumenameprefix: This is an optional parameter. It depicts the name of the volume created by heketi. For more information see, Section 3.2.1.1.6, "(Optional) Providing a Custom Volume Name Prefix for Persistent Volumes"



NOTE

The value for this parameter cannot contain ` ` in the storageclass.

2. To register the storage class to Openshift, execute the following command:

```
# oc create -f glusterfs-block-storageclass.yaml
storageclass "gluster-block" created
```

3. To get the details of the storage class, execute the following command:

```
# oc describe storageclass gluster-block
Name: gluster-block
IsDefaultClass: No
Annotations: <none>
Provisioner: gluster.org/glusterblock
Parameters:
chapauthenabled=true, hacount=3, opmode=heketi, restsecretname=heketi-secret, restsecretnamespace=default, resturl=http://heketi-storage-project.cloudapps.mystorage.com, restuser=admin
Events: <none>
```

3.2.1.1.4. Creating a Persistent Volume Claim

To create a persistent volume claim execute the following commands:

1. Create a Persistent Volume Claim file. A sample persistent volume claim is provided below:

```
# cat glusterfs-block-pvc-claim.yaml
kind: PersistentVolumeClaim
apiVersion: v1
metadata:
   name: claim1
   annotations:
    volume.beta.kubernetes.io/storage-class: gluster-block
spec:
   persistentVolumeReclaimPolicy: Retain
   accessModes:
    - ReadWriteOnce
   resources:
     requests:
        storage: 5Gi
```

persistentVolumeReclaimPolicy: This is an optional parameter. When this parameter is set to "Retain" the underlying persistent volume is retained even after the corresponding persistent volume claim is deleted.



NOTE

When PVC is deleted, the underlying heketi and gluster volumes are not deleted if "persistentVolumeReclaimPolicy:" is set to "Retain". To delete the volume, you must use heketi cli and then delete the PV.

2. Register the claim by executing the following command:

```
# oc create -f glusterfs-block-pvc-claim.yaml
persistentvolumeclaim "claim1" created
```

3. To get the details of the claim, execute the following command:

```
# oc describe pvc <claim_name>
```

For example:

```
# oc describe pvc claim1
           claim1
Name:
Namespace: block-test
StorageClass: gluster-block
Status: Bound
Volume: pvc-ee30ff43-7ddc-11e7-89da-5254002ec671
Labels:
             <none>
Annotations: control-plane.alpha.kubernetes.io/leader=
{"holderIdentity": "8d7fecb4-7dba-11e7-a347-
0a580a830002", "leaseDurationSeconds":15, "acquireTime": "2017-08-
10T15:02:30Z", "renewTime": "2017-08-10T15:02:58Z", "lea...
      pv.kubernetes.io/bind-completed=yes
      pv.kubernetes.io/bound-by-controller=yes
      volume.beta.kubernetes.io/storage-class=gluster-block
      volume.beta.kubernetes.io/storage-
provisioner=gluster.org/glusterblock
Capacity: 5Gi
Access Modes:
                RW0
Events:
 FirstSeen LastSeen Count From
SubObjectPath Type
                        Reason
                                            Message
                                ----
                -----
          1m
                   1
                        gluster.org/glusterblock 8d7fecb4-7dba-
11e7-a347-0a580a830002
                                Normal
                                             Provisioning
External provisioner is provisioning volume for claim "block-
test/claim1"
                         persistentvolume-controller
1 m
     1 m
                   18
             ExternalProvisioning cannot find provisioner
"gluster.org/glusterblock", expecting that a volume for the claim is
provisioned either manually or via external software
                        gluster.org/glusterblock 8d7fecb4-7dba-
          1m
                   1
11e7-a347-0a580a830002
                                Normal
ProvisioningSucceeded Successfully provisioned volume pvc-
ee30ff43-7ddc-11e7-89da-5254002ec671
```

3.2.1.1.5. Verifying Claim Creation

To verify if the claim is created, execute the following commands:

1. To get the details of the persistent volume claim and persistent volume, execute the following command:

oc get pv,pvc NAME CAPACITY ACCESSMODES RECLAIMPOLICY STATUS CLAIM STORAGECLASS REASON AGE pv/pvc-ee30ff43-7ddc-11e7-89da-5254002ec671 5Gi **RWO** Delete Bound block-test/claim1 gluster-block 3m NAME STATUS **VOLUME** CAPACITY ACCESSMODES STORAGECLASS AGE pvc-ee30ff43-7ddc-11e7-89da-5254002ec671 pvc/claim1 Bound

gluster-block

4m

3.2.1.1.6. (Optional) Providing a Custom Volume Name Prefix for Persistent Volumes

You can provide a custom volume name prefix to the persistent volume that is created. By providing a custom volume name prefix, users can now easily search/filter the volumes based on:

- Any string that was provided as the field value of "volnameprefix" in the storageclass file.
- Persistent volume claim name.

RWO

• Project / Namespace name.

5Gi

To set the name, ensure that you have added the parameter **volumenameprefix** to the storage class file. For more information, refer Section 3.2.1.1.3, "Registering a Storage Class"



NOTE

The value for this parameter cannot contain `_` in the storageclass.

To verify if the custom volume name prefix is set, execute the following command:

```
# oc describe pv <pv_name>
```

```
# oc describe pv pvc-4e97bd84-25f4-11e8-8f17-005056a55501
    Name:
                     pvc-4e97bd84-25f4-11e8-8f17-005056a55501
    Labels:
                     <none>
                     AccessKey=glusterblk-67d422eb-7b78-4059-9c21-
    Annotations:
a58e0eabe049-secret
                     AccessKeyNs=glusterfs
Blockstring=url:http://172.31.251.137:8080,user:admin,secret:heketi-
secret, secretnamespace: glusterfs
                     Description=Gluster-external: Dynamically
provisioned PV
                     gluster.org/type=block
                     gluster.org/volume-
id=cd37c089372040eba20904fb60b8c33e
                     glusterBlkProvIdentity=gluster.org/glusterblock
                     glusterBlockShare=test-
```

```
vol_glusterfs_bclaim1_4eab5a22-25f4-11e8-954d-0a580a830003
                     kubernetes.io/createdby=heketi
                     pv.kubernetes.io/provisioned-
by=gluster.org/glusterblock
                     v2.0.0=v2.0.0
    StorageClass:
                     gluster-block-prefix
    Status:
                     Bound
    Claim:
                     glusterfs/bclaim1
    Reclaim Policy: Delete
    Access Modes:
                   RW0
    Capacity:
                     5Gi
    Message:
    Source:
        Type:
                            ISCSI (an ISCSI Disk resource that is
attached to a kubelet's host machine and then exposed to the pod)
                            10.70.46.177
        TargetPortal:
                            iqn.2016-12.org.gluster-block:67d422eb-7b78-
        IQN:
4059-9c21-a58e0eabe049
        Lun:
        ISCSIInterface
                            default
                            xfs
        FSType:
        ReadOnly:
                            false
        Portals:
                            [10.70.46.142 10.70.46.4]
        DiscoveryCHAPAuth: false
        SessionCHAPAuth:
                            true
        SecretRef:
                            {glusterblk-67d422eb-7b78-4059-9c21-
a58e0eabe049-secret }
        InitiatorName:
                            <none>
    Events:
                            <none>
```

The value for **glusterBlockShare** will have the custom volume name prefix attached to the namespace and the claim name, which is "test-vol" in this case.

3.2.1.1.7. Using the Claim in a Pod

Execute the following steps to use the claim in a pod.

1. To use the claim in the application, for example

```
# cat app.yaml
apiVersion: v1
kind: Pod
metadata:
  name: busybox
spec:
  containers:
    - image: busybox
      command:
        - sleep
        - "3600"
      name: busybox
      volumeMounts:
        - mountPath: /usr/share/busybox
          name: mypvc
  volumes:
```

- name: mypvc

persistentVolumeClaim:
 claimName: claim1

oc create -f app.yaml
pod "busybox" created

For more information about using the glusterfs claim in the application see, https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html-single/configuring_clusters/#install-config-storage-examples-gluster-example.

2. To verify that the pod is created, execute the following command:

# oc get pods -n storage-project			
NAME	READY	STATUS	RESTARTS
AGE block-test-router-1-deploy	0/1	Running	0
4h	4 /4	· ·	0
busybox 43s	1/1	Running	0
glusterblock-provisioner-1-bjpz4 4h	1/1	Running	0
glusterfs-715xf 4h	1/1	Running	0
glusterfs-hhxtk 4h	1/1	Running	3
glusterfs-m4rbc 4h	1/1	Running	0
heketi-1-3h9nb 4h	1/1	Running	0

3. To verify that the persistent volume is mounted inside the container, execute the following command:

oc rsh busybox

```
/ # df -h
Filesystem
                          Size
                                    Used Available Use% Mounted on
/dev/mapper/docker-253:1-11438-
39febd9d64f3a3594fc11da83d6cbaf5caf32e758eb9e2d7bdd798752130de7e
                        10.0G
                                  33.9M
                                             9.9G
                                                    0% /
tmpfs
                                                     0% /dev
                          3.8G
                                       0
                                              3.8G
tmpfs
                          3.8G
                                              3.8G
                                                     0%
/sys/fs/cgroup
/dev/mapper/VolGroup00-LogVol00
                                   2.8G
                         7.7G
                                             4.5G 39%
/dev/termination-log
/dev/mapper/VolGroup00-LogVol00
                                   2.8G
                                             4.5G
                                                   39%
/run/secrets
/dev/mapper/VolGroup00-LogVol00
                         7.7G
                                   2.8G
                                             4.5G 39%
/etc/resolv.conf
```

/dev/mapper/VolGroup00-LogVol00				
	7.7G	2.8G	4.5G	39%
/etc/hostname				
/dev/mapper/VolGroup00-L	.ogVol00			
	7.7G	2.8G	4.5G	39% /etc/hosts
shm	64.0M	Θ	64.0M	0% /dev/shm
/dev/mpatha	5.0G	32.2M	5	.0G 1%
/usr/share/busybox				
tmpfs	3.8G	16.0K	3.8G	0%
/var/run/secrets/kuberne	tes.io/ser	viceaccoun	t	
tmpfs	3.8G	Θ	3.8G	0%
/proc/kcore				
tmpfs	3.8G	Θ	3.8G	0%
/proc/timer_list				
tmpfs	3.8G	Θ	3.8G	0%
/proc/timer_stats				
tmpfs	3.8G	Θ	3.8G	0%
/proc/sched_debug				

3.2.1.1.8. Deleting a Persistent Volume Claim



NOTE

If the "persistentVolumeReclaimPolicy" parameter was set to "Retain" when registering the storageclass, the underlying PV and the corresponding volume remains even when a PVC is deleted.

1. To delete a claim, execute the following command:

```
# oc delete pvc <claim-name>
```

For example:

```
# oc delete pvc claim1
persistentvolumeclaim "claim1" deleted
```

2. To verify if the claim is deleted, execute the following command:

```
# oc get pvc <claim-name>
```

For example:

```
# oc get pvc claim1
No resources found.
```

When the user deletes a persistent volume claim that is bound to a persistent volume created by dynamic provisioning, apart from deleting the persistent volume claim, Kubernetes will also delete the persistent volume, endpoints, service, and the actual volume. Execute the following commands if this has to be verified:

• To verify if the persistent volume is deleted, execute the following command:

```
# oc get pv <pv-name>
```

For example:

oc get pv pvc-962aa6d1-bddb-11e6-be23-5254009fc65b No resources found.

Next step: If you are installing Red Hat Openshift Container Storage 3.10, and you want to use block storage as the backend storage for logging and metrics, proceed to Chapter 7, *Gluster Block Storage as Backend for Logging and Metrics*.

3.2.2. Replacing a Block on Block Storage

If you want to replace a block from a node that is out of resource or is faulty, it can be replaced to a new node.

Execute the following commands

1. Execute the following command to fetch the zone and cluster info from heketi

```
# heketi-cli topology info --user=<user> --secret=<user key>
```

- --user heketi user
- --secret Secret key for a specified user
- 2. After obtaining the cluster id and zone id add a new node to heketi by executing the following command:



NOTE

Before adding the node, ensure the node is labeled as a glusterfs storage host by adding the label "glusterfs=storage-host", using the following command;

oc label node <NODENAME> glusterfs=storage-host

```
# heketi-cli node add --zone=<zoneid> --cluster=<clusterid> --
management-host-name=<new hostname> --storage-host-name=<new node
ip> --user=<user> --secret=<user key>
```

- --cluster The cluster in which the node should reside
- --management-host-name Management hostname. This is the new node that has to be added.
- --storage-host-name Storage hostname.
- --zone The zone in which the node should reside
- --user heketi user.
- --secret Secret key for a specified user

```
heketi-cli node add --zone=1 --
cluster=607204cb27346a221f39887a97cf3f90 --management-host-
name=dhcp43-241.lab.eng.blr.redhat.com --storage-host-
name=10.70.43.241 --user=admin --secret=adminkey

Node information:
Id: 2639c473a2805f6e19d45997bb18cb9c
State: online
Cluster Id: 607204cb27346a221f39887a97cf3f90
Zone: 1
Management Hostname dhcp43-241.lab.eng.blr.redhat.com
Storage Hostname 10.70.43.241
```

3. Execute the following command to add the device

```
# heketi-cli device add --name=<device name> --node=<node id> --
user=<user> --secret=<user key>
```

- --name Name of device to add
- --node Newly added node id

For example:

```
# heketi-cli device add --name=/dev/vdc --
node=2639c473a2805f6e19d45997bb18cb9c --user=admin --secret=adminkey
Device added successfully
```

4. After the new node and its associated devices are added to heketi, the faulty or unwanted node can be removed from heketi

To remove any node from heketi, follow this workflow:

- node disable (Disallow usage of a node by placing it offline)
- o node replace (Removes a node and all its associated devices from Heketi)
- o device delete (Deletes a device from Heketi node)
- node delete (Deletes a node from Heketi management)
- 5. Execute the following command to fetch the node list from heketi

```
#heketi-cli node list --user=<user> --secret=<user key>
```

```
# heketi-cli node list --user=admin --secret=adminkey
Id:05746c562d6738cb5d7de149be1dac04
Cluster:607204cb27346a221f39887a97cf3f90
Id:ab37fc5aabbd714eb8b09c9a868163df
Cluster:607204cb27346a221f39887a97cf3f90
Id:c513da1f9bda528a9fd6da7cb546a1ee
Cluster:607204cb27346a221f39887a97cf3f90
Id:e6ab1fe377a420b8b67321d9e60c1ad1
```

Cluster:607204cb27346a221f39887a97cf3f90

6. Execute the following command to fetch the node info of the node, that has to be deleted from heketi:

```
# heketi-cli node info <nodeid> --user=<user> --secret=<user key>
```

For example:

```
# heketi-cli node info c513da1f9bda528a9fd6da7cb546a1ee --user=admin
--secret=adminkev
Node Id: c513da1f9bda528a9fd6da7cb546a1ee
State: online
Cluster Id: 607204cb27346a221f39887a97cf3f90
Zone: 1
Management Hostname: dhcp43-171.lab.eng.blr.redhat.com
Storage Hostname: 10.70.43.171
Id:3a1e0717e6352a8830ab43978347a103
                                     Name:/dev/vdc
               Size (GiB):499
                                  Used (GiB):100
State:online
                                                     Free (GiB):399
Bricks:1
Id:89a57ace1c3184826e1317fef785e6b7
                                     Name:/dev/vdd
State:online Size (GiB):499 Used (GiB):10
                                                     Free (GiB):489
Bricks:5
```

7. Execute the following command to disable the node from heketi. This makes the node go offline:

```
# heketi-cli node disable <node-id> --user=<user> --secret=<user
key>
```

For example:

```
# heketi-cli node disable ab37fc5aabbd714eb8b09c9a868163df --
user=admin --secret=adminkey
Node ab37fc5aabbd714eb8b09c9a868163df is now offline
```

8. Execute the following command to remove a node and all its associated devices from Heketi:

```
#heketi-cli node remove <node-id> --user=<user> --secret=<user key>
```

For example:

```
# heketi-cli node remove ab37fc5aabbd714eb8b09c9a868163df --
user=admin --secret=adminkey
Node ab37fc5aabbd714eb8b09c9a868163df is now removed
```

9. Execute the following command to delete the devices from heketi node:

```
# heketi-cli device delete <device-id> --user=<user> --secret=<user
key>
```

For example:

```
# heketi-cli device delete 0fca78c3a94faabfbe5a5a9eef01b99c --
user=admin --secret=adminkey
Device 0fca78c3a94faabfbe5a5a9eef01b99c deleted
```

10. Execute the following command to delete a node from Heketi management:

```
#heketi-cli node delete <nodeid> --user=<user> --secret=<user key>
```

For example:

```
# heketi-cli node delete ab37fc5aabbd714eb8b09c9a868163df --
user=admin --secret=adminkey
Node ab37fc5aabbd714eb8b09c9a868163df deleted
```

- 11. Execute the following commands on any one of the gluster pods to replace the faulty node with the new node:
 - 1. Execute the following command to get list of blockvolumes hosted under block-hosting-volume

```
# gluster-block list <block-hosting-volume> --json-pretty
```

2. Execute the following command to find out which all blockvolumes are hosted on the old node, with the help of info command

```
# gluster-block info <block-hosting-volume>/<block-volume> --
json-pretty
```

3. Execute the following command to replace the faulty node with the new node:

```
# gluster-block replace <volname/blockname> <old-node> <new-node>
[force]
```

```
{
  "NAME":"block",
  "CREATE SUCCESS":"192.168.124.73",
  "DELETE SUCCESS":"192.168.124.63",
  "REPLACE PORTAL SUCCESS ON":[
      "192.168.124.79"
  ],
  "RESULT":"SUCCESS"
}

Note: If the old node is down and does not come up again then you can force replace:
  gluster-block replace sample/block 192.168.124.63 192.168.124.73
force --json-pretty
{
```

```
"NAME":"block",
"CREATE SUCCESS":"192.168.124.73",
"DELETE FAILED (ignored)":"192.168.124.63",
"REPLACE PORTAL SUCCESS ON":[
    "192.168.124.79"
],
"RESULT":"SUCCESS"
}
```



NOTE

The next steps henceforth are to be executed only if the block that is to be replaced is still in use.

12. Logout of the old portal by executing the following command on the initiator:

```
# iscsiadm -m node -T <targetname> -p <old node> -u
```

For example:

```
# iscsiadm -m node -T iqn.2016-12.org.gluster-block:d6d18f43-8a74-
4b2c-a5b7-df1fa3f5bc9a -p 192.168.124.63 -u
Logging out of session [sid: 8, target: iqn.2016-12.org.gluster-block:d6d18f43-8a74-4b2c-a5b7-df1fa3f5bc9a, portal:
192.168.124.63,3260]
Logout of [sid: 8, target: iqn.2016-12.org.gluster-block:d6d18f43-8a74-4b2c-a5b7-df1fa3f5bc9a, portal: 192.168.124.63,3260]
successful.
```

13. To re-discover the new node execute the following command:

```
# iscsiadm -m discovery -t st -p <new node>
```

For example:

```
# iscsiadm -m discovery -t st -p 192.168.124.73
192.168.124.79:3260,1 iqn.2016-12.org.gluster-block:d6d18f43-8a74-
4b2c-a5b7-df1fa3f5bc9a
192.168.124.73:3260,2 iqn.2016-12.org.gluster-block:d6d18f43-8a74-
4b2c-a5b7-df1fa3f5bc9a
```

14. Login to the new portal by executing the following command:

```
# iscsiadm -m node -T <targetname> -p <new node ip> -l
```

For example:

```
# iscsiadm -m node -T iqn.2016-12.org.gluster-block:d6d18f43-8a74-4b2c-a5b7-df1fa3f5bc9a -p 192.168.124.73 -l
```

15. To verify if the enabled hosting volume is replaced and running successfully, execute the following command on the initiator:

ll /dev/disk/by-path/ip-* | grep <targetname> | grep <"new node ip">

CHAPTER 4. SHUTTING DOWN GLUSTER-BLOCK CLIENT NODES

Follow this procedure to shutdown gluster-block client nodes:

- 1. Evacuate the pods. For more information, refer https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html-single/cluster_administration/#evacuating-pods-on-nodes
- 2. Ensure that no gluster block mounts exist in the system.
- 3. Reboot the nodes. For more information, refer https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html-single/cluster_administration/#rebooting-nodes

CHAPTER 5. S3 COMPATIBLE OBJECT STORE IN A RED HAT OPENSHIFT CONTAINER STORAGE ENVIRONMENT



IMPORTANT

Support for S3 compatible Object Store in Container-Native Storage is under technology preview. Technology Preview features are not fully supported under Red Hat service-level agreements (SLAs), may not be functionally complete, and are not intended for production use.

Tech Preview features provide early access to upcoming product innovations, enabling customers to test functionality and provide feedback during the development process.

As Red Hat considers making future iterations of Technology Preview features generally available, we will provide commercially reasonable efforts to resolve any reported issues that customers experience when using these features.

Object Store provides a system for data storage that enables users to access the same data, both as an object and as a file, thus simplifying management and controlling storage costs. The S3 API is the de facto standard for HTTP based access to object storage services.

5.1. SETTING UP S3 COMPATIBLE OBJECT STORE FOR RED HAT OPENSHIFT CONTAINER STORAGE



NOTE

Ensure that cns-deploy package has been installed before setting up S3 Compatible Object Store. For more information on how to install cns-deploy package, see https://access.redhat.com/documentation/en-us/red_hat_openshift_container_storage/3.10/html-single/deployment_guide/#part-Appendix

Execute the following steps from the /usr/share/heketi/templates/ directory to set up S3 compatible object store for Red Hat Openshift Container Storage:

1. (Optional): If you want to create a secret for heketi, then execute the following command:

```
# oc create secret generic heketi-${NAMESPACE}-admin-secret
--from-literal=key=${ADMIN_KEY} --type=kubernetes.io/glusterfs
```

For example:

```
# oc create secret generic heketi-storage-project-admin-secret
--from-literal=key= --type=kubernetes.io/glusterfs
```

1. Execute the following command to label the secret:

```
# oc label --overwrite secret heketi-${NAMESPACE}-admin-secret
glusterfs=s3-heketi-${NAMESPACE}-admin-secret
gluster-s3=heketi-${NAMESPACE}-admin-secret
```

For example:

```
# oc label --overwrite secret heketi-storage-project-admin-secret
glusterfs=s3-heketi-storage-project-admin-secret
gluster-s3=heketi-storage-project-admin-secret
```

2. Create a GlusterFS StorageClass file. Use the **HEKETI_URL** and **NAMESPACE** from the current setup and set a **STORAGE_CLASS** name.

```
# sed -e 's/${HEKETI_URL}/heketi-storage-
project.cloudapps.mystorage.com/g' -e 's/${STORAGE_CLASS}/gluster-
s3-store/g' -e 's/${NAMESPACE}/storage-project/g'
/usr/share/heketi/templates/gluster-s3-storageclass.yaml | oc create
-f -
```

For example:

```
# sed -e 's/${HEKETI_URL}/heketi-storage-
project.cloudapps.mystorage.com/g' -e 's/${STORAGE_CLASS}/gluster-
s3-store/g' -e 's/${NAMESPACE}/storage-project/g'
/usr/share/heketi/templates/gluster-s3-storageclass.yaml | oc create
-f -storageclass "gluster-s3-store" created
```

NOTE

You can run the following command to obtain the HEKETI_URL:

```
# oc get routes --all-namespaces | grep heketi
```

A sample output of the command is as follows:

```
glusterfs heketi-storage
heketi-storage-
glusterfs.router.default.svc.cluster.local
heketi-storage <all> None
```

If there are multiple lines in the output then you can choose the most relevant one.

You can run the following command to obtain the NAMESPACE:

```
oc get project
```

A sample output of the command is as follows:

where, glusterfs is the NAMESPACE.

3. Create the Persistent Volume Claims using the storage class.

```
# sed -e 's/${VOLUME_CAPACITY}/2Gi/g' -e
's/${STORAGE_CLASS}/gluster-s3-store/g'
/usr/share/heketi/templates/gluster-s3-pvcs.yaml | oc create -f -
```

For Example:

```
# sed -e 's/${VOLUME_CAPACITY}/2Gi/g' -e
's/${STORAGE_CLASS}/gluster-s3-store/g'
/usr/share/heketi/templates/gluster-s3-pvcs.yaml | oc create -f -
persistentvolumeclaim "gluster-s3-claim" created
persistentvolumeclaim "gluster-s3-meta-claim" created
```

Use the **STORAGE_CLASS** created from the previous step. Modify the **VOLUME_CAPACITY** as per the environment requirements. Wait till the PVC is bound. Verify the same using the following command:

```
# oc get pvc
NAME
                     STATUS
                               VOLUME
CAPACITY ACCESSMODES AGE
gluster-s3-claim
                     Bound
                               pvc-0b7f75ef-9920-11e7-9309-
00151e000016 2Gi
                   RWX
gluster-s3-meta-claim Bound
                               pvc-0b87a698-9920-11e7-9309-
00151e000016
                       RWX
            1Gi
                                    2m
```

4. Start the glusters3 object storage service using the template:



NOTE

Set the S3_ACCOUNT name, S3_USER name, and S3_PASSWORD. PVC and META_PVC are obtained from the previous step.

```
# oc new-app /usr/share/heketi/templates/gluster-s3-template.yaml \
--param=S3_ACCOUNT=testvolume --param=S3_USER=adminuser \
--param=S3_PASSWORD=itsmine --param=PVC=gluster-s3-claim \
--param=META_PVC=gluster-s3-meta-claim
--> Deploying template "storage-project/gluster-s3" for
"/usr/share/heketi/templates/gluster-s3-template.yaml" to project
storage-project
     gluster-s3
     Gluster s3 service template
     * With parameters:
        * S3 Account Name=testvolume
        * S3 User=adminuser
        * S3 User Password=itsmine
        * Primary GlusterFS-backed PVC=gluster-s3-claim
        * Metadata GlusterFS-backed PVC=gluster-s3-meta-claim
--> Creating resources ...
    service "gluster-s3-service" created
```

```
route "gluster-s3-route" created deploymentconfig "gluster-s3-dc" created --> Success
Run 'oc status' to view your app.
```

5. Execute the following command to verify if the S3 pod is up:

```
# oc get route
NAME
                 HOST/PORT
                                      TERMINATION
PATH
         SERVICES
                            PORT
                                                    WILDCARD
gluster-S3-route gluster-s3-route-storage-
project.cloudapps.mystorage.com ... 1 more
                                                      gluster-s3-
service <all>
                 heketi-storage-project.cloudapps.mystorage.com ...
heketi
                                              <all>
1 more
                           heketi
```

5.2. OBJECT OPERATIONS

This section lists some of the object operation that can be performed:

• Get the URL of the route which provides S3 OS

```
# s3_storage_url=$(oc get routes | grep "gluster.*s3" | awk
'{print $2}')
```



NOTE

Ensure to download the s3curl tool from https://aws.amazon.com/code/128. This tool will be used for verifying the object operations.

 s3curl.pl requires Digest::HMAC_SHA1 and Digest::MD5. Install the perl-Digest-HMAC package to get this. You can install the perl-Digest-HMAC package by running this command:

```
# yum install perl-Digest-HMAC
```

Update the s3curl.pl perl script with glusters3object url which was retrieved:

For example:

```
my @endpoints = ( 'glusters3object-storage-
project.cloudapps.mystorage.com');
```

• To perform **PUT** operation of the bucket:

```
s3curl.pl --debug --id "testvolume:adminuser" --key "itsmine" --put
/dev/null -- -k -v http://$s3_storage_url/bucket1
```

• To perform **PUT** operation of the object inside the bucket:

```
s3curl.pl --debug --id "testvolume:adminuser" --key "itsmine" --put
my_object.jpg -- -k -v -s
http://$s3_storage_url/bucket1/my_object.jpg
```

• To verify listing of objects in the bucket:

```
s3curl.pl --debug --id "testvolume:adminuser" --key "itsmine" -- -k -v -s http://$s3_storage_url/bucket1/
```

CHAPTER 6. CLUSTER ADMINISTRATOR SETUP

Authentication

Set up the authentication using AllowAll Authentication method.

AllowAll Authentication

Set up an authentication model which allows all passwords. Edit /etc/origin/master/master-config.yaml on the OpenShift master and change the value of DenyAllPasswordIdentityProvider to AllowAllPasswordIdentityProvider. Then restart the OpenShift master.

1. Now that the authentication model has been setup, login as a user, for example admin/admin:

```
# oc login openshift master e.g. https://1.1.1.1:8443 -- username=admin --password=admin
```

2. Grant the admin user account the **cluster-admin** role.

```
# oc login -u system:admin -n default
 Logged into "https:// <<openshift_master_fqdn>>:8443" as
"system:admin" using existing credentials.
 You have access to the following projects and can switch between
them with 'oc project ctname>':
  *default
  glusterfs
  infra-storage
  kube-public
  kube-system
  management-infra
  openshift
  openshift-infra
  openshift-logging
  openshift-node
  openshift-sdn
  openshift-web-console
 Using project "default".
 # oc adm policy add-cluster-role-to-user cluster-admin admin
 cluster role "cluster-admin" added: "admin"
```

For more information on authentication methods, see https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html-single/configuring_clusters/#identity-providers-configuring.

CHAPTER 7. GLUSTER BLOCK STORAGE AS BACKEND FOR LOGGING AND METRICS

Following section guides to configure Gluster Block Storage as the backend storage for logging and metrics



NOTE

Block volume expansion is not supported in CNS 3.6. Administrators are required to do proper capacity planning while using Gluster Block as backend storage when using dynamic provisioning.

7.1. PREREQUISITES

Before setting gluster block storage as the backend for logging or metrics, check if the following prerequisites are met:

• In the storage class file, check if the default storage class is set to the storage class of gluster block. For example:

• If the default is not set to **gluster-block** (or any other name that you have provided) then execute the following command. For example:

Execute the following command to verify:

```
oc get storageclass
NAME TYPE
gluster-block (default) gluster.org/glusterblock
```

7.2. ENABLING GLUSTER BLOCK STORAGE AS BACKEND FOR LOGGING

Follow the tasks mentioned below to enable Gluster Block Storage as backend for logging:

- 1. To enable logging in Openshift Container platform, see https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html-single/configuring_clusters/#install-config-aggregate-logging
- 2. The **openshift_logging_es_pvc_dynamic** ansible variable has to be set to true.

```
[OSEv3:vars] openshift_logging_es_pvc_dynamic=true
```

For example, a sample set of variables for openshift logging are listed below.

```
openshift_logging_install_logging=true
openshift_logging_es_pvc_dynamic=true
openshift_logging_kibana_nodeselector={"node-
role.kubernetes.io/infra": "true"}
openshift_logging_curator_nodeselector={"node-
role.kubernetes.io/infra": "true"}
openshift_logging_es_nodeselector={"node-role.kubernetes.io/infra":
"true"}
openshift_logging_es_pvc_size=10Gi
openshift_logging_es_pvc_storage_class_name="glusterfs-registry-
block"
```

- 3. Run the Ansible playbook. For more information, see .https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html-single/configuring_clusters/#install-config-aggregate-logging
- 4. To verify, execute the following command:

```
# oc get pods -n openshift-logging
```



For more information regarding logging storage considerations, see https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html-single/configuring clusters/#install-config-aggregate-logging-sizing-guidelines-storage.

7.3. ENABLING GLUSTER BLOCK STORAGE AS BACKEND FOR METRICS

Follow the tasks mentioned below to enable Gluster Block Storage as backend for metrics



NOTE

By default, since Container Native Storage performs three-way replication, data will be available to the restarted node from anywhere in the cluster. As a result, it is recommended that Cassandra-level replication is turned off to avoid capacity overhead

- To enable metrics in Openshift Container platform, see https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html-single/configuring_clusters/#install-config-cluster-metrics
- 2. The **openshift_metrics_cassandra_storage_type** ansible variable should be set to **dynamic**:

```
[OSEv3:vars]openshift_metrics_cassandra_storage_type=dynamic
```

For example, a sample set of variables for openshift_metrics_ are listed below.

```
openshift_metrics_install_metrics=true
openshift_metrics_storage_kind=dynamic
openshift_metrics_hawkular_nodeselector={"node-role.kubernetes.io/infra": "true"}
```

```
openshift_metrics_cassandra_nodeselector={"node-
role.kubernetes.io/infra": "true"}
openshift_metrics_heapster_nodeselector={"node-
role.kubernetes.io/infra": "true"}
openshift_metrics_storage_volume_size=10Gi
openshift_metrics_cassandra_pvc_storage_class_name="glusterfs-
registry-block"
```

- 3. Run the Ansible playbook. For more information, see https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html-single/configuring_clusters/#install-config-cluster-metrics.
- 4. To verify, execute the following command:

```
# oc get pods --n openshift-infra
```

It should list the following pods running:

```
heapster-cassandra
heapster-metrics
hawkular-&*9
```



NOTE

For more information regarding metrics storage considerations, see https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html-single/configuring_clusters/#metrics-data-storage.

7.4. VERIFYING IF GLUSTER BLOCK IS SETUP AS BACKEND

Execute the following commands to verify if gluster block is setup as the backend for logging and metrics:

1. To get an overview of the infrastructure, execute the following command:

```
# oc get pods -n logging -o jsonpath='{range
.items[*].status.containerStatuses[*]}{"Name: "}{.name}{"\n "}
{"Image: "}{.image}{"\n"}{" State: "}{.state}{"\n"}{end}'
```

2. To get the details of all the persistent volume claims, execute the following command:

```
# oc get pvc
```

3. To get the details of the pvc, execute the following command:

```
# oc describe pvc <claim_name>
```

Verify the volume is mountable and that permissions allow read/write. Also, PVC claim name should match the dynamically provisioned gluster block storage class.

For more information, see https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html-single/configuring_clusters/#install-config-aggregate-logging-sizing.

PART III. SECURITY

CHAPTER 8. ENABLING ENCRYPTION

Red Hat Gluster Storage supports network encryption using TLS/SSL. Red Hat Gluster Storage uses TLS/SSL for authentication and authorization, in place of the home grown authentication framework used for normal connections. Red Hat Gluster Storage supports the following encryption types:

- I/O encryption encryption of the I/O connections between the Red Hat Gluster Storage clients and servers.
- Management encryption encryption of the management (glusterd) connections within a trusted storage pool.

8.1. PREREQUISITES

To enable encryption it is necessary to have 3 certificates per node (glusterfs.key, gluserfs.pem and glusterfs.ca). For more information about the steps to be performed as prerequisites, see https://access.redhat.com/documentation/en-us/red_hat_gluster_storage/3.4/html-single/administration_guide/#chap-Network_Encryption-Preregs.

Ensure to enable encryption while registering the storageclass file using the volumeoptions parameter. For more information on registering a storageclass file for File storage, see

https://access.qa.redhat.com/documentation/en-us/red_hat_openshift_container_storage/3.10/html-single/operations_guide/#chap-Documentation-

Red_Hat_Gluster_Storage_Container_Native_with_OpenShift_Platform-OpenShift Creating Persistent Volumes-Dynamic Prov.



NOTE

- Ensure to perform the steps on all the OpenShift nodes except master.
- All the Red Hat Gluster Storage volumes are mounted on the OpenShift nodes and then bind mounted to the application pods. Hence, it is not required to perform any encryption related operations specifically on the application pods.

8.2. ENABLING ENCRYPTION FOR A NEW RED HAT OPENSHIFT CONTAINER STORAGE SETUP

You can configure network encryption for a new Red Hat Openshift Container Storage setup for both I/O encryption and management encryption.

8.2.1. Enabling Management Encryption

Though Red Hat Gluster Storage can be configured only for I/O encryption without using management encryption, it is recommended to have management encryption. If you want to enable SSL only on the I/O path, skip this section and proceed with Section 8.2.2, "Enabling I/O encryption for a Volume".

On the server

Perform the following on all the server, ie, the OpenShift nodes on which Red Hat Gluster Storage pods are running.

1. Create the /var/lib/glusterd/secure-access file.

touch /var/lib/glusterd/secure-access

On the clients

Perform the following on the clients, that is, on all the remaining OpenShift nodes on which Red Hat Gluster Storage is not running.

1. Create the /var/lib/glusterd/secure-access file.





Deploy_CNS

NOTE

All the Red Hat Gluster Storage volumes are mounted on the OpenShift nodes and then bind mounted to the application pods. Hence, it is not required to perform any encryption related operations specifically on the application pods.

After running the commands on the server and clients, deploy Red Hat Openshift Container Storage. For more information, see https://access.redhat.com/documentation/en-us/red_hat_openshift_container_storage/3.10/html-single/deployment_guide/#chap-Documentation-Red Hat Gluster Storage Container Native with OpenShift Platform-Setting the environment-

8.2.2. Enabling I/O encryption for a Volume

Enable the I/O encryption between the servers and clients:



NOTE

The servers are the OpenShift nodes on which Red Hat Gluster Storage pods are running.

The clients are the remaining OpenShift nodes on which Red Hat Gluster Storage is not running.

- Ensure Red Hat Openshift Container Storage is deployed before proceeding with further steps.
 For more information see, https://access.redhat.com/documentation/enus/red_hat_openshift_container_storage/3.10/html-single/deployment_guide/#chapDocumentation-Red_Hat_Gluster_Storage_Container_Native_with_OpenShift_PlatformSetting_the_environment-Deploy_CNS
- 2. You can either create a statically provisioned volume or a dynamically provisioned volume. For more information about static provisioning of volumes, see https://access.redhat.com/documentation/en-us/red_hat_openshift_container_storage/3.10/html-single/operations_guide/#chap-Documentation-Red_Hat_Gluster_Storage_Container_Native_with_OpenShift_Platform-OpenShift_Creating_Persistent_Volumes-Static_Prov. For more information about dynamic provisioning of volumes, see https://access.redhat.com/documentation/en-us/red_hat_openshift_container_storage/3.10/html-single/operations_guide/#chap-Documentation-Red_Hat_Gluster_Storage_Container_Native_with_OpenShift_Platform-OpenShift_Creating_Persistent_Volumes-Dynamic_Prov



To enable encryption during the creation of statically provisioned volume, execute the following command:

heketi-cli volume create --size=100 --gluster-volumeoptions="client.ssl on","server.ssl on"

3. Stop the volume by executing the following command:

```
# oc rsh <gluster_pod_name> gluster volume stop VOLNAME
```

The *gluster pod name* is the name of one of the Red Hat Gluster Storage pods of the trusted storage pool to which the volume belongs.



NOTE

To get the VOLNAME, execute the following command:

oc describe pv <pv_name>

For example:

oc describe pv pvc-01569c5c-1ec9-11e7-a794-005056b38171

Name: pvc-01569c5c-1ec9-11e7-a794-005056b38171

Labels: <none>
StorageClass: fast
Status: Bound

Claim: storage-project/storage-claim68

Reclaim Policy: Delete Access Modes: RWO Capacity: 1Gi

Message: Source:

Type: Glusterfs (a Glusterfs mount on

the host that shares a pod's lifetime)

EndpointsName: glusterfs-dynamic-storage-claim68

Path:

vol 0e81e5d6e46dcbf02c11ffd9721fca28

ReadOnly: false

No events.

The VOLNAME is the value of "path" in the above output.

4. Set the list of common names of all the servers to access the volume. Ensure to include the common names of clients which will be allowed to access the volume.

oc rsh <gluster_pod_name> gluster volume set VOLNAME auth.sslallow 'server1, server2, server3, client1, client2, client3'



If you set auth.ssl-allow option with * as value, any TLS authenticated clients can mount and access the volume from the application side. Hence, you set the option's value to * or provide common names of clients as well as the nodes in the trusted storage pool.

5. Enable the client.ssl and server.ssl options on the volume.

```
# oc rsh <gluster_pod_name> gluster volume set VOLNAME client.ssl on
# oc rsh <gluster_pod_name> gluster volume set VOLNAME server.ssl on
```

6. Start the volume.

oc rsh <gluster_pod_name> gluster volume start VOLNAME

8.3. ENABLING ENCRYPTION FOR AN EXISTING RED HAT OPENSHIFT CONTAINER STORAGE SETUP

You can configure network encryption for an existing Red Hat Openshift Container Storage Storage setup for both I/O encryption and management encryption.

8.3.1. Enabling I/O encryption for a Volume

Enable the I/O encryption between the servers and clients for a volume:



NOTE

The servers are the OpenShift nodes on which Red Hat Gluster Storage pods are running.

The clients are the remaining OpenShift nodes on which Red Hat Gluster Storage is not running.

- 1. Stop all the application pods that have the Red Hat Gluster Storage volumes.
- 2. Stop the volume.

```
# oc rsh <gluster_pod_name> gluster volume stop VOLNAME
```

The *gluster pod name* is the name of one of the Red Hat Gluster Storage pods of the trusted storage pool to which the volume belongs.

3. Set the list of common names for clients allowed to access the volume. Be sure to include the common names of all the servers.

```
# oc rsh <gluster_pod_name> gluster volume set VOLNAME auth.ssl-
allow 'server1, server2, server3, client1, client2, client3'
```



If you set auth.ssl-allow option with * as value, any TLS authenticated clients can mount and access the volume from the application side. Hence, you set the option's value to * or provide common names of clients as well as the nodes in the trusted storage pool.

4. Enable client.ssl and server.ssl on the volume by using the following command:

```
# oc rsh <gluster_pod_name> gluster volume set VOLNAME client.ssl on
# oc rsh <gluster_pod_name> gluster volume set VOLNAME server.ssl on
```

5. Start the volume.

```
# oc rsh <gluster_pod_name> gluster volume start VOLNAME
```

6. Start the application pods to use the I/O encrypted Red Hat Gluster Storage volumes.

8.3.2. Enabling Management Encryption

Management encryption is recommended, even though, Red Hat Gluster Storage can be configured only for I/O encryption without using management encryption. On an existing installation, with running servers and clients, schedule a downtime of volumes, applications, clients, and other end-users to enable management encryption.

You cannot currently change between unencrypted and encrypted connections dynamically. Bricks and other local services on the servers and clients do not receive notifications from glusterd if they are running when the switch to management encryption is made.

- 1. Stop all the application pods that have the Red Hat Gluster Storage volumes.
- 2. Stop all the volumes.

```
# oc rsh <gluster_pod_name> gluster volume stop VOLNAME
```

3. Stop the Red Hat Gluster Storage pods.

```
# oc delete daemonset glusterfs
```

4. On deletion of daemon set the pods go down. To verify if the pods are down, execute the following command:

```
# oc get pods
```

5. Create the /var/lib/glusterd/secure-access file on all OpenShift nodes.

```
# touch /var/lib/glusterd/secure-access
```

6. Create the Red Hat Gluster Storage daemonset by executing the following command:



For Ansible deployments, the image name and the version has to be specified in the template, before executing the command.

oc process glusterfs | oc create -f -

7. On creation of daemon set the pods are started. To verify if the pods are started, execute the following command:

```
# oc get pods
```

8. Start all the volumes.

```
# oc rsh <gluster_pod_name> gluster volume start VOLNAME
```

9. Start the application pods to use the management encrypted Red Hat Gluster Storage.

8.4. DISABLING ENCRYPTION

You can disable encryption for on Red Hat Openshift Container Storage setup in the following two scenarios:

- Disabling I/O Encryption for a Volume
- Disabling Management Encryption

8.4.1. Disabling I/O Encryption for all the Volumes

Execute the following commands to disable the I/O encryption between the servers and clients for a volume:



NOTE

The servers are the OpenShift nodes on which Red Hat Gluster Storage pods are running.

The clients are the remaining OpenShift nodes on which Red Hat Gluster Storage is not running.

- 1. Stop all the application pods that have the Red Hat Gluster Storage volumes.
- 2. Stop all the volumes.

```
# oc rsh <gluster_pod_name> gluster volume stop VOLNAME
```

3. Reset all the encryption options for a volume:

```
# oc rsh <gluster_pod_name> gluster volume reset VOLNAME auth.ssl-
allow
# oc rsh <gluster_pod_name> gluster volume reset VOLNAME client.ssl
```

oc rsh <gluster_pod_name> gluster volume reset VOLNAME server.ssl

4. Delete the files that were used for network encryption using the following command on all the OpenShift nodes:

rm /etc/ssl/glusterfs.pem /etc/ssl/glusterfs.key
/etc/ssl/glusterfs.ca



NOTE

Deleting these files in a setup where management encryption is enabled will result in glusterd failing on all gluster pods and hence should be avoided.

- 5. Stop the Red Hat Gluster Storage pods.
 - # oc delete daemonset glusterfs
- 6. On deletion of daemon set the pods go down. To verify if the pods are down, execute the following command:
 - # oc get pods
- 7. Create the Red Hat Gluster Storage daemonset by executing the following command:



NOTE

For Ansible deployments, the image name and the version has to be specified in the template, before executing the command.

- # oc process glusterfs | oc create -f -
- 8. On creation of daemon set the pods are started. To verify if the pods are started, execute the following command:
 - # oc get pods
- 9. Start the volume.
 - # oc rsh <gluster_pod_name> gluster volume start VOLNAME
- 10. Start the application pods to use the I/O encrypted Red Hat Gluster Storage volumes.

8.4.2. Disabling Management Encryption

You cannot currently change between unencrypted and encrypted connections dynamically. Bricks and other local services on the servers and clients do not receive notifications from glusterd if they are running when the switch to management encryption is made.

Execute the following commands to disable the management encryption

- 1. Stop all the application pods that have the Red Hat Gluster Storage volumes.
- 2. Stop all the volumes.

```
# oc rsh <gluster_pod_name> gluster volume stop VOLNAME
```

3. Stop the Red Hat Gluster Storage pods.

```
# oc delete daemonset glusterfs
```

4. On deletion of daemon set the pods go down. To verify if the pods are down, execute the following command:

```
# oc get pods
```

5. Delete the /var/lib/glusterd/secure-access file on all OpenShift nodes to disable management encryption.

```
# rm /var/lib/glusterd/secure-access
```

6. Delete the files that were used for network encryption using the following command on all the OpenShift nodes:

```
# rm /etc/ssl/glusterfs.pem /etc/ssl/glusterfs.key
/etc/ssl/glusterfs.ca
```

7. Create the Red Hat Gluster Storage daemonset by executing the following command:



NOTE

For Ansible deployments, the image name and the version has to be specified in the template, before executing the command.

```
# oc process glusterfs | oc create -f -
```

8. On creation of daemon set the pods are started. To verify if the pods are started, execute the following command:

```
# oc get pods
```

9. Start all the volumes.

```
# oc rsh <gluster_pod_name> gluster volume start VOLNAME
```

10. Start the application pods to use the management encrypted Red Hat Gluster Storage.

PART IV. MIGRATION

CHAPTER 9. UPDATING THE REGISTRY WITH RED HAT OPENSHIFT CONTAINER STORAGE AS THE STORAGE BACK-END

OpenShift Container Platform provides an integrated registry with storage using an NFS-backed persistent volume that is automatically setup. Red Hat Openshift Container Storage allows you to replace this with a Gluster persistent volume for registry storage. This provides increased reliability, scalability and failover.

For additional information about OpenShift Container Platform and the docker-registry, see https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html/configuring_clusters/setting-up-the-registry.

9.1. VALIDATING THE OPENSHIFT CONTAINER PLATFORM REGISTRY DEPLOYMENT

To verify that the registry is properly deployed, execute the following commands:

1. On the master or client, execute the following command to login as the cluster admin user:

```
# oc login
```

For example:

```
# oc login

Authentication required for https://master.example.com:8443
(openshift)
Username: <cluster-admin-user>
Password: <password>
```

You have access to the following projects and can switch between them with 'oc project ctname':

* default
 management-infra
 openshift
 openshift-infra

Login successful.

Using project "default".

If you are not automatically logged into project default, then switch to it by executing the following command:

```
# oc project default
```

2. To verify that the pod is created, execute the following command:

```
# oc get pods
```

For example:

```
# oc get pods
NAME
                        READY
                                  STATUS
                                           RESTARTS
                                                     AGE
docker-registry-2-mbu0u
                        1/1
                                                     6d
                                  Running
docker-registry-2-spw0o 1/1
                                  Running
                                                     6d
                                           3
registry-console-1-rblwo 1/1
                                  Running
                                                     6d
                                           3
```

3. To verify that the endpoints are created, execute the following command:

```
# oc get endpoints
```

For example:

4. To verify that the persistent volume is created, execute the following command:

```
# oc get pv
NAME CAPACITY ACCESSMODES RECLAIMPOLICY STATUS CLAIM
REASON AGE
registry-volume 5Gi RWX Retain
Bound default/registry-claim 7d
```

5. To obtain the details of the persistent volume that was created for the NFS registry, execute the following command:

```
# oc describe pv registry-volume
Name: registry-volume
Labels:
             <none>
StorageClass:
Status:
             Bound
Claim:
            default/registry-claim
Reclaim Policy:
                 Retain
Access Modes:
               RWX
Capacity:
          5Gi
Message:
Source:
   Type: NFS (an NFS mount that lasts the lifetime of a pod)
   Server: cns30.rh73
         /exports/registry
   Path:
   ReadOnly:
               false
No events.
```

9.2. CONVERTING THE OPENSHIFT CONTAINER PLATFORM REGISTRY WITH RED HAT OPENSHIFT CONTAINER STORAGE

This section provides the steps to create a Red Hat Gluster Storage volume and use it to provide storage for the integrated registry.

Setting up a Red Hat Gluster Storage Persistent Volume

Execute the following commands to create a Red Hat Gluster Storage volume to store the registry data and create a persistent volume.



NOTE

The commands must be executed in the default project.

1. Login to the **default** project:

```
# oc project default
```

For example:

```
# oc project default
Now using project "default" on server "https://cns30.rh73:8443"
```

2. Execute the following command to create the **gluster-registry-endpoints.yaml** file:

```
oc get endpoints <heketi-db-storage-endpoint-name> -o yaml --namespace=project-name> > gluster-registry-endpoints.yaml
```



NOTE

You must create an endpoint for each project from which you want to utilize the Red Hat Gluster Storage registry. Hence, you will have a service and an endpoint in both the **default** project and the new project (**storage-project**) created in earlier steps.

3. Edit the **gluster-registry-endpoints.yaml** file. Change the name to gluster-registry-endpoints and remove all the other metadata, leaving everything else the same.

```
# cat gluster-registry-endpoints.yaml
apiVersion: v1
kind: Endpoints
metadata:
   name: gluster-registry-endpoints
subsets:
   - addresses:
        - ip: 192.168.124.114
        - ip: 192.168.124.52
        - ip: 192.168.124.83
   ports:
        - port: 1
        protocol: TCP
```

4. Execute the following command to create the endpoint:

```
# oc create -f gluster-registry-endpoints.yaml
endpoints "gluster-registry-endpoints" created
```

5. To verify the creation of the endpoint, execute the following command:

```
# oc get endpoints
NAME
                           ENDPOINTS
AGE
docker-registry
                          10.129.0.8:5000,10.130.0.5:5000
gluster-registry-endpoints
192.168.124.114:1,192.168.124.52:1,192.168.124.83:1
10s
kubernetes
192.168.124.250:8443,192.168.124.250:8053,192.168.124.250:8053
registry-console
                          10.131.0.6:9090
28d
router
192.168.124.114:443,192.168.124.83:443,192.168.124.114:1936 + 3
more...
          28d
```

6. Execute the following command to create the **gluster-registry-service.yaml** file:

```
oc get services <heketi-storage-endpoint-name> -o yaml --namespace= cet-name> > gluster-registry-service.yaml
```

7. Edit the **gluster-registry-service.yaml** file. Change the name to gluster-registry-service and remove all the other metadata. Also, remove the specific cluster IP addresses:

```
# cat gluster-registry-service.yaml
apiVersion: v1
kind: Service
metadata:
   name: gluster-registry-service
spec:
   ports:
        - port: 1
        protocol: TCP
        targetPort: 1
   sessionAffinity: None
   type: ClusterIP
status:
   loadBalancer: {}
```

8. Execute the following command to create the service:

```
# oc create -f gluster-registry-service.yaml
services "gluster-registry-service" created
```

9. Execute the following command to verify if the service are running:

# oc get services NAME AGE	CLUSTER-IP	EXTERNAL-IP	PORT(S)
docker-registry 28d	172.30.197.118	<none></none>	5000/TCP
gluster-registry-service 6s	172.30.0.183	<none></none>	1/TCP
kubernetes 443/TCP,53/UDP,53/TCP	172.30.0.1 29d	<none></none>	
registry-console 28d	172.30.146.178	<none></none>	9000/TCP
router 80/TCP,443/TCP,1936/TCP	172.30.232.238 28d	<none></none>	

10. Execute the following command to obtain the fsGroup GID of the existing docker-registry pods:

```
# export GID=$(oc get po --selector="docker-registry=default" -o go-
template --template='{{printf "%.0f" ((index .items
0).spec.securityContext.fsGroup)}}')
```

11. Execute the following command to create a volume

```
# heketi-cli volume create --size=5 --name=gluster-registry-volume -
-gid=${GID}
```

12. Create the persistent volume file for the Red Hat Gluster Storage volume:

```
# cat gluster-registry-volume.yaml
kind: PersistentVolume
apiVersion: v1
metadata:
  name: gluster-registry-volume
  labels:
    glusterfs: registry-volume
spec:
 capacity:
    storage: 5Gi
 glusterfs:
    endpoints: gluster-registry-endpoints
    path: gluster-registry-volume
  accessModes:
    - ReadWriteMany
  persistentVolumeReclaimPolicy: Retain
```

13. Execute the following command to create the persistent volume:

```
# oc create -f gluster-registry-volume.yaml
```

14. Execute the following command to verify and get the details of the created persistent volume:

```
# oc get pv/gluster-registry-volume
NAME CAPACITY ACCESSMODES RECLAIMPOLICY
STATUS CLAIM REASON AGE
```

```
gluster-registry-volume 5Gi RWX Retain
Available 21m
```

15. Create a new persistent volume claim. Following is a sample Persistent Volume Claim that will be used to replace the existing registry-storage volume claim.

```
# cat gluster-registry-claim.yaml
apiVersion: v1
kind: PersistentVolumeClaim
metadata:
   name: gluster-registry-claim
spec:
   accessModes:
    - ReadWriteMany
   resources:
        requests:
        storage: 5Gi
   selector:
        matchLabels:
        glusterfs: registry-volume
```

16. Create the persistent volume claim by executing the following command:

```
# oc create -f gluster-registry-claim.yaml
```

For example:

```
# oc create -f gluster-registry-claim.yaml
persistentvolumeclaim "gluster-registry-claim" created
```

17. Execute the following command to verify if the claim is bound:

```
# oc get pvc/gluster-registry-claim
```

For example:

```
# oc get pvc/gluster-registry-claim
NAME STATUS VOLUME
CAPACITY ACCESSMODES AGE
gluster-registry-claim Bound gluster-registry-volume 5Gi
RWX 22s
```

18. Make the registry read-only by executing the following command:

```
# oc set env -n default dc/docker-registry
'REGISTRY_STORAGE_MAINTENANCE_READONLY={"enabled":true}'
```

To confirm the value is set to readonly, execute the following command:

```
# oc set env -n default dc/docker-registry --list
```

19. If you want to migrate the data from the old registry to the Red Hat Gluster Storage registry, then execute the following commands:



NOTE

These steps are optional.

1. Add the Red Hat Gluster Storage registry to the old registry deployment configuration (dc) by executing the following command:

```
# oc volume dc/docker-registry --add --name=gluster-registry-
storage -m /gluster-registry -t pvc --claim-name=gluster-
registry-claim
```

2. Save the Registry pod name by executing the following command:

```
# export REGISTRY_POD=$(oc get po --selector="docker-
registry=default" -o go-template --template='{{printf "%s"
  ((index .items 0).metadata.name)}}')
```

3. Copy the data from the old registry directory to the Red Hat Gluster Storage registry directory by executing the following command:

```
# oc rsh $REGISTRY_POD cp -a /registry/ /gluster-registry/
```

4. Remove the Red Hat Gluster Storage registry from the old dc registry by executing the following command:

```
# oc volume dc/docker-registry --remove --name=gluster-registry-
storage
```

20. Replace the existing registry-storage volume with the new gluster-registry-claim PVC:

```
# oc volume dc/docker-registry --add --name=registry-storage -t pvc
--claim-name=gluster-registry-claim --overwrite
```

21. Make the registry read write by executing the following command:

```
# oc set env dc/docker-registry
REGISTRY_STORAGE_MAINTENANCE_READONLY-
```

To validate if the setting is set to read write, execute the following command:

```
# oc set env -n default dc/docker-registry --list
```

For more information about accessing the registry, see https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html/configuring_clusters/setting-up-the-registry#install-config-registry-accessing.

PART V. MONITORING

CHAPTER 10. ENABLING VOLUME METRICS

To enable volume metrics for glusterfs plugin in order to collect the statistics of GlusterFS PVs, set up Prometheus, a monitoring toolkit. You can use Prometheus to visualize metrics and alerts for OpenShift Container Platform system resources.

For more information on how to setup Prometheus, see https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html-single/configuring_clusters/#openshift-prometheus

10.1. ENABLING VOLUME METRICS FOR FILE STORAGE AND BLOCK STORAGE

Following is the list of different metrics of the PVs that can be viewed on Prometheus:

- **kubelet_volume_stats_available_bytes**: Number of available bytes in the volume.
- kubelet_volume_stats_capacity_bytes: Capacity in bytes of the volume.
- **kubelet_volume_stats_inodes**: Maximum number of inodes in the volume.
- **kubelet volume stats inodes free**: Number of free inodes in the volume.
- kubelet_volume_stats_inodes_used: Number of used inodes in the volume.
- kubelet_volume_stats_used_bytes: Number of used bytes in the volume.
- heketi cluster count: Number of clusters.
- heketi_device_brick_count: Number of bricks on device.
- heketi_device_count: Number of devices on host.
- heketi_device_free: Amount of free space available on the device.
- heketi_device_size: Total size of the device.
- heketi_device_used: Amount of space used on the device.
- heketi_nodes_count: Number of nodes on the cluster.
- heketi_up: Verifies if heketi is running.
- heketi_volumes_count: Number of volumes on cluster.


Viewing Metrics

To view any metrics:

- 1. Add the metrics name in **Prometheus**, and click **Execute**.
- 2. In the **Graph** tab, the value for the metrics for the volume is displayed as a graph.

For example, in the following image, to check the available bytes, kubelet_volume_stats_available_bytes metric is added to the search bar on
Prometheus. On clicking Execute, the available bytes value is depicted as a graph. You can

hover the mouse on the line to get more details. (To view the image in detail, right-click and select View Image.)



Viewing Heketi Metrics

To view Heketi metrics on **Prometheus**, execute the following commands:

1. Add annotations to the **heketi-storage**.

```
# oc annotate svc heketi-storage prometheus.io/scheme=http
# oc annotate svc heketi-storage prometheus.io/scrape=true
```

oc describe svc heketi-storage Name: heketi-storage Namespace: app-storage glusterfs=heketi-storage-service Labels: heketi=storage-service Annotations: description=Exposes Heketi service prometheus.io/scheme=http prometheus.io/scrape=true Selector: glusterfs=heketi-storage-pod Type: ClusterIP IP: 172.30.90.87 Port: heketi 8080/TCP TargetPort: 8080/TCP Endpoints: 172.18.14.2:8080 Session Affinity: None

2. Add the **app-storage** namespace for the heketi service in the Prometheus configmap.

3. Restart the **prometheus-0** pod to query the Heketi metrics in Prometheus.

PART VI. TROUBLESHOOT

CHAPTER 11. TROUBLESHOOTING

This chapter describes the most common troubleshooting scenarios related to Red Hat Openshift Container Storage.

What to do if a Red Hat Openshift Container Storage node Fails

If a Red Hat Openshift Container Storage node fails, and you want to delete it, then, disable the node before deleting it. For more information, see Section 1.2.3, "Deleting Node".

If a Red Hat Openshift Container Storage node fails and you want to replace it, see Section 1.2.3.3, "Replacing a Node".

What to do if a Red Hat Openshift Container Storage device fails

If a Red Hat Openshift Container Storage device fails, and you want to delete it, then, disable the device before deleting it. For more information, see Section 1.2.2, "Deleting Device".

If a Red Hat Openshift Container Storage device fails, and you want to replace it, see Section 1.2.2.3, "Replacing a Device".

What to do if Red Hat Openshift Container Storage volumes require more capacity:

You can increase the storage capacity by either adding devices, increasing the cluster size, or adding an entirely new cluster. For more information, see Section 1.1, "Increasing Storage Capacity".

How to upgrade Openshift when Red Hat Openshift Container Storage is installed

To upgrade Openshift Container Platform, see https://access.redhat.com/documentation/en-us/openshift_container_platform/3.10/html/upgrading_clusters/install-config-upgrading-automated-upgrades#upgrading-to-ocp-3-10.

Viewing Log Files

Viewing Red Hat Gluster Storage Container Logs

Debugging information related to Red Hat Gluster Storage containers is stored on the host where the containers are started. Specifically, the logs and configuration files can be found at the following locations on the openshift nodes where the Red Hat Gluster Storage server containers run:

- /etc/glusterfs
- /var/lib/glusterd
- /var/log/glusterfs

Viewing Heketi Logs

Debugging information related to Heketi is stored locally in the container or in the persisted volume that is provided to Heketi container.

You can obtain logs for Heketi by running the **docker logs** *container-id* command on the openshift node where the container is being run.

Heketi command returns with no error or empty error

Sometimes, running heketi-cli command returns with no error or empty error like **Error**. It is mostly due to heketi server not properly configured. You must first ping to validate that the Heketi server is available and later verify with a **curl** command and /hello endpoint.

```
# curl http://deploy-heketi-storage-
project.cloudapps.mystorage.com/hello
```

Heketi reports an error while loading the topology file

Running heketi-cli reports: Error "Unable to open topology file" error while loading the topology file. This could be due to the use of old syntax of single hyphen (-) as a prefix for JSON option. You must use the new syntax of double hyphens and reload the topology file.

cURL command to heketi server fails or does not respond

If the router or heketi is not configured properly, error messages from the heketi may not be clear. To troubleshoot, ping the heketi service using the endpoint and also using the IP address. If ping by the IP address succeeds and ping by the endpoint fails, it indicates a router configuration error.

After the router is setup properly, run a simple curl command like the following:

```
# curl http://deploy-heketi-storage-
project.cloudapps.mystorage.com/hello
```

If heketi is configured correctly, a welcome message from heketi is displayed. If not, check the heketi configuration.

• Heketi fails to start when Red Hat Gluster Storage volume is used to store heketi.db file

Sometimes Heketi fails to start when Red Hat Gluster Storage volume is used to store heketi.db and reports the following error:

```
[heketi] INFO 2016/06/23 08:33:47 Loaded kubernetes executor [heketi] ERROR 2016/06/23 08:33:47 /src/github.com/heketi/heketi/apps/glusterfs/app.go:149: write /var/lib/heketi/heketi.db: read-only file system ERROR: Unable to start application
```

The read-only file system error as shown above could be seen while using a Red Hat Gluster Storage volume as backend. This could be when the quorum is lost for the Red Hat Gluster Storage volume. In a replica-3 volume, this would be seen if 2 of the 3 bricks are down. You must ensure the quorum is met for heketi gluster volume and it is able to write to heketi.db file again.

Even if you see a different error, it is a recommended practice to check if the Red Hat Gluster Storage volume serving heketi.db file is available or not. Access deny to heketi.db file is the most common reason for it to not start.

CHAPTER 12. CLIENT CONFIGURATION USING PORT FORWARDING

If a router is not available, you may be able to set up port forwarding so that heketi-cli can communicate with the Heketi service. Execute the following commands for port forwarding:

1. Obtain the Heketi service pod name by running the following command:

```
# oc get pods
```

2. To forward the port on your local system to the pod, execute the following command on another terminal of your local system:

```
# oc port-forward <heketi pod name> 8080:8080
```

3. On the original terminal execute the following command to test the communication with the server:

```
# curl http://localhost:8080/hello
```

This will forward the local port 8080 to the pod port 8080.

4. Setup the Heketi server environment variable by running the following command:

```
# export HEKETI_CLI_SERVER=http://localhost:8080
```

5. Get information from Heketi by running the following command:

```
# heketi-cli topology info
```

APPENDIX A. REVISION HISTORY

Revision 1.0-02 Wed Sep 12 2018 Bhavana Mohan

Publishing for Red Hat Openshift Container Storage 3.10

Revision 1.0-01 Tue Sep 11 2018 Bhavana Mohan

Rebranded the product from Container-Native Storage to Red Hat OpenShift Container Storage. The terms describing the method of deployment have also been changed to Converged mode (formerly referred to as 'Container Native Storage' or 'CNS') and Independent mode (formerly referred to as 'Container Ready Storage' or 'CRS')

Created two separate guides; one for Deployment and upgrade and another for administrative tasks.

Documented details about ennhanced OCS monitoring and configuration visibility using the Prometheus framework

Documented detailed procedure to reclaim persistent volume

Documented detailed procedure to replace a block on block storage

INDEX