Provision Baremetal using Cobbler

A. Configure the Kickstart file as per the requirement:

1. Make selinux as permissive.

Selinux --permissive

2. Create partition as per the requirement

```
Ex:
# autopart
part /boot --fstype xfs --size 1008 --ondisk=sda
part / --fstype xfs --size 256000 --ondisk=sda
```

3. Add redhat subscription and enable required rpm in post installation section

```
subscription-manager register --username=XXXX --password=XXXX --auto-attach yum -y install yum-utils subscription-manager repos --enable rhel-7-server-optional-rpms subscription-manager repos --enable rhel-7-server-extra-rpms NOTE: Avoid above steps by just adding yum-utils in %package section.
```

4. **Configure keybased login** (add in the post installation section)

```
mkdir -m 0700 /root/.ssh/
cat <<EOF >/root/.ssh/authorized_keys
ssh-rsa
```

AAAAB3NzaC1yc2EAAAADAQABAAABAQCtLjvyNp1B34cwV5Hwhr2W3xikxDELBLdYD tYa77ZNjtR2W0nrj9JxGG6RbHrPjCpn39VVB7IYdMceti95hl3/WcZQwX00Uxy640iBqR nX71dAYZ54VGn22QsBeGc+hVr/3+IHwS0tCKOdl6inIzBArWlZha9WAt9kJA3TDy+uOC VOc2DdhEA+kRlXzsm/OsMkPNWX6E2hx3Ry1/DbxUlyVAQi1y+bwm+4QVY0cVeTQC+Fe5Rfy7ESR0TznElesoNUHYgmMec6hbjLOHm3ZGAtdxhccPpnrcqA/1N56SyOjJDG9x W/aVOTNpaQd4b/unNpfEHK93uychQS5LL3v0Vx root@cobbler EOF

```
### set permissions chmod 0600 /root/.ssh/authorized_keys
```

Note: provide public key to target server and use private key to login the target server

5. Configure static IP

Provide IP Address, Gateway, Netmask, Name Server and static=True in the time of cobbler system creation.

EX:

cobbler system add --name=<pnda-edge> --mac=<00:25:B5:DD:01:4F> --profile=<generic> --hostname=<pnda-edge> --interface=eth0 --ip-address=<9.0.8.151> --subnet=<255.255.240.0> --gateway=<9.0.1.196> --name-servers=<9.0.1.70> --static=True

6. Remove Duplicate interface file

Add after \$\$NIPPET('post_install_network_config') rm -f /etc/sysconfig/network-scripts/ifcfg-\$IFNAME chkconfig NetworkManager off

B. Create profile

cobbler profile add --name <generic> --distro <rhel-x86_64> --kickstart /var/lib/cobbler/kickstarts/<generic.ks>

C. Enable Mac address to get IP from the DHCP

Add Dhcp Entry: /etc/cobbler/ dhcp.template

host pnda-otsdb-0 { hardware ethernet 00:25:B5:DD:01:FF; }

D. Create system

cobbler system add --name=<pnda-edge> --mac=<00:25:B5:DD:01:4F> --profile=<generic> --hostname=<pnda-edge> --interface=eth0 --ip-address=<9.0.8.151> --subnet=<255.255.240.0> --gateway=<9.0.1.196> --name-servers=<9.0.1.70> --static=True

Profile pnda manager:

Kickstart filename: pnda_manager.ks

1. Create cobbler profile:

cobbler profile add --name <pnda_manager> --distro rhel-x86_64 --kickstart /var/lib/cobbler/kickstarts/<pnda_manager.ks>

2. Create Cobbler System:

pnda-mgr Node:

cobbler system add --name=pnda-mgr-01 --mac=00:25:B5:DD:00:7F --profile=pnda_manager --hostname=pnda-mgr-01 --interface=eth0 --ip-address=9.0.8.130 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True

cobbler system add --name=pnda-mgr-02 --mac=00:25:B5:DD:00:4F --profile=pnda_manager --hostname=pnda-mgr-02 --interface=eth0 --ip-address=9.0.8.137 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True

cobbler system add --name=pnda-mgr-03 --mac=00:25:B5:DD:00:5F --profile=pnda_manager --hostname=pnda-mgr-03 --interface=eth0 --ip-address=9.0.8.131 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True

 $cobbler\ system\ add\ --name=pnda-mgr-04\ --mac=00:25:B5:DD:00:2F\ --profile=pnda_manager\ --hostname=pnda-mgr-04\ --interface=eth0\ --ip-address=9.0.8.138\ --subnet=255.255.240.0\ --gateway=9.0.1.196\ --name-servers=9.0.1.70\ --static=True$

3. Add Dhcp Entry: /etc/cobbler/ dhcp.template

```
host pnda-mgr-01 { hardware ethernet 00:25:B5:DD:00:7F; } host pnda-mgr-02 { hardware ethernet 00:25:B5:DD:00:4F; } host pnda-mgr-03 { hardware ethernet 00:25:B5:DD:00:5F; } host pnda-mgr-04 { hardware ethernet 00:25:B5:DD:00:2F; }
```

Profile datanode:

Partition:

Kickstart filename: datanode.ks

1. Create cobbler profile:

```
cobbler profile add --name <datanode02> --distro rhel-x86_64 --kickstart /var/lib/cobbler/kickstarts/<datanode02.ks> cobbler profile add --name <datanode13> --distro rhel-x86_64 --kickstart /var/lib/cobbler/kickstarts/<datanode13.ks>
```

2. <u>Create Cobbler System:</u>

Data Nodes:

```
cobbler system add --name=pnda-DN-0 --mac-address=00:25:B5:DD:01:EF --profile=datanode02 --hostname=pnda-DN-0 --interface=eth0 --ip-address=9.0.8.143 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True

cobbler system add --name=pnda-DN-1 --mac-address=00:25:B5:DD:01:BF --profile=datanode13 --hostname=pnda-DN-1 --interface=eth0 --ip-address=9.0.8.144 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True

cobbler system add --name=pnda-DN-2 --mac-address=00:25:B5:DD:01:CF --profile=datanode02 --hostname=pnda-DN-2 --interface=eth0 --ip-address=9.0.8.145 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True

cobbler system add --name=pnda-DN-3 --mac-address=00:25:B5:DD:01:AF --profile=datanode13 --hostname=pnda-DN-3 --interface=eth0 --ip-address=9.0.8.146 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True
```

3. Add Dhcp Entry: /etc/cobbler/ dhcp.template

```
host pnda-DN-0 { hardware ethernet 00:25:B5:DD:01:EF; } host pnda-DN-1 { hardware ethernet 00:25:B5:DD:01:BF; } host pnda-DN-2 { hardware ethernet 00:25:B5:DD:01:CF; } host pnda-DN-3 { hardware ethernet 00:25:B5:DD:01:AF; }
```

Profile zookeeper:

Kickstart filename: zookeeper.ks

1. Create cobbler profile:

cobbler profile add --name <zookeeper> --distro rhel-x86_64 --kickstart /var/lib/cobbler/kickstarts/<zookeeper.ks>

2. Create Cobbler System:

Zookeeper Nodes:

```
cobbler system add --name=pnda-zk-0 --mac=00:25:B5:DD:00:3F --profile=zookeeper --hostname=pnda-zk-0 --interface=eth0 --ip-address=9.0.8.132 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True
```

```
cobbler system add --name=pnda-zk-1 --mac=00:25:B5:DD:00:0F --profile=zookeeper --hostname=pnda-zk-1 --interface=eth0 --ip-address=9.0.8.133 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True
```

```
cobbler system add --name=pnda-zk-2 --mac=00:25:B5:DD:00:1F --profile=zookeeper --hostname=pnda-zk-2 --interface=eth0 --ip-address=9.0.8.139 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True
```

3. Add Dhcp Entry: /etc/cobbler/ dhcp.template

```
host pnda-zk-0 { hardware ethernet 00:25:B5:DD:00:3F; } host pnda-zk-1 { hardware ethernet 00:25:B5:DD:00:0F; } host pnda-zk-2 { hardware ethernet 00:25:B5:DD:00:1F; }
```

Profile kafka

Kickstart filename: kafka.ks

1. Create cobbler profile:

cobbler profile add --name kafka --distro rhel-x86_64 --kickstart /var/lib/cobbler/kickstarts/kafka.ks

2. Cobbler System:

Kafka Nodes:

```
cobbler system add --name=pnda-kafka-0 --mac=00:25:B5:DD:00:8F --profile=kafka --hostname=pnda-kafka-0 --interface=eth0 --ip-address=9.0.8.147 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True
```

```
cobbler system add --name=pnda-kafka-1 --mac=00:25:B5:DD:00:9F --profile=kafka --hostname=pnda-kafka-1 --interface=eth0 --ip-address=9.0.8.148 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True
```

cobbler system add --name=pnda-kafka-2 --mac=00:25:B5:DD:00:6F --profile=kafka --hostname=pnda-kafka-2 --interface=eth0 --ip-address=9.0.8.149 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True

3. Add Dhcp Entry: /etc/cobbler/ dhcp.template

```
host pnda-kafka-0 { hardware ethernet 00:25:B5:DD:00:8F; } host pnda-kafka-1 { hardware ethernet 00:25:B5:DD:00:9F; } host pnda-kafka-2 { hardware ethernet 00:25:B5:DD:00:6F; }
```

Profile generic & edge

Kickstart filename: generic.ks

1. Create cobbler profile:

cobbler profile add --name <generic> --distro rhel-x86_64 --kickstart /var/lib/cobbler/kickstarts/<generic.ks> cobbler profile add --name <edge> --distro rhel-x86_64 --kickstart /var/lib/cobbler/kickstarts/<edge.ks>

2. Cobbler System:

Opentsdb Node:

cobbler system add --name=pnda-otsdb-0 --mac=00:25:B5:DD:01:FF --profile=generic --hostname=pnda-otsdb-0 --interface=eth0 --ip-address=9.0.8.136 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True

 $cobbler\ system\ add\ --name=pnda-otsdb-1\ --mac=00:25:B5:DD:01:DF\ --profile=generic\ --hostname=pnda-otsdb-1\ --interface=eth0\ --ip-address=9.0.8.141\ --subnet=255.255.240.0\ --gateway=9.0.1.196\ --name-servers=9.0.1.70\ --static=True$

Tools Node:

cobbler system add --name=pnda-tools --mac=00:25:B5:DD:01:9F --profile=generic --hostname=pnda-tools --interface=eth0 --ip-address=9.0.8.142 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True

Build Node:

cobbler system add --name=pnda-build --mac=00:25:B5:DD:01:5F --profile=generic --hostname=pnda-build --interface=eth0 --ip-address=9.0.8.150 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True

Edge Node:

cobbler system add --name=pnda-edge --mac=00:25:B5:DD:01:4F --profile=edge --hostname=pnda-edge --interface=eth0 --ip-address=9.0.8.151 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True

Hadoop manager Node:

cobbler system add --name=hadoop-mgr --mac=00:25:B5:DD:01:8F --profile=generic --hostname=hadoop_manager --interface=eth0 --ip-address=9.0.8.134 --subnet=255.255.240.0 --gateway=9.0.1.196 --name-servers=9.0.1.70 --static=True

3. Add Dhcp Entry: /etc/cobbler/ dhcp.template

host pnda-otsdb-0 { hardware ethernet 00:25:B5:DD:01:FF; } host pnda-otsdb-1 { hardware ethernet 00:25:B5:DD:01:DF; } host pnda-tools { hardware ethernet 00:25:B5:DD:01:9F; } host pnda-build { hardware ethernet 00:25:B5:DD:01:5F; } host pnda-edge { hardware ethernet 00:25:B5:DD:01:4F; } host hadoop-mgr { hardware ethernet 00:25:B5:DD:01:8F; }