Plasmonic Wire Grating

Introduction

A plane electromagnetic wave is incident on a wire grating on a dielectric substrate. The model computes transmission and reflection coefficients for the refraction, specular reflection, and first order diffraction.

Model Definition

Figure 1 shows the considered grating, with a gold wire on a dielectric material with refractive index n_{β} . The grating constant, or the distance between the wires, is d. A plane-polarized wave traveling through a medium with refractive index n_{α} is incident on the grating, at an angle α in a plane perpendicular to the grating.




Figure 1: The modeled grating. The model considers a unit cell of a slice through this geometry. The grating is assumed to consist of an infinite number of infinitely long wires.

If the wavelengths involved in the model are sufficiently short compared to the grating constant, one or several diffraction orders can be present. The diagram in Figure 2

shows two transmissive paths taken by light incident on adjacent cells of the grating, exactly one grating constant apart.




Figure 2: The geometric path lengths of two transmitted parallel beams. The optical path length is the geometric path length multiplied by the local refractive index.

The criterion for positive interference is that the difference in optical path length along the two paths equals an integer number of vacuum wavelengths, or:

$$m\lambda_0 = d(n_\beta \sin \beta_m - n_\alpha \sin \alpha) \tag{1}$$

with $m = 0, \pm 1, \pm 2, ..., \lambda_0$ the vacuum wavelength, and $\beta_{\rm m}$ the transmitted diffracted beam of order m. For m = 0, this reduces to refraction, as described by Snell's law:

$$\sin\beta_0 = \frac{n_\alpha}{n_\beta} \sin\alpha$$

Because the sine functions can only vary between -1 and 1, the existence of higher diffraction order requires that

$$-(n_{\alpha}+n_{\beta})<\frac{m\lambda_0}{d}<(n_{\alpha}+n_{\beta})$$

The model instructions cover only first order diffraction, and are hence only valid for under the condition

$$2\lambda_0 > d(n_\alpha |\sin\alpha| + n_\beta) \tag{2}$$

Note that for the special cases of perpendicular and grazing incidence, the right-hand side of the inequality evaluates to dn_{β} and $d(n_{\alpha} + n_{\beta})$ respectively.




Figure 3 shows the corresponding paths of the reflected light.

Figure 3: The geometric path lengths of two parallel reflected beams.

For positive interference we get

$$m\lambda_0 = dn_\alpha(\sin\alpha_m - \sin\alpha) \tag{3}$$

where α_m is the reflected beam of diffraction order m. Setting m = 0 in this equation renders

$$\sin \alpha_0 = \sin \alpha$$

or specular reflection. The condition for no reflected diffracted beams of order 2 or greater being present is

$$2\lambda_0 > dn_a (1 + |\sin\alpha|) \tag{4}$$

The model uses $n_{\alpha}=1$ for air and $n_{\beta}=1.2$ for the dielectric substrate. Allowing for arbitrary angles of incidence and with a grating constant d=400 nm, Equation 2 sets the validity limit to vacuum wavelengths greater than 440 nm. The model uses $\lambda_0=441$ nm. For the wire, a complex-valued permittivity of -1.75-5.4i approximates that of gold at the corresponding frequency.

The performance of the grating depends on the polarization of the incident wave. Therefore both a transverse electric (TE) and a transverse magnetic (TM) case are considered. The TE wave has the electric field component in the z direction, out of the modeling xy-plane. For the TM wave, the electric field vector is pointing in the xy-plane and perpendicular to the direction of propagation, whereas the magnetic field

has only a component in the z direction. The angle of incidence is for both cases swept from 0 to $\pi/2$, with a pitch of $\pi/40$.

Results and Discussion

As an example of the output from the model, Figure 4 and Figure 5 show the electric field norm for an angle of incidence equal to $\pi/5$, for the TE and TM case respectively.

9: lambda0=4.41E-7, alpha=0.6283 Electric field norm (V/m) Incident wave (magenta) Reflected wave (blue) Transmitted wave (blue) Reflected mode, m = -1 (cyan) Reflected mode, m = 1 (green) Transmitted mode, m = -1 (cyan)




Figure 4: Electric field norm for TE incidence at $\pi/5$.




Figure 5: Electric field norm for TM incidence at $\pi/5$.

All the computed transmission and reflection coefficients for TE incidence are plotted in Figure 6. R_0 , the coefficient for specular reflection, increases rather steadily with the angle of incidence. This is both because of reflection in the material interface and because the wave "sees" the wire as increasingly wider at greater angles—the same effect as achieved by a Venetian blind. T_0 , the refracted but not diffracted transmission, decreases accordingly. For the considered wavelength to period length ratio, the transmitted diffracted beam T_{-1} is propagating only for nearly perpendicular incidence. The reflected diffraction order R_1 would need a shorter wavelength or a larger grating period to show up. Instead, the most prominent diffraction orders are R_{-1} and T_1 .

Note first that the sum of all coefficients is consistently less than 1. This is because of the dielectric losses in the wire. This is even more apparent for TM incidence, as Figure 7 shows. Here, approximately half of the wave is absorbed in the wire. Another important feature of the TM case is that there is very little specular reflection (R_0) around 60 degrees.




Figure 6: Transmission and reflection coefficients for TE incidence.




Figure 7: Transmission and reflection coefficients for TM incidence.

Notes About the COMSOL Implementation

The model is set up for one unit cell of the grating, flanked by Floquet boundary conditions describing the periodicity. As applied, this condition states that the solution on one side of the unit equals the solution on the other side multiplied by a complex-valued phase factor. The phase shift between the boundaries is evaluated from the perpendicular component of the wave vector. Because the periodicity boundaries are parallel with the y-axis, only the x-component is required. Note that due to the continuity of the field, the phase factor is the same for the refracted and reflected beams as for the incident wave.

Port conditions are used both for specifying the incident wave and for letting the resulting solution leave the model without any non-physical reflections. In order to achieve perfect transmission through the port boundaries, one port for each mode (m = 0, m = -1, m = 1) in each direction must be present. This gives a total of 6 ports.

The input to each periodic port is an electric or magnetic field amplitude vector and an angle of incidence. The angle of incidence is defined as

$$\mathbf{k} \times \mathbf{n} = k \sin \alpha \mathbf{z}$$

where \mathbf{k} is the propagation vector of the incident wave, \mathbf{n} is the normalized normal vector, k is the wave number, α is the angle of incidence, and z is the unit vector in the z direction. Note that this definition means that the angle of incidence on the opposite sides have opposite signs. To automatically create ports for the diffraction orders, you also provide the refractive index at the port boundary and the maximum frequency (which in this model is the single frequency that is used).

The below table lists the parameters names used in the model. "Internal" means that the variable is not provided as an input parameter

TABLE 4-I: PARAMETER NAMES

MODEL DESCRIPTION	MODEL	DESCRIPTION
n_{α}	na	Refractive index, air
n_{β}	nb	Refractive index, dielectric
α	alpha	Angle of incidence
α_1	Internal	Reflected diffraction angle, order I
α_1	Internal	Reflected diffraction angle, order - I
β_0	beta	Refraction angle

TABLE 4-I: PARAMETER NAMES

MODEL DESCRIPTION	MODEL	DESCRIPTION
β_1	Internal	Refracted diffraction angle, order I
β ₋₁	Internal	Refracted diffraction angle, order -I

Application Library path: RF_Module/Tutorials/plasmonic_wire_grating

Modeling Instructions

From the File menu, choose New.

NEW

I In the New window, click Model Wizard.

MODEL WIZARD

- I In the Model Wizard window, click 2D.
- 2 In the Select physics tree, select Radio Frequency>Electromagnetic Waves, Frequency Domain (emw).
- 3 Click Add.
- 4 Click Study.
- 5 In the Select study tree, select Preset Studies>Frequency Domain.
- 6 Click Done.

GLOBAL DEFINITIONS

Parameters

- I On the Home toolbar, click Parameters.
- 2 In the Settings window for Parameters, locate the Parameters section.

3	In the	table,	enter	the	follo	owing	settings:
•	III tiic	tabic,	CIILCI	uic	TOIL	wing	scungs

Name	Expression	Value	Description
na	1	I	Refractive index, air
nb	1.2	1.2	Refractive index, dielectric
d	400[nm]	4E-7 m	Grating constant
lam0	441[nm]	4.41E-7 m	Vacuum wavelength
f0	c_const/lam0	6.798E14 1/s	Frequency
alpha	0	0	Angle of incidence
beta	asin(na*sin(alpha)/nb)	0 rad	Refraction angle

Although the angle of incidence will not remain constant at 0, it needs to be specified as a parameter to be accessible to the parametric solver.

GEOMETRY I

Create the geometry entirely in terms of the grating constant, for easy scalability.

Rectangle I (rI)

- I On the Geometry toolbar, click Primitives and choose Rectangle.
- 2 In the Settings window for Rectangle, locate the Size section.
- 3 In the Width text field, type d.
- 4 In the Height text field, type 3*d.
- 5 Right-click Component I (compl)>Geometry I>Rectangle I (rl) and choose Build Selected.

Rectangle 2 (r2)

- I On the Geometry toolbar, click Primitives and choose Rectangle.
- 2 In the Settings window for Rectangle, locate the Size section.
- 3 In the Width text field, type d.
- 4 In the Height text field, type 3*d.
- 5 Locate the Position section. In the y text field, type -3*d.
- 6 Right-click Component I (compl)>Geometry I>Rectangle 2 (r2) and choose Build Selected.

Circle I (c1)

I On the Geometry toolbar, click Primitives and choose Circle.

- 2 In the Settings window for Circle, locate the Size and Shape section.
- 3 In the Radius text field, type d/5.
- 4 Locate the **Position** section. In the x text field, type d/2.
- 5 Right-click Component I (compl)>Geometry I>Circle I (cl) and choose Build Selected.
- 6 Click the **Zoom Extents** button on the **Graphics** toolbar.

The geometry now consists of two rectangular domains for the air and the dielectric, and a circle centered on their intersection. You can remove the line through the circle if you first create a union of the objects.

Union I (uni I)

- I On the Geometry toolbar, click Booleans and Partitions and choose Union.
- 2 Click in the **Graphics** window and then press Ctrl+A to select all objects.
- 3 Right-click Component I (compl)>Geometry I>Union I (unil) and choose Build Selected.


Delete Entities I (del I)

- I Right-click Geometry I and choose Delete Entities.
- 2 On the object unil, select Boundary 6 only (this is the horizontal diameter of the circle in the center of the geometry).

Form Union (fin)

I Right-click Component I (compl)>Geometry I>Delete Entities I (dell) and choose **Build Selected.**

2 In the Model Builder window, under Component I (compl)>Geometry I right-click Form Union (fin) and choose Build Selected.



ELECTROMAGNETIC WAVES, FREQUENCY DOMAIN (EMW)

Before setting up the materials, define which constitutive relations you want to use in the Electromagnetic Waves interface.

Wave Equation, Electric 1

- I In the Model Builder window, expand the Electromagnetic Waves, Frequency Domain (emw) node, then click Wave Equation, Electric I.
- 2 In the Settings window for Wave Equation, Electric, locate the Electric Displacement Field section.
- 3 From the Electric displacement field model list, choose Refractive index.

Wave Equation, Electric 2

- I On the Physics toolbar, click Domains and choose Wave Equation, Electric.
- **2** Select Domain 3 only.
- **3** In the **Settings** window for Wave Equation, Electric, locate the **Electric Displacement Field** section.
- 4 From the Electric displacement field model list, choose Dielectric loss.

MATERIALS

Material I (mat I)

- I In the Model Builder window, under Component I (compl) right-click Materials and choose Blank Material.
- 2 In the Settings window for Material, type Air in the Label text field.
- **3** Locate the **Material Contents** section. In the table, enter the following settings:

Property	Name	Value	Unit	Property group
Refractive index	n	na	ı	Refractive index

Material 2 (mat2)

- I In the Model Builder window, right-click Materials and choose Blank Material.
- 2 In the Settings window for Material, type Dielectric in the Label text field.
- **3** Select Domain 1 only.
- **4** Locate the **Material Contents** section. In the table, enter the following settings:

Property	Name	Value	Unit	Property group
Refractive index	n	nb	I	Refractive index

Material 3 (mat3)

- I Right-click Materials and choose Blank Material.
- 2 In the Settings window for Material, type Gold in the Label text field.
- **3** Select Domain 3 only.
- **4** Locate the **Material Contents** section. In the table, enter the following settings:

Property	Name	Value	Unit	Property group
Relative permittivity (imaginary part)	epsilonBis	5.4	I	Dielectric losses
Relative permittivity (real part)	epsilonPrim	-1.75	I	Dielectric losses
Relative permeability	mur	1	I	Basic
Electrical conductivity	sigma	0	S/m	Basic

ELECTROMAGNETIC WAVES, FREQUENCY DOMAIN (EMW)

In the first version of this example, you will assume a TE-polarized wave. This means that E_x and E_y will be zero throughout the geometry, and that you consequently only need to solve for E_z .

- I In the Model Builder window, under Component I (compl) click Electromagnetic Waves, Frequency Domain (emw).
- 2 In the Settings window for Electromagnetic Waves, Frequency Domain, locate the Components section.
- 3 From the Electric field components solved for list, choose Out-of-plane vector.

Now define the excitation port. A periodic port assumes that the structure is periodic and simplifies the setup of ports for the diffraction orders.

Port 1

- I On the Physics toolbar, click Boundaries and choose Port.
- 2 Select Boundary 5 only.

should not be entered.

- 3 In the Settings window for Port, locate the Port Properties section.
- 4 From the Type of port list, choose Periodic.
- 5 From the Wave excitation at this port list, choose On. Notice that you define the electric field by only setting the amplitude. A phase factor
- **6** Locate the **Port Mode Settings** section. Specify the \mathbf{E}_0 vector as

0	x
0	у
1	z

- 7 In the α text field, type alpha.
- **8** In the *n* text field, type na.
- **9** In the f_{max} text field, type **f0**.

he order in which you set up the ports will determine how the S-parameters are labeled. You have just created Port 1 for the excitation. If you set up the next port for the transmission of the purely refracted beam, the S21-parameter will contain information on the zero order transmission.

Port 2

- I On the Physics toolbar, click Boundaries and choose Port.
- 2 Select Boundary 2 only.
- 3 In the Settings window for Port, locate the Port Properties section.
- 4 From the Type of port list, choose Periodic.

5 Locate the **Port Mode Settings** section. Specify the \mathbf{E}_0 vector as

0	x
0	у
1	z

The angle of incidence on the exit side corresponds to the angle of incidence an incident wave on that side would have to provide the correct propagation angle in the material. Notice that this also means that the sign is opposite that on the entry side.

- **6** In the α text field, type -beta.
- 7 In the *n* text field, type nb.
- **8** In the f_{max} text field, type f0.

Port I

Continue with the ports for the reflected diffraction orders. Since these diffraction orders are not propagating at normal incidence, you have to add the ports manually.

Diffraction Order 1

- I On the Physics toolbar, click Attributes and choose Diffraction Order.
- 2 In the Settings window for Diffraction Order, locate the Port Mode Settings section.
- 3 From the Components list, choose Out-of-plane vector.
- 4 In the m text field, type -1.

Diffraction Order 2

- I Right-click Component I (compl)>Electromagnetic Waves, Frequency Domain (emw)>Port I>Diffraction Order I and choose Duplicate.
- 2 In the Settings window for Diffraction Order, locate the Port Properties section.
- 3 In the Port name text field, type 4.
- **4** Locate the **Port Mode Settings** section. In the *m* text field, type 1.

The transmitted diffraction orders are propagating at normal incidence. Thus, you can create them automatically by clicking the **Compute Diffraction Orders** button.

Port 2

- I In the Model Builder window, under Component I (compl)>Electromagnetic Waves, Frequency Domain (emw) click Port 2.
- 2 In the Settings window for Port, locate the Port Mode Settings section.

3 Click Compute Diffraction Orders. You now find the Diffraction Order ports as subfeatures to Port 2.

Periodic Condition I

- I On the Physics toolbar, click Boundaries and choose Periodic Condition.
- **2** Select Boundaries 1, 3, 7, and 8 only.
- 3 In the Settings window for Periodic Condition, locate the Periodicity Settings section.
- 4 From the Type of periodicity list, choose Floquet periodicity.

The wave vector in the direction for the periodicity is used by the periodic port. Thus, you can use that wave vector also for the Floquet periodic condition.

5 From the k-vector for Floquet periodicity list, choose From periodic port.

MESH I

The periodic boundary conditions perform better if the mesh is identical on the periodicity boundaries. This is especially important when dealing with vector degrees of freedom, as will be the case in the TM version of this example.

- I In the Model Builder window, under Component I (compl) click Mesh I.
- 2 In the Settings window for Mesh, locate the Mesh Settings section.
- 3 From the Sequence type list, choose User-controlled mesh.

Free Triangular I

I In the Model Builder window, under Component I (compl)>Mesh I right-click Free **Triangular I** and choose **Delete**. Click **Yes** to confirm.

Size

- I In the Model Builder window, under Component I (compl)>Mesh I click Size.
- 2 In the Settings window for Size, locate the Element Size section.
- 3 From the Predefined list, choose Extra fine.

Edge 1

- I In the Model Builder window, right-click Mesh I and choose More Operations>Edge.
- **2** Select Boundaries 1 and 3 only.

Copy Edge 1

- I Right-click Mesh I and choose More Operations>Copy Edge.
- **2** Select Boundary 3 only.

- 3 In the Settings window for Copy Edge, locate the Destination Boundaries section.
- **4** Select the **Active** toggle button.
- **5** Select Boundary 8 only.

Copy Edge 2

- I Right-click Mesh I and choose More Operations>Copy Edge.
- **2** Select Boundary 1 only.
- 3 In the Settings window for Copy Edge, locate the Destination Boundaries section.
- 4 Select the Active toggle button.
- **5** Select Boundary 7 only.

Free Triangular I

- I Right-click Mesh I and choose Free Triangular.
- 2 In the Model Builder window, under Component I (compl)>Mesh I right-click Free Triangular I and choose Build All.

To set up the study to sweep for the angle of incidence, some modifications of the solver is required.

STUDY I

Step 1: Frequency Domain

- I In the Model Builder window, expand the Study I node, then click Step I: Frequency Domain.
- 2 In the Settings window for Frequency Domain, locate the Study Settings section.
- **3** In the **Frequencies** text field, type **f**0.

Parametric Sweep

- I On the Study toolbar, click Parametric Sweep.
- 2 In the Settings window for Parametric Sweep, locate the Study Settings section.
- 3 Click Add.
- **4** In the table, enter the following settings:

Parameter name	Parameter value list	Parameter unit
alpha		

- 5 Click Range.
- 6 In the Range dialog box, type 0 in the Start text field.

- 7 In the **Stop** text field, type pi/2-pi/40.
- 8 In the Step text field, type pi/40.
- 9 Click Replace.
- 10 On the Study toolbar, click Compute.

Add arrow plots for the incident wave vector of the excitation port and the mode wave vector of each diffraction order.

RESULTS

Electric Field (emw)

- I In the Model Builder window, under Results right-click Electric Field (emw) and choose Arrow Line.
- 2 In the Settings window for Arrow Line, click Replace Expression in the upper-right corner of the Expression section. From the menu, choose Component I>Electromagnetic Waves, Frequency Domain>Ports>emw.klncx I,emw.klncy I -Incident wave vector.
- 3 Locate the Coloring and Style section. From the Color list, choose Magenta.
- **4** Locate the **Expression** section. Select the **Description** check box.
- 5 In the associated text field, type Incident wave (magenta).
- 6 In the Model Builder window, right-click Electric Field (emw) and choose Arrow Line.
- 7 In the Settings window for Arrow Line, click Replace Expression in the upper-right corner of the Expression section. From the menu, choose Component I>Electromagnetic Waves, Frequency Domain>Ports>emw.kModex_I,emw.kModey_I -Port mode wave vector.
- 8 Locate the Coloring and Style section. From the Color list, choose Blue.
- **9** Locate the **Expression** section. Select the **Description** check box.
- 10 In the associated text field, type Reflected wave (blue).
- II Right-click Electric Field (emw) and choose Arrow Line.
- 12 In the Settings window for Arrow Line, click Replace Expression in the upper-right corner of the Expression section. From the menu, choose Component I>Electromagnetic Waves, Frequency Domain>Ports>emw.kModex_2,emw.kModey_2 -Port mode wave vector.
- 13 Locate the Coloring and Style section. From the Color list, choose Blue.
- **14** Locate the **Expression** section. Select the **Description** check box.

- **IS** In the associated text field, type Transmitted wave (blue).
- **16** Right-click **Electric Field (emw)** and choose **Arrow Line**.
- 17 In the Settings window for Arrow Line, click Replace Expression in the upper-right corner of the **Expression** section. From the menu, choose **Component** I>Electromagnetic Waves, Frequency Domain>Ports>emw.kModex_3,emw.kModey_3 -Port mode wave vector.
- 18 Locate the Coloring and Style section. From the Color list, choose Cyan.
- **19** Locate the **Expression** section. Select the **Description** check box.
- **20** In the associated text field, type Reflected mode, m = -1 (cyan).
- 21 Right-click Results>Electric Field (emw)>Arrow Line 4 and choose Duplicate.
- 22 In the Settings window for Arrow Line, click Replace Expression in the upper-right corner of the Expression section. From the menu, choose Component I>Electromagnetic Waves, Frequency Domain>Ports>emw.kModex_4,emw.kModey_4 -Port mode wave vector.
- 2 Locate the Coloring and Style section. From the Color list, choose Green.
- **24** Locate the **Expression** section. Select the **Description** check box.
- **25** In the associated text field, type Reflected mode, m = 1 (green).
- 26 Right-click Arrow Line 4 and choose Duplicate.
- **27** In the **Settings** window for Arrow Line, locate the **Expression** section.
- **28** In the **x component** text field, type emw.kModex_5.
- **29** In the **y component** text field, type emw.kModey 5.
- **30** Select the **Description** check box.
- 31 In the associated text field, type Transmitted mode, m = -1 (cyan).
- 32 In the Model Builder window, under Results>Electric Field (emw) right-click Arrow Line 5 and choose Duplicate.
- **33** In the **Settings** window for Arrow Line, locate the **Expression** section.
- **34** In the **x component** text field, type emw.kModex 6.
- **35** In the y component text field, type emw.kModey 6.
- **36** Select the **Description** check box.
- 37 In the associated text field, type Transmitted mode, m = 1 (green).
- 38 In the Model Builder window, click Electric Field (emw).

39 In the Settings window for 2D Plot Group, type 2D Plot Group TE in the Label text field.

The default plot shows the electric field norm for the last solution, almost tangential incidence. Look at a more interesting angle of incidence.

- 40 Locate the Data section. From the Parameter value (alpha) list, choose 0.6283. Shorten the title, by removing plot types.
- 4 Click to expand the Title section. From the Title type list, choose Custom.
- **4** Find the **Type and data** subsection. Clear the **Type** check box.
- 48 On the 2D Plot Group TE toolbar, click Plot.
- **44** Click the **Zoom Extents** button on the **Graphics** toolbar. The plot should now look like Figure 4.

Add a 1D plot to look at the various orders of reflectance and transmittance versus the angle of incidence.

ID Plot Group 2

- I On the Home toolbar, click Add Plot Group and choose ID Plot Group.
- **2** In the **Settings** window for 1D Plot Group, click to expand the **Title** section.
- 3 From the Title type list, choose Manual.
- 4 In the **Title** text area, type Reflectance and Transmittance of TE Wave.
- **5** Locate the **Plot Settings** section. Select the **x-axis label** check box.
- 6 In the associated text field, type Angle of incidence (degrees).
- 7 Select the y-axis label check box.
- **8** In the associated text field, type Reflectance and transmittance.
- 9 On the ID Plot Group 2 toolbar, click Global.
- 10 In the Settings window for Global, locate the y-Axis Data section.
- II In the table, enter the following settings:

Expression	Unit	Description
abs(emw.S11)^2	1	
abs(emw.S21)^2	1	
abs(emw.S31)^2	1	
abs(emw.S41)^2	1	
abs(emw.S51)^2	1	
abs(emw.S61)^2	1	

- 12 Locate the x-Axis Data section. From the Parameter list, choose Expression.
- 13 In the Expression text field, type alpha*180/pi.
- 14 Click to expand the Coloring and style section. Locate the Coloring and Style section. Find the Line markers subsection. From the Marker list, choose Cycle.
- **15** Click to expand the **Legends** section. From the **Legends** list, choose **Manual**.
- **16** In the table, enter the following settings:

Legends
R ₀
T ₀
R ₋₁
R ₁
T ₋₁
T ₁

- 17 On the 1D Plot Group 2 toolbar, click Plot.
- 18 In the Model Builder window, click ID Plot Group 2.
- 19 In the Settings window for 1D Plot Group, type 1D Plot Group TE in the Label text field. The plot should now look like Figure 6.

The remaining instructions show to alter the physics so that you solve for an incident TM wave.

ELECTROMAGNETIC WAVES, FREQUENCY DOMAIN (EMW)

- I In the Model Builder window, under Component I (compl) click Electromagnetic Waves, Frequency Domain (emw).
- 2 In the Settings window for Electromagnetic Waves, Frequency Domain, locate the **Components** section.
- 3 From the Electric field components solved for list, choose In-plane vector. You will now solve for E_x and E_y instead of E_z ; for a TM wave, E_z is zero.

The easiest way to specify a TM wave is to define the magnetic field, since only the z component is used.

- I In the Model Builder window, under Component I (compl)>Electromagnetic Waves, Frequency Domain (emw) click Port 1.
- 2 In the Settings window for Port, locate the Port Mode Settings section.

- 3 From the Input quantity list, choose Magnetic field.
- **4** Specify the \mathbf{H}_0 vector as

0	x
0	у
1	z

Diffraction Order I

- I In the Model Builder window, under Component I (compl)>Electromagnetic Waves, Frequency Domain (emw)>Port I click Diffraction Order I.
- 2 In the Settings window for Diffraction Order, locate the Port Mode Settings section.
- 3 From the Components list, choose In-plane vector.

Diffraction Order 2

- I In the Model Builder window, under Component I (compl)>Electromagnetic Waves, Frequency Domain (emw)>Port I click Diffraction Order 2.
- 2 In the Settings window for Diffraction Order, locate the Port Mode Settings section.
- 3 From the Components list, choose In-plane vector.

Port 2

- I In the Model Builder window, under Component I (compl)>Electromagnetic Waves, Frequency Domain (emw) click Port 2.
- 2 In the Settings window for Port, locate the Port Mode Settings section.
- 3 From the Input quantity list, choose Magnetic field.
- **4** Specify the \mathbf{H}_0 vector as

0	x
0	у
1	z

5 Click Compute Diffraction Orders to change components for the diffraction orders that are propagating at normal incidence.

ROOT

Add a new study in order not to overwrite the TE solution.

ADD STUDY

I On the Home toolbar, click Add Study to open the Add Study window.

- 2 Go to the Add Study window.
- 3 Find the Studies subsection. In the Select study tree, select Preset Studies>Frequency Domain.
- 4 Click Add Study in the window toolbar.
- 5 On the Home toolbar, click Add Study to close the Add Study window.

STUDY 2

Step 1: Frequency Domain

- I In the Model Builder window, expand the Study 2 node, then click Step I: Frequency
- 2 In the Settings window for Frequency Domain, locate the Study Settings section.
- **3** In the **Frequencies** text field, type **f**0.

Parametric Sweep

- I On the Study toolbar, click Parametric Sweep.
- 2 In the Settings window for Parametric Sweep, locate the Study Settings section.
- 3 Click Add.
- **4** In the table, enter the following settings:

Parameter name	Parameter value list	Parameter unit
alpha		

- 5 Click Range.
- 6 In the Range dialog box, type 0 in the Start text field.
- 7 In the **Stop** text field, type pi/2-pi/40.
- 8 In the Step text field, type pi/40.
- 9 Click Replace.
- 10 On the Study toolbar, click Compute.

RESULTS

Electric Field (emw)

- I In the Model Builder window, under Results right-click Electric Field (emw) and choose Arrow Line.
- 2 In the Settings window for Arrow Line, click Replace Expression in the upper-right corner of the Expression section. From the menu, choose Component

- I>Electromagnetic Waves, Frequency Domain>Ports>emw.klncx_I,emw.klncy_I -Incident wave vector.
- 3 Locate the Coloring and Style section. From the Color list, choose Magenta.
- **4** Locate the **Expression** section. Select the **Description** check box.
- **5** In the associated text field, type Incident wave (magenta).
- 6 In the Model Builder window, right-click Electric Field (emw) and choose Arrow Line.
- 7 In the Settings window for Arrow Line, click Replace Expression in the upper-right corner of the **Expression** section. From the menu, choose **Component** I>Electromagnetic Waves, Frequency Domain>Ports>emw.kModex_I,emw.kModey_I -Port mode wave vector.
- 8 Locate the Coloring and Style section. From the Color list, choose Blue.
- **9** Locate the **Expression** section. Select the **Description** check box.
- **10** In the associated text field, type Reflected wave (blue).
- II Right-click Electric Field (emw) and choose Arrow Line.
- 12 In the Settings window for Arrow Line, click Replace Expression in the upper-right corner of the **Expression** section. From the menu, choose **Component** I>Electromagnetic Waves, Frequency Domain>Ports>emw.kModex_2,emw.kModey_2 -Port mode wave vector.
- 13 Locate the Coloring and Style section. From the Color list, choose Blue.
- **14** Locate the **Expression** section. Select the **Description** check box.
- **IS** In the associated text field, type Transmitted wave (blue).
- **16** Right-click **Electric Field (emw)** and choose **Arrow Line**.
- 17 In the Settings window for Arrow Line, click Replace Expression in the upper-right corner of the Expression section. From the menu, choose Component I>Electromagnetic Waves, Frequency Domain>Ports>emw.kModex 3,emw.kModey 3 -Port mode wave vector.
- 18 Locate the Coloring and Style section. From the Color list, choose Cyan.
- 19 Locate the Expression section. Select the Description check box.
- **20** In the associated text field, type Reflected mode, m = -1 (cyan).
- 21 Right-click Results>Electric Field (emw)>Arrow Line 4 and choose Duplicate.
- **22** In the **Settings** window for Arrow Line, click **Replace Expression** in the upper-right corner of the **Expression** section. From the menu, choose **Component** I>Electromagnetic Waves, Frequency Domain>Ports>emw.kModex 4,emw.kModey 4 -Port mode wave vector.

- **23** Locate the Coloring and Style section. From the Color list, choose Green.
- **24** Locate the **Expression** section. Select the **Description** check box.
- **25** In the associated text field, type Reflected mode, m = 1 (green).
- **26** Right-click **Arrow Line 4** and choose **Duplicate**.
- **27** In the **Settings** window for Arrow Line, locate the **Expression** section.
- **28** In the **x component** text field, type emw.kModex 5.
- **29** In the y component text field, type emw.kModey 5.
- **30** Select the **Description** check box.
- **3I** In the associated text field, type Transmitted mode, m = -1 (cyan).
- 32 In the Model Builder window, under Results>Electric Field (emw) right-click Arrow Line 5 and choose Duplicate.
- **33** In the **Settings** window for Arrow Line, locate the **Expression** section.
- **34** In the **x component** text field, type emw.kModex 6.
- **35** In the y component text field, type emw.kModey 6.
- **36** Select the **Description** check box.
- **37** In the associated text field, type Transmitted mode, m = 1 (green).
- 38 In the Model Builder window, click Electric Field (emw).
- 39 In the Settings window for 2D Plot Group, type 2D Plot Group TM in the Label text field.
- 40 Locate the Data section. From the Parameter value (alpha) list, choose 0.6283.
- 41 Click to expand the **Title** section. From the **Title type** list, choose **Custom**.
- **42** Find the **Type and data** subsection. Clear the **Type** check box.
- 48 On the 2D Plot Group TM toolbar, click Plot.
- 44 Click the Zoom Extents button on the Graphics toolbar. You have now reproduced Figure 5.

For the reflectance and transmittance of the TM waves, copy and reuse the 1D plot for the TE waves.

ID Plot Group TE I

- I In the Model Builder window, under Results right-click ID Plot Group TE and choose Duplicate.
- 2 In the Settings window for 1D Plot Group, type 1D Plot Group TM in the Label text field.

- 3 Locate the Title section. In the Title text area, type Reflectance and Transmittance of TM Wave.
- 4 Locate the Data section. From the Data set list, choose Study 2/Solution 2.
- 5 On the ID Plot Group TM toolbar, click Plot. Compare the resulting plot with that in Figure 7.