

# Supra Short Forms (supra.dtx)

Charles Duan

September 6, 2026

Some citations use a short form that reads “*<desc>*, *supra* note *<num>*.” Additionally, a writer may specify the *hereinafter* reference parameter for a reference, which applies a *supra* short form to that reference. This section describes how such citations are produced and managed.

`\hi@supra@form`  $\{\langle ref \rangle\}\{\langle desc \rangle\}$

Reference types that uses *supra* short forms must execute the above macro in the course of defining a reference. The argument  $\langle ref \rangle$  is the reference name, and  $\langle desc \rangle$  is the description to precede the word “*supra*.” The description is usually the reference author’s last name, and it may use font shortcut commands as described in `fonts.dtx`.

The *hereinafter* parameter also calls `\hi@supra@form`, overriding any other short form defined for the reference.

Setting up a *supra* form involves performing the following tasks:

- Registering the description as a short citation name for duplicate checking, as described in `short.dtx`.
- Creating both a short citation form and an inline form, where the inline form displays the description text.
- Records that  $\langle ref \rangle$  is a *supra*-type reference that does not follow the five-footnote rule, to conform with the expectations of short citation state described in `state.dtx`.

```
\def\hi@supra@form#1#2{%
  \hi@short@register{#1}{#2}{n}%
  \hi@newcite@form{sc}{#1}{%
    \hi@short@use{#1}%
    \hi@inline@only{%
      \hi@citeguts{%
        \unexpanded{#2}%
      }%
    }%
    \hi@inline@never{%
      \hi@citeguts{%
        \noexpand\hi@usevol{%
          \unexpanded{#2}%
          \noexpand\hi@supra@word{#1}%
          \hi@maybepage{, \hi@page@atorsect}%
        }%
      }%
    }%
  }%
}%
\global\cslet{sc@#1@supra}\empty
}
```

Produces the word “supra” with the footnote number.

```
\def\hi@supra@word#1{%
  \hi@font@comma \hi@nocap \hi@fn@latin{supra}%
  \hi@notepos{#1}%
  \hi@dotfalse
}
```

Displays the footnote number for the *supra* citation. Following the conventions described in `state.dtx`, the number is displayed only if (1) the reference has only been cited in footnotes (`\hi@dfc@{ref}` is positive) and the reference number is not the same as the current footnote number.

This macro is not incorporated into `\hi@supra@word` because it is redefined in the `tex4ht` conversion file or by the cross-reference mechanism as described below.

```
\def\hi@notepos#1{%
  \ifnum\csname hi@dfc@#1\endcsname=\c@footnote\else
    \ifnum\csname hi@dfc@#1\endcsname>\z@
      \space note-\csname hi@dfc@#1\endcsname
    \fi
  \fi
}%
```

**0(a) Cross-Reference *Supra* Forms** In legal memoranda, *supra* short citations contain no information other than the word *supra*. If the option `xrefsupra` is given to *Hereinafter*, then the short citation further includes a cross-reference to the first full citation to the reference. The cross-reference is generated using `\hilabel` as described in `xref.dtx`.

```
\let\hi@supra@make@xref\@gobble
\def\hi@supra@opt@xref{%
  \def\hi@supra@make@xref##1{%
    \hilabel{hi@supra@xref@##1}%
  }%
  \def\hi@notepos##1{%
    \space
    \@ifundefined{r@hi@supra@xref@##1}{%
      \textbf{??}%
    }{%
      \expand{\@unbrace\hi@supra@use@xref}{%
        \csname r@hi@supra@xref@##1\endcsname
      }{ii}%
    }%
  }%
}
\def\hi@supra@use@xref#1#2#3#4{#2#3#4}
```