compilers move loads/stores (1)

```
void WaitForReady() {
    do {} while (!ready);
}
```

```
WaitForOther:
  movl ready, %eax  // eax <- other_ready
.L2:
  testl %eax, %eax
  je .L2                    // while (eax == 0) repeat
  ...
```

compilers move loads/stores (1)

```
void WaitForReady() {
    do {} while (!ready);
}
```

```
WaitForOther:
  movl ready, %eax  // eax <- other_ready
.L2:
  testl %eax, %eax
  je .L2                      // while (eax == 0) repeat
  ...
```

compilers move loads/stores (2)

```
void WaitForOther() {
    is_waiting = 1;
    do {} while (!other_ready);
    is_waiting = 0;
}
```

```
WaitForOther:
  // compiler optimization: don't set is_waiting to 1,
  // (why? it will be set to 0 anyway)
  movl other_ready, %eax  // eax <- other_ready
.L2:
  testl %eax, %eax
  je .L2                      // while (eax == 0) repeat
  ...
  movl $0, is_waiting  // is_waiting <- 0
```

compilers move loads/stores (2)

```
void WaitForOther() {
    is_waiting = 1;
    do {} while (!other_ready);
    is_waiting = 0;
}
```

```
WaitForOther:
  // compiler optimization: don't set is_waiting to 1,
  // (why? it will be set to 0 anyway)
  movl other_ready, %eax  // eax <- other_ready
.L2:
  testl %eax, %eax
  je .L2                        // while (eax == 0) repeat
  ...
  movl $0, is_waiting  // is_waiting <- 0
```

compilers move loads/stores (2)

```
void WaitForOther() {
    is_waiting = 1;
    do {} while (!other_ready);
    is_waiting = 0;
}
```

```
WaitForOther:
  // compiler optimization: don't set is_waiting to 1,
  // (why? it will be set to 0 anyway)
  movl other_ready, %eax   // eax <- other_ready
.L2:
  testl %eax, %eax
  je .L2                        // while (eax == 0) repeat
  ...
  movl $0, is_waiting  // is_waiting <- 0
```

fixing compiler reordering?

isn't there a way to tell compiler not to do these optimizations?

yes, but that is still not enough!

processors sometimes do this kind of reordering too (between cores)

pthreads and reordering

many pthreads functions prevent reordering

- everything before function call actually happens before

includes preventing some optimizations

- e.g. keeping global variable in register for too long

pthread_create, pthread_join, other tools we'll talk about ...

- basically: if pthreads is waiting for/starting something, no weird ordering

implementation part 1: prevent compiler reordering

implementation part 2: use special instructions

- example: x86 `mfence` instruction

some definitions

mutual exclusion: ensuring only one thread does a particular thing at a time

- like checking for and, if needed, buying milk

some definitions

mutual exclusion: ensuring only one thread does a particular thing at a time

- like checking for and, if needed, buying milk

critical section: code that exactly one thread can execute at a time

- result of critical section

some definitions

mutual exclusion: ensuring only one thread does a particular thing at a time

- like checking for and, if needed, buying milk

critical section: code that exactly one thread can execute at a time

- result of critical section

lock: object only one thread can hold at a time

- interface for creating critical sections

lock analogy

agreement: only change account balances while wearing this hat

normally hat kept on table

put on hat when editing balance

hopefully, only one person (= thread) can wear hat a time

need to wait for them to remove hat to put it on

lock analogy

agreement: only change account balances while wearing this hat

normally hat kept on table

put on hat when editing balance

hopefully, only one person (= thread) can wear hat a time

need to wait for them to remove hat to put it on

“lock (or acquire) the lock” = get and put on hat

“unlock (or release) the lock” = put hat back on table

the lock primitive

locks: an object with (at least) two operations:

- *acquire* or *lock* — wait until lock is free, then "grab" it
- *release* or *unlock* — let others use lock, wakeup waiters

typical usage: everyone acquires lock before using shared resource

- forget to acquire lock? weird things happen

```
Lock(account_lock);
balance += ...;
Unlock(account_lock);
```

the lock primitive

locks: an object with (at least) two operations:

- *acquire* or *lock* — wait until lock is free, then "grab" it
- *release* or *unlock* — let others use lock, wakeup waiters

typical usage: everyone acquires lock before using shared resource

- forget to acquire lock? weird things happen

```
Lock(account_lock);
balance += ...;
Unlock(account_lock);
```

waiting for lock?

when waiting — ideally:

not using processor (at least if waiting a while)

OS can context switch to other programs

pthread mutex

```
#include <pthread.h>

pthread_mutex_t account_lock;
pthread_mutex_init(&account_lock, NULL);
    // or: pthread_mutex_t account_lock =
    //                PTHREAD_MUTEX_INITIALIZER;
...
pthread_mutex_lock(&account_lock);
balance += ...;
pthread_mutex_unlock(&account_lock);
```

exercise

```
pthread_mutex_t lock1 = PTHREAD_MUTEX_INITIALIZER;
pthread_mutex_t lock2 = PTHREAD_MUTEX_INITIALIZER;
string one = "init one", two = "init two";
void ThreadA() {
    pthread_mutex_lock(&lock1);
    one = "one in ThreadA";  // (A1)
    pthread_mutex_unlock(&lock1);
    pthread_mutex_lock(&lock2);
    two = "two in ThreadA";  // (A2)
    pthread_mutex_unlock(&lock2);
}
void ThreadB() {
    pthread_mutex_lock(&lock1);
    one = "one in ThreadB";  // (B1)
    pthread_mutex_lock(&lock2);
    two = "two in ThreadB";  // (B2)
    pthread_mutex_unlock(&lock2);
    pthread_mutex_unlock(&lock1);
}
```

possible values of one/two after A+B run?

exercise (alternate 1)

```
pthread_mutex_t lock1 = PTHREAD_MUTEX_INITIALIZER;
pthread_mutex_t lock2 = PTHREAD_MUTEX_INITIALIZER;
string one = "init one", two = "init two";
void ThreadA() {
    pthread_mutex_lock(&lock2);
    two = "two in ThreadA";   // (A2)
    pthread_mutex_unlock(&lock2);
    pthread_mutex_lock(&lock1);
    one = "one in ThreadA";   // (A1)
    pthread_mutex_unlock(&lock1);
}
void ThreadB() {
    pthread_mutex_lock(&lock1);
    one = "one in ThreadB";   // (B1)
    pthread_mutex_lock(&lock2);
    two = "two in ThreadB";   // (B2)
    pthread_mutex_unlock(&lock2);
    pthread_mutex_unlock(&lock1);
}
```

possible values of one/two after A+B run?

exercise (alternate 2)

```
pthread_mutex_t lock1 = PTHREAD_MUTEX_INITIALIZER;
pthread_mutex_t lock2 = PTHREAD_MUTEX_INITIALIZER;
string one = "init one", two = "init two";
void ThreadA() {
    pthread_mutex_lock(&lock2);
    two = "two in ThreadA";   // (A2)
    pthread_mutex_unlock(&lock2);
    pthread_mutex_lock(&lock1);
    one = "one in ThreadA";   // (A1)
    pthread_mutex_unlock(&lock1);
}
void ThreadB() {
    pthread_mutex_lock(&lock1);
    one = "one in ThreadB";   // (B1)
    pthread_mutex_unlock(&lock1);
    pthread_mutex_lock(&lock2);
    two = "two in ThreadB";   // (B2)
    pthread_mutex_unlock(&lock2);
}
```

possible values of one/two after A+B run?

preview: general sync

lots of coordinating threads beyond locks/barriers

will talk about two general tools later:

- monitors/condition variables
- semaphores

big added feature: wait for arbitrary thing to happen

a bad idea

one bad idea to wait for an event:

```
bool ready = false;
void WaitForReady() {
    do {} while (!ready);
}

void MarkReady() {
    ready = true;
}
```

wastes processor time

and also doesn't work!

beyond locks

in practice: want more than locks for synchronization

for waiting for arbtirary events (without CPU-hogging-loop):

- monitors
- semaphores

for common synchornization patterns:

- barriers
- reader-writer locks

higher-level interface:

- transactions

barriers

compute minimum of 100M element array with 2 processors

algorithm:

compute minimum of 50M of the elements on each CPU

- one thread for each CPU

wait for all computations to finish

take minimum of all the minimums

barriers

compute minimum of 100M element array with 2 processors

algorithm:

compute minimum of 50M of the elements on each CPU

- one thread for each CPU

wait for all computations to finish

take minimum of all the minimums

barriers API

barrier.Initialize(NumberOfThreads)

barrier.Wait() — return after all threads have waited

idea: multiple threads perform computations in parallel

threads wait for all other threads to call Wait()

barrier: waiting for finish

```
barrier.Initialize(2);
```

Thread 0

```
partial_mins[0] =
    /* min of first
       50M elems */;

barrier.Wait();


total_min = min(
    partial_mins[0],
    partial_mins[1]
);
```

Thread 1

```
partial_mins[1] =
    /* min of last
       50M elems */
barrier.Wait();
```

barriers: reuse

Thread 0

```
results[0][0] = getInitial(0);
barrier.Wait();

results[1][0] =
    computeFrom(
        results[0][0],
        results[0][1]
    );
barrier.Wait();

results[2][0] =
    computeFrom(
        results[1][0],
        results[1][1]
    );
```

Thread 1

```
results[0][1] = getInitial(1);
barrier.Wait();

results[1][1] =
    computeFrom(
        results[0][0],
        results[0][1]
    );
barrier.Wait();

results[2][1] =
    computeFrom(
        results[1][0],
        results[1][1]
    );
```

barriers: reuse

Thread 0

```
results[0][0] = getInitial(0);
barrier.Wait();

results[1][0] =
    computeFrom(
        results[0][0],
        results[0][1]
    );
barrier.Wait();

results[2][0] =
    computeFrom(
        results[1][0],
        results[1][1]
    );
```

Thread 1

```
results[0][1] = getInitial(1);
barrier.Wait();

results[1][1] =
    computeFrom(
        results[0][0],
        results[0][1]
    );
barrier.Wait();

results[2][1] =
    computeFrom(
        results[1][0],
        results[1][1]
    );
```

barriers: reuse

Thread 0

```
results[0][0] = getInitial(0);
barrier.Wait();

results[1][0] =
    computeFrom(
        results[0][0],
        results[0][1]
    );
barrier.Wait();

results[2][0] =
    computeFrom(
        results[1][0],
        results[1][1]
    );
```

Thread 1

```
results[0][1] = getInitial(1);
barrier.Wait();

results[1][1] =
    computeFrom(
        results[0][0],
        results[0][1]
    );
barrier.Wait();

results[2][1] =
    computeFrom(
        results[1][0],
        results[1][1]
    );
```

pthread barriers

```
pthread_barrier_t barrier;
pthread_barrier_init(
    &barrier,
    NULL /* attributes */,
    numberOfThreads
);
...
...
pthread_barrier_wait(&barrier);
```

exercise

```c
pthread_barrier_t barrier;
int x = 0, y = 0;
void thread_one() {
    y = 10;
    pthread_barrier_wait(&barrier);
    y = x + y;
    pthread_barrier_wait(&barrier);
    pthread_barrier_wait(&barrier);
    printf("%d %d\n", x, y);
}

void thread_two() {
    x = 20;
    pthread_barrier_wait(&barrier);
    pthread_barrier_wait(&barrier);
    x = x + y;
    pthread_barrier_wait(&barrier);
}
```

if both thread_one, thread_two run at once

deadlock

the one-way bridge



the one-way bridge



the one-way bridge



the one-way bridge



moving two files

```
struct Dir {
  mutex_t lock; HashMap entries;
};
void MoveFile(Dir *from_dir, Dir *to_dir, string filename) {
  mutex_lock(&from_dir->lock);
  mutex_lock(&to_dir->lock);

  Map_put(to_dir->entries, filename,
        Map_get(from_dir->entries, filename));
  Map_erase(from_dir->entries, filename);

  mutex_unlock(&to_dir->lock);
  mutex_unlock(&from_dir->lock);
}
```

Thread 1: `MoveFile(A, B, "foo")`

Thread 2: `MoveFile(B, A, "bar")`

moving two files: lucky timeline (1)

Thread 1 `MoveFile(A, B, "foo")`	**Thread 2** `MoveFile(B, A, "bar")`
`lock(&A->lock);`	
`lock(&B->lock);`	
(do move)	
`unlock(&B->lock);`	
`unlock(&A->lock);`	
	`lock(&B->lock);`
	`lock(&A->lock);`
	(do move)
	`unlock(&B->lock);`
	`unlock(&A->lock);`

moving two files: lucky timeline (2)

Thread 1 `MoveFile(A, B, "foo")`	Thread 2 `MoveFile(B, A, "bar")`
`lock(&A->lock);`	
`lock(&B->lock);`	
	`lock(&B->lock...`
(do move)	(waiting for B lock)
`unlock(&B->lock);`	
	`lock(&B->lock);`
	`lock(&A->lock...`
`unlock(&A->lock);`	
	`lock(&A->lock);`
	(do move)
	`unlock(&A->lock);`
	`unlock(&B->lock);`

moving two files: unlucky timeline

Thread 1	Thread 2
`MoveFile(A, B, "foo")`	`MoveFile(B, A, "bar")`
`lock(&A->lock);`	
	`lock(&B->lock);`

moving two files: unlucky timeline

Thread 1	Thread 2
`MoveFile(A, B, "foo")`	`MoveFile(B, A, "bar")`
`lock(&A->lock);`	
	`lock(&B->lock);`
`lock(&B->lock…` stalled	
(waiting for lock on B)	`lock(&A->lock…` stalled
(waiting for lock on B)	(waiting for lock on A)

moving two files: unlucky timeline

Thread 1	Thread 2
`MoveFile(A, B, "foo")`	`MoveFile(B, A, "bar")`
`lock(&A->lock);`	
	`lock(&B->lock);`
`lock(&B->lock…` stalled	
(waiting for lock on B)	`lock(&A->lock…` stalled
(waiting for lock on B)	(waiting for lock on A)
~~(do move)~~ unreachable	~~(do move)~~ unreachable
~~`unlock(&B->lock);`~~ unreachable	~~`unlock(&A->lock);`~~ unreachable
~~`unlock(&A->lock);`~~ unreachable	~~`unlock(&B->lock);`~~ unreachable

moving two files: unlucky timeline

Thread 1 `MoveFile(A, B, "foo")`	Thread 2 `MoveFile(B, A, "bar")`
`lock(&A->lock);`	
	`lock(&B->lock);`
`lock(&B->lock…` stalled	
(waiting for lock on B)	`lock(&A->lock…` stalled
(waiting for lock on B)	(waiting for lock on A)
~~(do move)~~ unreachable	~~(do move)~~ unreachable
~~`unlock(&B->lock);`~~ unreachable	~~`unlock(&A->lock);`~~ unreachable
~~`unlock(&A->lock);`~~ unreachable	~~`unlock(&B->lock);`~~ unreachable

Thread 1 holds A lock, waiting for Thread 2 to release B lock
Thread 2 holds B lock, waiting for Thread 1 to release A lock

moving two files: dependencies



moving three files: dependencies



moving three files: unlucky timeline

Thread 1	**Thread 2**	**Thread 3**
`MoveFile(A, B, "foo")`	`MoveFile(B, C, "bar")`	`MoveFile(C, A, "quux")`
`lock(&A->lock);`		
	`lock(&B->lock);`	
		`lock(&C->lock);`
`lock(&B->lock…` stalled		
	`lock(&C->lock…` stalled	
		`lock(&A->lock…` stalled

deadlock with free space

Thread 1	Thread 2
`AllocateOrWaitFor(1 MB)`	`AllocateOrWaitFor(1 MB)`
`AllocateOrWaitFor(1 MB)`	`AllocateOrWaitFor(1 MB)`
`(do calculation)`	`(do calculation)`
`Free(1 MB)`	`Free(1 MB)`
`Free(1 MB)`	`Free(1 MB)`

2 MB of space — deadlock possible with unlucky order

deadlock with free space (unlucky case)

Thread 1	Thread 2
`AllocateOrWaitFor(1 MB)`	
	`AllocateOrWaitFor(1 MB)`
`AllocateOrWaitFor(1 MB`... stalled	
	`AllocateOrWaitFor(1 MB`... stalled

free space: dependency graph



deadlock with free space (lucky case)

Thread 1	Thread 2
`AllocateOrWaitFor(1 MB)`	
`AllocateOrWaitFor(1 MB)`	
`(do calculation)`	
`Free(1 MB);`	
`Free(1 MB);`	
	`AllocateOrWaitFor(1 MB)`
	`AllocateOrWaitFor(1 MB)`
	`(do calculation)`
	`Free(1 MB);`
	`Free(1 MB);`

dining philosophers



five philosophers either think or eat

to eat:

grab chopstick on left, then

grba chopstick on right, then

then eat, then

return chopsticks

dining philosophers



everyone eats at the same time?
grab left chopstick, then...

dining philosophers



everyone eats at the same time?
grab left chopstick, then
try to grab right chopstick, ...
we're at an impasse

deadlock

deadlock — circular waiting for resources

resource = something needed by a thread to do work

- locks
- CPU time
- disk space
- memory
- ...

often non-deterministic in practice

most common example: when acquiring multiple locks

deadlock

deadlock — circular waiting for resources

resource = something needed by a thread to do work

- locks
- CPU time
- disk space
- memory
- ...

often non-deterministic in practice

most common example: when acquiring multiple locks

deadlock versus starvation

starvation: one+ unlucky (no progress), one+ lucky (yes progress)

example: low priority threads versus high-priority threads

deadlock: no one involved in deadlock makes progress

deadlock versus starvation

starvation: one+ unlucky (no progress), one+ lucky (yes progress)

- example: low priority threads versus high-priority threads

deadlock: no one involved in deadlock makes progress

starvation: once starvation happens, taking turns will resolve

- low priority thread just needed a chance...

deadlock: once it happens, taking turns won't fix

deadlock requirements

mutual exclusion

one thread at a time can use a resource

hold and wait

thread holding a resources waits to acquire *another* resource

no preemption of resources

resources are only released voluntarily

thread trying to acquire resources can't 'steal'

circular wait

there exists a set $\{T_1, \ldots, T_n\}$ of waiting threads such that

T_1 is waiting for a resource held by T_2

T_2 is waiting for a resource held by T_3

...

T_n is waiting for a resource held by T_1

how is deadlock possible?

Given list: A, B, C, D, E

```
RemoveNode(LinkedListNode *node) {
    pthread_mutex_lock(&node->lock);
    pthread_mutex_lock(&node->prev->lock);
    pthread_mutex_lock(&node->next->lock);
    node->next->prev = node->prev; node->prev->next = node->next;
    pthread_mutex_unlock(&node->next->lock); pthread_mutex_unlock(&node->p
    pthread_mutex_unlock(&node->lock);
}
```

Which of these (all run in parallel) can deadlock?

A. RemoveNode(B) and RemoveNode(C)
B. RemoveNode(B) and RemoveNode(D)
C. RemoveNode(B) and RemoveNode(C) and RemoveNode(D)
D. A and C
E. B and C
F. all of the above
G. none of the above

deadlock prevention techniques

infinite resources or at least enough that never run out	no *mutual exclusion*
no shared resources	no *mutual exclusion*
no waiting “busy signal” — abort and (maybe) retry revoke/preempt resources	no *hold and wait*/ *preemption*
acquire resources in **consistent order**	no *circular wait*
request **all resources at once**	no *hold and wait*

deadlock prevention techniques

infinite resources or at least enough that never run out	no *mutual exclusion*
no shared resources	no *mutual exclusion*
no waiting “busy signal” — abort and (maybe) retry revoke/preempt resources	no *hold and wait*/ *preemption*
acquire resources in **consistent order**	no *circular wait*
request **all resources at once**	no *hold and wait*

deadlock prevention techniques

infinite resources or at least enough that never run out	no *mutual exclusion*
no shared resources	no *mutual exclusion*
no waiting "busy signal" — abort and (maybe) retry revoke/preempt resources	no *hold and wait*/ *preemption*
acquire resources in **consistent order**	no *circular wait*
request **all resources at once**	no *hold and wait*

deadlock prevention techniques

infinite resources — no *mutual exclusion*

or at least enough that never run out

memory allocation: malloc() fails rather than waiting (no deadlock)
locks: `pthread_mutex_trylock` fails rather than waiting
...

r … *exclusion*

no waiting — no *hold and wait*/ *preemption*

“busy signal” — abort and (maybe) retry

revoke/preempt resources

acquire resources in **consistent order** — no *circular wait*

request **all resources at once** — no *hold and wait*

stealing locks???

how do we make stealing locks possible

unclean: just kill the thread

- problem: inconsistent state?

clean: have code to undo partial oepration

- some databases do this

won't go into detail in this class

revokable locks?

```
try {
    AcquireLock();
    use shared data
} catch (LockRevokedException le) {
    undo operation hopefully?
} finally {
    ReleaseLock();
}
```

deadlock prevention techniques

infinite resources or at least enough that never run out	no *mutual exclusion*
no shared resources	no *mutual exclusion*
no waiting "busy signal" — abort and (maybe) retry revoke/preempt resources	no *hold and wait*/ *preemption*
acquire resources in **consistent order**	no *circular wait*
request **all resources at once**	no *hold and wait*

abort and retry limits?

abort-and-retry

pthread's mutexes:

```
pthread_mutex_trylock
pthread_mutex_timedlock
```

how many times will you retry?

moving two files: abort-and-retry

```
struct Dir { mutex_t lock; HashMap entries; };
void MoveFile(Dir *from_dir, Dir *to_dir, string filename) {
  while (true) {
    mutex_lock(&from_dir->lock);
    if (mutex_trylock(&to_dir->lock) == LOCKED) break;
    mutex_unlock(&from_dir->lock);
  }

  Map_put(to_dir->entries, filename, Map_get(from_dir->entries, fil
  from_dir->entries.erase(filename);

  mutex_unlock(&to_dir->lock);
  mutex_unlock(&from_dir->lock);
}
```

Thread 1: `MoveFile(A, B, "foo")`; Thread 2: `MoveFile(B, A, "bar")`

moving two files: lots of bad luck?

Thread 1 `MoveFile(A, B, "foo")`	Thread 2 `MoveFile(B, A, "bar")`
`lock(&A->lock)` → `LOCKED`	
	`lock(&B->lock)` → `LOCKED`
`trylock(&B->lock)` → `FAILED`	
	`trylock(&A->lock)` → `FAILED`
`unlock(&A->lock)`	
	`unlock(&B->lock)`
`lock(&A->lock)` → `LOCKED`	
	`lock(&B->lock)` → `LOCKED`
`trylock(&B->lock)` → `FAILED`	
	`trylock(&A->lock)` → `FAILED`
`unlock(&A->lock)`	
	`unlock(&B->lock)`

livelock

livelock: keep aborting and retrying without end

like deadlock — no one's making progress

potentially forever

unlike deadlock — threads are not waiting

preventing livelock

make schedule random — e.g. random waiting after abort

make threads run one-at-a-time if lots of aborting

other ideas?

deadlock prevention techniques

infinite resources — no *mutual exclusion*

or at least enough that never run out

no shared resources — no *mutual exclusion*

requires some way to undo partial changes to avoid errors

common approach for databases

…

no waiti

"busy signal" — abort and (maybe) retry

revoke/preempt resources

no *hold and wait/ preemption*

acquire resources in **consistent order** — no *circular wait*

request **all resources at once** — no *hold and wait*

deadlock prevention techniques

infinite resources or at least enough that never run out	no *mutual exclusion*
no shared resources	no *mutual exclusion*
no waiting "busy signal" — abort and (maybe) retry revoke/preempt resources	no *hold and wait*/ *preemption*
acquire resources in **consistent order**	no *circular wait*
request **all resources at once**	no *hold and wait*

acquiring locks in consistent order (1)

```
MoveFile(Dir* from_dir, Dir* to_dir, string filename) {
  if (from_dir->path < to_dir->path) {
    lock(&from_dir->lock);
    lock(&to_dir->lock);
  } else {
    lock(&to_dir->lock);
    lock(&from_dir->lock);
  }
  ...
}
```

acquiring locks in consistent order (1)

```
MoveFile(Dir* from_dir, Dir* to_dir, string filename) {
  if (from_dir->path < to_dir->path) {
    lock(&from_dir->lock);
    lock(&to_dir->lock);
  } else {
    lock(&to_dir->lock);
    lock(&from_dir->lock);
  }
  ...
}
```

any ordering will do
e.g. compare pointers

acquiring locks in consistent order (2)

often by convention, e.g. Linux kernel comments:

```
/*
 * ...
 * Lock order:
 *      contex.ldt_usr_sem
 *        mmap_sem
 *          context.lock
 */
```

```
/*
 * ...
 * Lock order:
 *   1. slab_mutex (Global Mutex)
 *   2. node->list_lock
 *   3. slab_lock(page) (Only on some arches and for debugging)
 * ...
 */
```

deadlock prevention techniques

infinite resources or at least enough that never run out	no *mutual exclusion*
no shared resources	no *mutual exclusion*
no waiting "busy signal" — abort and (maybe) retry revoke/preempt resources	no *hold and wait*/ *preemption*
acquire resources in **consistent order**	no *circular wait*
request **all resources at once**	no *hold and wait*

beyond locks

in practice: want more than locks for synchronization

for waiting for arbtirary events (without CPU-hogging-loop):

- monitors
- semaphores

for common synchornization patterns:

- barriers
- reader-writer locks

higher-level interface:

- transactions

backup slides

POSIX mutex restrictions

pthread_mutex rule: unlock from same thread you lock in

does this actually matter?

depends on how pthread_mutex is implemented

generalizing locks: semaphores

semaphore has a non-negative integer **value** and two operations:

P() or **down** or **wait**:
wait for semaphore to become positive (> 0),
then decerement by 1

V() or **up** or **signal** or **post**:
increment semaphore by 1 (waking up thread if needed)

P, V from Dutch: *proberen* (test), *verhogen* (increment)

semaphores are kinda integers

semaphore like an integer, but...

cannot read/write directly

- down/up operaion only way to access (typically)
- exception: initialization

never negative — wait instead

- down operation wants to make negative? thread waits

reserving books

suppose tracking copies of library book...

```
Semaphore free_copies = Semaphore(3);
void ReserveBook() {
    // wait for copy to be free
    free_copies.down();
    ... // ... then take reserved copy
}

void ReturnBook() {
    ... // return reserved copy
    free_copies.up();
    // ... then wakeup waiting thread
}
```

counting resources: reserving books

suppose tracking copies of same library book

non-negative integer count = # how many books used?

up = give back book; down = take book

Copy 1
Copy 2
Copy 3

free copies $\boxed{3}$

counting resources: reserving books

suppose tracking copies of same library book

non-negative integer count = # how many books used?

up = give back book; down = take book

taken out ~~Copy 1~~

Copy 2

Copy 3

free copies $\cancel{\boxed{3}}$ $\boxed{2}$

after calling down to reserve

counting resources: reserving books

suppose tracking copies of same library book
non-negative integer count = # how many books used?
up = give back book; down = take book

taken out



free copies $\boxed{2}$

after calling down to reserve

counting resources: reserving books

suppose tracking copies of same library book
non-negative integer count = # how many books used?
up = give back book; down = take book



free copies $\boxed{0}$

after calling down three times
to reserve all copies

counting resources: reserving books

suppose tracking copies of same library book

non-negative integer count = # how many books used?

up = give back book; down = take book



<u>reserve book</u>

call *down* again

start waiting...

counting resources: reserving books

suppose tracking copies of same library book

non-negative integer count = # how many books used?

up = give back book; down = take book





return book

call *up*

release waiter

reserve book

call *down*

~~waiting~~

done waiting

implementing mutexes with semaphores

```
struct Mutex {
    Semaphore s; /* with inital value 1 */
    /* value = 1 --> mutex if free */
    /* value = 0 --> mutex is busy */
}

MutexLock(Mutex *m) {
    m->s.down();
}

MutexUnlock(Mutex *m) {
    m->s.up();
}
```

implementing join with semaphores

```
struct Thread {
    ...
    Semaphore finish_semaphore; /* with initial value 0 */
    /* value = 0: either thread not finished OR already joined */
    /* value = 1: thread finished AND not joined */
};
thread_join(Thread *t) {
    t->finish_semaphore.down();
}

/* assume called when thread finishes */
thread_exit(Thread *t) {
    t->finish_semaphore.up();
    /* tricky part: deallocating struct Thread safely? */
}
```

POSIX semaphores

```
#include <semaphore.h>
...
sem_t my_semaphore;
int process_shared = /* 1 if sharing between processes */;
sem_init(&my_semaphore, process_shared, initial_value);
...
sem_wait(&my_semaphore);  /* down */
sem_post(&my_semaphore);  /* up */
...
sem_destroy(&my_semaphore);
```

semaphore exercise

```
int value;  sem_t empty, ready;  // with some initial values

void PutValue(int argument) {
    sem_wait(&empty);
    value = argument;
    sem_post(&ready);
}

int GetValue() {
    int result;
    _________________
    result = value;
    _________________
    return result;
}
```

What goes in the blanks?

A: `sem_post(&empty)` / `sem_wait(&ready)`

B: `sem_wait(&ready)` / `sem_post(&empty)`

C: `sem_post(&ready)` / `sem_wait(&empty)`

D: `sem_post(&ready)` / `sem_post(&empty)`

E: `sem_wait(&empty)` / `sem_post(&ready)`

F: something else

GetValue() waits for PutValue() to happen, retrieves value, then allows next PutValue().

PutValue() waits for prior GetValue(), places value, then allows next GetValue().

semaphore intuition

What do you need to wait for?

- critical section to be finished
- queue to be non-empty
- array to have space for new items

what can you count that will be 0 when you need to wait?

- # of threads that can start critical section now
- # of threads that can join another thread without waiting
- # of items in queue
- # of empty spaces in array

use up/down operations to maintain count

producer/consumer constraints

consumer waits for producer(s) if buffer is empty

producer waits for consumer(s) if buffer is full

any thread waits while a thread is manipulating the buffer

producer/consumer constraints

consumer waits for producer(s) if buffer is empty

producer waits for consumer(s) if buffer is full

any thread waits while a thread is manipulating the buffer

one semaphore per constraint:

```
sem_t full_slots;   // consumer waits if empty
sem_t empty_slots;  // producer waits if full
sem_t mutex;        // either waits if anyone changing buffer
FixedSizedQueue buffer;
```

producer/consumer pseudocode

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 /* # thread that can use buffer at once */);
buffer.set_size(BUFFER_CAPACITY);
...
Produce(item) {
    sem_wait(&empty_slots);  // wait until free slot, reserve it
    sem_wait(&mutex);
    buffer.enqueue(item);
    sem_post(&mutex);
    sem_post(&full_slots);  // tell consumers there is more data
}

Consume() {
    sem_wait(&full_slots);  // wait until queued item, reserve it
    sem_wait(&mutex);
    item = buffer.dequeue();
    sem_post(&mutex);
    sem_post(&empty_slots);  // let producer reuse item slot
    return item;
}
```

producer/consumer pseudocode

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 /* # thread that can use buffer at once */);
buffer.set_size(BUFFER_CAPACITY);
...
Produce(item) {
    sem_wait(&empty_slots);  // wait until free slot, reserve it
    sem_wait(&mutex);
    buffer.enqueue(item);
    sem_post(&mutex);
    sem_post(&full_slots);  // tell consumers there is more data
}

Consume() {
    sem_wait(&full_slots);  // wait until queued item, reserve it
    sem_wait(&mutex);
    item = buffer.dequeue();
    sem_post(&mutex);
    sem_post(&empty_slots);  // let producer reuse item slot
    return item;
}
```

producer/consumer pseudocode

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 /* # thread that can use buffer at once */);
buffer.set_size(BUFFER_CAPACITY);
...
Produce(item) {
    sem_wait(&empty_slots);  // wait until free slot, reserve it
    sem_wait(&mutex);
    buffer.enqueue(item);
    sem_post(&mutex);
    sem_post(&full_slots);  // tell consumers there is more data
}

Consume() {
    sem_wait(&full_slots);  // wait until queued item, reserve it
    sem_wait(&mutex);
    item = buffer.dequeue();
    sem_post(&mutex);
    sem_post(&empty_slots);  // let producer reuse item slot
    return item;
}
```

producer/consumer pseudocode

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 /* # thread that can use buffer at once */);
buffer.set_size(BUFFER_CAPACITY);
...
Produce(item) {
    sem_wait(&empty_slots);  // wait until free slot, reserve it
    sem_wait(&mutex);
    buffer.enqueue(item);
    sem_post(&mutex);
    sem_post(&full_slots);                                      data
}

Consume() {
    sem_wait(&full_slots);  // wait until queued item, reserve it
    sem_wait(&mutex);
    item = buffer.dequeue();
    sem_post(&mutex);
    sem_post(&empty_slots);  // let producer reuse item slot
    return item;
}
```

Can we do

```
sem_wait(&mutex);
sem_wait(&empty_slots);
```

instead?

producer/consumer pseudocode

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 /* # thread that can use buffer at once */);
buffer.set_size(BUFFER_CAPACITY);
...
Produce(item) {
    sem_wait(&empty_slots);  // wait until free slot, reserve it
    sem_wait(&mutex);
    buffer.enqueue(item);
    sem_post(&mutex);
    sem_post(&full_slots);                                    data
}

Consume() {
    sem_wait(&full_slots);
    sem_wait(&mutex);
    item = buffer.dequeue()
    sem_post(&mutex);
    sem_post(&empty_slots);
    return item;
}
```

Can we do

```
sem_wait(&mutex);
sem_wait(&empty_slots);
```

instead?

No. Consumer waits on `sem_wait(&mutex)` so can't `sem_post(&empty_slots)` (result: producer waits forever problem called *deadlock*)

producer/consumer: cannot reorder mutex/empty

```
ProducerReordered() {
  // BROKEN: WRONG ORDER
  sem_wait(&mutex);
  sem_wait(&empty_slots);

  ...

  sem_post(&mutex);
```

```
Consumer() {
  sem_wait(&full_slots);

  // can't finish until
  // Producer's sem_post(&mutex):
  sem_wait(&mutex);

  ...

  // so this is not reached
  sem_post(&full_slots);
```

producer/consumer pseudocode

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 /* # thread that can use buffer at once */);
buffer.set_size(BUFFER_CAPACITY);
...
Produce(item) {
    sem_wait(&empty_slots);  // wait until free slot, reserve it
    sem_wait(&mutex);
    buffer.enqueue(item);
    sem_post(&mutex);
    sem_post(&full_slots                                  more data
}

Consume() {
    sem_wait(&full_slots                                  reserve it
    sem_wait(&mutex);
    item = buffer.dequeu
    sem_post(&mutex);
    sem_post(&empty_slots);  // let producer reuse item slot
    return item;
}
```

Can we do

```
sem_post(&full_slots);
sem_post(&mutex);
```

instead?

Yes — post never waits

producer/consumer summary

producer: wait (down) empty_slots, post (up) full_slots

consumer: wait (down) full_slots, post (up) empty_slots

two producers or consumers?

- still works!

atomic read-modfiy-write

really hard to build locks for atomic load store

and normal load/stores aren't even atomic...

...so processors provide read/modify/write operations

one instruction that
atomically
reads *and* modifies *and* writes back a value

used by OS to implement higher-level synchronization tools

x86 atomic exchange

`lock xchg (%ecx), %eax`

atomic exchange

`temp` $\leftarrow$ `M[ECX]`

`M[ECX]` $\leftarrow$ `EAX`

`EAX` $\leftarrow$ `temp`

…without being interrupted by other processors, etc.

implementing atomic exchange

make sure other processors don't have cache block

- probably need to be able to do this to keep caches in sync

do read+modify+write operation

higher level tools

usually we won't use atomic operations directly

instead rely on OS/standard libraries using them

(along with context switching, disabling interrupts, ...)

OS/standard libraries will provide higher-level tools like...

pthread_join

locks (pthread_mutex)

...and more

backup slides

backup slides

using atomic exchange?

example: OS wants something done by whichever core tries first

does not want it started twice!

if two cores try at once, only one should do it

```
int global_flag = 0;
void DoThingIfFirstToTry() {
    int my_value = 1;
    AtomicExchange(&my_value, &global_flag);
    if (my_value == 0) {
        /* flag was zero before, so I was first!*/
        DoThing();
    } else {
        /* flag was already 1 when we exchanged */
        /* I was second, so some other core is handling it */
    }
}
```

recall: pthread mutex

```
#include <pthread.h>

pthread_mutex_t some_lock;
pthread_mutex_init(&some_lock, NULL);
// or: pthread_mutex_t some_lock = PTHREAD_MUTEX_INITIALIZER;
...
pthread_mutex_lock(&some_lock);
...
pthread_mutex_unlock(&some_lock);
pthread_mutex_destroy(&some_lock);
```

life homework even/odd

naive way has an operation that needs locking:

```
for (int time = 0; time < MAX_ITERATIONS; ++time) {
    ... compute to_grid ...
    swap(from_grid, to_grid);
}
```

but this alternative needs less locking:

```
Grid grids[2];
for (int time = 0; time < MAX_ITERATIONS; ++time) {
    from_grid = &grids[time % 2];
    to_grid = &grids[(time % 2) + 1];
    ... compute to_grid ...
}
```

life homework even/odd

naive way has an operation that needs locking:

```
for (int time = 0; time < MAX_ITERATIONS; ++time) {
    ... compute to_grid ...
    swap(from_grid, to_grid);
}
```

but this alternative needs less locking:

```
Grid grids[2];
for (int time = 0; time < MAX_ITERATIONS; ++time) {
    from_grid = &grids[time % 2];
    to_grid = &grids[(time % 2) + 1];
    ... compute to_grid ...
}
```


swap

x86-64 spinlock with xchg

lock variable in shared memory: `the_lock`

if 1: someone has the lock; if 0: lock is free to take

```
acquire:
    movl $1, %eax                 // %eax <- 1
    lock xchg %eax, the_lock      // swap %eax and the_lock
                                        // sets the_lock to 1 (taken)
                                        // sets %eax to prior val. of t
    test %eax, %eax               // if the_lock wasn't 0 before:
    jne acquire                   //   try again
    ret

release:
    mfence                        // for memory order reasons
    movl $0, the_lock             // then, set the_lock to 0 (not taken
    ret
```

x86-64 spinlock with xchg

lock variable in shared memory: `the_lock`

if 1: someone has the lock; if 0: lock is free to take

```
acquire:
    movl $1, %eax               // %eax <- 1
    lock xchg %eax, the_lock    // swap %eax and the_lock
                                        // sets the_lock to 1 (taken)
                                        // sets %eax to prior val. of t
    test %eax, %eax             // if
    jne acquire                 //
    ret

release:
    mfence                      // for memory order reasons
    movl $0, the_lock           // then, set the_lock to 0 (not taken
    ret
```

set lock variable to 1 (taken)

read old value

x86-64 spinlock with xchg

lock variable in shared memory: `the_lock`

if 1: someone has the lock; if 0: lock is free to take

```
acquire:
    movl $1, %eax                 // %eax <- 1
    lock xchg %eax, the_lock      // swap %eax and the_lock
                                        // sets the_lock to 1 (taken)
                                        // sets %eax to prior val. of t
    test %eax, %eax
    jne acquire
    ret

release:
    mfence                        // for memory order reasons
    movl $0, the_lock             // then, set the_lock to 0 (not taken
    ret
```

if lock was already locked retry
“spin” until lock is released elsewhere

x86-64 spinlock with xchg

lock variable in shared memory: `the_lock`

if 1: someone has the lock; if 0: lock is free to take

```
acquire:
    movl $1, %eax               // %eax <- 1
    lock xchg %eax, the_lock    // swap %eax and the_lock
                                      // sets the_lock to 1 (taken)
                                      // sets %eax to prior val. of t
    test %eax, %eax
    jne acquire
    ret

release:
    mfence                      // for memory order reasons
    movl $0, the_lock           // then, set the_lock to 0 (not taken
    ret
```

release lock by setting it to 0 (not taken)
allows looping acquire to finish

x86-64 spinlock with xchg

lock variable in shared memory: `the_lock`

if 1: someone has the lock; if 0: lock is free to take

```
acquire:
    movl $1, %eax                 // %eax <- 1
    lock xchg %eax, the_lock      // swap %eax and the_lock
                                     // sets the_lock to 1 (taken)
                                                              of t
    test %eax, %eax
    jne acquire
    ret

release:
    mfence                        // for memory order reasons
    movl $0, the_lock             // then, set the_lock to 0 (not taken
    ret
```

Intel's manual says:
no reordering of loads/stores across a `lock`
or `mfence` instruction

exercise: spin wait

consider implementing 'waiting' functionality of pthread_join

thread calls ThreadFinish() when done

complete code below:

```
finished: .quad 0
ThreadFinish:
    ________________________
    ret
ThreadWaitForFinish:
    ________________________
    lock xchg %eax, finished
    cmp $0, %eax
    ____ ThreadWaitForFinish
    ret
```

A. `mfence; mov $1, finished`
B. `mov $1, finished; mfence`
C. `mov $0, %eax`
D. `mov $1, %eax`
E. je
F. jne

spinlock problems

lock abstraction is not powerful enough

- lock/unlock operations don't handle "wait for event"
- common thing we want to do with threads
- solution: other synchronization abstractions

spinlocks waste CPU time more than needed

- want to run another thread instead of infinite loop
- solution: lock implementation integrated with scheduler

spinlocks can send a lot of messages on the shared bus

- more efficient atomic operations to implement locks

spinlock problems

lock abstraction is not powerful enough

- lock/unlock operations don't handle "wait for event"
- common thing we want to do with threads
- solution: other synchronization abstractions

spinlocks waste CPU time more than needed

- want to run another thread instead of infinite loop
- solution: lock implementation integrated with scheduler

spinlocks can send a lot of messages on the shared bus

- more efficient atomic operations to implement locks

mutexes: intelligent waiting

want: locks that wait better

- example: POSIX mutexes

instead of running infinite loop, give away CPU

lock = go to sleep, add self to list

- sleep = scheduler runs something else

unlock = wake up sleeping thread

mutexes: intelligent waiting

want: locks that wait better

- example: POSIX mutexes

instead of running infinite loop, give away CPU

lock = go to sleep, add self to list

- sleep = scheduler runs something else

unlock = wake up sleeping thread

better lock implementation idea

shared list of waiters

spinlock protects list of waiters from concurrent modification

lock = use spinlock to add self to list, then wait without spinlock

unlock = use spinlock to remove item from list

better lock implementation idea

shared list of waiters

spinlock protects list of waiters from concurrent modification

lock = use spinlock to add self to list, then wait without spinlock

unlock = use spinlock to remove item from list

one possible implementation

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

one possible implementation

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

spinlock protecting `lock_taken` and `wait_queue`
only held for very short amount of time (compared to mutex itself)

one possible implementation

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

tracks whether any thread has locked and not unlocked

one possible implementation

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

list of threads that discovered lock is taken
and are waiting for it be free
these threads are not runnable

one possible implementation

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

```
LockMutex(Mutex *m) {
  LockSpinlock(&m->guard_spinlock);
  if (m->lock_taken) {
    put current thread on m->wait_queue
    mark current thread as waiting
    /* xv6: myproc()->state = SLEEPING; */
    UnlockSpinlock(&m->guard_spinlock);
    run scheduler (context switch)
  } else {
    m->lock_taken = true;
    UnlockSpinlock(&m->guard_spinlock);
  }
}
```

```
UnlockMutex(Mutex *m) {
  LockSpinlock(&m->guard_spinlock);
  if (m->wait_queue not empty) {
    remove a thread from m->wait_queue
    mark thread as no longer waiting
    /* xv6: myproc()->state = RUNNABLE; */
  } else {
     m->lock_taken = false;
  }
  UnlockSpinlock(&m->guard_spinlock);
}
```

one possible implementation

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

instead of setting lock_taken to false
choose thread to hand-off lock to

```
LockMutex(Mutex *m) {
  LockSpinlock(&m->guard_spinlock);
  if (m->lock_taken) {
    put current thread on m->wait_queue
    mark current thread as waiting
    /* xv6: myproc()->state = SLEEPING; */
    UnlockSpinlock(&m->guard_spinlock);
    run scheduler (context switch)
  } else {
    m->lock_taken = true;
    UnlockSpinlock(&m->guard_spinlock);
  }
}
```

```
UnlockMutex(Mutex *m) {
  LockSpinlock(&m->guard_spinlock);
  if (m->wait_queue not empty) {
    remove a thread from m->wait_queue
    mark thread as no longer waiting
    /* xv6: myproc()->state = RUNNABLE; */
  } else {
     m->lock_taken = false;
  }
  UnlockSpinlock(&m->guard_spinlock);
}
```

one possible implementation

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

subtly: if UnlockMutex runs here on another core
need to make sure scheduler on the other core doesn't switch to thread
while it is still running (would 'clone' thread/mess up registers)

```
LockMutex(Mutex *m) {
  LockSpinlock(&m->guard_spinlock);
  if (m->lock_taken) {
    put current thread on m->wait_queue
    mark current thread as waiting
    /* xv6: myproc()->state = SLEEPING; */
    UnlockSpinlock(&m->guard_spinlock);
    run scheduler (context switch)
  } else {
    m->lock_taken = true;
    UnlockSpinlock(&m->guard_spinlock);
  }
}
```

```
UnlockMutex(Mutex *m) {
  LockSpinlock(&m->guard_spinlock);
  if (m->wait_queue not empty) {
    remove a thread from m->wait_queue
    mark thread as no longer waiting
    /* xv6: myproc()->state = RUNNABLE; */
  } else {
     m->lock_taken = false;
  }
  UnlockSpinlock(&m->guard_spinlock);
}
```

one possible implementation

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

```
LockMutex(Mutex *m) {
  LockSpinlock(&m->guard_spinlock);
  if (m->lock_taken) {
    put current thread on m->wait_queue
    mark current thread as waiting
    /* xv6: myproc()->state = SLEEPING; */
    UnlockSpinlock(&m->guard_spinlock);
    run scheduler (context switch)
  } else {
    m->lock_taken = true;
    UnlockSpinlock(&m->guard_spinlock);
  }
}
```

```
UnlockMutex(Mutex *m) {
  LockSpinlock(&m->guard_spinlock);
  if (m->wait_queue not empty) {
    remove a thread from m->wait_queue
    mark thread as no longer waiting
    /* xv6: myproc()->state = RUNNABLE; */
  } else {
    m->lock_taken = false;
  }
  UnlockSpinlock(&m->guard_spinlock);
}
```

mutex and scheduler subtly

core 0 (thread A)	core 1 (thread B)	
start LockMutex		
acquire spinlock		
discover lock taken		
enqueue thread A		
thread A set not runnable		
release spinlock	start UnlockMutex	
	thread A set runnable	
	finish UnlockMutex	
	run scheduler	
	scheduler switches to A	
	…with old verison of registers	
thread A runs scheduler		…
…finally saving registers		…

Linux soln.: track 'thread running' separately from 'thread runnable'

xv6 soln.: hold scheduler lock until thread A saves registers

mutex and scheduler subtly

core 0 (thread A)	core 1 (thread B)	
start LockMutex		
acquire spinlock		
discover lock taken		
enqueue thread A		
thread A set not runnable		
release spinlock	start UnlockMutex	
	thread A set runnable	
	finish UnlockMutex	
	run scheduler	
	scheduler switches to A	
	…with old verison of registers	
thread A runs scheduler		…
…finally saving registers		…

Linux soln.: track 'thread running' separately from 'thread runnable'

xv6 soln.: hold scheduler lock until thread A saves registers

mutex efficiency

'normal' mutex **uncontended** case:

lock: acquire + release spinlock, see lock is free

unlock: acquire + release spinlock, see queue is empty

not much slower than spinlock

implementing locks: single core

intuition: context switch only happens on interrupt

- timer expiration, I/O, etc. causes OS to run

solution: disable them

- reenable on unlock

implementing locks: single core

intuition: context switch only happens on interrupt

- timer expiration, I/O, etc. causes OS to run

solution: disable them

- reenable on unlock

x86 instructions:

- `cli` — disable interrupts
- `sti` — enable interrupts

naive interrupt enable/disable (1)

```
Lock() {
    disable interrupts
}
```

```
Unlock() {
    enable interrupts
}
```

naive interrupt enable/disable (1)

```
Lock() {
    disable interrupts
}
```

```
Unlock() {
    enable interrupts
}
```

problem: user can hang the system:

```
Lock(some_lock);
while (true) {}
```

naive interrupt enable/disable (1)

```
Lock() {
    disable interrupts
}
```

```
Unlock() {
    enable interrupts
}
```

problem: user can hang the system:

```
Lock(some_lock);
while (true) {}
```

problem: can't do I/O within lock

```
Lock(some_lock);
read from disk
    /* waits forever for (disabled) interrupt
       from disk IO finishing */
```

naive interrupt enable/disable (2)

```
Lock() {
    disable interrupts
}
```

```
Unlock() {
    enable interrupts
}
```

naive interrupt enable/disable (2)

```
Lock() {
    disable interrupts
}
```

```
Unlock() {
    enable interrupts
}
```

naive interrupt enable/disable (2)

```
Lock() {
    disable interrupts
}
```

```
Unlock() {
    enable interrupts
}
```

naive interrupt enable/disable (2)

```
Lock() {
    disable interrupts
}
```

```
Unlock() {
    enable interrupts
}
```

problem: nested locks

```
Lock(milk_lock);
if (no milk) {
    Lock(store_lock);
    buy milk
    Unlock(store_lock);
    /* interrupts enabled here?? */
}
Unlock(milk_lock);
```

C++ containers and locking

can you use a vector from multiple threads?

…question: how is it implemented?

C++ containers and locking

can you use a vector from multiple threads?

…question: how is it implemented?

- dynamically allocated array
- reallocated on size changes

C++ containers and locking

can you use a vector from multiple threads?

...question: how is it implemented?

- dynamically allocated array
- reallocated on size changes

can access from multiple threads ...as long as not append/erase/etc.?

assuming it's implemented like we expect...

- but can we really depend on that?
- e.g. could shrink internal array after a while with no expansion save memory?

C++ standard rules for containers

multiple threads can read anything at the same time

can only read element if no other thread is modifying it

can safely add/remove elements if no other threads are accessing container

(sometimes can safely add/remove in extra cases)

exception: vectors of bools — can't safely read and write at same time

might be implemented by putting multiple bools in one int

a simple race

```
thread_A:                              thread_B:
    movl $1, x   /* x <- 1 */              movl $1, y   /* y <- 1 */
    movl y, %eax /* return y */            movl x, %eax /* return x */
    ret                                    ret
```

```
x = y = 0;
pthread_create(&A, NULL, thread_A, NULL);
pthread_create(&B, NULL, thread_B, NULL);
pthread_join(A, &A_result); pthread_join(B, &B_result);
printf("A:%d B:%d\n", (int) A_result, (int) B_result);
```

a simple race

```
thread_A:
    movl $1, x   /* x <- 1 */
    movl y, %eax /* return y */
    ret
```

```
thread_B:
    movl $1, y   /* y <- 1 */
    movl x, %eax /* return x */
    ret
```

```
x = y = 0;
pthread_create(&A, NULL, thread_A, NULL);
pthread_create(&B, NULL, thread_B, NULL);
pthread_join(A, &A_result); pthread_join(B, &B_result);
printf("A:%d B:%d\n", (int) A_result, (int) B_result);
```

if loads/stores atomic, then possible results:

A:1 B:1 — both moves into x and y, then both moves into eax execute

A:0 B:1 — thread A executes before thread B

A:1 B:0 — thread B executes before thread A

a simple race: results

```
thread_A:
    movl $1, x   /* x <- 1 */
    movl y, %eax /* return y */
    ret
```

```
thread_B:
    movl $1, y   /* y <- 1 */
    movl x, %eax /* return x */
    ret
```

```
x = y = 0;
pthread_create(&A, NULL, thread_A, NULL);
pthread_create(&B, NULL, thread_B, NULL);
pthread_join(A, &A_result); pthread_join(B, &B_result);
printf("A:%d B:%d\n", (int) A_result, (int) B_result);
```

my desktop, 100M trials:

frequency	result	
99 823 739	A:0 B:1	(‘A executes before B’)
171 161	A:1 B:0	(‘B executes before A’)
4 706	A:1 B:1	(‘execute moves into x+y first’)
394	A:0 B:0	???

a simple race: results

```
thread_A:
    movl $1, x   /* x <- 1 */
    movl y, %eax /* return y */
    ret
```

```
thread_B:
    movl $1, y   /* y <- 1 */
    movl x, %eax /* return x */
    ret
```

```
x = y = 0;
pthread_create(&A, NULL, thread_A, NULL);
pthread_create(&B, NULL, thread_B, NULL);
pthread_join(A, &A_result); pthread_join(B, &B_result);
printf("A:%d B:%d\n", (int) A_result, (int) B_result);
```

my desktop, 100M trials:

frequency	result	
99 823 739	A:0 B:1	('A executes before B')
171 161	A:1 B:0	('B executes before A')
4 706	A:1 B:1	('execute moves into x+y first')
394	A:0 B:0	???

why reorder here?

```
thread_A:
    movl $1, x   /* x <- 1 */
    movl y, %eax /* return y */
    ret
```

```
thread_B:
    movl $1, y   /* y <- 1 */
    movl x, %eax /* return x */
    ret
```

thread A: faster to load y right now!

...rather than wait for write of x to finish

why load/store reordering?

fast processor designs can execute instructions out of order

goal: do something instead of waiting for slow memory accesses, etc.

more on this later in the semester

GCC: preventing reordering example (1)

```
void Alice() {
    int one = 1;
    __atomic_store(&note_from_alice, &one, __ATOMIC_SEQ_CST);
    do {
    } while (__atomic_load_n(&note_from_bob, __ATOMIC_SEQ_CST));
    if (no_milk) {++milk;}
}
```

```
Alice:
  movl $1, note_from_alice
  mfence
.L2:
  movl note_from_bob, %eax
  testl %eax, %eax
  jne .L2
  ...
```

GCC: preventing reordering example (2)

```
void Alice() {
    note_from_alice = 1;
    do {
        __atomic_thread_fence(__ATOMIC_SEQ_CST);
    } while (note_from_bob);
    if (no_milk) {++milk;}
}
```

```
Alice:
  movl $1, note_from_alice  // note_from_alice <- 1
.L3:
  mfence  // make sure store is visible to other cores before
          // on x86: not needed on second+ iteration of loop
  cmpl $0, note_from_bob  // if (note_from_bob == 0) repeat fe
  jne .L3
  cmpl $0, no_milk
  ...
```

exercise: fetch-and-add with compare-and-swap

exercise: implement fetch-and-add with compare-and-swap

```
compare_and_swap(address, old_value, new_value) {
    if (memory[address] == old_value) {
        memory[address] = new_value;
        return true;   // x86: set ZF flag
    } else {
        return false;  // x86: clear ZF flag
    }
}
```

solution

xv6 spinlock: acquire

```
void
acquire(struct spinlock *lk)
{
  pushcli(); // disable interrupts to avoid deadlock.
  ...
  // The xchg is atomic.
  while(xchg(&lk->locked, 1) != 0)
    ;

  // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that the critical section's memory
  // references happen after the lock is acquired.
  __sync_synchronize();
  ...
}
```

xv6 spinlock: acquire

```
void
acquire(struct spinlock *lk)
{
  pushcli(); // disable interrupts to avoid deadlock.
  ...
  // The xchg is atomic.
  while(xchg(&lk->locked, 1) != 0)
    ;

  // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that the critical section's memory
  // references happen after the lock is acquired.
  __
  ..
}
```

don't let us be interrupted after while have the lock

problem: interruption might try to do something with the lock

...but that can never succeed until we release the lock

...but we won't release the lock until interruption finishes

xv6 spinlock: acquire

```
void
acquire(struct spinlock *lk)
{
  pushcli(); // disable interrupts to avoid deadlock.
  ...
  // The xchg is atomic.
  while(xchg(&lk->locked, 1) != 0)
    ;

  // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that the critical section's memory
  // references happen after the lock is acquired.
  __sync_synchronize();
  ...
}
```

xchg wraps the lock xchg instruction
same loop as before

xv6 spinlock: acquire

```
void
acquire(struct spinlock *lk)
{
  pushcli(); // disable interrupts to avoid deadlock.
  ...
  // The xchg is atomic.
  while(xchg(&lk->locked, 1) != 0)
    ;

  // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that the critical section's memory
  // references happen after the lock is acquired.
  __sync_synchronize();
  ...
}
```

avoid load store reordering (including by compiler)

on x86, `xchg` alone is enough to avoid processor's reordering

(but compiler may need more hints)

xv6 spinlock: release

```
void
release(struct spinlock *lk)
  ...
  // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that all the stores in the critical
  // section are visible to other cores before the lock is released
  // Both the C compiler and the hardware may re-order loads and
  // stores; __sync_synchronize() tells them both not to.
  __sync_synchronize();

  // Release the lock, equivalent to lk->locked = 0.
  // This code can't use a C assignment, since it might
  // not be atomic. A real OS would use C atomics here.
  asm volatile("movl $0, %0" : "+m" (lk->locked) : );

  popcli();
}
```

xv6 spinlock: release

```
void
release(struct spinlock *lk)
  ...
  // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that all the stores in the critical
  // section are visible to other cores before the lock is released
  // Both the C compiler and the hardware may re-order loads and
  // stores; __sync_synchronize() tells them both not to.
  __sync_synchronize();

  // Release the lock, equivalent to lk->locked = 0.
  // This code can't use a C assignment, since it might
  // not be atomic. A real OS would use C atomics here.
  asm volatile("movl $0, %0" : "+m" (lk->locked) : );

  popcli
}
```

turns into instruction to tell processor not to reorder
plus tells compiler not to reorder

xv6 spinlock: release

```
void
release(struct spinlock *lk)
  ...
  // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that all the stores in the critical
  // section are visible to other cores before the lock is released
  // Both the C compiler and the hardware may re-order loads and
  // stores; __sync_synchronize() tells them both not to.
  __sync_synchronize();

  // Release the lock, equivalent to lk->locked = 0.
  // This code can't use a C assignment, since it might
  // not be atomic. A real OS would use C atomics here.
  asm volatile("movl $0, %0" : "+m" (lk->locked) : );

  popcli();
}
```

turns into mov of constant 0 into `lk->locked`

xv6 spinlock: release

```
void
release(struct spinlock *lk)
  ...
  // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that all the stores in the critical
  // section are visible to other cores before the lock is releasea
  // Both the C compiler and the hardware may re-order loads and
  // stores; __sync_synchronize() tells them both not to.
  __sync_synchronize();

  // Release the lock, equivalent to lk->locked = 0.
  // This code can't use a C assignment, since it might
  // not be atomic. A real OS would use C atomics here.
  asm volatile("movl $0, %0" : "+m" (lk->locked) : );

  popcli();
}
```

reenable interrupts (taking nested locks into account)

fetch-and-add with CAS (1)

```
compare-and-swap(address, old_value, new_value) {
    if (memory[address] == old_value) {
        memory[address] = new_value;
        return true;
    } else {
        return false;
    }
}
```

```
long my_fetch_and_add(long *pointer, long amount) { ... }
```

implementation sketch:

- fetch value from pointer `old`
- compute in temporary value result of addition `new`
- try to change value at pointer from `old` to `new` [`compare-and-swap`]
- if not successful, repeat

fetch-and-add with CAS (2)

```
long my_fetch_and_add(long *p, long amount) {
    long old_value;
    do {
        old_value = *p;
    } while (!compare_and_swap(p, old_value, old_value + amount);
    return old_value;
}
```

exercise: append to singly-linked list

ListNode is a singly-linked list

assume: threads *only* append to list (no deletions, reordering)

use `compare-and-swap(pointer, old, new)`:

atomically change `*pointer` from `old` to `new`

return true if successful

return false (and change nothing) if `*pointer` is not `old`

```
void append_to_list(ListNode *head, ListNode *new_last_node) {
    ...
}
```

some common atomic operations (1)

```
// x86: emulate with exchange
test_and_set(address) {
    old_value = memory[address];
    memory[address] = 1;
    return old_value != 0;  // e.g. set ZF flag
}

// x86: xchg REGISTER, (ADDRESS)
exchange(register, address) {
    temp = memory[address];
    memory[address] = register;
    register = temp;
}
```

some common atomic operations (2)

```
// x86: mov OLD_VALUE, %eax; lock cmpxchg NEW_VALUE, (ADDRESS)
compare-and-swap(address, old_value, new_value) {
    if (memory[address] == old_value) {
        memory[address] = new_value;
        return true;    // x86: set ZF flag
    } else {
        return false;  // x86: clear ZF flag
    }
}

// x86: lock xaddl REGISTER, (ADDRESS)
fetch-and-add(address, register) {
    old_value = memory[address];
    memory[address] += register;
    register = old_value;
}
```

common atomic operation pattern

try to do operation, …

detect if it failed

if so, repeat

atomic operation does "try and see if it failed" part

cache coherency states

extra information for each cache block

- overlaps with/replaces valid, dirty bits

stored in each cache

update states based on reads, writes and heard messages on bus

different caches may have different states for same block

MSI state summary

Modified value may be different than memory *and* I am the only one who has it

Shared value is the same as memory

Invalid I don't have the value; I will need to ask for it

MSI scheme

from state	hear read	hear write	read	write
Invalid	—	—	to Shared	to Modified
Shared	—	to Invalid	—	to Modified
Modified	to Shared	to Invalid	—	—

blue: transition requires sending message on bus

MSI scheme

from state	hear read	hear write	read	write
Invalid	—	—	to Shared	to Modified
Shared	—	to Invalid	—	to Modified
Modified	to Shared	to Invalid	—	—

blue: transition requires sending message on bus

example: write while Shared

- must send write — inform others with Shared state
- then change to Modified

MSI scheme

from state	hear read	hear write	read	write
Invalid	—	—	to Shared	to Modified
Shared	—	to Invalid	—	to Modified
Modified	to Shared	to Invalid	—	—

blue: transition requires sending message on bus

example: write while Shared

- must send write — inform others with Shared state
- then change to Modified

example: hear write while Shared

- change to Invalid
- can send read later to get value from writer

example: write while Modified

- nothing to do — no other CPU can have a copy

MSI example



address	value	state
0xA300	100	Shared
0xC400	200	Shared
0xE500	300	Shared

address	value	state
0x9300	172	Shared
0xA300	100	Shared
0xC500	200	Shared

MSI example



address	**value**	**state**
0xA300	~~100~~101	Modified
0xC400	200	Shared
0xE500	300	Shared

address	**value**	**state**
0x9300	172	Shared
~~0xA300~~	~~100~~	Invalid
0xC500	200	Shared

cache sees write:
invalidate 0xA300

CPU1 writes 101 to 0xA300

MSI example

nothing changed yet (writeback)

CPU1

CPU2

MEM1

address	value	state
0xA300	~~101~~102	Modified
0xC400	200	Shared
0x[illegible]	[illegible]	[illegible]

address	value	state
0x9300	172	Shared
~~0xA300~~	~~100~~	Invalid
[illegible]	[illegible]	Shared

modified state — nothing communicated!
will “fix” later if there’s a read

CPU1 writes 102 to 0xA300

MSI example



address	value	state
0xA300	102	Modified
0xC400	200	Shared
0		

address	value	state
0x9300	172	Shared
~~0xA300~~	~~100~~	Invalid
		Shared

modified state — must update for CPU2!

CPU2 reads 0xA300

MSI example


“Write 102 into 0xA300”
CPU1
CPU2
MEM1
address value state
0xA300 102 Shared
0xC400 200 Shared
0xE
address value state
0x9300 172 Shared
~~0xA300~~ ~~100~~ Invalid
Shared
written back to memory early
(could also become Invalid at CPU1)
CPU2 reads 0xA300

MSI example



address	**value**	**state**
`0xA300`	`102`	Shared
`0xC400`	`200`	Shared
`0xE500`	`300`	Shared

address	**value**	**state**
`0x9300`	`172`	Shared
~~`0xA300`~~	~~`100`~~`102`	Shared
`0xC500`	`200`	Shared

MSI: update memory

to write value (enter modified state), need to invalidate others

can avoid sending actual value (shorter message/faster)

"I am writing address X" versus "I am writing Y to address X"

MSI: on cache replacement/writeback

still happens — e.g. want to store something else

changes state to invalid

requires writeback if modified (= dirty bit)

cache coherency exercise

modified/shared/invalid; all initially invalid; 32B blocks, 8B read/writes

CPU 1: read 0x1000
CPU 2: read 0x1000
CPU 1: write 0x1000
CPU 1: read 0x2000
CPU 2: read 0x1000
CPU 2: write 0x2008
CPU 3: read 0x1008

Q1: final state of 0x1000 in caches?
Modified/Shared/Invalid for CPU 1/2/3
CPU 1: CPU 2: CPU 3:

Q2: final state of 0x2000 in caches?
Modified/Shared/Invalid for CPU 1/2/3
CPU 1: CPU 2: CPU 3:

why load/store reordering?

fast processor designs can execute instructions out of order

goal: do something instead of waiting for slow memory accesses, etc.

more on this later in the semester

C++: preventing reordering

to help implementing things like pthread_mutex_lock

C++ 2011 standard: *atomic* header, *std::atomic* class

prevent CPU reordering *and* prevent compiler reordering

also provide other tools for implementing locks (more later)

could also hand-write assembly code

- compiler can't know what assembly code is doing

C++: preventing reordering example

```
#include <atomic>
void Alice() {
    note_from_alice = 1;
    do {
        std::atomic_thread_fence(std::memory_order_seq_cst);
    } while (note_from_bob);
    if (no_milk) {++milk;}
}
```

```
Alice:
  movl $1, note_from_alice  // note_from_alice <- 1
.L2:
  mfence  // make sure store visible on/from other cores
  cmpl $0, note_from_bob  // if (note_from_bob == 0) repeat fence
  jne .L2
  cmpl $0, no_milk
  ...
```

C++ atomics: no reordering

```
std::atomic<int> note_from_alice, note_from_bob;
void Alice() {
    note_from_alice.store(1);
    do {
    } while (note_from_bob.load());
    if (no_milk) {++milk;}
}
```

```
Alice:
  movl $1, note_from_alice
  mfence
.L2:
  movl note_from_bob, %eax
  testl %eax, %eax
  jne .L2
  ...
```

GCC: built-in atomic functions

used to implement std::atomic, etc.

predate std::atomic

builtin functions starting with `__sync` and `__atomic`

these are what xv6 uses

aside: some x86 reordering rules

each core sees its own loads/stores in order

(if a core stores something, it can always load it back)

stores *from other cores* appear in a consistent order

(but a core might observe its own stores too early)

causality:
if a core reads X=a and (after reading X=a) writes Y=b,
then a core that reads Y=b cannot later read X=older value than a

Source: Intel 64 and IA-32 Software Developer's Manual, Volume 3A, Chapter 8

how do you do anything with this?

difficult to reason about what modern CPU's reordering rules do

typically: don't depend on details, instead:

special instructions with stronger (and simpler) ordering rules

- often same instructions that help with implementing locks in other ways

special instructions that restrict ordering of instructions around them ("fences")

- loads/stores can't cross the fence

spinlock problems

lock abstraction is not powerful enough

- lock/unlock operations don't handle "wait for event"
- common thing we want to do with threads
- solution: other synchronization abstractions

spinlocks waste CPU time more than needed

- want to run another thread instead of infinite loop
- solution: lock implementation integrated with scheduler

spinlocks can send a lot of messages on the shared bus

- more efficient atomic operations to implement locks

ping-ponging

address	value	state
`lock`	`locked`	Modified

address	value	state
`lock`	`---`	Invalid

address	value	state
`lock`	`---`	Invalid

ping-ponging



address	value	state
lock	---	Invalid

address	value	state
lock	locked	Modified

address	value	state
lock	---	Invalid

CPU2 read-modify-writes lock
(to see it is still locked)

ping-ponging



address	value	state
lock	---	Invalid

address	value	state
lock	---	Invalid

address	value	state
lock	locked	Modified

CPU3 read-modify-writes lock
(to see it is still locked)

ping-ponging



address	value	state
lock	---	Invalid

address	value	state
lock	locked	Modified

address	value	state
lock	---	Invalid

CPU2 read-modify-writes lock
(to see it is still locked)

ping-ponging



address	value	state
lock	---	Invalid

address	value	state
lock	---	Invalid

address	value	state
lock	locked	Modified

CPU3 read-modify-writes lock
(to see it is still locked)

ping-ponging

"I want to modify `lock`"

address	value	state
`lock`	`unlocked`	Modified

address	value	state
`lock`	`---`	Invalid

address	value	state
`lock`		Invalid

CPU1 sets lock to unlocked

ping-ponging

"I want to modify `lock`"

address	value	state
lock	---	Invalid

address	value	state
lock	locked	Modified

address	value	state
lock		Invalid

some CPU (this example: CPU2) acquires lock

ping-ponging

test-and-set problem: cache block "ping-pongs" between caches

- each waiting processor reserves block to modify
- could maybe wait until it determines modification needed — but not typical implementation

each transfer of block sends messages on bus

...so bus can't be used for real work

- like what the processor with the lock is doing

test-and-test-and-set (pseudo-C)

```
acquire(int *the_lock) {
    do {
        while (ATOMIC-READ(the_lock) == 0) { /* try again */ }
    } while (ATOMIC-TEST-AND-SET(the_lock) == ALREADY_SET);
}
```

test-and-test-and-set (assembly)

```
acquire:
    cmp $0, the_lock          // test the lock non-atomically
            // unlike lock xchg --- keeps lock in Shared state!
    jne acquire               // try again (still locked)
    // lock possibly free
    // but another processor might lock
    // before we get a chance to
    // ... so try wtih atomic swap:
    movl $1, %eax              // %eax <- 1
    lock xchg %eax, the_lock   // swap %eax and the_lock
           // sets the_lock to 1
           // sets %eax to prior value of the_lock
    test %eax, %eax            // if the_lock wasn't 0 (someone else
    jne acquire                //    try again
    ret
```

less ping-ponging

address	value	state
lock	locked	Modified

address	value	state
lock	---	Invalid

address	value	state
lock	---	Invalid

less ping-ponging



address	value	state
lock	locked	Modified

address	value	state
lock		Invalid

address	value	state
lock		Invalid

CPU2 reads lock
(to see it is still locked)

less ping-ponging



address	value	state
lock	locked	Shared

address	value	state
lock	locked	Shared

address	value	state
lock		Invalid

CPU1 writes back lock value,
then CPU2 reads it

less ping-ponging



address	value	state
lock	locked	Shared

address	value	state
lock	locked	Shared

address	value	state
lock	locked	Shared

CPU3 reads lock
(to see it is still locked)

less ping-ponging



CPU2, CPU3 continue to read lock from cache
no messages on the bus

less ping-ponging

“I want to modify `lock`”

address	value	state
`lock`	`unlocked`	Modified

address	value	state
`lock`	`---`	Invalid

address	value	state
`lock`	`---`	Invalid

CPU1 sets lock to unlocked

less ping-ponging



some CPU (this example: CPU2) acquires lock
(CPU1 writes back value, then CPU2 reads + modifies it)

couldn't the read-modify-write instruction…

notice that the value of the lock isn't changing…

and keep it in the shared state

maybe — but extra step in "common" case
(swapping different values)

more room for improvement?

can still have a lot of attempts to modify locks after unlocked

there other spinlock designs that avoid this

- ticket locks
- MCS locks
- …

MSI extensions

real cache coherency protocols sometimes more complex:

separate tracking modifications from whether other caches have copy

send values directly between caches (maybe skip write to memory)

send messages only to cores which might care (no shared bus)

too much milk

roommates Alice and Bob want to keep fridge stocked with milk:

time	Alice	Bob
3:00	look in fridge. no milk	
3:05	leave for store	
3:10	arrive at store	look in fridge. no milk
3:15	buy milk	leave for store
3:20	return home, put milk in fridge	arrive at store
3:25		buy milk
3:30		return home, put milk in fridge

how can Alice and Bob coordinate better?

too much milk “solution” 1 (algorithm)

leave a note: “I am buying milk”

- place before buying, remove after buying
- don’t try buying if there’s a note

≈ setting/checking a variable (e.g. “`note = 1`”)

- with atomic load/store of variable

```
if (no milk) {
    if (no note) {
        leave note;
        buy milk;
        remove note;
    }
}
```

too much milk "solution" 1 (algorithm)

leave a note: "I am buying milk"

place before buying, remove after buying

don't try buying if there's a note

≈ setting/checking a variable (e.g. "`note = 1`")

with atomic load/store of variable

```
if (no milk) {
    if (no note) {
        leave note;
        buy milk;
        remove note;
    }
}
```

exercise: why doesn't this work?

too much milk “solution” 1 (timeline)

Alice

```
if (no milk) {
    if (no note) {



        leave note;
        buy milk;
        remove note;
    }
}
```

Bob

```


if (no milk) {
    if (no note) {









        leave note;
        buy milk;
        remove note;
    }
}
```

too much milk “solution” 2 (algorithm)

intuition: leave note when buying or checking if need to buy

```
leave note;
if (no milk) {
    if (no note) {
        buy milk;
    }
}
remove note;
```

too much milk: “solution” 2 (timeline)

Alice

```
leave note;
if (no milk) {
    if (no note) {
        buy milk;
    }
}
remove note;
```

too much milk: “solution” 2 (timeline)

Alice

```
leave note;
if (no milk) {
    if (no note) {
        buy milk;
    }
}
remove note;
```

but there’s always a note

too much milk: “solution” 2 (timeline)

Alice

```
leave note;
if (no milk) {
    if (no note) {
        buy milk;
    }
}
remove note;
```

but there’s always a note

…will never buy milk (twice *or* once)

“solution” 3: algorithm

intuition: label notes so Alice knows which is hers (and vice-versa)

computer equivalent: separate noteFromAlice and noteFromBob variables

Alice

```
leave note from Alice;
if (no milk) {
    if (no note from Bob) {
        buy milk
    }
}
remove note from Alice;
```

Bob

```
leave note from Bob;
if (no milk) {
    if (no note from Alice
        buy milk
    }
}
remove note from Bob;
```

too much milk: “solution” 3 (timeline)

Alice

```
leave note from Alice
if (no milk) {
    if (no note from Bob) {
        buy milk
    }
}
remove note from Alice
```

Bob

```
leave note from Bob
if (no milk) {
    if (no note from Alice) {
        buy milk
    }
}
remove note from Bob
```

too much milk: is it possible

is there a solutions with writing/reading notes?

$\approx$ loading/storing from shared memory

yes, but it's not very elegant

too much milk: solution 4 (algorithm)

Alice

```
leave note from Alice
while (note from Bob) {
    do nothing
}
if (no milk) {
    buy milk
}
remove note from Alice
```

Bob

```
leave note from Bob
if (no note from Alice) {
    if (no milk) {
        buy milk
    }
}
remove note from Bob
```

too much milk: solution 4 (algorithm)

Alice

```
leave note from Alice
while (note from Bob) {
    do nothing
}
if (no milk) {
    buy milk
}
remove note from Alice
```

Bob

```
leave note from Bob
if (no note from Alice) {
    if (no milk) {
        buy milk
    }
}
remove note from Bob
```

exercise (hard): prove (in)correctness

too much milk: solution 4 (algorithm)

Alice

```
leave note from Alice
while (note from Bob) {
    do nothing
}
if (no milk) {
    buy milk
}
remove note from Alice
```

Bob

```
leave note from Bob
if (no note from Alice) {
    if (no milk) {
        buy milk
    }
}
remove note from Bob
```

exercise (hard): prove (in)correctness

too much milk: solution 4 (algorithm)

Alice

```
leave note from Alice
while (note from Bob) {
    do nothing
}
if (no milk) {
    buy milk
}
remove note from Alice
```

Bob

```
leave note from Bob
if (no note from Alice) {
    if (no milk) {
        buy milk
    }
}
remove note from Bob
```

exercise (hard): prove (in)correctness

exercise (hard): extend to three people

Peterson's algorithm

general version of solution

see, e.g., Wikipedia

we'll use special hardware support instead

mfence

x86 instruction `mfence`

make sure all loads/stores in progress finish

...and make sure no loads/stores were started early

fairly expensive

- Intel 'Skylake': order 33 cycles + time waiting for pending stores/loads

mfence

x86 instruction `mfence`

make sure all loads/stores in progress finish

...and make sure no loads/stores were started early

fairly expensive

- Intel 'Skylake': order 33 cycles + time waiting for pending stores/loads

aside: this instruction is did not exist in the original x86
so xv6 uses something older that's equivalent

modifying cache blocks in parallel

cache coherency works on cache blocks

but typical memory access — less than cache block

- e.g. one 4-byte array element in 64-byte cache block

what if two processors modify different parts same cache block?

- 4-byte writes to 64-byte cache block

cache coherency — write instructions happen one at a time:

- processor 'locks' 64-byte cache block, fetching latest version
- processor updates 4 bytes of 64-byte cache block
- later, processor might give up cache block

modifying things in parallel (code)

```
void *sum_up(void *raw_dest) {
    int *dest = (int *) raw_dest;
    for (int i = 0; i < 64 * 1024 * 1024; ++i) {
        *dest += data[i];
    }
}

__attribute__((aligned(4096)))
int array[1024];  /* aligned = address is mult. of 4096 */

void sum_twice(int distance) {
    pthread_t threads[2];
    pthread_create(&threads[0], NULL, sum_up, &array[0]);
    pthread_create(&threads[1], NULL, sum_up, &array[distance]);
    pthread_join(threads[0], NULL);
    pthread_join(threads[1], NULL);
}
```

performance v. array element gap

(assuming `sum_up` compiled to not omit memory accesses)



false sharing

synchronizing to access two independent things

two parts of same cache block

solution: separate them

exercise (1)

```c
int values[1024];
int results[2];
void *sum_front(void *ignored_argument) {
    results[0] = 0;
    for (int i = 0; i < 512; ++i)
        results[0] += values[i];
    return NULL;
}
void *sum_back(void *ignored_argument) {
    results[1] = 0;
    for (int i = 512; i < 1024; ++i)
        results[1] += values[i];
    return NULL;
}
int sum_all() {
    pthread_t sum_front_thread, sum_back_thread;
    pthread_create(&sum_front_thread, NULL, sum_front, NULL);
    pthread_create(&sum_back_thread, NULL, sum_back, NULL);
    pthread_join(sum_front_thread, NULL);
    pthread_join(sum_back_thread, NULL);
    return results[0] + results[1];
}
```

Where is false sharing likely to occur? How to fix?

exercise (2)

```
struct ThreadInfo { int *values; int start; int end; int result };
void *sum_thread(void *argument) {
    ThreadInfo *my_info = (ThreadInfo *) argument;
    int sum = 0;
    for (int i = my_info->start; i < my_info->end; ++i) {
        my_info->result += my_info->values[i];
    }
    return NULL;

}
int sum_all(int *values) {
    ThreadInfo info[2]; pthread_t thread[2];
    for (int i = 0; i < 2; ++i) {
        info[i].values = values; info[i].start = i*512; info[i].end = (i+1)*512;
        pthread_create(&threads[i], NULL, sum_thread, (void *) &info[i]);
    }
    for (int i = 0; i < 2; ++i)
        pthread_join(threads[i], NULL);
    return info[0].result + info[1].result;
}
```

Where is false sharing likely to occur?

connecting CPUs and memory

multiple processors, common memory

how do processors communicate with memory?

shared bus



one possible design

- we'll revisit later when we talk about I/O

tagged messages — everyone gets everything, filters

contention if multiple communicators

- some hardware enforces only one at a time

shared buses and scaling

shared buses perform poorly with “too many” CPUs

so, there are other designs

we’ll gloss over these for now

shared buses and caches

remember caches?

memory is pretty slow

each CPU wants to keep local copies of memory

what happens when multiple CPUs cache same memory?

the cache coherency problem



address	value
0xA300	100
0xC400	200
0xE500	300

CPU1's cache

address	value
0x9300	172
0xA300	100
0xC500	200

CPU2's cache

the cache coherency problem



CPU1 writes 101 to 0xA300?

producer/consumer signal?

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;

Produce(item) {
    pthread_mutex_lock(&lock);
    buffer.enqueue(item);
    /* GOOD CODE: pthread_cond_signal(&data_ready); */
    /* BAD CODE: */
    if (buffer.size() == 1)
        pthread_cond_signal(&item);
    pthread_mutex_unlock(&lock);
}

Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    }
    item = buffer.dequeue();
    pthread_mutex_unlock(&lock);
    return item;
}
```

bad case (setup)

thread 0	1	2	3
Consume():			
lock			
empty? wait on cv	Consume():		
	lock		
	empty? wait on cv		
		Produce():	
		lock	Produce():

bad case

thread 0	1	2	3
Consume():			
lock			
empty? wait on cv	Consume():		
	lock		
	empty? wait on cv		
		Produce():	
		lock	Produce():
			wait for lock
		enqueue	
wait for lock		size $=$ 1? signal	
		unlock	gets lock
			enqueue
			size $\neq$ 1: don't signal
			unlock
gets lock			
dequeue			
	still waiting		

monitor exercise: ConsumeTwo

suppose we want producer/consumer, but...

but change Consume() to ConsumeTwo() which returns a pair of values

- and don't want two calls to ConsumeTwo() to wait...
- with each getting one item

what should we change below?

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;

Produce(item) {
  pthread_mutex_lock(&lock);
  buffer.enqueue(item);
  pthread_cond_signal(&data_ready);
  pthread_mutex_unlock(&lock);
}
```

```
Consume() {
  pthread_mutex_lock(&lock);
  while (buffer.empty()) {
    pthread_cond_wait(&data_ready, &lock
  }
  item = buffer.dequeue();
  pthread_mutex_unlock(&lock);
  return item;
}
```

monitor exercise: ordering

suppose we want producer/consumer, but...

but want to ensure first call to Consume() **always** returns first

(no matter what ordering cond_signal/cond_broadcast use)

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;

Produce(item) {
  pthread_mutex_lock(&lock);
  buffer.enqueue(item);
  pthread_cond_signal(&data_ready);
  pthread_mutex_unlock(&lock);
}
```

```
Consume() {
  pthread_mutex_lock(&lock);
  while (buffer.empty()) {
    pthread_cond_wait(&data_ready, &lock
  }
  item = buffer.dequeue();
  pthread_mutex_unlock(&lock);
  return item;
}
```

Anderson-Dahlin and semaphores

Anderson/Dahlin complains about semaphores

> "Our view is that programming with locks and condition variables is superior to programming with semaphores."

argument 1: clearer to have separate constructs for

- waiting for condition to be come true, and
- allowing only one thread to manipulate a thing at a time

arugment 2: tricky to verify thread calls up exactly once for every down

- alternatives allow one to be sloppier (in a sense)

monitors with semaphores: locks

```
sem_t semaphore;  // initial value 1

Lock() {
    sem_wait(&semaphore);
}

Unlock() {
    sem_post(&semaphore);
}
```

monitors with semaphores: [broken] cvs

start with only wait/signal:

```
sem_t threads_to_wakeup;  // initially 0
Wait(Lock lock) {
    lock.Unlock();
    sem_wait(&threads_to_wakeup);
    lock.Lock();
}
Signal() {
    sem_post(&threads_to_wakeup);
}
```

monitors with semaphores: [broken] cvs

start with only wait/signal:

```
sem_t threads_to_wakeup;  // initially 0
Wait(Lock lock) {
    lock.Unlock();
    sem_wait(&threads_to_wakeup);
    lock.Lock();
}
Signal() {
    sem_post(&threads_to_wakeup);
}
```

problem: signal wakes up non-waiting threads (in the far future)

monitors with semaphores: cvs (better)

start with only wait/signal:

```
sem_t private_lock;  // initially 1
int num_waiters;
sem_t threads_to_wakeup;  // initially 0
Wait(Lock lock) {
  sem_wait(&private_lock);
  ++num_waiters;
  sem_post(&private_lock);
  lock.Unlock();
  sem_wait(&threads_to_wakeup);
  lock.Lock();
}
```

```
Signal() {
  sem_wait(&private_lock);
  if (num_waiters > 0) {
    sem_post(&threads_to_wakeup);
    --num_waiters;
  }
  sem_post(&private_lock);
}
```

monitors with semaphores: broadcast

now allows broadcast:

```
sem_t private_lock;  // initially 1
int num_waiters;
sem_t threads_to_wakeup;  // initially 0
Wait(Lock lock) {
  sem_wait(&private_lock);
  ++num_waiters;
  sem_post(&private_lock);
  lock.Unlock();
  sem_wait(&threads_to_wakeup);
  lock.Lock();
}
```

```
Broadcast() {
  sem_wait(&private_lock);
  while (num_waiters > 0) {
    sem_post(&threads_to_wakeup);
    --num_waiters;
  }
  sem_post(&private_lock);
}
```

building semaphore with monitors

```
pthread_mutex_t lock;
```

lock to protect shared state

building semaphore with monitors

```
pthread_mutex_t lock;
unsigned int count;
```

lock to protect shared state

shared state: semaphore tracks a count

building semaphore with monitors

```
pthread_mutex_t lock;
unsigned int count;
/* condition, broadcast when becomes count > 0 */
pthread_cond_t count_is_positive_cv;
```

lock to protect shared state

- shared state: semaphore tracks a count

add cond var for each reason we wait

- semaphore: wait for count to become positive (for down)

building semaphore with monitors

```
pthread_mutex_t lock;
unsigned int count;
/* condition, broadcast when becomes count > 0 */
pthread_cond_t count_is_positive_cv;
void down() {
    pthread_mutex_lock(&lock);
    while (!(count > 0)) {
        pthread_cond_wait(
            &count_is_positive_cv,
            &lock);
    }
    count -= 1;
    pthread_mutex_unlock(&lock);
}
```

lock to protect shared state

- shared state: semaphore tracks a count

add cond var for each reason we wait

- semaphore: wait for count to become positive (for down)

wait using condvar; broadcast/signal when condition changes

building semaphore with monitors

```
pthread_mutex_t lock;
unsigned int count;
/* condition, broadcast when becomes count > 0 */
pthread_cond_t count_is_positive_cv;
void down() {
    pthread_mutex_lock(&lock);
    while (!(count > 0)) {
        pthread_cond_wait(
            &count_is_positive_cv,
            &lock);
    }
    count -= 1;
    pthread_mutex_unlock(&lock);
}
```

```
void up() {
    pthread_mutex_lock(&lock);
    count += 1;
    /* count must now be
       positive, and at most
       one thread can go per
       call to Up() */
    pthread_cond_signal(
        &count_is_positive_cv
    );
    pthread_mutex_unlock(&lock);
}
```

lock to protect shared state

- shared state: semaphore tracks a count

add cond var for each reason we wait

- semaphore: wait for count to become positive (for down)

wait using condvar; broadcast/signal when condition changes

binary semaphores

binary semaphores — semaphores that are only zero or one

as powerful as normal semaphores

- exercise: simulate counting semaphores with binary semaphores (more than one) and an integer

counting semaphores with binary semaphores

via Hemmendinger, “Comments on ‘A correect and unrestrictive implementation of general semaphores’ ” (1989); Barz, “Implementing semaphores by binary semaphores” (1983)

```
// assuming initialValue > 0
BinarySemaphore mutex(1);
int value = initialValue ;
BinarySemaphore gate(1 /* if initialValue >= 1 */);
    /* gate = # threads that can Down() now */
```

```
void Down() {
  gate.Down();
  // wait, if needed
  mutex.Down();
  value -= 1;
  if (value > 0) {
    gate.Up();
    // because next down should finish
    // now (but not marked to before)
  }
  mutex.Up();
}
```

```
void Up() {
  mutex.Down();
  value += 1;
  if (value == 1) {
    gate.Up();
    // because down should finish now
    // but could not before
  }
  mutex.Up();
}
```

gate intuition/pattern

pattern to allow one thread at a time:

```
sem_t gate; // 0 = closed; 1 = open
ReleasingThread() {
    ... // finish what the other thread is waiting for
    while (another thread is waiting and can go) {
        sem_post(&gate)  // allow EXACTLY ONE thread
        ... // other bookkeeping
    }
    ...
}
WaitingThread() {
    ... // indicate that we're waiting
    sem_wait(&gate) // wait for gate to be open
    ... // indicate that we're not waiting
}
```