synchronization

a threading race #include <pthread.h>

#include <stdio.h>

return NULL;

```
int main() {
    printf("About_to_start_thread\n");
    pthread_t the_thread;
    /* assume does not fail */
    pthread_create(&the_thread, NULL, print_message, NULL);
    printf("Done_starting_thread\n");
    return 0;
My machine: outputs In the thread about 4% of the time.
```

void *print_message(void *ignored_argument) {

printf("In_the_thread\n");

a race

returning from main exits the entire process (all its threads) same as calling exit; not like other threads race: main's return 0 or print_message's printf first? time main: printf/pthread create/printf/return print message: printf/return return from main ends all threads in the process

the correctness problem

two threads?

introduces non-determinism

which one runs first?

allows for "race condition" bugs

...to be avoided with synchronization constructs

example application: ATM server

commands: withdraw, deposit

one correctness goal: don't lose money

```
ATM server
(pseudocode)
ServerLoop() {
    while (true) {
        ReceiveRequest(&operation, &accountNumber, &amount);
        if (operation == DEPOSIT) {
             Deposit(accountNumber, amount);
         } else ...
Deposit(accountNumber, amount) {
    account = GetAccount(accountNumber);
    account->balance += amount;
    SaveAccountUpdates(account);
```

a threaded server?

```
Deposit(accountNumber, amount) {
    account = GetAccount(accountId);
    account->balance += amount;
    SaveAccountUpdates(account):
maybe GetAccount/SaveAccountUpdates can be slow?
    read/write disk sometimes? contact another server sometimes?
maybe lots of requests to process?
    maybe real logic has more checks than Deposit()
all reasons to handle multiple requests at once
```

ightarrow many threads all running the server loop

7

multiple threads

```
main() {
    for (int i = 0; i < NumberOfThreads; ++i) {</pre>
        pthread create(&server loop threads[i], NULL,
                        ServerLoop, NULL);
ServerLoop() {
    while (true) {
        ReceiveRequest(&operation, &accountNumber, &amount);
        if (operation == DEPOSIT) {
            Deposit(accountNumber, amount);
        } else ...
```

the lost write

```
account->balance += amount; (in two threads, same account)
          Thread A
                                       Thread B
mov account->balance, %rax
add amount, %rax
                         context switch
                                mov account->balance, %rax
                                add amount, %rax
                         context switch
mov %rax, account->balance
                         context switch
                                mov %rax, account->balance
```

the lost write

```
account->balance += amount; (in two threads, same account)
          Thread A
                                       Thread B
mov account->balance, %rax
add amount, %rax
                         context switch
                                 mov account->balance, %rax
                                add amount, %rax
                         context switch
mov %rax, account->balance
                         context switch
     lost write to balance
                                mov %rax, account->balance
```

"winner" of the race

the lost write

```
account->balance += amount; (in two threads, same account)
          Thread A
                                       Thread B
mov account->balance, %rax
add amount, %rax
                         context switch
                                 mov account->balance, %rax
                                 add amount, %rax
                         context switch
mov %rax, account->balance
                         context switch
     lost write to balance
                                 mov %rax, account->balance
                                      "winner" of the race
```

thinking about race conditions (1)

what are the possible values of x? (initially x = y = 0)

| Thread A | Thread B |
|------------------|------------------|
| $x \leftarrow 1$ | $y \leftarrow 2$ |

thinking about race conditions (1)

what are the possible values of x? (initially x = y = 0)

Thread A Thread B $x \leftarrow 1$ $y \leftarrow 2$

must be 1. Thread B can't do anything

thinking about race conditions (2)

possible values of x? (initially x = y = 0)

thinking about race conditions (2)

possible values of x? (initially x = y = 0)

Thread A Thread B

$$\begin{array}{ccc} x \leftarrow y + 1 & y \leftarrow 2 \\ & y \leftarrow y \times 2 \end{array}$$

if A goes first, then B: 1

if B goes first, then A: 5

if B line one, then A, then B line two: 3

thinking about race conditions (3)

what are the possible values of x?

(initially
$$x = y = 0$$
)

Thread A Thread B
$$x \leftarrow 1 \qquad x \leftarrow 2$$

thinking about race conditions (3)

what are the possible values of x?

(initially
$$x = y = 0$$
)

Thread A Thread B
$$x \leftarrow 1 \qquad x \leftarrow 2$$

1 or 2

thinking about race conditions (3)

what are the possible values of x?

(initially
$$x = y = 0$$
)

Thread A Thread B

 $x \leftarrow 1$ $x \leftarrow 2$

1 or 2

...but why not 3?

B: $x \text{ bit } 0 \leftarrow 0$

A: x bit $0 \leftarrow 1$

A: $x \text{ bit } 1 \leftarrow 0$

B: x bit $1 \leftarrow 1$

thinking about race conditions (2)

possible values of x? (initially x = y = 0)

Thread A Thread B
$$x \leftarrow y + 1 \quad y \leftarrow 2$$

$$y \leftarrow y \times 2$$

if A goes first, then B: 1

if B goes first, then A: 5

if B line one, then A, then B line two: 3

...and why not 7:

B (start): $y \leftarrow 2 = 0010_{\text{TWO}}$; then y bit 3 \leftarrow 0; y bit 2 \leftarrow 1; then A: x $\leftarrow 110_{\text{TWO}} + 1 = 7$; then

B (finish): y bit $1 \leftarrow 0$; y bit $0 \leftarrow 0$

atomic operation

atomic operation = operation that runs to completion or not at all we will use these to let threads work together

most machines: loading/storing (aligned) words is atomic so can't get 3 from $x \leftarrow 1$ and $x \leftarrow 2$ running in parallel aligned \approx address of word is multiple of word size (typically done by compilers)


but some instructions are not atomic; examples:

x86: integer add constant to memory location many CPUs: loading/storing values that cross cache blocks
e.g. if cache blocks 0x40 bytes, load/store 4 byte from addr. 0x3E is not atomic

lost adds (program)

```
.global update loop
update_loop:
   addl $1, the_value // the_value (global variable) += 1
   dec %rdi // argument 1 -= 1
   jg update_loop // if argument 1 >= 0 repeat
   ret
int the value:
extern void *update loop(void *);
int main(void) {
   the value = 0;
   pthread t A, B;
   pthread_create(&A, NULL, update_loop, (void*) 1000000);
   pthread create(&B, NULL, update loop, (void*) 1000000);
   pthread join(A, NULL); pthread join(B, NULL);
   // expected result: 1000000 + 1000000 = 2000000
   printf("the value,=,%d\n", the value);
```

lost adds (results)



but how?

probably not possible on single core exceptions can't occur in the middle of add instruction

...but 'add to memory' implemented with multiple steps still needs to load, add, store internally can be interleaved with what other cores do

but how?

```
probably not possible on single core exceptions can't occur in the middle of add instruction
```

...but 'add to memory' implemented with multiple steps still needs to load, add, store internally can be interleaved with what other cores do

(and actually it's more complicated than that — we'll talk later)

so, what is actually atomic

```
for now we'll assume: load/stores of 'words' (64-bit machine = 64-bits words)
```

in general: processor designer will tell you

their job to design caches, etc. to work as documented

compilers move loads/stores (1)

```
void WaitForReady() {
    do {} while (!ready);
}

WaitForOther:
    movl ready, %eax // eax <- other_ready
.L2:
    testl %eax, %eax
    je .L2 // while (eax == 0) repeat
...</pre>
```

compilers move loads/stores (1)

compilers move loads/stores (2)

```
void WaitForOther() {
    is waiting = 1;
    do {} while (!other_ready);
    is waiting = 0;
WaitForOther:
 // compiler optimization: don't set is waiting to 1,
 // (why? it will be set to 0 anyway)
  movl other ready, %eax // eax <- other ready
.L2:
  testl %eax, %eax
  ie .L2
                             // while (eax == 0) repeat
  movl $0, is_waiting // is_waiting <- 0</pre>
```

compilers move loads/stores (2)

```
void WaitForOther() {
    is waiting = 1;
    do {} while (!other_ready);
    is waiting = 0;
WaitForOther:
 // compiler optimization: don't set is waiting to 1,
 // (why? it will be set to 0 anyway)
  movl other ready, %eax // eax <- other ready
.L2:
  testl %eax, %eax
  ie .L2
                             // while (eax == 0) repeat
 movl $0, is_waiting // is_waiting <- 0</pre>
```

compilers move loads/stores (2)

```
void WaitForOther() {
    is waiting = 1;
    do {} while (!other_ready);
    is waiting = 0;
WaitForOther:
 // compiler optimization: don't set is waiting to 1,
 // (why? it will be set to 0 anyway)
 movl other ready, %eax // eax <- other ready
.L2:
  testl %eax, %eax
  ie .L2
                             // while (eax == 0) repeat
  movl $0, is_waiting // is_waiting <- 0</pre>
```

fixing compiler reordering?

isn't there a way to tell compiler not to do these optimizations?

yes, but that is still not enough!

processors sometimes do this kind of reordering too (between cores)

pthreads and reordering

many pthreads functions prevent reordering everything before function call actually happens before

includes preventing some optimizations
e.g. keeping global variable in register for too long

pthread_create, pthread_join, other tools we'll talk about ... basically: if pthreads is waiting for/starting something, no weird ordering

implementation part 1: prevent compiler reordering

implementation part 2: use special instructions example: x86 mfence instruction

some definitions

mutual exclusion: ensuring only one thread does a particular thing at a time

like updating shared balance

23

some definitions

mutual exclusion: ensuring only one thread does a particular thing at a time

like updating shared balance

critical section: code that exactly one thread can execute at a time

result of critical section

some definitions

mutual exclusion: ensuring only one thread does a particular thing at a time

like updating shared balance

critical section: code that exactly one thread can execute at a time

result of critical section

lock: object only one thread can hold at a time
 interface for creating critical sections

lock analogy

agreement: only change account balances while wearing this hat normally hat kept on table put on hat when editing balance

hopefully, only one person (= thread) can wear hat a time need to wait for them to remove hat to put it on

lock analogy

agreement: only change account balances while wearing this hat normally hat kept on table put on hat when editing balance

hopefully, only one person (= thread) can wear hat a time need to wait for them to remove hat to put it on

"lock (or acquire) the lock" = get and put on hat

"unlock (or release) the lock" = put hat back on table

the lock primitive

```
locks: an object with (at least) two operations: 

acquire or lock — wait until lock is free, then "grab" it 

release or unlock — let others use lock, wakeup waiters
```

typical usage: everyone acquires lock before using shared resource forget to acquire lock? weird things happen

```
Lock(account_lock);
balance += ...;
Unlock(account_lock);
```

the lock primitive

```
locks: an object with (at least) two operations: 

acquire or lock — wait until lock is free, then "grab" it 

release or unlock — let others use lock, wakeup waiters
```

typical usage: everyone acquires lock before using shared resource forget to acquire lock? weird things happen

```
Lock(account_lock);
balance += ...;
Unlock(account_lock);
```

waiting for lock?

when waiting — ideally:

not using processor (at least if waiting a while)

OS can context switch to other programs

pthread mutex

```
#include <pthread.h>
pthread mutex t account lock;
pthread mutex init(&account lock, NULL);
   // or: pthread_mutex_t account_lock =
                    PTHREAD MUTEX INITIALIZER;
pthread mutex lock(&account lock);
balance += ...:
pthread mutex unlock(&account lock);
```

```
exercise
```

```
pthread mutex t lock1 = PTHREAD MUTEX INITIALIZER;
pthread mutex t lock2 = PTHREAD MUTEX INITIALIZER;
string one = "init_one", two = "init_two";
void ThreadA() {
    pthread mutex lock(&lock1);
    one = "one_in_ThreadA"; // (A1)
    pthread mutex unlock(&lock1):
    pthread mutex lock(&lock2);
    two = "two_in_ThreadA"; // (A2)
    pthread mutex unlock(&lock2):
void ThreadB() {
    pthread mutex lock(&lock1);
    one = "one_in_ThreadB"; // (B1)
    pthread mutex lock(&lock2);
    two = "two_in_ThreadB"; // (B2)
    pthread mutex unlock(&lock2);
    pthread mutex unlock(&lock1):
```

```
exercise (alternate 1)
pthread mutex t lock1 = PTHREAD MUTEX INITIALIZER;
pthread mutex t lock2 = PTHREAD MUTEX INITIALIZER;
string one = "init_one", two = "init_two";
void ThreadA() {
    pthread_mutex_lock(&lock2);
    two = "two_in_ThreadA"; // (A2)
    pthread mutex unlock(&lock2);
    pthread mutex lock(&lock1);
    one = "one_in_ThreadA"; // (A1)
    pthread mutex unlock(&lock1):
void ThreadB() {
    pthread mutex lock(&lock1);
    one = "one_in_ThreadB"; // (B1)
    pthread mutex lock(&lock2);
    two = "two_in_ThreadB"; // (B2)
    pthread_mutex_unlock(&lock2):
    pthread mutex unlock(&lock1):
```

```
exercise (alternate 2)
pthread_mutex_t lock1 = PTHREAD_MUTEX_INITIALIZER;
 pthread mutex t lock2 = PTHREAD MUTEX INITIALIZER;
 string one = "init_one", two = "init_two";
 void ThreadA() {
     pthread_mutex_lock(&lock2);
     two = "two_in_ThreadA"; // (A2)
     pthread mutex unlock(&lock2);
     pthread mutex lock(&lock1);
     one = "one_in_ThreadA"; // (A1)
     pthread mutex unlock(&lock1):
void ThreadB() {
     pthread mutex lock(&lock1);
     one = "one_in_ThreadB"; // (B1)
     pthread mutex unlock(&lock1);
     pthread mutex lock(&lock2);
     two = "two_in_ThreadB"; // (B2)
     pthread mutex unlock(&lock2):
```

POSIX mutex restrictions

pthread_mutex rule: unlock from same thread you lock in

does this actually matter?

depends on how pthread_mutex is implemented

preview: general sync

lots of coordinating threads beyond locks/barriers

will talk about two general tools later:

monitors/condition variables semaphores

big added feature: wait for arbitrary thing to happen

a bad idea

one bad idea to wait for an event: pthread mutex t lock = PTHREAD MUTEX INITIALIZER; bool ready = false; void WaitForReady() { pthread_mutex_lock(&lock); do { pthread_mutex_unlock(&lock): /* only time MarkReady() can run */ pthread mutex lock(&lock); } while (!readv); pthread mutex unlock(&lock); void MarkReady() { pthread_mutex_lock(&lock); ready = true; pthread mutex unlock(&lock):

wastes processor time; MarkReady can stall waiting for unlock

beyond locks

```
in practice: want more than locks for synchronization
for waiting for arbtirary events (without CPU-hogging-loop):
     monitors
    semaphores
for common synchornization patterns:
     barriers
     reader-writer locks
higher-level interface:
    transactions
```

barriers

compute minimum of 100M element array with 2 processors algorithm:

compute minimum of 50M of the elements on each CPU one thread for each CPU

wait for all computations to finish

take minimum of all the minimums

barriers

compute minimum of 100M element array with 2 processors algorithm:

compute minimum of 50M of the elements on each CPU one thread for each CPU

wait for all computations to finish

take minimum of all the minimums

barriers API

barrier.Initialize(NumberOfThreads)

barrier.Wait() — return after all threads have waited

idea: multiple threads perform computations in parallel

threads wait for all other threads to call Wait()

barrier: waiting for finish

```
barrier.Initialize(2);
       Thread 0
                                 Thread 1
 partial mins[0] =
    /* min of first
        50M elems */:
                           partial_mins[1] =
                               /* min of last
                                   50M elems */
 barrier.Wait():
                            barrier.Wait():
 total_min = min(
     partial_mins[0],
     partial mins[1]
```

barriers: reuse

Thread 0

```
results[0][0] = getInitial(0);
                                     results[0][1] = getInitial(1);
barrier.Wait();
                                     barrier.Wait();
results[1][0] =
                                     results[1][1] =
    computeFrom(
                                          computeFrom(
        results[0][0],
                                              results[0][0],
        results[0][1]
                                              results[0][1]
barrier.Wait();
                                     barrier.Wait();
results[2][0] =
                                     results[2][1] =
    computeFrom(
                                          computeFrom(
        results[1][0],
                                              results[1][0],
        results[1][1]
                                              results[1][1]
    );
                                                                    38
```

Thread 1

barriers: reuse

```
Thread 0
                                                 Thread 1
results[0][0] = getInitial(0);
                                     results[0][1] = getInitial(1);
barrier.Wait():
                                     barrier.Wait();
results[1][0] =
                                     results[1][1] =
    computeFrom(
                                         computeFrom(
        results[0][0],
                                              results[0][0],
        results[0][1]
                                              results[0][1]
                                     barrier.Wait();
barrier.Wait();
results[2][0] =
                                     results[2][1] =
    computeFrom(
                                         computeFrom(
        results[1][0],
                                              results[1][0],
        results[1][1]
                                              results[1][1]
    );
```

barriers: reuse

```
Thread 0
                                                 Thread 1
results[0][0] = getInitial(0);
                                     results[0][1] = getInitial(1);
barrier.Wait();
                                     barrier.Wait();
results[1][0] =
                                     results[1][1] =
    computeFrom(
                                          computeFrom(
        results[0][0],
                                              results[0][0],
        results[0][1]
                                              results[0][1]
                                     barrier.Wait();
barrier.Wait();
results[2][0] =
                                     results[2][1] =
    computeFrom(
                                          computeFrom(
        results[1][0],
                                              results[1][0],
                                              results[1][1]
        results[1][1]
    );
```

pthread barriers

```
pthread_barrier_t barrier;
pthread_barrier_init(
    &barrier,
    NULL /* attributes */,
    numberOfThreads
);
...
pthread_barrier_wait(&barrier);
```

exercise

```
pthread barrier t barrier; int x = 0, y = 0;
void thread one() {
    \vee = 10;
    pthread barrier wait(&barrier);
    y = x + y;
    pthread_barrier_wait(&barrier);
    pthread_barrier_wait(&barrier);
    printf("%d_{\square}%d\n", x, y);
void thread_two() {
    x = 20;
    pthread barrier wait(&barrier);
    pthread_barrier_wait(&barrier);
    x = x + y;
```

pthread_barrier_wait(&barrier);

life homework (pseudocode)

```
for (int time = 0; time < MAX_ITERATIONS; ++time) {
    for (int y = 0; y < size; ++y) {
        for (int x = 0; x < size; ++x) {
            to_grid(x, y) = computeValue(from_grid, x, y);
        }
    }
    swap(from_grid, to_grid);
}</pre>
```

life homework

compute grid of values for time t from grid for time t-1 compute new value at i,j based on surrounding values


parallel version: produce parts of grid in different threads use barriers to finish time t before going to time t+1

example: producer/consumer



shared buffer (queue) of fixed size
one or more producers inserts into queue
one or more consumers removes from queue


example: producer/consumer



shared buffer (queue) of fixed size
one or more producers inserts into queue
one or more consumers removes from queue

producer(s) and consumer(s) don't work in lockstep (might need to wait for each other to catch up)

example: producer/consumer



shared buffer (queue) of fixed size
one or more producers inserts into queue
one or more consumers removes from queue

producer(s) and consumer(s) don't work in lockstep (might need to wait for each other to catch up)

example: C compiler preprocessor \rightarrow compiler \rightarrow assembler \rightarrow linker

monitors/condition variables

locks for mutual exclusion

```
condition variables for waiting for event
    represents list of waiting threads
    operations: wait (for event); signal/broadcast (that event happened)
```

related data structures

```
\begin{aligned} & \text{monitor} = \text{lock} + 0 \text{ or more condition variables} + \text{shared data} \\ & \text{Java: every object is a monitor (has instance variables, built-in lock, cond. var)} \\ & \text{pthreads: build your own: provides you locks} + \text{condition variables} \end{aligned}
```


a monitor


| lock |
|--------------|
| shared data |
| condvar 1 |
| condvar 2 |
| |
| operation1() |
| operation2() |
| |

a monitor

| lock |
|--------------|
| shared data |
| condvar 1 |
| condvar 2 |
| |
| operation1() |
| operation2() |

lock must be acquired before accessing any part of monitor's stuff






condvar operations:

Wait(cv, lock) — unlock lock, add current thread to cv queue ...and reacquire lock before returning

Broadcast(cv) — remove all from condvar queue

Signal(cv) — remove one from condvar queue




condvar operations:

Wait(cv, lock) — unlock lock, add current thread to cv queue

...and reacquire lock before returning

Broadcast(cv) — remove all from condvar queue

Signal(cv) — remove one from condvar queue




condvar operations:

Wait(cv, lock) — unlock lock, add current thread to cv queue

...and reacquire lock before returning


Broadcast(cv) — remove all from condvar queue



condvar operations:

Wait(cv, lock) — unlock lock, add current thread to cv queue ...and reacquire lock before returning

Broadcast(cv) — remove all from condvar queue Signal(cv) — remove one from condvar queue




condvar operations:

Wait(cv, lock) — unlock lock, add current thread to cv queue

...and reacquire lock before returning

Broadcast(cv) — remove all from condvar queue

Signal(cv) — remove one from condvar queue



```
// MISSING: init calls, etc.
pthread mutex t lock:
bool finished: // data, only accessed with after acquiring lock
pthread cond t finished cv: // to wait for 'finished' to be true
void WaitForFinished() {
  pthread mutex lock(&lock);
  while (!finished) {
    pthread cond wait(&finished cv, &lock);
  pthread_mutex_unlock(&lock);
void Finish() {
  pthread mutex lock(&lock);
  finished = true;
  pthread cond broadcast(&finished cv):
  pthread_mutex_unlock(&lock);
```

pthread cond broadcast(&finished cv):

pthread mutex unlock(&lock):

```
// MISSING: init calls, etc.
pthread mutex t lock:
bool finished: // data, only accessed with after acquiring lock
pthread cond t finished cv: // to wait for 'finished' to be true
void WaitForFinished() {
  pthread mutex lock(&lock);
  while (!finished) {
    pthread cond wait(&finished cv,
                                       acquire lock before
  pthread mutex unlock(&lock):
                                       reading or writing finished
void Finish() {
  pthread mutex lock(&lock);
  finished = true;
```

47

finished = true;

pthread cond broadcast(&finished cv):

pthread_mutex_unlock(&lock);

```
// MISSING: init calls, etc.
pthread mutex t lock:
bool finished: // data, only accessed with after acquiring lock
pthread cond t finished cv: // to wait for 'finished' to be true
void WaitForFinished() {
  pthread mutex lock(&lock);
                                 check whether we need to wait at all
  while (!finished) { ←
    pthread_cond_wait(&finished_(why a loop? we'll explain later)
  pthread_mutex_unlock(&lock);
void Finish() {
  pthread mutex lock(&lock);
```

```
// MISSING: init calls, etc.
pthread mutex t lock:
bool finished: // data, only accessed with after acquiring lock
pthread cond t finished cv: // to wait for 'finished' to be true
void WaitForFinished() {
  pthread mutex lock(&lock);
  while (!finished) {
    pthread cond wait(&finished cv, &lock);
 pthread_mutex_unlock(&locknow we need to wait
                            (finished can't change while we have lock)
                           so wait, releasing lock...
void Finish() {
  pthread mutex lock(&lock
  finished = true;
  pthread cond broadcast(&finished cv):
  pthread mutex unlock(&lock):
```

pthread mutex unlock(&lock);

```
// MISSING: init calls, etc.
pthread mutex t lock:
bool finished: // data, only accessed with after acquiring lock
pthread cond t finished cv: // to wait for 'finished' to be true
void WaitForFinished() {
  pthread mutex lock(&lock);
  while (!finished) {
    pthread cond wait(&finished cv, &lock);
  pthread mutex unlock(&lock):
                                          allow all waiters to proceed
                                          (once we unlock the lock)
void Finish() {
  pthread mutex lock(&lock);
  finished = true;
  pthread cond broadcast(&finished cv):
```

WaitForFinish timeline 1 WaitForFinish thread Finish thread mutex lock(&lock) (thread has lock) mutex lock(&lock) (start waiting for lock) while (!finished) ... cond wait(&finished cv, &lock); (start waiting for cv) (done waiting for lock) finished = truecond broadcast(&finished cv) (done waiting for cv) (start waiting for lock) mutex_unlock(&lock) (done waiting for lock) while (!finished) ... (finished now true, so return)

WaitForFinish timeline 2

| WaitForFinish thread | Finish thread |
|------------------------------------|---|
| | <pre>mutex_lock(&lock)</pre> |
| | finished = true |
| | <pre>cond_broadcast(&finished_cv)</pre> |
| | <pre>mutex_unlock(&lock)</pre> |
| <pre>mutex_lock(&lock)</pre> | |
| while (!finished) | |
| (finished now true, so return) | |
| <pre>mutex_unlock(&lock)</pre> | |

why the loop

```
while (!finished) {
   pthread_cond_wait(&finished_cv, &lock);
}
we only broadcast if finished is true
so why check finished afterwards?
```

why the loop

```
while (!finished) {
  pthread cond wait(&finished cv, &lock);
we only broadcast if finished is true
so why check finished afterwards?
pthread cond wait manual page:
    "Spurious wakeups ... may occur."
spurious wakeup = wait returns even though nothing happened
```

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedOueue buffer:
Produce(item) {
    pthread_mutex_lock(&lock);
    buffer.engueue(item);
    pthread cond signal(&data ready):
    pthread mutex unlock(&lock):
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread mutex unlock(&lock);
    return item:
```

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedOueue buffer:
Produce(item) {
    pthread mutex lock(&lock);
    buffer.engueue(item);
    pthread_cond_signal(&data_ready); simulatenously en/dequeue?
    pthread_mutex_unlock(&lock);
Consume()
    pthread mutex lock(&lock);
   while (buffer.empty()) {
        pthread cond wait(&data ready, &lock);
    item = buffer.dequeue();
    pthread mutex unlock(&lock);
    return item:
```

rule: never touch buffer without acquiring lock otherwise: what if two threads (both use same array/linked list entry?) (both reallocate array?)

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
    buffer.engueue(item);
    pthread cond signal(&data ready):
                                                check if empty
    pthread mutex unlock(&lock):
                                                if so, dequeue
Consume()
    pthread_mutex_lock(&lock);
   while (buffer.empty()) {
                                                okay because have lock
        pthread cond wait(&data_ready, &lock);
                                  other threads cannot dequeue here
    item = buffer.dequeue();
    pthread mutex unlock(&lock);
    return item:
```


```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
                                                wake one Consume thread
    buffer.engueue(item);
                                                if any are waiting
    pthread cond signal(&data ready);
    pthread mutex unlock(&lock):
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread cond wait(&data ready, &lock);
    item = buffer.dequeue();
    pthread mutex unlock(&lock);
    return item:
```

```
Thread 1
                                                                  Thread 2
pthread_mutex_t lock;
                                         Produce()
pthread_cond_t data_ready;
                                          ...lock
UnboundedQueue buffer:
                                          ...enqueue
                                          ...signal
Produce(item) {
                                          ...unlock
    pthread_mutex_lock(&lock);
                                                             Consume()
    buffer.engueue(item);
                                                             ...lock
    pthread cond signal(&data readv)
                                                             ...empty? no
    pthread mutex unlock(&lock):
                                                             ...dequeue
                                                             ...unlock
Consume() {
                                                             return
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
         pthread cond wait(&data ready, &lock);
    item = buffer.dequeue();
    pthread mutex unlock(&lock)
                                     O iterations: Produce() called before Consume()
                                       iteration: Produce() signalled, probably
    return item:
                                         iterations: spurious wakeup or ...?
```

```
Thread 1
                                                                  Thread 2
pthread_mutex_t lock;
                                                              Consume()
pthread_cond_t data_ready;
                                                              ...lock
UnboundedQueue buffer;
                                                              ...empty? ves
                                                              ...unlock/start wait
Produce(item) {
                                                  Produce()
                                                                   waiting for
    pthread_mutex_lock(&lock);
                                                  ...lock
                                                                  data ready
    buffer.engueue(item);
                                                  ...enqueue
    pthread cond signal(&data ready):
                                                  ...signal
                                                              stop wait
    pthread mutex unlock(&lock):
                                                  ...unlock
                                                              lock
                                                              ...empty? no
Consume() {
                                                              ...deaueue
    pthread_mutex_lock(&lock);
                                                              ...unlock
    while (buffer.empty()) {
                                                              return
         pthread cond_wait(&data_ready, &loc
    item = buffer.dequeue();
    pthread mutex unlock(&lock)
                                      0 iterations: Produce() called before Consume()
                                        iteration: Produce() signalled, probably
    return item:
```

iterations: spurious wakeup or ...?

```
Thread 1
                                                         Thread 2
                                                                         Thread 3
pthread_mutex_t lock;
                                                    Consume()
pthread_cond_t data_ready;
                                                    ...lock
UnboundedOueue buffer:
                                                    ...empty? ves
                                                    ...unlock/start wait
Produce(item) {
                                        Produce()
                                                         waiting for
     pthread_mutex_lock(&lock);
                                        ...lock
                                                                         Consume()
                                                         data ready
     buffer.engueue(item);
                                        ...enqueue
                                                                         waiting for
    pthread_cond_signal(&data_rea
                                        ...signal
                                                    stop wait
                                                                            lock
     pthread mutex unlock(&lock):
                                        ...unlock
                                                                        lock
                                                         waiting for
                                                                         ...empty? no
Consume() {
                                                            lock
                                                                         ...deaueue
     pthread_mutex_lock(&lock);
                                                                         ...unlock
    while (buffer.empty()) {
                                                    ...lock
                                                                        return
         pthread cond wait(&data r
                                                    ...empty? yes
                                                    ...unlock/start wait
     item = buffer.dequeue();
     pthread mutex unlock(&lock)
                                       0 iterations: Produce() called before Consume()
                                         iteration: Produce() signalled, probably
     return item:
                                          iterations: spurious wakeup or ...?
```



Hoare versus Mesa monitors

```
Hoare-style monitors signal 'hands off' lock to awoken thread
```

```
Mesa-style monitors

any eligible thread gets lock next

(maybe some other idea of priority?)
```

every current threading library I know of does Mesa-style

```
pthread_mutex_t lock;
pthread cond t data ready; pthread cond t space ready;
BoundedQueue buffer;
Produce(item) {
   pthread_mutex_lock(&lock);
   while (buffer.full()) { pthread_cond_wait(&space_ready, &lock); }
   buffer.engueue(item);
    pthread_cond_signal(&data_ready);
   pthread_mutex_unlock(&lock);
Consume() {
   pthread_mutex_lock(&lock);
   while (buffer.empty()) {
        pthread cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread cond signal(&space ready);
    pthread mutex unlock(&lock):
    return item:
```

```
pthread_mutex_t lock;
pthread cond t data ready; pthread cond t space ready;
BoundedQueue buffer;
Produce(item) {
   pthread_mutex_lock(&lock);
   while (buffer.full()) { pthread_cond_wait(&space_ready, &lock); }
   buffer.engueue(item);
    pthread_cond_signal(&data_ready);
   pthread_mutex_unlock(&lock);
Consume() {
   pthread_mutex_lock(&lock);
   while (buffer.empty()) {
        pthread cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread cond signal(&space ready);
    pthread mutex unlock(&lock):
    return item:
```

```
pthread_mutex_t lock;
pthread cond t data ready; pthread cond t space ready;
BoundedQueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
   while (buffer.full()) { pthread_cond_wait(&space_ready, &lock); }
    buffer.engueue(item);
    pthread cond signal (&data ready):
   pt correct (but slow?) to replace with:
Consum pthread_cond_broadcast(&space_ready);
      (just more "spurious wakeups")
        pthread cond wait(&data ready, &lock);
    item = buffer.dequeue();
    pthread cond signal(&space ready);
    pthread mutex unlock(&lock):
    return item:
```

return item:

```
pthread_mutex_t lock;
pthread cond t data ready; pthread cond t space ready;
BoundedQueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
   while (buffer.full()) { pthread_cond_wait(&space_ready, &lock); }
    buffer.engueue(item);
                                              correct but slow to replace
    pthread_cond_signal(&data_ready);
                                              data ready and space ready
   pthread_mutex_unlock(&lock);
                                              with 'combined' condvar ready
Consume() {
                                              and use broadcast.
   pthread_mutex_lock(&lock);
                                              (just more "spurious wakeups")
   while (buffer.empty()) {
        pthread cond wait(&data ready, &lock);
    item = buffer.dequeue();
    pthread cond signal(&space ready);
    pthread_mutex_unlock(&lock);
```

monitor pattern

pthread mutex unlock(&lock)

```
pthread mutex lock(&lock);
while (!condition A) {
    pthread cond_wait(&condvar_for_A, &lock);
... /* manipulate shared data, changing other conditions */
if (set condition A) {
    pthread_cond_broadcast(&condvar_for_A);
    /* or signal, if only one thread cares */
if (set condition B) {
    pthread cond broadcast(&condvar for B);
    /* or signal, if only one thread cares */
```

54

monitors rules of thumb

never touch shared data without holding the lock keep lock held for entire operation: verifying condition (e.g. buffer not full) up to and including manipulating data (e.g. adding to buffer) create condvar for every kind of scenario waited for always write loop calling cond wait to wait for condition X broadcast/signal condition variable every time you change X

monitors rules of thumb

never touch shared data without holding the lock

```
keep lock held for entire operation:
```

verifying condition (e.g. buffer not full) up to and including manipulating data (e.g. adding to buffer)

create condvar for every kind of scenario waited for

always write loop calling cond_wait to wait for condition X

broadcast/signal condition variable every time you change X

correct but slow to...

broadcast when just signal would work broadcast or signal when nothing changed use one condvar for multiple conditions

mutex/cond var init/destroy

```
pthread mutex t mutex;
pthread cond t cv:
pthread mutex init(&mutex, NULL);
pthread cond init(&cv, NULL);
// --OR--
pthread mutex t mutex = PTHREAD MUTEX INITIALIZER;
pthread cond t cv = PTHREAD COND INITIALIZER:
// and when done:
pthread cond destroy(&cv):
pthread mutex destroy(&mutex):
```

wait for both finished

```
// MISSING: init calls, etc.
pthread mutex t lock:
bool finished[2]:
pthread cond t both finished cv:
void WaitForBothFinished() {
  pthread mutex lock(&lock);
 while (_____) {
   pthread_cond_wait(&both_finished cv, &lock):
  pthread_mutex_unlock(&lock);
void Finish(int index) {
  pthread mutex lock(&lock);
  finished[index] = true;
 pthread mutex unlock(&lock):
```

wait for both finished

```
// MISSING: init calls, etc.
pthread mutex t lock:
bool finished[2]:
pthread cond t both finished cv:
void WaitForBothFinished() {
 pthread mutex lock(&lock);
 while (
   pthread cond wait(&both finished cv, &lock);
  pthread_mutex_unlock(&lock);
void Finish(int index) {
  pthread mutex lock(&lock);
  finished[index] = true;
  pthread mutex unlock(&lock):
```

A. finished[0] && finished[1]
B. finished[0] || finished[1]
C. !finished[0] || !finished[1]
D. finished[0] != finished[1]
E. something else

wait for both finished

```
// MISSING: init calls, etc.
pthread mutex t lock:
                           A. pthread cond signal(&both finished cv)
bool finished[2];
                           B. pthread_cond_broadcast(&both_finished_cv)
pthread cond t both fini
                           C. if (finished[1-index])
                                   pthread_cond_signal(&both_finished_cv);
void WaitForBothFinished D if (finished[1-index])
  pthread mutex lock(&lo
                                   pthread cond broadcast(&both finished cv);
  while (
                           E. something else
    pthread cond wait(&both finished cv, &lock);
  pthread_mutex_unlock(&lock);
void Finish(int index) {
  pthread mutex lock(&lock);
  finished[index] = true;
  pthread mutex unlock(&lock):
```

monitor exercise: barrier

```
suppose we want to implement a one-use barrier; fill in blanks:
struct BarrierInfo {
    pthread mutex t lock;
    int total threads; // initially total # of threads
    int number reached; // initially 0
void BarrierWait(BarrierInfo *b) {
    pthread mutex lock(&b->lock);
    ++b->number reached:
    if (b->number reached == b->total threads) {
    } else {
    pthread mutex unlock(&b->lock);
```

monitor exercise: barrier

```
struct BarrierInfo {
    pthread mutex t lock;
    int total threads: // initially total # of threads
    int number reached; // initially 0
    pthread_cond_t cv;
};
void BarrierWait(BarrierInfo *b) {
    pthread mutex lock(&b->lock);
    ++b->number_reached;
    if (b->number reached == b->total threads) {
        pthread cond broadcast(&b->cv):
    } else {
        while (b->number reached < b->total threads)
            pthread_cond_wait(&b->cv, &b->lock);
    pthread mutex unlock(&b->lock):
```

generalizing locks: semaphores

semaphore has a non-negative integer value and two operations:

P() or **down** or **wait**: wait for semaphore to become positive (>0), then decerement by 1

V() or **up** or **signal** or **post**: increment semaphore by 1 (waking up thread if needed)

P, V from Dutch: proberen (test), verhogen (increment)

semaphores are kinda integers

semaphore like an integer, but...

cannot read/write directly

down/up operaion only way to access (typically) exception: initialization

never negative — wait instead

down operation wants to make negative? thread waits

reserving books

```
suppose tracking copies of library book...
Semaphore free copies = Semaphore(3);
void ReserveBook() {
    // wait for copy to be free
    free copies.down();
    ... // ... then take reserved copy
void ReturnBook() {
    ... // return reserved copy
    free_copies.up();
    // ... then wakekup waiting thread
```


counting resources: reserving books

suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book

Copy 1 Copy 2 Copy 3 free copies 3


counting resources: reserving books

suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book






suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book




free copies 2 after calling down to reserve


suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book



free copies 0 after calling down three times to reserve all copies


suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book





reserve book call down again start waiting...

suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book



implementing mutexes with semaphores

```
struct Mutex {
    Semaphore s; /* with inital value 1 */
   /* value = 1 --> mutex if free */
   /* value = 0 --> mutex is busy */
MutexLock(Mutex *m) {
   m->s.down();
MutexUnlock(Mutex *m) {
   m->s.up();
```

implementing join with semaphores

```
struct Thread {
    Semaphore finish_semaphore; /* with initial value 0 */
   /* value = 0: either thread not finished OR already joined */
   /* value = 1: thread finished AND not joined */
thread join(Thread *t) {
    t->finish semaphore.down();
/* assume called when thread finishes */
thread exit(Thread *t) {
    t->finish semaphore.up();
   /* tricky part: deallocating struct Thread safely? */
```

POSIX semaphores

```
#include <semaphore.h>
sem t my semaphore;
int process_shared = /* 1 if sharing between processes */;
sem_init(&my_semaphore, process_shared, initial_value);
sem wait(&my_semaphore); /* down */
sem post(&my semaphore); /* up */
. . .
sem destroy(&my semaphore);
```

semaphore exercise

PutValue()

```
int value; sem t empty, ready; // with some initial values
void PutValue(int argument) {
    sem wait(&empty);
    value = argument;
                        What goes in the blanks?
    sem_post(&ready);
                        A: sem post(&empty) / sem wait(&ready)
                        B: sem_wait(&ready) / sem_post(&empty)
                        C: sem post(&ready) / sem wait(&empty)
int GetValue() {
                        D: sem post(&readv) / sem post(&emptv)
    int result:
                        E: sem_wait(&empty) / sem_post(&ready)
    result = value:
                        F: something else
    return result;
```

GetValue() waits for PutValue() to happen, retrieves value, then allows next

67

semaphore exercise [solution]

```
int value;
sem_t empty, ready;
void PutValue(int argument) {
    sem_wait(&empty):
    value = argument;
    sem post(&ready);
int GetValue() {
    int result;
    sem wait(&readv):
    result = value;
    sem post(&empty);
    return result:
```

semaphore intuition

```
What do you need to wait for?
     critical section to be finished
    queue to be non-empty
     array to have space for new items
what can you count that will be 0 when you need to wait?
     # of threads that can start critical section now
     # of threads that can join another thread without waiting
     # of items in queue
     # of empty spaces in array
```

use up/down operations to maintain count

producer/consumer constraints

consumer waits for producer(s) if buffer is empty producer waits for consumer(s) if buffer is full any thread waits while a thread is manipulating the buffer

producer/consumer constraints

```
consumer waits for producer(s) if buffer is empty producer waits for consumer(s) if buffer is full any thread waits while a thread is manipulating the buffer
```

one semaphore per constraint:

```
sem_t full_slots; // consumer waits if empty
sem_t empty_slots; // producer waits if full
sem_t mutex; // either waits if anyone changing buffer
FixedSizedQueue buffer;
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 /* # thread that can use buffer at once */):
buffer.set size(BUFFER CAPACITY):
. . .
Produce(item) {
    sem wait(&empty slots): // wait until free slot. reserve it
    sem wait(&mutex);
    buffer.engueue(item);
    sem_post(&mutex);
    sem post(&full slots): // tell consumers there is more data
Consume() {
    sem_wait(&full_slots); // wait until queued item, reserve it
    sem wait(&mutex);
    item = buffer.dequeue();
    sem post(&mutex);
    sem post(&empty slots); // let producer reuse item slot
    return item;
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem init(&empty slots, ..., BUFFER CAPACITY);
sem init(&mutex, ..., 1 /* # thread that can use buffer at once */):
buffer.set size(BUFFER CAPACITY):
. . .
Produce(item) {
    sem wait(&empty slots): // wait until free slot. reserve it
    sem wait(&mutex);
    buffer.engueue(item);
    sem_post(&mutex);
    sem_post(&full_slots); // tell consumers there is more data
Consume() {
    sem_wait(&full_slots); // wait until queued item, reserve it
    sem wait(&mutex);
    item = buffer.dequeue();
    sem post(&mutex);
    sem post(&empty slots); // let producer reuse item slot
    return item;
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem init(&empty slots, ..., BUFFER CAPACITY);
sem init(&mutex, ..., 1 /* # thread that can use buffer at once */):
buffer.set size(BUFFER CAPACITY):
. . .
Produce(item) {
    sem wait(&empty slots): // wait until free slot. reserve it
    sem wait(&mutex);
    buffer.engueue(item);
    sem_post(&mutex);
    sem_post(&full_slots); // tell consumers there is more data
Consume() {
    sem_wait(&full_slots); // wait until queued item, reserve it
    sem wait(&mutex);
    item = buffer.dequeue();
    sem post(&mutex);
    sem post(&empty slots); // let producer reuse item slot
    return item;
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem init(&emptv slots, ..., BUFFER CAPACITY);
sem_init(&mutex, ..., 1 /* # thread that can use buffer at once */):
buffer.set size(BUFFER CAPACITY):
Produce(item) {
   sem wait(&empty slots): // wait until free slot, reserve it
   sem wait(&mutex);
                           Can we do
   buffer.engueue(item);
                              sem wait(&mutex);
    sem_post(&mutex);
   sem post(&full slots);
                              sem wait(&empty slots);
                                                            data
                            instead?
Consume() {
   sem_wait(&full_slots); // wait until queued item, reserve it
   sem wait(&mutex);
    item = buffer.degueue():
   sem post(&mutex);
    sem post(&empty slots); // let producer reuse item slot
   return item;
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 /* # thread that can use buffer at once */):
buffer.set size(BUFFER CAPACITY):
Produce(item) {
   sem wait(&empty slots): // wait until free slot, reserve it
   sem wait(&mutex);
                           Can we do
    buffer.enqueue(item);
                              sem wait(&mutex);
    sem_post(&mutex);
    sem post(&full slots);
                                                            data
                              sem wait(&empty slots);
                            instead?
Consume() {
                           No. Consumer waits on sem wait(&mutex)
   sem wait(&full slots):
   sem wait(&mutex);
                           so can't sem post(&empty slots)
    item = buffer.dequeue()
                            (result: producer waits forever
   sem post(&mutex);
   sem_post(&empty_slots);
                            problem called deadlock)
   return item;
```

producer/consumer: cannot reorder mutex/empty

```
ProducerReordered() {
    // BROKEN: WRONG ORDER
    sem_wait(&mutex);
    sem_wait(&empty_slots);
    ...
    sem_post(&mutex);
```

```
Consumer() {
   sem_wait(&full_slots);

// can't finish until
   // Producer's sem_post(&mutex):
   sem_wait(&mutex);

...

// so this is not reached
```

sem post(&full slots);

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 /* # thread that can use buffer at once */):
buffer.set size(BUFFER CAPACITY):
Produce(item) {
    sem wait(&empty slots): // wait until free slot. reserve it
    sem wait(&mutex);
    buffer.engueue(item);
    sem_post(&mutex);
   sem_post(&full_slots Can we do
                                                       more data
                           sem_post(&full_slots);
Consume() {
                           sem post(&mutex);
   sem wait(&full slots
                                                       reserve it
                        instead?
   sem wait(&mutex);
   item = buffer.dequeu Yes — post never waits
   sem post(&mutex);
   sem_post(&empty_slots); // let producer reuse item slot
   return item;
```

73

producer/consumer summary

```
producer: wait (down) empty_slots, post (up) full_slots consumer: wait (down) full_slots, post (up) empty_slots
```

two producers or consumers? still works!

transactions

transaction: set of operations that occurs atomically idea: something higher-level handles locking, etc.: BeginTransaction(); int FromOldBalance = GetBalance(FromAccount); int ToOldBalance = GetBalance(ToAccount); SetBalance(FromAccount, FromOldBalance - 100); SetBalance(ToAccount, FromOldBalance + 100); EndTransaction(); idea: library/database/etc. makes "transaction" happens all at once

consistency / durability

"happens all at once" = could mean:

locking to make sure no other operations interfere (consistency) making sure on crash, no partial transaction seen (durability)

(some systems provide both, some provide only one)

we'll just talk about implementing consistency

implementing consistency: simple

simplest idea: only one run transaction at a time

implementing consistency: locking

everytime something read/written: acquire associated lock

on end transaction: release lock

if deadlock: undo everything, go back to BeginTransaction(), retry how to undo?
one idea: keep list of writes instead of writing apply writes only at EndTransaction()

implementing consistency: locking

everytime something read/written: acquire associated lock

on end transaction: release lock

```
if deadlock: undo everything, go back to BeginTransaction(), retry how to undo? one idea: keep list of writes instead of writing apply writes only at EndTransaction()
```

implementing consistency: optimistic

on read: copy version # for value read

on write: record value to be written, but don't write yet

on end transaction:

acquire locks on everything make sure values read haven't been changed since read

if they have changed, just retry transaction

backup slides

atomic read-modfiy-write

really hard to build locks for atomic load store and normal load/stores aren't even atomic...

...so processors provide read/modify/write operations

one instruction that atomically reads and modifies and writes back a value

used by OS to implement higher-level synchronization tools

x86 atomic exchange

```
lock xchg (%ecx), %eax
atomic exchange
temp ← M[ECX]
M[ECX] \leftarrow EAX
\mathsf{EAX} \leftarrow \mathsf{temp}
...without being interrupted by other processors, etc.
```

implementing atomic exchange

make sure other processors don't have cache block probably need to be able to do this to keep caches in sync

do read+modify+write operation

higher level tools

```
usually we won't use atomic operations directly instead rely on OS/standard libraries using them (along with context switching, disabling interrupts, ...)
OS/standard libraries will provide higher-level tools like...
```

```
pthread_join
locks (pthread_mutex)
...and more
```

backup slides

backup slides

using atomic exchange?

example: OS wants something done by whichever core tries first does not want it started twice!

```
if two cores try at once, only one should do it
int global flag = 0;
void DoThingIfFirstToTrv() {
    int mv value = 1:
    AtomicExchange(&my_value, &global_flag);
    if (my value == 0) {
        /* flag was zero before, so I was first!*/
        DoThing();
    } else {
        /* flag was already 1 when we exchanged */
        /* I was second, so some other core is handling it */
```

recall: pthread mutex


```
#include <pthread.h>
pthread mutex t some lock;
pthread mutex init(&some lock, NULL);
// or: pthread mutex_t some_lock = PTHREAD_MUTEX_INITIALIZER;
pthread_mutex_lock(&some lock);
pthread_mutex_unlock(&some_lock);
pthread mutex destroy(&some lock);
```

life homework even/odd

```
naive way has an operation that needs locking:
for (int time = 0; time < MAX ITERATIONS; ++time) {</pre>
    ... compute to_grid ...
    swap(from grid, to grid);
but this alternative needs less locking:
Grid grids[2];
for (int time = 0; time < MAX ITERATIONS; ++time) {</pre>
    from grid = &grids[time % 2];
    to grid = &grids[(time % 2) + 1];
    ... compute to_grid ...
```

life homework even/odd

```
naive way has an operation that needs locking:
for (int time = 0; time < MAX ITERATIONS; ++time) {</pre>
    ... compute to_grid ...
    swap(from grid, to grid);
but this alternative needs less locking:
Grid grids[2];
for (int time = 0; time < MAX ITERATIONS; ++time) {</pre>
    from grid = &grids[time % 2];
    to grid = &grids[(time % 2) + 1];
    ... compute to_grid ...
```



movl \$0, the_lock

ret

lock variable in shared memory: the_lock

```
if 1: someone has the lock: if 0: lock is free to take
acquire:
    movl $1, %eax <- 1
    lock xchg %eax, the lock // swap %eax and the lock
                                   // sets the lock to 1 (taken)
                                   // sets %eax to prior val. of t
    test %eax, %eax
                             // if the lock wasn't 0 before:
    ine acquire
                             // trv again
    ret
release:
    mfence
                             // for memory order reasons
```

// then, set the lock to 0 (not taker

lock variable in shared memory: the lock

if 1: someone has the lock; if 0: lock is free to take

acquire: movl \$1, %eax // %eax <- 1 lock xchg %eax, the lock // swap %eax and the lock // sets the lock to 1 (taken) // if set lock variable to 1 (taken) read old value test %eax, %eax ine acquire ret release: mfence // for memory order reasons // then, set the lock to 0 (not taker movl \$0, the_lock ret

lock variable in shared memory: the lock if 1: someone has the lock; if 0: lock is free to take acquire: movl \$1, %eax <- 1 lock xchg %eax, the lock // swap %eax and the lock // sets the_lock to 1 (taken) if lock was already locked retry test %eax, %eax ine acquire "spin" until lock is released elsewhere ret release: mfence // for memory order reasons // then, set the lock to 0 (not taker movl \$0, the_lock ret

lock variable in shared memory: the lock

if 1: someone has the lock; if 0: lock is free to take

acquire: movl \$1, %eax <- 1 lock xchg %eax, the lock // swap %eax and the lock // sets the lock to 1 (taken) release lock by setting it to 0 (not taken) test %eax, %eax ine acquire allows looping acquire to finish ret release: mfence // for memory order reasons // then, set the lock to 0 (not taker movl \$0, the lock ret

ret

lock variable in shared memory: the lock

if 1: someone has the lock; if 0: lock is free to take acquire: movl \$1, %eax <- 1 lock xchg %eax, the_lock // swap %eax and the_lock // sets the lock to 1 (taken) Intel's manual says: test %eax, %eax no reordering of loads/stores across a lock ine acquire or mfence instruction ret release: mfence // for memory order reasons // then, set the lock to 0 (not taker movl \$0, the lock

exercise: spin wait

consider implementing 'waiting' functionality of pthread_join

A mfanca, may \$1 finished C may \$0 gray E is

```
thread calls ThreadFinish() when done complete code below:
```

```
finished: .quad 0
ThreadFinish:
```

```
------
ret
```

ThreadWaitForFinish:

```
lock xchg %eax, finished
cmp $0, %eax
____ ThreadWaitForFinish
ret
```

exercise: spin wait

```
finished: .quad 0
ThreadFinish:
   Α
   ret
ThreadWaitForFinish:
                              /* or without using a writing instr
                              mov %eax, finished
   lock xchg %eax, finished
                              mfence
                              cmp $0, %eax
   cmp $0, %eax
   C ThreadWaitForFinish
                              ie ThreadWaitForFinish
   ret
                              ret
A. mfence; mov $1, finished C. mov $0, %eax E. je
B. mov $1, finished; mfence D. mov $1, %eax F. jne
```

spinlock problems

lock abstraction is not powerful enough lock/unlock operations don't handle "wait for event" common thing we want to do with threads solution: other synchronization abstractions

spinlocks waste CPU time more than needed want to run another thread instead of infinite loop solution: lock implementation integrated with scheduler

spinlocks can send a lot of messages on the shared bus more efficient atomic operations to implement locks

spinlock problems

lock abstraction is not powerful enough lock/unlock operations don't handle "wait for event" common thing we want to do with threads solution: other synchronization abstractions

spinlocks waste CPU time more than needed

want to run another thread instead of infinite loop solution: lock implementation integrated with scheduler

spinlocks can send a lot of messages on the shared bus more efficient atomic operations to implement locks

mutexes: intelligent waiting

want: locks that wait better example: POSIX mutexes

instead of running infinite loop, give away CPU

```
lock = go to sleep, add self to list sleep = scheduler runs something else
```

unlock = wake up sleeping thread

mutexes: intelligent waiting

want: locks that wait better example: POSIX mutexes

instead of running infinite loop, give away CPU

```
lock = go to sleep, add self to list
sleep = scheduler runs something else
```

unlock = wake up sleeping thread

better lock implementation idea

shared list of waiters

spinlock protects list of waiters from concurrent modification

lock = use spinlock to add self to list, then wait without spinlock

unlock = use spinlock to remove item from list

better lock implementation idea

shared list of waiters

spinlock protects list of waiters from concurrent modification

lock = use spinlock to add self to list, then wait without spinlock unlock = use spinlock to remove item from list

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

spinlock protecting lock_taken and wait_queue
only held for very short amount of time (compared to mutex itself)

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

tracks whether any thread has locked and not unlocked

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

list of threads that discovered lock is taken and are waiting for it be free these threads are not runnable

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

```
LockMutex(Mutex *m) {
                                            UnlockMutex(Mutex *m) {
 LockSpinlock(&m->guard_spinlock);
                                              LockSpinlock(&m->guard_spinlock);
 if (m->lock taken) {
                                              if (m->wait queue not empty) {
   put current thread on m->wait_queue
                                                remove a thread from m->wait_queue
   mark current thread as waiting
                                                mark thread as no longer waiting
   /* xv6: mvproc()->state = SLEEPING: */
                                                /* xv6: mvproc()->state = RUNNABLE: *,
   UnlockSpinlock(&m->guard_spinlock);
                                              } else {
   run scheduler (context switch)
                                                 m->lock_taken = false;
 } else {
   m->lock taken = true;
                                              UnlockSpinlock(&m->guard spinlock);
```

UnlockMutex(Mutex *m) {

} else {

LockSpinlock(&m->guard_spinlock);

remove a thread from m->wait_queue

/* xv6: mvproc()->state = RUNNABLE: *,

mark thread as no longer waiting

UnlockSpinlock(&m->guard spinlock);

if (m->wait queue not empty) {

m->lock_taken = false;

```
struct Mutex {
    SpinLock guard spinlock:
    bool lock taken = false;
    WaitOueue wait queue:
};
instead of setting lock taken to false
choose thread to hand-off lock to
```

```
LockMutex(Mutex *m) {
 LockSpinlock(&m->guard spinlock):
 if (m->lock taken) {
   put current thread on m->wait_queue
   mark current thread as waiting
   /* xv6: mvproc()->state = SLEEPING: */
   UnlockSpinlock(&m->guard_spinlock);
   run scheduler (context switch)
 } else {
   m->lock taken = true;
```

run scheduler (context switch)

m->lock taken = true;

} else {

```
struct Mutex {
    SpinLock guard spinlock:
    bool lock taken = false;
    WaitOueue wait queue:
};
subtly: if UnlockMutex runs here on another core
while it is still running (would 'clone' thread/mess up registers)
LockMutex(Mutex *m) {
```

```
subtly: if UnlockMutex runs here on another core
need to make sure scheduler on the other core doesn't switch to thread
while it is still running (would 'clone' thread/mess up registers)

LockMutex(Mutex *m) {
    LockSpinlock(&m->guard_spinlock);
    if (m->lock_taken) {
        put current thread on m->wait_queue
        mark current thread as waiting
        /* xv6: myproc()->state = SLEEPING; */
    UnlockSpinlock(&m->guard_spinlock);
    if (m->wait_queue not empty) {
        remove a thread from m->wait_queue
        mark thread as no longer waiting
        /* xv6: myproc()->state = RUNNABLE; */
    UnlockSpinlock(&m->guard_spinlock);
    if (m->wait_queue not empty) {
        remove a thread from m->wait_queue
        mark thread as no longer waiting
        /* xv6: myproc()->state = RUNNABLE; */
        else {
```

m->lock_taken = false;

UnlockSpinlock(&m->guard spinlock);

```
struct Mutex {
   SpinLock guard spinlock:
    bool lock taken = false;
   WaitOueue wait queue:
```

} else {

```
};
LockMutex(Mutex *m) {
                                            UnlockMutex(Mutex *m) {
 LockSpinlock(&m->guard_spinlock);
                                              LockSpinlock(&m->guard_spinlock);
 if (m->lock taken) {
                                              if (m->wait queue not empty) {
   put current thread on m->wait_queue
                                                remove a thread from m->wait_queue
   mark current thread as waiting
                                                mark thread as no longer waiting
   /* xv6: myproc()->state = SLEEPING; */
                                                /* xv6: mvproc()->state = RUNNABLE: *,
```

UnlockSpinlock(&m->guard spinlock); } else { run scheduler (context switch) m->lock_taken = false; m->lock taken = true; UnlockSpinlock(&m->guard spinlock);

mutex and scheduler subtly

| core 0 (thread A) | core 1 (thread B) | |
|---------------------------|-------------------------------|--|
| start LockMutex | | |
| acquire spinlock | | |
| discover lock taken | | |
| enqueue thread A | | |
| thread A set not runnable | | |
| release spinlock | start UnlockMutex | |
| | thread A set runnable | |
| | finish UnlockMutex | |
| | run scheduler | |
| | scheduler switches to A | |
| | with old verison of registers | |
| thread A runs scheduler | | |
| finally saving registers | | |

Linux soln.: track 'thread running' separately from 'thread

mutex and scheduler subtly

| core 0 (thread A) | core 1 (thread B) | |
|---------------------------|-------------------------------|--|
| start LockMutex | | |
| acquire spinlock | | |
| discover lock taken | | |
| enqueue thread A | | |
| thread A set not runnable | | |
| release spinlock | start UnlockMutex | |
| | thread A set runnable | |
| | finish UnlockMutex | |
| | run scheduler | |
| | scheduler switches to A | |
| | with old verison of registers | |
| thread A runs scheduler | | |
| finally saving registers | | |

Linux soln.: track 'thread running' separately from 'thread

mutex efficiency

'normal' mutex uncontended case:

lock: acquire + release spinlock, see lock is free unlock: acquire + release spinlock, see queue is empty

not much slower than spinlock

implementing locks: single core

intuition: context switch only happens on interrupt timer expiration, I/O, etc. causes OS to run

solution: disable them reenable on unlock

implementing locks: single core

intuition: context switch only happens on interrupt timer expiration, I/O, etc. causes OS to run

solution: disable them reenable on unlock

x86 instructions:

cli — disable interrupts

sti — enable interrupts

```
Lock() {
    disable interrupts
}
Unlock() {
    enable interrupts
}
```

```
Lock() {
    disable interrupts
}

problem: user can hang the system:
    Lock(some_lock);
    while (true) {}
```

```
Lock() {
                             Unlock() {
    disable interrupts
                                  enable interrupts
problem: user can hang the system:
            Lock(some lock):
            while (true) {}
problem: can't do I/O within lock
            Lock(some lock);
             read from disk
                /* waits forever for (disabled) interrupt
                    from disk IO finishina */
```

```
Lock() {
    disable interrupts
}
Unlock() {
    enable interrupts
}
```

```
Lock() {
    disable interrupts
}
Unlock() {
    enable interrupts
}
```

```
Lock() {
    disable interrupts
}
Unlock() {
    enable interrupts
}
```

```
Unlock() {
Lock() {
    disable interrupts
                                 enable interrupts
problem: nested locks
        Lock(milk lock);
        if (no milk) {
            Lock(store lock);
            buv milk
            Unlock(store_lock);
            /* interrupts enabled here?? */
        Unlock(milk lock);
```

C++ containers and locking

can you use a vector from multiple threads?

...question: how is it implemented?

C++ containers and locking

can you use a vector from multiple threads?

...question: how is it implemented? dynamically allocated array reallocated on size changes

C++ containers and locking

can you use a vector from multiple threads?

```
...question: how is it implemented?
dynamically allocated array
reallocated on size changes
```

```
can access from multiple threads ...as long as not append/erase/etc.?
```

assuming it's implemented like we expect...

but can we really depend on that?

e.g. could shrink internal array after a while with no expansion save

memory?

C++ standard rules for containers

multiple threads can read anything at the same time

can only read element if no other thread is modifying it

can safely add/remove elements if no other threads are accessing container

(sometimes can safely add/remove in extra cases)

exception: vectors of bools — can't safely read and write at same time

might be implemented by putting multiple bools in one int

a simple race

```
thread A:
                                    thread B:
                                        movl $1, y /* y <- 1 */
    movl $1, x /* x <- 1 */
    movl v, %eax /* return v */
                                        movl x, %eax /* return x */
    ret
                                        ret
     x = y = 0;
     pthread_create(&A, NULL, thread_A, NULL);
     pthread create(&B, NULL, thread B, NULL);
     pthread_join(A, &A_result); pthread_join(B, &B_result);
     printf("A:%d<sub>\\\\\</sub>B:%d\\\\n", (int) A result, (int) B result);
```

a simple race

```
thread A:
                                    thread B:
   movl $1, x /* x <- 1 */
                                        movl $1, y /* y <- 1 */
   movl v, %eax /* return v */
                                        movl x, %eax /* return x */
    ret
                                         ret
     x = y = 0;
     pthread_create(&A, NULL, thread_A, NULL);
     pthread create(&B, NULL, thread B, NULL);
     pthread_join(A, &A_result); pthread_join(B, &B_result);
     printf("A:%d<sub>\\\\\</sub>B:%d\\\\n", (int) A result, (int) B result);
```

if loads/stores atomic, then possible results: A:1 B:1 — both moves into x and y, then both moves into eax execute

A·0 B·1 — thread A executes before thread B A:1 B:0 — thread B executes before thread A

a simple race: results

204

4706 A:1 B:1 ('execute moves into x+y first')

 $\Lambda \cdot \cap \mathbb{R} \cdot \cap |222$

a simple race: results

printf("A:%d\B:%d\n", (int) A result, (int) B result);

 $4706 \mid A:1 \mid B:1 \mid \text{('execute moves into x+y first')}$

my desktop, 100M trials:

frequency result

99 823 739 A:0 B:1 ('A executes before B')

171 161 A:1 B:0 ('B executes before A')

204 | A.O. R.O. | 222

why reorder here?

thread A: faster to load y right now!

...rather than wait for write of x to finish

why load/store reordering?

fast processor designs can execute instructions out of order

goal: do something instead of waiting for slow memory accesses, etc.

more on this later in the semester

GCC: preventing reordering example (1)

```
void Alice() {
   int one = 1:
    atomic store(&note from alice, &one, ATOMIC SEO CST);
    } ob
   } while (__atomic_load_n(&note_from_bob, __ATOMIC_SEQ_CST));
    if (no milk) {++milk;}
Alice:
  movl $1, note_from_alice
  mfence
.12:
  movl note from bob, %eax
```

testl %eax, %eax
jne .L2
...

GCC: preventing reordering example (2)

void Alice() {
 note_from_alice = 1;
 do {
 __atomic_thread_fence(__ATOMIC_SEQ_CST);
 } while (note_from_bob);
 if (no_milk) {++milk;}
}

```
Alice:
   movl $1, note_from_alice // note_from_alice <- 1
.L3:
```

ine .L3

cmnl \$0 no milk

exercise: fetch-and-add with compare-and-swap

exercise: implement fetch-and-add with compare-and-swap

```
compare_and_swap(address, old_value, new_value) {
    if (memory[address] == old_value) {
        memory[address] = new_value;
        return true; // x86: set ZF flag
    } else {
        return false; // x86: clear ZF flag
    }
}
```

solution

```
long my_fetch_and_add(long *p, long amount) {
    long old_value;
    do {
        old_value = *p;
    while (!compare_and_swap(p, old_value, old_value + amount);
    return old_value;
}
```

```
void
acquire(struct spinlock *lk)
  pushcli(); // disable interrupts to avoid deadlock.
  // The xchq is atomic.
 while(xchg(&lk->locked, 1) != 0)
 // Tell the C compiler and the processor to not move loads or sto
 // past this point, to ensure that the critical section's memory
 // references happen after the lock is acquired.
 __sync_synchronize();
  . . .
```

```
void
acquire(struct spinlock *lk)
  pushcli(); // disable interrupts to avoid deadlock.
  // The xchq is atomic.
  while(xchg(&lk->locked, 1) != 0)
    don't let us be interrupted after while have the lock
     problem: interruption might try to do something with the lock
     \ldots but \ that \ can \ never succeed until we release the lock
     ...but we won't release the lock until interruption finishes
```

```
void
acquire(struct spinlock *lk)
  pushcli(); // disable interrupts to avoid deadlock.
 // The xchq is atomic.
 while(xchg(&lk->locked, 1) != 0)
 // Tell the C compiler and the processor to not move loads or sto
 // past this point, to ensure that the critical section's memory
 // references happen after the lock is acquired.
 --sync_synchr xchg wraps the lock xchg instruction
                same loop as before
```

```
void
acquire(struct spinlock *lk)
  pushcli(); // disable interrupts to avoid deadlock.
  // The xchq is atomic.
  while(xchg(&lk->locked, 1) != 0)
  // Tell the C compiler and the processor to not move loads or sto
     avoid load store reordering (including by compiler)
    on x86, xchg alone is enough to avoid processor's reordering
     (but compiler may need more hints)
```

```
void
release(struct spinlock *lk)
 // Tell the C compiler and the processor to not move loads or sto
 // past this point, to ensure that all the stores in the critical
 // section are visible to other cores before the lock is released
 // Both the C compiler and the hardware may re-order loads and
 // stores; __sync_synchronize() tells them both not to.
 sync synchronize();
  // Release the lock, equivalent to lk->locked = 0.
 // This code can't use a C assignment, since it might
 // not be atomic. A real OS would use C atomics here.
  asm volatile("movlu$0,u%0" : "+m" (lk->locked) : );
 popcli();
```

```
void
release(struct spinlock *lk)
  // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that all the stores in the critical
  // section are visible to other cores before the lock is released
  // Both the C compiler and the hardware may re-order loads and
  // stores; __sync_synchronize() tells them both not to.
  sync synchronize();
  // Release the lock, equivalent to lk->locked = 0.
  // This code can't use a C assignment, since it might
  // not
  turns into instruction to tell processor not to reorder plus tells compiler not to reorder
  popcli (),
```

```
void
release(struct spinlock *lk)
 // Tell the C compiler and the processor to not move loads or sto
 // past this point, to ensure that all the stores in the critical
 // section are visible to other cores before the lock is released
 // Both the C compiler and the hardware may re-order loads and
 // stores; __sync_synchronize() tells them both not to.
  sync synchronize();
  // Release the lock, equivalent to lk->locked = 0.
 // This code can't use a C assignment, since it might
 // not be atomic. A real OS would use C atomics here.
  asm volatile("movlu$0...%0" : "+m" (lk->locked) : ):
         turns into mov of constant 0 into lk->locked
 popcli()
```

```
void
release(struct spinlock *lk)
 // Tell the C compiler and the processor to not move loads or sto
 // past this point, to ensure that all the stores in the critical
 // section are visible to other cores before the lock is released
 // Both the C compiler and the hardware may re-order loads and
 // stores; __sync_synchronize() tells them both not to.
  sync synchronize();
  // Release the lock, equivalent to lk->locked = 0.
 // This code can't use a C assignment, since it might
  // not be atomic. A real OS would use C atomics here.
       reenable interrupts (taking nested locks into account)
```

fetch-and-add with CAS (1)

[compare-and-swap] if not successful, repeat

```
compare-and-swap(address, old value, new value) {
    if (memory[address] == old value) {
        memorv[address] = new_value;
        return true;
    } else {
        return false;
long my fetch and add(long *pointer, long amount) { ... }
implementation sketch:
    fetch value from pointer old
    compute in temporary value result of addition new
    try to change value at pointer from old to new
```

fetch-and-add with CAS (2)

```
long my_fetch_and_add(long *p, long amount) {
    long old_value;
    do {
        old_value = *p;
    } while (!compare_and_swap(p, old_value, old_value + amount);
    return old_value;
}
```

exercise: append to singly-linked list

ListNode is a singly-linked list assume: threads *only* append to list (no deletions, reordering) use compare-and-swap(pointer, old, new): atomically change *pointer from old to new return true if successful return false (and change nothing) if *pointer is not old void append_to_list(ListNode *head, ListNode *new_last_node) {

append to singly-linked list

```
/* assumption: other threads may be appending to list,
               but nodes are not being removed, reordered, etc.
void append to list(ListNode *head, ListNode *new last node) {
 memorv_ordering_fence();
 ListNode *current last node:
  qo {
    current last node = head;
   while (current last node->next) {
      current last_node = current_last_node->next;
  } while (
    !compare-and-swap(&current_last_node->next,
                      NULL, new last node)
```

some common atomic operations (1)

```
// x86: emulate with exchange
test and set(address) {
    old value = memory[address];
    memory[address] = 1;
    return old_value != 0; // e.g. set ZF flag
// x86: xchq REGISTER, (ADDRESS)
exchange(register, address) {
    temp = memory[address];
    memory[address] = register;
    register = temp:
```

some common atomic operations (2)

```
// x86: mov OLD VALUE, %eax; lock cmpxchg NEW VALUE, (ADDRESS)
compare-and-swap(address, old value, new value) {
    if (memory[address] == old value) {
        memory[address] = new value;
        return true: // x86: set ZF flaa
    } else {
        return false; // x86: clear ZF flag
// x86: lock xaddl REGISTER. (ADDRESS)
fetch-and-add(address, register) {
    old value = memory[address];
    memory[address] += register;
    register = old_value;
```

common atomic operation pattern

```
try to do operation, ...
```

detect if it failed

if so, repeat

atomic operation does "try and see if it failed" part

cache coherency states

extra information for each cache block overlaps with/replaces valid, dirty bits

stored in each cache

update states based on reads, writes and heard messages on bus different caches may have different states for same block

MSI state summary

Modified value may be different than memory and I am the only one who has it

Shared value is the same as memory

Invalid I don't have the value; I will need to ask for it

MSI scheme

| from state | hear read | hear write | read | write | | |
|--|-----------|------------|-----------|-------------|--|--|
| Invalid | | | to Shared | to Modified | | |
| Shared | | to Invalid | | to Modified | | |
| Modified | to Shared | to Invalid | | _ | | |
| blue: transition requires sending message on bus | | | | | | |

MSI scheme

```
from state hear read hear write read write

Invalid — to Shared to Modified

Shared — to Invalid — to Modified

Modified to Shared to Invalid — —

blue: transition requires sending message on bus
```

```
example: write while Shared must send write — inform others with Shared state then change to Modified
```

MSI scheme


| from state | hear read | hear write | read | write | | |
|--|-----------|------------|-----------|-------------|--|--|
| Invalid | | | to Shared | to Modified | | |
| Shared | | to Invalid | | to Modified | | |
| Modified | to Shared | to Invalid | | | | |
| blue: transition requires sending message on bus | | | | | | |

```
example: write while Shared must send write — inform others with Shared state then change to Modified
```


example: hear write while Shared change to Invalid can send read later to get value from writer


example: write while Modified

MSI example




MSI example







127



CPU2 reads 0xA300





MSI: update memory

to write value (enter modified state), need to invalidate others can avoid sending actual value (shorter message/faster)

"I am writing address X" versus "I am writing Y to address X"

MSI: on cache replacement/writeback

still happens — e.g. want to store something else changes state to invalid

requires writeback if modified (= dirty bit)

cache coherency exercise

modified/shared/invalid; all initially invalid; 32B blocks, 8B read/writes

CPU 1: read 0x1000 CPU 2: read 0x1000

CPU 1:

CPU 1: write 0x1000

CPU 1: read 0x2000

CPU 2: read 0x1000

CPU 2: write 0x2008 CPU 3: read 0x1008

NA 1:0: 1/C1 1/1 1:10 CD114/0/2

Q1: final state of 0x1000 in caches? Modified/Shared/Invalid for CPU 1/2/3 CPU 3: CPU 2:

Q2: final state of 0x2000 in caches?

130

cache coherency exercise solution

| action | CPU 1 | CPU 2 | CPU 3 | CPU 1 | CPU 2 | CPU |
|---------------------|-------|-------|-------|-------|-------|-----|
| | I | I | I | I | I | I |
| CPU 1: read 0x1000 | S | I | I | I | I | I |
| CPU 2: read 0x1000 | S | S | I | I | I | I |
| CPU 1: write 0x1000 | M | I | I | I | I | Ι |
| CPU 1: read 0x2000 | M | I | I | S | I | Ι |
| CPU 2: read 0x1000 | S | S | I | S | I | Ι |
| CPU 2: write 0x2008 | S | S | I | I | M | Ι |
| CPU 3: read 0x1008 | S | S | S | I | М | Ι |

 $0 \times 1000 - 0 \times 101f$ $0 \times 2000 - 0 \times 201f$

why load/store reordering?

fast processor designs can execute instructions out of order

goal: do something instead of waiting for slow memory accesses, etc.

more on this later in the semester

C++: preventing reordering

to help implementing things like pthread_mutex_lock

C++ 2011 standard: *atomic* header, *std::atomic* class prevent CPU reordering *and* prevent compiler reordering also provide other tools for implementing locks (more later)

could also hand-write assembly code compiler can't know what assembly code is doing

C++: preventing reordering example

```
#include <atomic>
void Alice() {
    note from_alice = 1;
    do {
        std::atomic_thread_fence(std::memory_order_seg_cst);
   } while (note_from_bob);
    if (no milk) {++milk;}
Alice:
 movl $1, note from alice // note from alice <- 1
.12:
 mfence // make sure store visible on/from other cores
 cmpl $0, note from bob // if (note from bob == 0) repeat fence
  ine .L2
  cmpl $0, no milk
```

C++ atomics: no reordering

```
std::atomic<int> note_from_alice, note_from_bob;
void Alice() {
    note from alice.store(1);
    do {
    } while (note_from_bob.load());
    if (no milk) {++milk;}
Alice:
  movl $1, note from alice
  mfence
.12:
  movl note from bob, %eax
  testl %eax, %eax
  ine .L2
```

GCC: built-in atomic functions

used to implement std::atomic, etc.

predate std::atomic

builtin functions starting with __sync and __atomic these are what xv6 uses

aside: some x86 reordering rules

```
each core sees its own loads/stores in order (if a core stores something, it can always load it back) stores from other cores appear in a consistent order
```

(but a core might observe its own stores too early)

causality:

if a core reads X=a and (after reading X=a) writes Y=b, then a core that reads Y=b cannot later read X=older value than a

how do you do anything with this?

difficult to reason about what modern CPU's reordering rules do typically: don't depend on details, instead:

special instructions with stronger (and simpler) ordering rules often same instructions that help with implementing locks in other ways

special instructions that restrict ordering of instructions around them ("fences")


loads/stores can't cross the fence


spinlock problems

lock abstraction is not powerful enough lock/unlock operations don't handle "wait for event" common thing we want to do with threads solution: other synchronization abstractions


spinlocks waste CPU time more than needed want to run another thread instead of infinite loop solution: lock implementation integrated with scheduler

spinlocks can send a lot of messages on the shared bus more efficient atomic operations to implement locks







CPU2 read-modify-writes lock (to see it is still locked)




CPU3 read-modify-writes lock (to see it is still locked)



CPU2 read-modify-writes lock (to see it is still locked)



CPU3 read-modify-writes lock (to see it is still locked)



CPU1 sets lock to unlocked

"I want to modify lock" CPU1 CPU₂ CPU3 MEM1 address value state address value state address value state Modified lock lock Invalid lock locked Invalid

some CPU (this example: CPU2) acquires lock

test-and-set problem: cache block "ping-pongs" between caches each waiting processor reserves block to modify could maybe wait until it determines modification needed — but not typical implementation

each transfer of block sends messages on bus


...so bus can't be used for real work like what the processor with the lock is doing


test-and-test-and-set (pseudo-C)

```
acquire(int *the_lock) {
    do {
        while (ATOMIC-READ(the_lock) == 0) { /* try again */ }
    } while (ATOMIC-TEST-AND-SET(the_lock) == ALREADY_SET);
}
```


test-and-test-and-set (assembly)

```
acquire:
   cmp $0, the lock  // test the lock non-atomically
          // unlike lock xchg --- keeps lock in Shared state!
               // try again (still locked)
   ine acquire
   // lock possibly free
   // but another processor might lock
   // before we get a chance to
   // ... so try wtih atomic swap:
   movl $1, %eax <- 1
   lock xchg %eax, the_lock // swap %eax and the_lock
         // sets the lock to 1
         // sets %eax to prior value of the_lock
   test %eax, %eax // if the lock wasn't 0 (someone else
   jne acquire
              // trv again
   ret
```







CPU2 reads lock (to see it is still locked)



CPU1 writes back lock value, then CPU2 reads it




CPU3 reads lock (to see it is still locked)




CPU2, CPU3 continue to read lock from cache no messages on the bus

"I want to modify lock"



CPU1 sets lock to unlocked

"I want to modify lock"



some CPU (this example: CPU2) acquires lock (CPU1 writes back value, then CPU2 reads + modifies it)

couldn't the read-modify-write instruction...

notice that the value of the lock isn't changing...

and keep it in the shared state

maybe — but extra step in "common" case (swapping different values)

more room for improvement?

can still have a lot of attempts to modify locks after unlocked there other spinlock designs that avoid this ticket locks

MCS locks

...

MSI extensions

real cache coherency protocols sometimes more complex:

separate tracking modifications from whether other caches have copy

send values directly between caches (maybe skip write to memory) send messages only to cores which might care (no shared bus)

too much milk

roommates Alice and Bob want to keep fridge stocked with milk:

| 3:00look in fridge. no milk3:05leave for store3:10arrive at storelook in fridge. no milk3:15buy milkleave for store3:20return home, put milk in fridge arrive at store3:25buy milk3:30return home, put milk in fridge | time | Alice | Bob |
|---|------|---------------------------------|-------------------------|
| 3:10 arrive at store look in fridge. no milk 3:15 buy milk leave for store 3:20 return home, put milk in fridge arrive at store 3:25 buy milk 3:30 return home, put milk in fridge | 3:00 | look in fridge. no milk | |
| 3:15 buy milk leave for store 3:20 return home, put milk in fridge arrive at store 3:25 buy milk 3:30 return home, put milk in fridge | 3:05 | leave for store | |
| 3:20 return home, put milk in fridge arrive at store 3:25 buy milk 3:30 return home, put milk in fridge | 3:10 | arrive at store | look in fridge. no milk |
| 3:25 buy milk 3:30 return home, put milk in fridge | 3:15 | buy milk | leave for store |
| 3:30 return home, put milk in fridge | 3:20 | return home, put milk in fridge | arrive at store |
| 71 | 3:25 | | buy milk |
| 1 Al: 1 D 1 1: . 1 2 | 3:30 | | |

how can Alice and Bob coordinate better?

```
leave a note: "I am buying milk"
    place before buying, remove after buying
    don't try buying if there's a note
\approx setting/checking a variable (e.g. "note = 1")
    with atomic load/store of variable
if (no milk) {
    if (no note) {
         leave note:
         buy milk;
         remove note:
```

```
leave a note: "I am buying milk"
    place before buying, remove after buying
    don't try buying if there's a note
\approx setting/checking a variable (e.g. "note = 1")
    with atomic load/store of variable
if (no milk) {
    if (no note) {
         leave note:
         buy milk;
         remove note;
exercise: why doesn't this work?
```

too much milk "solution" 1 (timeline) Alice Bob if (no milk) { if (no note) { if (no milk) {

```
if (no note) {
leave note:
```

buy milk; remove note;

leave note: buy milk; remove note:

150

```
intuition: leave note when buying or checking if need to buy
leave note:
if (no milk) {
    if (no note) {
         buy milk;
remove note;
```

too much milk: "solution" 2 (timeline)

Alice

```
leave note;
if (no milk) {
    if (no note) {
        buy milk;
    }
}
remove note;
```

too much milk: "solution" 2 (timeline)

```
Alice
```

```
leave note;
if (no milk) {
    if (no note) { ← but there's always a note
        buy milk;
    }
}
remove note;
```

too much milk: "solution" 2 (timeline)

Alice

"solution" 3: algorithm

```
intuition: label notes so Alice knows which is hers (and vice-versa)
    computer equivalent: separate noteFromAlice and noteFromBob
    variables
            Alice
                                                     Bob
leave note from Alice:
                                       leave note from Bob;
if (no milk) {
                                       if (no milk) {
    if (no note from Bob) {
                                            if (no note from Alice
         buy milk
                                                buy milk
remove note from Alice;
                                       remove note from Bob:
```

too much milk: "solution" 3 (timeline) Alice Bob leave note from Alice if (no milk) { leave note from Bob if (no note from Bob) {

if (no milk) {

remove note from Bob

if (no note from Alice) {

154

too much milk: is it possible

is there a solutions with writing/reading notes? \approx loading/storing from shared memory

yes, but it's not very elegant

Alice

```
leave note from Alice
while (note from Bob) {
    do nothing
}
if (no milk) {
    buy milk
}
remove note from Alice
```

Bob

```
leave note from Bob
if (no note from Alice) {
    if (no milk) {
        buy milk
    }
}
remove note from Bob
```

```
Alice
                                             Bob
leave note from Alice
                                 leave note from Bob
while (note from Bob) {
                                 if (no note from Alice) {
    do nothing
                                     if (no milk) {
                                          buv milk
if (no milk) {
    buy milk
                                 remove note from Bob
remove note from Alice
exercise (hard): prove (in)correctness
```

```
Alice
                                             Bob
leave note from Alice
                                 leave note from Bob
while (note from Bob) {
                                 if (no note from Alice) {
    do nothing
                                     if (no milk) {
                                          buv milk
if (no milk) {
    buy milk
                                 remove note from Bob
remove note from Alice
exercise (hard): prove (in)correctness
```

```
Alice
                                             Bob
leave note from Alice
                                  leave note from Bob
while (note from Bob) {
                                  if (no note from Alice) {
    do nothing
                                      if (no milk) {
                                          buv milk
if (no milk) {
    buy milk
                                  remove note from Bob
remove note from Alice
exercise (hard): prove (in)correctness
exercise (hard): extend to three people
```

Peterson's algorithm

general version of solution

see, e.g., Wikipedia

we'll use special hardware support instead

mfence

x86 instruction mfence

make sure all loads/stores in progress finish

...and make sure no loads/stores were started early

fairly expensive

Intel 'Skylake': order 33 cycles + time waiting for pending stores/loads

mfence

x86 instruction mfence

make sure all loads/stores in progress finish

...and make sure no loads/stores were started early

fairly expensive

Intel 'Skylake': order 33 cycles + time waiting for pending stores/loads

aside: this instruction is did not exist in the original x86 so xv6 uses something older that's equivalent

modifying cache blocks in parallel

typical memory access — less than cache block e.g. one 4-byte array element in 64-byte cache block

what if two processors modify different parts same cache block?

4-byte writes to 64-byte cache block

typically how caches work — write instructions happen one at a time:


processor 'locks' 64-byte cache block, fetching latest version processor updates 4 bytes of 64-byte cache block later, processor might give up cache block

modifying things in parallel (code)

```
void *sum_up(void *raw_dest) {
    int *dest = (int *) raw dest;
    for (int i = 0; i < 64 * 1024 * 1024; ++i) {
        *dest += data[i]:
__attribute__((aligned(4096)))
int array[1024]; /* aligned = address is mult. of 4096 */
void sum twice(int distance) {
    pthread t threads[2];
    pthread_create(&threads[0], NULL, sum_up, &array[0]);
    pthread create(&threads[1], NULL, sum up, &array[distance]);
    pthread_join(threads[0], NULL);
    pthread join(threads[1], NULL);
```

performance v. array element gap

(assuming sum_up compiled to not omit memory accesses)



false sharing

synchronizing to access two independent things

two parts of same cache block

solution: separate them

exercise (1)

```
int values[1024];
int results[2]:
void *sum front(void *ignored argument) {
    results[0] = 0;
    for (int i = 0; i < 512; ++i)
        results[0] += values[i];
    return NULL;
void *sum_back(void *ignored_argument) {
    results[1] = 0;
    for (int i = 512; i < 1024; ++i)
        results[1] += values[i]:
    return NULL;
int sum all() {
    pthread_t sum_front_thread, sum_back_thread;
    pthread_create(&sum_front_thread, NULL, sum_front, NULL);
    pthread create(&sum back thread, NULL, sum back, NULL);
    pthread_join(sum_front_thread, NULL);
    pthread join(sum back thread, NULL);
    return results[0] + results[1];
```

exercise (2)


```
struct ThreadInfo { int *values; int start; int end; int result };
void *sum thread(void *argument) {
    ThreadInfo *my_info = (ThreadInfo *) argument;
    int sum = 0;
    for (int i = my_info->start; i < my_info->end; ++i) {
        my_info->result += my_info->values[i];
    return NULL:
int sum all(int *values) {
    ThreadInfo info[2]; pthread_t thread[2];
    for (int i = 0; i < 2; ++i) {
        info[i].values = values; info[i].start = i*512; info[i].end = (i+1)*512;
        pthread create(&threads[i], NULL, sum_thread, (void *) &info[i]);
    for (int i = 0; i < 2; ++i)
        pthread_join(threads[i], NULL);
    return info[0].result + info[1].result;
```

connecting CPUs and memory

multiple processors, common memory

how do processors communicate with memory?

shared bus



one possible design

we'll revisit later when we talk about I/O

tagged messages — everyone gets everything, filters

contention if multiple communicators some hardware enforces only one at a time

shared buses and scaling

shared buses perform poorly with "too many" CPUs

so, there are other designs

we'll gloss over these for now

shared buses and caches


remember caches?

memory is pretty slow


each CPU wants to keep local copies of memory

what happens when multiple CPUs cache same memory?

the cache coherency problem



the cache coherency problem



CPU1 writes 101 to 0xA300?

BROKEN: producer/consumer signal

exercise: example why signal here is BROKEN? hint: two consume()+two produce()

```
pthread_mutex_t lock; pthread_cond_t data_ready; UnboundedQueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
    buffer.engueue(item);
   /* GOOD CODE: pthread cond signal(&data ready); */
    /* BAD CODE: */ if (buffer.size() == 1) pthread_cond_signal(&item);
    pthread mutex unlock(&lock):
Consume() {
    pthread mutex lock(&lock):
    while (buffer.emptv()) {
        pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue():
    pthread mutex unlock(&lock);
    return item;
```

bad case (setup)

| thread 0 | 1 | 2 | 3 |
|-------------------|-------------------|--------------------|------------|
| Consume(): | | | |
| lock | | | |
| empty? wait on cv | Consume(): | | ı |
| | lock | | |
| | empty? wait on cv | | |
| | | Produce(): | |
| | | Produce(): lock | Produce(): |

bad case

| thread 0 | 1 | 2 | 3 | |
|-------------------|---|---------------------|---|----|
| Consume(): | | | | |
| lock | | | | |
| empty? wait on cv | Consume(): lock empty? wait on cv | | | |
| | empty: wait on cv | Draduca(). | | |
| | | Produce(): | Dua duas () | |
| | | lock | Produce(): | |
| | | | wait for lock | |
| | | enqueue | | |
| wait for lock | | size $= 1$? signal | | |
| | | unlock | gets lock | |
| | | | enqueue | |
| | | | $\frac{\text{size}}{\text{size}} \neq 1$: don't signal | |
| | | | unlock | |
| gets lock | | | | |
| dequeue | | | | 17 |

monitor exercise: ConsumeTwo

suppose we want producer/consumer, but...

but change Consume() to ConsumeTwo() which returns a pair of values

and don't want two calls to ConsumeTwo() to wait... with each getting one item

```
what should we change below?
```

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;
```

pthread mutex unlock(&lock);

```
Produce(item) {
  pthread_mutex_lock(&lock);
  buffer.engueue(item);
  pthread cond signal(&data ready);
```

```
Consume() {
  pthread_mutex_lock(&lock);
  while (buffer.empty()) {
    pthread cond wait(&data ready, &lock
```

item = buffer.dequeue(); pthread mutex unlock(&lock); return item;

```
173
```

monitor exercise: solution (1)

```
(one of many possible solutions)
Assuming Consume Two replaces Consume:
Produce() {
  pthread_mutex_lock(&lock);
  buffer.enqueue(item);
  if (buffer.size() > 1) { pthread_cond_signal(&data_ready); }
  pthread_mutex_unlock(&lock):
ConsumeTwo() {
    pthread_mutex_lock(&lock);
    while (buffer.size() < 2) { pthread_cond_wait(&data_ready, &lock); }</pre>
    item1 = buffer.dequeue(); item2 = buffer.dequeue();
    pthread_mutex_unlock(&lock);
    return Combine(item1, item2);
```

monitor exercise: solution (2)

```
(one of many possible solutions)
Assuming Consume Two is in addition to Consume (using two CVs):
Produce() {
  pthread_mutex_lock(&lock);
  buffer.enqueue(item);
  pthread_cond_signal(&one_ready);
  if (buffer.size() > 1) { pthread cond signal(&two ready); }
  pthread_mutex_unlock(&lock);
Consume() {
  pthread_mutex_lock(&lock);
  while (buffer.size() < 1) { pthread_cond_wait(&one_ready, &lock); }</pre>
  item = buffer.dequeue():
  pthread mutex unlock(&lock):
  return item;
ConsumeTwo() {
  pthread mutex lock(&lock):
  while (buffer.size() < 2) { pthread cond wait(&two ready, &lock); }</pre>
  item1 = buffer.dequeue(); item2 = buffer.dequeue();
  nthread mutay unlock (&lock).
```

175

monitor exercise: slower solution

```
(one of many possible solutions)
Assuming Consume Two is in addition to Consume (using one CV):
Produce() {
  pthread_mutex_lock(&lock);
  buffer.enqueue(item);
  // broadcast and not signal, b/c we might wakeup only ConsumeTwo() otherwise
  pthread cond broadcast(&data ready):
  pthread_mutex_unlock(&lock);
Consume() {
  pthread_mutex_lock(&lock);
  while (buffer.size() < 1) { pthread_cond_wait(&data_ready, &lock); }</pre>
  item = buffer.dequeue():
  pthread mutex unlock(&lock):
  return item;
ConsumeTwo() {
  pthread mutex lock(&lock):
  while (buffer.size() < 2) { pthread cond wait(&data ready, &lock); }</pre>
  item1 = buffer.dequeue(): item2 = buffer.dequeue():
                                                                                  176
  nthread mutay unlock (&lock).
```

monitor exercise: ordering

suppose we want producer/consumer, but...

but want to ensure first call to Consume() always returns first

(no matter what ordering cond_signal/cond_broadcast use)

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;

Produce(item) {
    pthread_mutex_lock(&lock);
    buffer.enqueue(item);
    pthread_cond_signal(&data_ready);
    pthread_mutex_unlock(&lock);
}

Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
        item = buffer.dequeue();
        pthread_mutex_unlock(&lock);
        return item;
}
```

monitor ordering exercise: solution

pthread_mutex_lock(&lock);

Waiter *waiter = waiters.dequeue();

if (!waiters.empty()) {

waiter->done = true;

waiter->item = item;

buffer.enqueue(item);

++num pending;

} else {

cond_signal(&waiter->cv);

pthread mutex unlock(&lock):

Produce(item) {

```
(one of many possible solutions)
struct Waiter {
                                          Consume() {
    pthread_cond_t cv;
                                            pthread_mutex_lock(&lock);
    bool done;
                                            if (buffer.empty()) {
                                              Waiter waiter:
    T item:
                                              cond_init(&waiter.cv);
Oueue<Waiter*> waiters:
                                              waiter.done = false:
                                              waiters.engueue(&waiter);
```

while (!waiter.done)

item = waiter.item:

item = buffer.dequeue();

pthread_mutex_unlock(&lock):

} else {

return item;

cond_wait(&waiter.cv, &lock);

178

Anderson-Dahlin and semaphores

Anderson/Dahlin complains about semaphores

"Our view is that programming with locks and condition variables is superior to programming with semaphores."

argument 1: clearer to have separate constructs for waiting for condition to be come true, and allowing only one thread to manipulate a thing at a time

arugment 2: tricky to verify thread calls up exactly once for every down

alternatives allow one to be sloppier (in a sense)

monitors with semaphores: locks

```
sem_t semaphore; // initial value 1
Lock() {
    sem_wait(&semaphore);
}
Unlock() {
    sem_post(&semaphore);
}
```

monitors with semaphores: [broken] cvs

start with only wait/signal:

```
sem_t threads_to_wakeup; // initially 0
Wait(Lock lock) {
    lock.Unlock();
    sem_wait(&threads_to_wakeup);
    lock.Lock();
}
Signal() {
    sem_post(&threads_to_wakeup);
}
```

monitors with semaphores: [broken] cvs

start with only wait/signal:

```
sem_t threads_to_wakeup; // initially 0
Wait(Lock lock) {
    lock.Unlock();
    sem_wait(&threads_to_wakeup);
    lock.Lock();
}
Signal() {
    sem_post(&threads_to_wakeup);
}
```

problem: signal wakes up non-waiting threads (in the far future)

monitors with semaphores: cvs (better)

start with only wait/signal:

```
sem_t private_lock; // initially 1
int num waiters;
sem_t threads_to_wakeup; // initially 0
Wait(Lock lock) {
                                           Signal() {
  sem_wait(&private_lock);
                                             sem_wait(&private_lock);
  ++num_waiters;
                                             if (num_waiters > 0) {
                                               sem_post(&threads_to_wakeup);
  sem_post(&private_lock);
  lock.Unlock();
                                               --num_waiters;
  sem_wait(&threads_to_wakeup);
  lock.Lock();
                                             sem_post(&private_lock);
```

monitors with semaphores: broadcast

now allows broadcast:

```
sem t private lock; // initially 1
int num waiters;
sem_t threads_to_wakeup; // initially 0
Wait(Lock lock) {
                                          Broadcast() {
                                            sem_wait(&private_lock);
  sem wait(&private lock);
  ++num waiters:
                                            while (num waiters > 0) {
  sem post(&private lock);
                                               sem post(&threads to wakeup):
  lock.Unlock();
                                               --num waiters;
  sem_wait(&threads_to_wakeup);
  lock.Lock();
                                            sem_post(&private_lock);
```

pthread_mutex_t lock;

lock to protect shared state

```
pthread_mutex_t lock;
unsigned int count;
```

lock to protect shared state

shared state: semaphore tracks a count

```
pthread_mutex_t lock;
unsigned int count;
/* condition, broadcast when becomes count > 0 */
pthread_cond_t count_is_positive_cv;
```

lock to protect shared state shared state: semaphore tracks a count

add cond var for each reason we wait

```
pthread mutex t lock;
unsigned int count:
/* condition, broadcast when becomes count > 0 */
pthread cond t count is positive cv;
void down() {
    pthread_mutex_lock(&lock);
    while (!(count > 0)) {
        pthread cond wait(
            &count_is_positive_cv,
            &lock):
    count -= 1;
    pthread_mutex_unlock(&lock);
```

lock to protect shared state shared state: semaphore tracks a count

add cond var for each reason we wait

```
pthread mutex t lock;
unsigned int count;
/* condition, broadcast when becomes count > 0 */
pthread cond t count is positive cv;
void down() {
                                        void up() {
                                            pthread_mutex_lock(&lock):
    pthread_mutex_lock(&lock);
    while (!(count > 0)) {
                                            count += 1:
        pthread cond wait(
                                            /* count must now be
            &count is positive cv.
                                               positive, and at most
            &lock):
                                               one thread can go per
                                               call to Up() */
    count -= 1:
                                            pthread_cond_signal(
    pthread_mutex_unlock(&lock);
                                                &count_is_positive_cv
                                            pthread mutex unlock(&lock):
lock to protect shared state
```

lock to protect shared state

shared state: semaphore tracks a count

add cond var for each reason we wait

binary semaphores

binary semaphores — semaphores that are only zero or one

as powerful as normal semaphores

exercise: simulate counting semaphores with binary semaphores (more than one) and an integer

counting semaphores with binary semaphores

via Hemmendinger, "Comments on 'A correct and unrestrictive implementation of general semaphores' " (1989); Barz, "Implementing semaphores by binary semaphores" (1983)

```
// assuming initialValue > 0
BinarySemaphore mutex(1);
int value = initialValue ;
BinarySemaphore gate(1 /* if initialValue >= 1 */);
    /* gate = # threads that can Down() now */
void Down() {
                                      } ()qU biov
 gate.Down():
                                       mutex.Down();
 // wait, if needed
                                       value += 1:
                                        if (value == 1) {
 mutex.Down();
                                         gate.Up();
 value -= 1:
  if (value > 0) {
                                         // because down should finish now
   gate.Up():
                                         // but could not before
   // because next down should finish
   // now (but not marked to before)
                                       mutex.Up();
 mutex.Up();
```

gate intuition/pattern

```
pattern to allow one thread at a time:
sem t gate; // 0 = closed; 1 = open
ReleasingThread() {
    ... // finish what the other thread is waiting for
    while (another thread is waiting and can go) {
        sem_post(&gate) // allow EXACTLY ONE thread
        ... // other bookkeepina
WaitingThread() {
    ... // indicate that we're waiting
    sem_wait(&gate) // wait for gate to be open
    ... // indicate that we're not waiting
```