threads

last time

caches misses and C code

thinking about how values map to cache sets ability evaluating cache sets independently

write policies

```
on write miss: add to cache? [yes = write-allocate] update next level immediately on write? [yes = write-through] dirty bits for write-back
```

next week logistics

code review lab

in-person attendance or arrangement with me feedback on code style/readability/maintainability not a debugging session show your code (reading from your screen—not transferring files, etc.)

next Thursday's lecture

I will be out-of-town Professor Skadron will cover lecture recording hopefully available, but possible delay/etc.

recall: writes for reads, lots of writes?

write-through:


write to cache needs write to memory seems quite slow?

write-back:

reads from and writes to cache may need to write dirty stuff less frequent than write-through, but still seems slow?


trick: do writes "in the background"

fast writes




write appears to complete immediately when placed in buffer memory can be much slower

another view



two-level page table lookup



cache accesses and multi-level PTs


four-level page tables — five cache accesses per program memory access

L1 cache hits — typically a couple cycles each?

so add 8 cycles to each program memory access?

not acceptable

program memory active sets



0xffff ffff ffff ffff

0xFFFF 8000 0000 0000

0x7F...

small areas of memory active at a time one or two pages in each area?

0x0000 0000 0040 0000

page table entries and locality

page table entries have excellent temporal locality

typically one or two pages of the stack active

typically one or two pages of code active

typically one or two pages of heap/globals active

each page contains whole functions, arrays, stack frames, etc.

page table entries and locality

page table entries have excellent temporal locality

typically one or two pages of the stack active

typically one or two pages of code active

typically one or two pages of heap/globals active

each page contains whole functions, arrays, stack frames, etc.

needed page table entries are very small

caled a **TLB** (translation lookaside buffer)

(usually very small) cache of page table entries

L1 cache	TLB
physical addresses	virtual page numbers
bytes from memory	page table entries
tens of bytes per block	one page table entry per block
usually thousands of blocks	usually tens of entries

caled a **TLB** (translation lookaside buffer)

(usually very small) cache of page table entries

L1 cache	TLB	
physical addresses	virtual page numbers	
bytes from memory	page table entries	
tens of bytes per block	one page /able entry per block	
usually thousands of blocks	only caches the page table lookup itself	
only caches the	only caches the page table lookup itself	
(generally) just	(generally) just entries from the last-level page tables	

caled a **TLB** (translation lookaside buffer)

(usually very small) cache of page table entries

L1 cache		TLB	
physical add	resses	virtual page num	bers
bytes from r	nemory	page table entries	S
tens of bytes		one page table er	ntry per block
usually thou	sands of blocks	usuraly tens of en	ntries
-	virtual page number divided into		
	index + tag		

caled a **TLB** (translation lookaside buffer)

(usually very small) cache of page table entries

L1 cache	TLB
physical addresses	virtual page numbers
bytes from memory	page table entries
tens of bytes per block	one page table entry per block
usually thousands of blocks	usually tens of entries

not much spatial locality between page table entries (they're used for kilobytes of data already)

caled a **TLB** (translation lookaside buffer)

(usually very small) cache of page table entries

L1 cache	TLB
physical addresses	virtual page numbers
bytes from memory	page table entries
tens of bytes per block one page table entry per block	
usually thousands of blocks	usually tens of entries

0 block offset bits

caled a **TLB** (translation lookaside buffer)

(usually very small) cache of page table entries

L1 cache	TLB
physical addresses	virtual page numbers
bytes from memory	page table entries
tens of bytes per block	one page table entry per block
usually thousands of blocks	usually tens of entries

few active page table entries at a time enables highly associative cache designs


TLB and multi-level page tables

TLB caches valid last-level page table entries


doesn't matter which last-level page table


means TLB output can be used directly to form address


TLB and two-level lookup





TLB and two-level lookup














exercise: TLB access pattern (setup)

4-entry, 2-way TLB, LRU replacement policy, initially empty

4096 byte pages

how many index bits?

TLB index of virtual address 0x12345?

exercise: TLB access pattern

4-entry, 2-way TLB, LRU replacement policy, initially empty

4096 byte pages

type	virtual	physical
read	0x440030	0x554030
write	0x440034	0x554034
read	0x7FFFE008	0x556008
read	0x7FFFE000	0x556000
read	0x7FFFDFF8	0x5F8FF8
read	0x664080	0x5F9080
read	0x440038	0x554038
write	0x7FFFDFF0	0x5F8FF0

which are TLB hits? which are TLB misses? final contents of TLB?


why threads?

```
concurrency: different things happening at once one thread per user of web server? one thread per page in web browser? one thread to play audio, one to read keyboard, ...? ...
```


parallelism: do same thing with more resources multiple processors to speed-up simulation (life assignment)

single and multithread processes

single-threaded process



multi-threaded process



```
void *ComputePi(void *argument) { ... }
void *PrintClassList(void *argument) { ... }
int main() {
  pthread_t pi_thread, list_thread;
  if (0 != pthread_create(&pi_thread, NULL, ComputePi, NULL))
     handle_error();
  if (0 != pthread_create(&list_thread, NULL, PrintClassList, NULL))
     handle_error();
  ... /* more code */
    main()
pthread_create.
                                           ComputePi
pthread_create.
                           PrintClassList
```

```
void *ComputePi(void *argument) { ... }
void *PrintClassList(void *argument) { ... }
int main() {
  pthread_t pi_thread, list_thread;
  if (0 != pthread_create(&pi_thread, NULL, ComputePi, NULL))
     handle_error();
  if (0 != pthread create(&list thread, NULL, PrintClassList, NULL))
      handle_error();
  ... /* more code */
pthread create arguments:
```

thread identifier

function to run thread starts here, terminates if this function returns

```
void *ComputePi(void *argument) { ... }
void *PrintClassList(void *argument) { ... }
int main() {
  pthread_t pi_thread, list_thread;
  if (0 != pthread_create(&pi_thread, NULL, ComputePi, NULL))
        handle_error();
  if (0 != pthread_create(&list_thread, NULL, PrintClassList, NULL))
        handle_error();
        ... /* more code */
}
```

pthread_create arguments:

thread identifier

function to run thread starts here, terminates if this function returns

```
void *ComputePi(void *argument) { ... }
void *PrintClassList(void *argument) { ... }
int main() {
  pthread_t pi_thread, list_thread;
  if (0 != pthread_create(&pi_thread, NULL, ComputePi, NULL))
      handle_error();
  if (0 != pthread create(&list thread, NULL, <a href="PrintClassList">PrintClassList</a>, NULL))
      handle_error();
  ... /* more code */
pthread create arguments:
```

thread identifier

function to run thread starts here, terminates if this function returns

```
void *ComputePi(void *argument) { ... }
void *PrintClassList(void *argument) { ... }
int main() {
  pthread_t pi_thread, list_thread;
  if (0 != pthread_create(&pi_thread, NULL, ComputePi, NULL))
      handle_error();
  if (0 != pthread create(&list thread, NULL, PrintClassList, NULL))
      handle_error();
  ... /* more code */
pthread create arguments:
```

thread identifier

function to run thread starts here, terminates if this function returns

a threading race

```
#include <pthread.h>
#include <stdio.h>
void *print message(void *ignored argument) {
    printf("In the thread\n");
    return NULL;
int main() {
    printf("About to start thread\n");
    pthread_t the_thread;
    /* assume does not fail */
    pthread create(&the thread, NULL, print message, NULL);
    printf("Done starting thread\n");
    return 0;
```

My machine: outputs In the thread about 4% of the time.

What happened?

a race

```
returning from main exits the entire process (all its threads)
     same as calling exit; not like other threads
race: main's return 0 or print message's printf first?
                                                              time
  main: printf/pthread_create/printf/return
                               print message: printf/return
                                return from main
                                 ends all threads
                                  in the process
```

fixing the race (version 1)

```
#include <pthread.h>
#include <stdio.h>
void *print_message(void *ignored_argument) {
    printf("In the thread\n");
    return NULL;
int main() {
    printf("About to start thread\n");
    pthread t the thread;
   /* missing: error checking */
    pthread create(&the thread, NULL, print message, NULL);
    printf("Done starting thread\n");
    pthread_join(the_thread, NULL); /* WAIT FOR THREAD */
    return 0;
```

fixing the race (version 2; not recommended)

```
#include <pthread.h>
#include <stdio.h>
void *print_message(void *ignored_argument) {
    printf("In the thread\n");
    return NULL;
int main() {
    printf("About to start thread\n");
    pthread t the thread;
   /* missing: error checking */
    pthread create(&the thread, NULL, print message, NULL);
    printf("Done starting thread\n");
    pthread_exit(NULL);
```

pthread_join, pthread_exit

 $R = pthread_join(X, \&P)$: wait for thread X, copies return value into P

like waitpid, but for a thread thread return value is pointer to anything R = 0 if successful, error code otherwise

pthread_exit: exit current thread, returning a value
 like exit or returning from main, but for a single thread
 same effect as returning from function passed to pthread_create

a note on error checking

from pthread_create manpage:

ERRORS

EAGAIN Insufficient resources to create another thread, or a system-imposed limit on the number of threads was encountered. The latter case may occur in two ways: the RLIMIT_NPROC soft resource limit (set via setrlimit(2)), which limits the number of process for a real user ID, was reached; or the kernel's system-wide limit on the number of threads, /proc/sys/kernel/threads-max, was reached.

EINVAL Invalid settings in attr.

EPERM No permission to set the scheduling policy and parameters specified in <u>attr</u>.

special constants for return value

same pattern for many other pthreads functions pthread_join, pthread_mutex_...(later), ...

will often omit error checking in slides for brevity

error checking pthread_create

```
int error = pthread_create(...);
if (error != 0) {
    /* print some error message */
}
```

sum example (only globals)

```
int values[1024]; int results[2];
void *sum_front(void *ignored_argument) {
    int sum = 0;
    for (int i = 0; i < 512; ++i) { sum += values[i]; }</pre>
    results[0] = sum;
    return NULL;
}
void *sum_back(void *ignored_argument) {
    int sum = 0;
    for (int i = 512; i < 1024; ++i) { sum += values[i]; }
    results[1] = sum;
    return NULL;
int sum all() {
    pthread_t sum_front_thread, sum_back_thread;
    /* missing: error handling */
    pthread create(&sum front thread, NULL, sum front, NULL);
    pthread_create(&sum_back_thread, NULL, sum_back, NULL);
    pthread_join(sum_front_thread, NULL); pthread_join(sum_back_thread, NULL);
    return results[0] + results[1];
```

sum example (only globals)


```
int values[1024]; int result values, results: global variables — shared
void *sum_front(void *ignored_argument) {
    int sum = 0;
    for (int i = 0; i < 512; ++i) { sum += values[i]; }
    results[0] = sum;
    return NULL;
void *sum_back(void *ignored_argument) {
    int sum = 0;
    for (int i = 512; i < 1024; ++i) { sum += values[i]; }
    results[1] = sum;
    return NULL;
int sum all() {
    pthread_t sum_front_thread, sum_back_thread;
   /* missing: error handling */
    pthread create(&sum front thread, NULL, sum front, NULL);
    pthread_create(&sum_back_thread, NULL, sum_back, NULL);
    pthread_join(sum_front_thread, NULL); pthread_join(sum_back_thread, NULL);
    return results[0] + results[1];
```

sum example (only alobals)


```
two different functions
int values[1024];
                      happen to be the same except for some numbers
void *sum_front(void
    int sum = 0;
    for (int i = 0; i < 512; ++i) { sum += values[i]; }
    results[0] = sum;
    return NULL;
void *sum_back(void *ignored_argument) {
    int sum = 0;
    for (int i = 512; i < 1024; ++i) { sum += values[i]; }
    results[1] = sum;
    return NULL;
int sum all() {
    pthread_t sum_front_thread, sum_back_thread;
    /* missing: error handling */
    pthread create(&sum front thread, NULL, sum front, NULL);
    pthread_create(&sum_back_thread, NULL, sum_back, NULL);
    pthread_join(sum_front_thread, NULL); pthread_join(sum_back_thread, NULL);
    return results[0] + results[1];
```

```
values returned from threads
        via global array instead of return value
int valu
         (partly to illustrate that memory is shared,
void *su
        partly because this pattern works when we don't join (later))
    int
    for
    results[0] = sum;
    return NULL;
void *sum_back(void *ignored_argument) {
    int sum = 0;
    for (int i = 512; i < 1024; ++i) { sum += values[i]; }
    results[1] = sum;
    return NULL;
int sum all() {
    pthread_t sum_front_thread, sum_back_thread;
    /* missing: error handling */
    pthread create(&sum front thread, NULL, sum front, NULL);
    pthread_create(&sum_back_thread, NULL, sum_back, NULL);
    pthread_join(sum_front_thread, NULL); pthread_join(sum_back_thread, NULL);
    return results[0] + results[1];
```

thread_sum memory layout



thread_sum memory layout



sum example (to global, with thread IDs)

```
int values[1024];
int results[2];
void *sum_thread(void *argument) {
    int id = (int) argument;
    int sum = 0;
    for (int i = id * 512; i < (id + 1) * 512; ++i) {
        sum += values[i];
    results[id] = sum;
    return NULL;
int sum all() {
    /* missing: error handling */
    pthread_t thread[2];
    for (int i = 0; i < 2; ++i) {
        pthread_create(&threads[i], NULL, sum_thread, (void *) i);
    for (int i = 0; i < 2; ++i)
        pthread_join(threads[i], NULL);
    return results[0] + results[1];
```

sum example (to global, with thread IDs)

```
int values[1024];
                              values, results: global variables — shared
int results[2];
void *sum_thread(void *argumed...,
    int id = (int) argument;
    int sum = 0;
    for (int i = id * 512; i < (id + 1) * 512; ++i) {
        sum += values[i];
    results[id] = sum;
    return NULL;
int sum all() {
    /* missing: error handling */
    pthread_t thread[2];
    for (int i = 0; i < 2; ++i) {
        pthread_create(&threads[i], NULL, sum_thread, (void *) i);
    for (int i = 0; i < 2; ++i)
        pthread_join(threads[i], NULL);
    return results[0] + results[1];
```


```
int values[1024];
struct ThreadInfo {
    int start, end, result;
};
void *sum_thread(void *argument) {
    struc tThreadInfo *my_info = (struct ThreadInfo *) argument;
    int sum = 0;
    for (int i = my_info->start; i < my_info->end; ++i) { sum += values[i]; }
    my_info->result = sum;
    return NULL;
int sum_all() {
    pthread_t thread[2]; struct ThreadInfo info[2];
    for (int i = 0; i < 2; ++i) {
        info[i].start = i*512; info[i].end = (i+1)*512;
        pthread_create(&threads[i], NULL, sum_thread, &info[i]);
    for (int i = 0; i < 2; ++i) { pthread_join(threads[i], NULL); }</pre>
    return info[0].result + info[1].result;
```

```
int values[1024]; values: global variable — shared
struct ThreadInfo
    int start, end, result;
};
void *sum_thread(void *argument) {
    struc tThreadInfo *my_info = (struct ThreadInfo *) argument;
    int sum = 0;
    for (int i = my_info->start; i < my_info->end; ++i) { sum += values[i]; }
   my_info->result = sum;
    return NULL;
int sum_all() {
    pthread_t thread[2]; struct ThreadInfo info[2];
    for (int i = 0; i < 2; ++i) {
        info[i].start = i*512; info[i].end = (i+1)*512;
        pthread_create(&threads[i], NULL, sum_thread, &info[i]);
    for (int i = 0; i < 2; ++i) { pthread_join(threads[i], NULL); }</pre>
    return info[0].result + info[1].result;
```

```
int values[1024];
struct ThreadInfo {
    int start, end, result;
};
void *sum_thread(void *argument) {
    struc tThreadInfo *my info =
                                  (struct ThreadInfo *) argument:
    int sum = 0;
                                  my info: pointer to sum all's stack
    for (int i = my_info->start;
                                  only okay because sum_all waits!
   my_info->result = sum;
    return NULL;
int sum_all() {
    pthread_t thread[2]; struct ThreadInfo info[2];
    for (int i = 0; i < 2; ++i) {
        info[i].start = i*512; info[i].end = (i+1)*512;
        pthread_create(&threads[i], NULL, sum_thread, &info[i]);
    for (int i = 0; i < 2; ++i) { pthread_join(threads[i], NULL); }</pre>
    return info[0].result + info[1].result;
```

```
int values[1024];
struct ThreadInfo {
    int start, end, result;
};
void *sum_thread(void *argument) {
    struc tThreadInfo *my_info = (struct ThreadInfo *) argument;
    int sum = 0;
    for (int i = my_info->start; i < my_info->end; ++i) { sum += values[i]; }
    my_info->result = sum;
    return NULL;
int sum_all() {
    pthread_t thread[2]; struct ThreadInfo info[2];
    for (int i = 0; i < 2; ++i) {
        info[i].start = i*512; info[i].end = (i+1)*512;
        pthread_create(&threads[i], NULL, sum_thread, &info[i]);
    for (int i = 0; i < 2; ++i) { pthread_join(threads[i], NULL); }</pre>
    return info[0].result + info[1].result;
```

thread_sum memory layout (info struct)




```
struct ThreadInfo { int *values; int start; int end; int result };
void *sum_thread(void *argument) {
    ThreadInfo *my_info = (ThreadInfo *) argument;
    int sum = 0;
    for (int i = my_info->start; i < my_info->end; ++i) {
        sum += my_info->values[i];
   my_info->result = sum;
    return NULL;
int sum all(int *values) {
    ThreadInfo info[2]; pthread_t thread[2];
    for (int i = 0; i < 2; ++i) {
        info[i].values = values; info[i].start = i*512; info[i].end = (i+1)*512;
        pthread_create(&threads[i], NULL, sum_thread, (void *) &info[i]);
    for (int i = 0; i < 2; ++i)
        pthread_join(threads[i], NULL);
    return info[0].result + info[1].result;
```

```
struct ThreadInfo { int *values; int start; int end; int result };
void *sum_thread(void *argument) {
    ThreadInfo *my_info = (ThreadInfo *) argument;
    int sum = 0;
    for (int i = my_info->start; i < my_info->end; ++i) {
        sum += my_info->values[i];
   my_info->result = sum;
    return NULL;
int sum all(int *values) {
    ThreadInfo info[2]; pthread_t thread[2];
    for (int i = 0; i < 2; ++i) {
        info[i].values = values; info[i].start = i*512; info[i].end = (i+1)*512;
        pthread_create(&threads[i], NULL, sum_thread, (void *) &info[i]);
    for (int i = 0; i < 2; ++i)
        pthread_join(threads[i], NULL);
    return info[0].result + info[1].result;
```

```
struct ThreadInfo { int *values; int start; int end; int result };
void *sum_thread(void *argument) {
    ThreadInfo *my_info = (ThreadInfo *) argument;
    int sum = 0;
    for (int i = my_info->start; i < my_info->end; ++i) {
        sum += my_info->values[i];
   my_info->result = sum;
    return NULL;
int sum all(int *values) {
    ThreadInfo info[2]; pthread_t thread[2];
    for (int i = 0; i < 2; ++i) {
        info[i].values = values; info[i].start = i*512; info[i].end = (i+1)*512;
        pthread_create(&threads[i], NULL, sum_thread, (void *) &info[i]);
    for (int i = 0; i < 2; ++i)
        pthread_join(threads[i], NULL);
    return info[0].result + info[1].result;
```

```
struct ThreadInfo { int *values; int start; int end; int result };
void *sum_thread(void *argument) {
    ThreadInfo *my_info = (ThreadInfo *) argument;
    int sum = 0;
    for (int i = my_info->start; i < my_info->end; ++i) {
        sum += my_info->values[i];
   my_info->result = sum;
    return NULL;
int sum all(int *values) {
    ThreadInfo info[2]; pthread_t thread[2];
    for (int i = 0; i < 2; ++i) {
        info[i].values = values; info[i].start = i*512; info[i].end = (i+1)*512;
        pthread_create(&threads[i], NULL, sum_thread, (void *) &info[i]);
    for (int i = 0; i < 2; ++i)
        pthread_join(threads[i], NULL);
    return info[0].result + info[1].result;
```

program memory (to main stack)



sum example (on heap)

```
struct ThreadInfo { pthread_t thread; int *values; int start; int end; int result
void *sum thread(void *argument) {
    . . .
struct ThreadInfo *start_sum_all(int *values) {
    struct ThreadInfo *info = calloc(2, sizeof(struct ThreadInfo);
    for (int i = 0; i < 2; ++i) {
        info[i].values = values; info[i].start = i*512; info[i].end = (i+1)*512;
        pthread_create(&info[i].thread, NULL, sum_thread, (void *) &info[i]);
    return info;
int finish_sum_all(ThreadInfo *info) {
    for (int i = 0; i < 2; ++i)
        pthread_join(info[i].thread, NULL);
    int result = info[0].result + info[1].result;
    free(info);
    return result;
```


sum example (on heap)

```
struct ThreadInfo { pthread_t thread; int *values; int start; int end; int result
void *sum thread(void *argument) {
    . . .
struct ThreadInfo *start_sum_all(int *values) {
    struct ThreadInfo *info = calloc(2, sizeof(struct ThreadInfo);
    for (int i = 0; i < 2; ++i) {
        info[i].values = values; info[i].start = i*512; info[i].end = (i+1)*512;
        pthread_create(&info[i].thread, NULL, sum_thread, (void *) &info[i]);
    return info;
int finish_sum_all(ThreadInfo *info) {
    for (int i = 0; i < 2; ++i)
        pthread_join(info[i].thread, NULL);
    int result = info[0].result + info[1].result;
    free(info);
    return result;
```

sum example (on heap)

```
struct ThreadInfo { pthread_t thread; int *values; int start; int end; int result
void *sum thread(void *argument) {
    . . .
struct ThreadInfo *start_sum_all(int *values) {
    struct ThreadInfo *info = calloc(2, sizeof(struct ThreadInfo);
    for (int i = 0; i < 2; ++i) {
        info[i].values = values; info[i].start = i*512; info[i].end = (i+1)*512;
        pthread_create(&info[i].thread, NULL, sum_thread, (void *) &info[i]);
    return info;
int finish_sum_all(ThreadInfo *info) {
    for (int i = 0; i < 2; ++i)
        pthread_join(info[i].thread, NULL);
    int result = info[0].result + info[1].result;
    free(info);
    return result;
```

thread_sum memory (heap version)



what's wrong with this?

```
/* omitted: headers */
void *create_string(void *ignored_argument) {
  char string[1024];
  ComputeString(string);
  return string;
int main() {
  pthread_t the_thread;
  pthread_create(&the_thread, NULL, create_string, NULL);
  char *string ptr;
  pthread join(the thread, (void**) &string ptr);
  printf("string is %s\n", string_ptr);
```

program memory

Used by OS main thread stack second thread stack third thread stack Heap / other dynamic Code / Data

0xFFFF FFFF FFFF
0xFFFF 8000 0000 0000
0x7F...

dynamically allocated stacks string result allocated here string_ptr pointed to here

...stacks deallocated when threads exit/are joined

0x0000 0000 0040 0000

program memory

Used by OS
main thread stack
second thread stack
third thread stack
Heap / other dynamic
Code / Data

0xFFFF FFFF FFFF
0xFFFF 8000 0000 0000
0x7F...

dynamically allocated stacks string result allocated here string_ptr pointed to here

...stacks deallocated when threads exit/are joined

0x0000 0000 0040 0000

thread joining

pthread_join allows collecting thread return value
if you don't join joinable thread, then memory leak!

thread joining

pthread_join allows collecting thread return value if you don't join joinable thread, then memory leak!

avoiding memory leak?

always join...or

"detach" thread to make it not joinable

pthread_detach

```
void *show_progress(void * ...) { ... }
void spawn_show_progress_thread() {
    pthread_t show_progress_thread;
    pthread_create(&show_progress_thread, NULL,
                   show progress, NULL);
    /* instead of keeping pthread_t around to join thread later: */
    pthread detach(show progress thread);
int main() {
    spawn show progress thread();
    do other stuff();
           detach = don't care about return value, etc.
            system will deallocate when thread terminates
```

starting threads detached

setting stack sizes

a threading race

```
#include <pthread.h>
#include <stdio.h>
void *print message(void *ignored argument) {
    printf("In the thread\n");
    return NULL;
int main() {
    printf("About to start thread\n");
    pthread_t the_thread;
    /* assume does not fail */
    pthread create(&the thread, NULL, print message, NULL);
    printf("Done starting thread\n");
    return 0;
```

My machine: outputs In the thread about 4% of the time. What happened?

a race

returning from main exits the entire process (all its threads) same as calling exit; not like other threads race: main's return 0 or print message's printf first? time main: printf/pthread_create/printf/return print message: printf/return return from main ends all threads in the process

the correctness problem

two threads?

introduces non-determinism

which one runs first?

allows for "race condition" bugs

...to be avoided with synchronization constructs

example application: ATM server

commands: withdraw, deposit

one correctness goal: don't lose money

ATM server (pseudocode) ServerLoop() { while (true) { ReceiveRequest(&operation, &accountNumber, &amount); if (operation == DEPOSIT) { Deposit(accountNumber, amount); } else ... Deposit(accountNumber, amount) { account = GetAccount(accountNumber); account->balance += amount; SaveAccountUpdates(account);

a threaded server?

```
Deposit(accountNumber, amount) {
    account = GetAccount(accountId);
    account->balance += amount;
    SaveAccountUpdates(account);
maybe GetAccount/SaveAccountUpdates can be slow?
    read/write disk sometimes? contact another server sometimes?
maybe lots of requests to process?
    maybe real logic has more checks than Deposit()
all reasons to handle multiple requests at once
```

 \rightarrow many threads all running the server loop

multiple threads

```
main() {
    for (int i = 0; i < NumberOfThreads; ++i) {</pre>
        pthread_create(&server_loop_threads[i], NULL,
                        ServerLoop, NULL);
ServerLoop() {
    while (true) {
        ReceiveRequest(&operation, &accountNumber, &amount);
        if (operation == DEPOSIT) {
            Deposit(accountNumber, amount);
        } else ...
```

the lost write

```
account->balance += amount; (in two threads, same account)
          Thread A
                                       Thread B
mov account->balance, %rax
add amount, %rax
                         context switch
                                mov account->balance, %rax
                                add amount, %rax
                         context switch
mov %rax, account->balance
                         context switch
                                mov %rax, account->balance
```

the lost write

```
account->balance += amount; (in two threads, same account)
          Thread A
                                        Thread B
mov account->balance, %rax
add amount, %rax
                         context switch
                                 mov account->balance, %rax
                                 add amount, %rax
                         context switch
mov %rax, account->balance
                         context switch
                                 mov %rax, account->balance
     lost write to balance
                                      "winner" of the race
```

the lost write

```
account->balance += amount; (in two threads, same account)
          Thread A
                                        Thread B
mov account->balance, %rax
add amount, %rax
                         context switch
                                 mov account->balance, %rax
                                 add amount, %rax
                         context switch
mov %rax, account->balance
                         context switch
                                 mov %rax, account->balance
     lost write to balance
                                      "winner" of the race
    lost track of thread A's money
```

thinking about race conditions (1)

what are the possible values of x? (initially x = y = 0)

Thread A Thread B $x \leftarrow 1$ $y \leftarrow 2$

thinking about race conditions (2)

possible values of x? (initially x = y = 0)

Thread A Thread B $x \leftarrow y + 1 \qquad y \leftarrow 2$ $y \leftarrow y \times 2$

thinking about race conditions (2)

possible values of x? (initially x = y = 0)

Thread A Thread B $x \leftarrow y + 1 \qquad y \leftarrow 2$ $y \leftarrow y \times 2$

thinking about race conditions (3)

what are the possible values of x?

(initially
$$x = y = 0$$
)

Thread A Thread B
$$x \leftarrow 1 \qquad x \leftarrow 2$$

thinking about race conditions (2)

possible values of x? (initially x = y = 0)

Thread A Thread B $x \leftarrow y + 1 \qquad y \leftarrow 2$ $y \leftarrow y \times 2$

atomic operation

atomic operation = operation that runs to completion or not at all we will use these to let threads work together

most machines: loading/storing (aligned) words is atomic so can't get 3 from $x \leftarrow 1$ and $x \leftarrow 2$ running in parallel aligned \approx address of word is multiple of word size (typically done by compilers)


but some instructions are not atomic; examples:

x86: integer add constant to memory location many CPUs: loading/storing values that cross cache blocks
e.g. if cache blocks 0x40 bytes, load/store 4 byte from addr. 0x3E is not atomic

lost adds (program)

```
.global update_loop
update loop:
   addl $1, the_value // the_value (global variable) += 1
   dec %rdi  // argument 1 -= 1
   jg update_loop // if argument 1 >= 0 repeat
   ret
int the_value;
extern void *update_loop(void *);
int main(void) {
    the value = 0;
    pthread t A, B;
    pthread_create(&A, NULL, update_loop, (void*) 1000000);
    pthread create(&B, NULL, update loop, (void*) 1000000);
   pthread_join(A, NULL); pthread_join(B, NULL);
   // expected result: 1000000 + 1000000 = 2000000
   printf("the value = %d\n", the value);
```

lost adds (results)



but how?

probably not possible on single core exceptions can't occur in the middle of add instruction

...but 'add to memory' implemented with multiple steps still needs to load, add, store internally can be interleaved with what other cores do

but how?

```
probably not possible on single core exceptions can't occur in the middle of add instruction
```

...but 'add to memory' implemented with multiple steps still needs to load, add, store internally can be interleaved with what other cores do

(and actually it's more complicated than that — we'll talk later)

so, what is actually atomic

```
for now we'll assume: load/stores of 'words' (64-bit machine = 64-bits words)
```

in general: processor designer will tell you

their job to design caches, etc. to work as documented

compilers move loads/stores (1)

compilers move loads/stores (1)

compilers move loads/stores (2)

```
void WaitForOther() {
    is waiting = 1;
    do {} while (!other_ready);
    is waiting = 0;
WaitForOther:
 // compiler optimization: don't set is waiting to 1,
 // (why? it will be set to 0 anyway)
  movl other_ready, %eax // eax <- other_ready</pre>
.L2:
  testl %eax, %eax
  je .L2
                             // while (eax == 0) repeat
  movl $0, is_waiting // is_waiting <- 0
```

compilers move loads/stores (2)

```
void WaitForOther() {
    is waiting = 1;
    do {} while (!other_ready);
    is waiting = 0;
WaitForOther:
 // compiler optimization: don't set is waiting to 1,
 // (why? it will be set to 0 anyway)
  movl other_ready, %eax // eax <- other_ready</pre>
.L2:
  testl %eax, %eax
  je .L2
                             // while (eax == 0) repeat
 movl $0, is_waiting // is_waiting <- 0</pre>
```

compilers move loads/stores (2)

```
void WaitForOther() {
    is waiting = 1;
    do {} while (!other_ready);
    is waiting = 0;
WaitForOther:
 // compiler optimization: don't set is waiting to 1,
  // (why? it will be set to 0 anyway)
 movl other_ready, %eax // eax <- other_ready</pre>
.L2:
  testl %eax, %eax
  je .L2
                             // while (eax == 0) repeat
  movl $0, is_waiting // is_waiting <- 0
```

fixing compiler reordering?

isn't there a way to tell compiler not to do these optimizations?

yes, but that is still not enough!

processors sometimes do this kind of reordering too (between cores)

pthreads and reordering

many pthreads functions prevent reordering everything before function call actually happens before

includes preventing some optimizations

e.g. keeping global variable in register for too long

pthread_create, pthread_join, other tools we'll talk about ... basically: if pthreads is waiting for/starting something, no weird ordering

implementation part 1: prevent compiler reordering

implementation part 2: use special instructions example: x86 mfence instruction

some definitions

mutual exclusion: ensuring only one thread does a particular thing at a time

like checking for and, if needed, buying milk

some definitions

mutual exclusion: ensuring only one thread does a particular thing at a time

like checking for and, if needed, buying milk

critical section: code that exactly one thread can execute at a time

result of critical section

some definitions

mutual exclusion: ensuring only one thread does a particular thing at a time

like checking for and, if needed, buying milk

critical section: code that exactly one thread can execute at a time

result of critical section

lock: object only one thread can hold at a time
interface for creating critical sections

lock analogy

agreement: only change account balances while wearing this hat normally hat kept on table put on hat when editing balance

hopefully, only one person (= thread) can wear hat a time need to wait for them to remove hat to put it on

lock analogy

agreement: only change account balances while wearing this hat normally hat kept on table put on hat when editing balance

hopefully, only one person (= thread) can wear hat a time need to wait for them to remove hat to put it on

"lock (or acquire) the lock" = get and put on hat

"unlock (or release) the lock" = put hat back on table

the lock primitive

```
locks: an object with (at least) two operations: 

acquire or lock — wait until lock is free, then "grab" it 

release or unlock — let others use lock, wakeup waiters
```

typical usage: everyone acquires lock before using shared resource forget to acquire lock? weird things happen

```
Lock(account_lock);
balance += ...;
Unlock(account_lock);
```

the lock primitive

```
locks: an object with (at least) two operations: 

acquire or lock — wait until lock is free, then "grab" it 

release or unlock — let others use lock, wakeup waiters
```

typical usage: everyone acquires lock before using shared resource forget to acquire lock? weird things happen

```
Lock(account_lock);
balance += ...;
Unlock(account_lock);
```

waiting for lock?

when waiting — ideally:

not using processor (at least if waiting a while)

OS can context switch to other programs

pthread mutex

```
#include <pthread.h>
pthread_mutex_t account_lock;
pthread mutex init(&account lock, NULL);
   // or: pthread_mutex_t account_lock =
                    PTHREAD MUTEX INITIALIZER;
pthread_mutex_lock(&account_lock);
balance += ...;
pthread_mutex_unlock(&account lock);
```

```
exercise
pthread mutex t lock1 = PTHREAD MUTEX INITIALIZER;
pthread mutex t lock2 = PTHREAD MUTEX INITIALIZER;
string one = "init one", two = "init two";
void ThreadA() {
    pthread_mutex_lock(&lock1);
    one = "one in ThreadA"; // (A1)
    pthread_mutex_unlock(&lock1);
    pthread mutex lock(&lock2);
    two = "two in ThreadA"; // (A2)
    pthread mutex unlock(&lock2);
}
void ThreadB() {
    pthread mutex lock(&lock1);
    one = "one in ThreadB"; // (B1)
    pthread mutex lock(&lock2);
    two = "two in ThreadB"; // (B2)
    pthread mutex unlock(&lock2);
    pthread mutex unlock(&lock1);
possible values of one/two after A+B run?
```

```
exercise (alternate 1)
pthread_mutex_t lock1 = PTHREAD_MUTEX_INITIALIZER;
 pthread mutex t lock2 = PTHREAD MUTEX INITIALIZER;
 string one = "init one", two = "init two";
void ThreadA() {
     pthread_mutex_lock(&lock2);
     two = "two in ThreadA"; // (A2)
     pthread mutex unlock(&lock2);
     pthread mutex lock(&lock1);
     one = "one in ThreadA"; // (A1)
     pthread mutex unlock(&lock1);
 }
void ThreadB() {
     pthread_mutex_lock(&lock1);
     one = "one in ThreadB"; // (B1)
     pthread mutex lock(&lock2);
     two = "two in ThreadB"; // (B2)
     pthread mutex unlock(&lock2);
     pthread mutex unlock(&lock1);
```

possible values of one/two after A+B run?

```
exercise (alternate 2)
pthread_mutex_t lock1 = PTHREAD_MUTEX_INITIALIZER;
 pthread mutex t lock2 = PTHREAD MUTEX INITIALIZER;
 string one = "init one", two = "init two";
 void ThreadA() {
     pthread_mutex_lock(&lock2);
     two = "two in ThreadA"; // (A2)
     pthread mutex unlock(&lock2);
     pthread mutex lock(&lock1);
     one = "one in ThreadA"; // (A1)
     pthread mutex unlock(&lock1);
 }
 void ThreadB() {
     pthread mutex lock(&lock1);
     one = "one in ThreadB"; // (B1)
     pthread mutex unlock(&lock1);
     pthread mutex lock(&lock2);
     two = "two in ThreadB"; // (B2)
     pthread mutex unlock(&lock2);
possible values of one/two after A+B run?
```

7

POSIX mutex restrictions

pthread_mutex rule: unlock from same thread you lock in

does this actually matter?

depends on how pthread_mutex is implemented

preview: general sync

lots of coordinating threads beyond locks/barriers

will talk about two general tools later:

monitors/condition variables semaphores

big added feature: wait for arbitrary thing to happen

a bad idea

```
one bad idea to wait for an event:
pthread mutex t lock = PTHREAD MUTEX INITIALIZER; bool ready = false;
void WaitForReadv() {
    pthread mutex lock(&lock);
    do {
        pthread_mutex_unlock(&lock);
        /* only time MarkReady() can run */
        pthread_mutex_lock(&lock);
    } while (!ready);
    pthread mutex unlock(&lock);
void MarkReady() {
    pthread mutex lock(&lock);
    ready = true;
    pthread_mutex_unlock(&lock);
```

wastes processor time; MarkReady can stall waiting for unlock window

beyond locks

transactions

```
in practice: want more than locks for synchronization
for waiting for arbtirary events (without CPU-hogging-loop):
    monitors
    semaphores
for common synchornization patterns:
    barriers
    reader-writer locks
higher-level interface:
```

barriers

compute minimum of 100M element array with 2 processors algorithm:

compute minimum of 50M of the elements on each CPU one thread for each CPU

wait for all computations to finish

take minimum of all the minimums

barriers

compute minimum of 100M element array with 2 processors algorithm:

compute minimum of 50M of the elements on each CPU one thread for each CPU

wait for all computations to finish

take minimum of all the minimums

barriers API

barrier.Initialize(NumberOfThreads)

barrier.Wait() — return after all threads have waited

idea: multiple threads perform computations in parallel

threads wait for all other threads to call Wait()

barrier: waiting for finish

```
barrier.Initialize(2);
       Thread 0
                                 Thread 1
 partial_mins[0] =
     /* min of first
        50M elems */;
                            partial_mins[1] =
                               /* min of last
barrier.Wait();
                                   50M elems */
                            barrier.Wait();
 total min = min(
     partial mins[0],
     partial mins[1]
```

barriers: reuse

Thread 0 results[0][0] = getInitial(0); barrier.Wait(); results[1][0] = computeFrom(results[0][0], results[0][1] barrier.Wait(); results[2][0] = computeFrom(results[1][0], results[1][1]);

Thread 1

```
results[0][1] = getInitial(1);
barrier.Wait();
results[1][1] =
    computeFrom(
        results[0][0],
        results[0][1]
barrier.Wait();
results[2][1] =
    computeFrom(
        results[1][0],
        results[1][1]
    );
```

barriers: reuse

Thread 0 results[0][0] = getInitial(0); barrier.Wait(); results[1][0] = computeFrom(results[0][0], results[0][1] barrier.Wait(); results[2][0] = computeFrom(results[1][0], results[1][1]);

Thread 1

```
results[0][1] = getInitial(1);
barrier.Wait();
results[1][1] =
    computeFrom(
        results[0][0],
        results[0][1]
barrier.Wait();
results[2][1] =
    computeFrom(
        results[1][0],
        results[1][1]
    );
```

barriers: reuse

Thread 0 results[0][0] = getInitial(0); barrier.Wait(); results[1][0] = computeFrom(results[0][0], results[0][1] barrier.Wait(); results[2][0] = computeFrom(results[1][0], results[1][1]);

Thread 1

```
results[0][1] = getInitial(1);
barrier.Wait();
results[1][1] =
    computeFrom(
        results[0][0],
        results[0][1]
barrier.Wait();
results[2][1] =
    computeFrom(
        results[1][0],
        results[1][1]
    );
```

pthread barriers

```
pthread_barrier_t barrier;
pthread_barrier_init(
    &barrier,
    NULL /* attributes */,
    numberOfThreads
);
...
pthread_barrier_wait(&barrier);
```

exercise

```
pthread_barrier_t barrier; int x = 0, y = 0;
void thread one() {
    y = 10;
    pthread_barrier_wait(&barrier);
    y = x + y;
    pthread barrier wait(&barrier);
    pthread barrier wait(&barrier);
    printf("%d %d\n", x, y);
void thread two() {
    x = 20;
    pthread barrier wait(&barrier);
    pthread barrier wait(&barrier);
    x = x + y;
    pthread barrier wait(&barrier);
}
```

output? (if both run at once, barrier set for 2 threads)

life homework (pseudocode)

```
for (int time = 0; time < MAX_ITERATIONS; ++time) {
    for (int y = 0; y < size; ++y) {
        for (int x = 0; x < size; ++x) {
            to_grid(x, y) = computeValue(from_grid, x, y);
        }
    }
    swap(from_grid, to_grid);
}</pre>
```

life homework

compute grid of values for time t from grid for time t-1 compute new value at i,j based on surrounding values

parallel version: produce parts of grid in different threads use barriers to finish time t before going to time t+1

example: producer/consumer



shared buffer (queue) of fixed size

one or more producers inserts into queue one or more consumers removes from queue


example: producer/consumer



shared buffer (queue) of fixed size

one or more producers inserts into queue one or more consumers removes from queue

example: producer/consumer



shared buffer (queue) of fixed size

one or more producers inserts into queue one or more consumers removes from queue

producer(s) and consumer(s) don't work in lockstep (might need to wait for each other to catch up)

example: C compiler \rightarrow preprocessor \rightarrow compiler \rightarrow assembler \rightarrow linker

monitors/condition variables

locks for mutual exclusion

```
condition variables for waiting for event
    operations: wait (for event); signal/broadcast (that event happened)
related data structures
```

a monitor


lock
shared data
condvar 1
condvar 2
operation1()
operation2()


a monitor

lock
shared data
condvar 1
condvar 2

operation1()
operation2()

lock must be acquired before accessing any part of monitor's stuff






condvar operations:

Wait(cv, lock) — unlock lock, add current thread to cv queue ...and reacquire lock before returning

Broadcast(cv) — remove all from condvar queue

Signal(cv) — remove one from condvar queue




condvar operations:

Wait(cv, lock) — unlock lock, add current thread to cv queue ...and reacquire lock before returning

Broadcast(cv) — remove all from condvar queue

Signal(cv) — remove one from condvar queue




condvar operations:

Wait(cv, lock) — unlock lock, add current thread to cv queue

...and reacquire lock before returning

Broadcast(cv) — remove all from condvar queue




condvar operations:

Wait(cv, lock) — unlock lock, add current thread to cv queue ...and reacquire lock before returning

Broadcast(cv) — remove all from condvar queue

Signal(cv) — remove one from condvar queue




condvar operations:

Wait(cv, lock) — unlock lock, add current thread to cv queue ...and reacquire lock before returning

Broadcast(cv) — remove all from condvar queue

Signal(cv) — remove one from condvar queue



```
// MISSING: init calls, etc.
pthread mutex t lock;
bool finished; // data, only accessed with after acquiring lock
pthread_cond_t finished_cv; // to wait for 'finished' to be true
void WaitForFinished() {
  pthread_mutex_lock(&lock);
  while (!finished) {
    pthread_cond_wait(&finished_cv, &lock);
  pthread_mutex_unlock(&lock);
void Finish() {
  pthread_mutex_lock(&lock);
  finished = true;
  pthread_cond_broadcast(&finished_cv);
  pthread_mutex_unlock(&lock);
```

```
// MISSING: init calls, etc.
pthread mutex t lock;
bool finished; // data, only accessed with after acquiring lock
pthread_cond_t finished_cv; // to wait for 'finished' to be true
void WaitForFinished() {
  pthread_mutex_lock(&lock);
  while (!finished) {
    pthread_cond_wait(&finished_cv, &tock);
                                       acquire lock before
  pthread_mutex_unlock(&lock);
                                       reading or writing finished
void Finish() {
  pthread_mutex_lock(&lock);
  finished = true;
  pthread_cond_broadcast(&finished_cv);
  pthread_mutex_unlock(&lock);
```

```
// MISSING: init calls, etc.
pthread mutex t lock;
bool finished; // data, only accessed with after acquiring lock
pthread_cond_t finished_cv; // to wait for 'finished' to be true
void WaitForFinished() {
  pthread_mutex_lock(&lock);
                                 check whether we need to wait at all
 while (!finished) {
    pthread_cond_wait(&finished_(why a loop? we'll explain later)
  pthread_mutex_unlock(&lock);
void Finish() {
  pthread_mutex_lock(&lock);
  finished = true;
  pthread_cond_broadcast(&finished_cv);
  pthread_mutex_unlock(&lock);
```

```
// MISSING: init calls, etc.
pthread mutex t lock;
bool finished; // data, only accessed with after acquiring lock
pthread_cond_t finished_cv; // to wait for 'finished' to be true
void WaitForFinished() {
  pthread_mutex_lock(&lock);
  while (!finished) {
    pthread cond_wait(&finished_cv, &lock);
  pthread_mutex_unlock(&lock);
                            know we need to wait
void Finish() {
                            (finished can't change while we have lock)
  pthread_mutex_lock(&lock
                            so wait, releasing lock...
  finished = true:
  pthread_cond_broadcast(&finished_cv);
  pthread_mutex_unlock(&lock);
```

```
// MISSING: init calls, etc.
pthread mutex t lock;
bool finished; // data, only accessed with after acquiring lock
pthread_cond_t finished_cv; // to wait for 'finished' to be true
void WaitForFinished() {
  pthread_mutex_lock(&lock);
  while (!finished) {
    pthread_cond_wait(&finished_cv, &lock);
  pthread_mutex_unlock(&lock);
                                          allow all waiters to proceed
                                          (once we unlock the lock)
void Finish() {
  pthread_mutex_lock(&lock);
  finished = true;
  pthread_cond_broadcast(&finished_cv);
  pthread mutex unlock(&lock);
```

WaitForFinish timeline 1

WaitForFinish thread	Finish thread
<pre>mutex_lock(&lock)</pre>	
(thread has lock)	
	<pre>mutex_lock(&lock)</pre>
	(start waiting for lock)
while (!finished)	
<pre>cond_wait(&finished_cv, &lock);</pre>	
(start waiting for cv)	(done waiting for lock)
	finished = true
	<pre>cond_broadcast(&finished_cv)</pre>
(done waiting for cv)	
(start waiting for lock)	
	mutex_unlock(&lock)
(done waiting for lock)	
while (!finished)	
(finished now true, so return)	
<pre>mutex_unlock(&lock)</pre>	

WaitForFinish thread | mutex_lock(&lock) | finished = true | cond_broadcast(&finished_cv) | mutex_unlock(&lock) | | while (!finished) ... (finished now true, so return) | mutex_unlock(&lock)

why the loop

```
while (!finished) {
   pthread_cond_wait(&finished_cv, &lock);
}
we only broadcast if finished is true
so why check finished afterwards?
```

why the loop

```
while (!finished) {
  pthread_cond_wait(&finished_cv, &lock);
we only broadcast if finished is true
so why check finished afterwards?
pthread cond wait manual page:
    "Spurious wakeups ... may occur."
spurious wakeup = wait returns even though nothing happened
```

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
    buffer.enqueue(item);
    pthread_cond_signal(&data_ready);
    pthread_mutex_unlock(&lock);
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread_mutex_unlock(&lock);
    return item;
```

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedOueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
    buffer.enqueue(item);
    pthread_cond_signal(&data_ready);
    pthread_mutex_unlock(&lock);
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread_mutex_unlock(&lock);
    return item:
```

rule: never touch buffer without acquiring lock
otherwise: what if two threads simulatenously en/dequeue?
(both use same array/linked list entry?)
(both reallocate array?)

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedOueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
    buffer.enqueue(item);
    pthread_cond_signal(&data_ready);
    pthread_mutex_unlock(&lock);
                                                check if empty
                                                if so, dequeue
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
                                                okay because have lock
        pthread_cond_wait(&data_ready, &lock);
                                   other threads cannot dequeue here
    item = buffer.dequeue();
    pthread_mutex_unlock(&lock);
    return item;
```

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
                                                wake one Consume thread
    buffer.enqueue(item);
    pthread_cond_signal(&data_ready);
                                                if any are waiting
    pthread_mutex_unlock(&lock);
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread_mutex_unlock(&lock);
    return item;
```

```
Thread 1
                                                                  Thread 2
pthread_mutex_t lock;
                                         Produce()
pthread_cond_t data_ready;
                                          ...lock
UnboundedOueue buffer;
                                          ...enqueue
                                          ...signal
Produce(item) {
                                          ...unlock
    pthread_mutex_lock(&lock);
                                                             Consume()
    buffer.engueue(item);
                                                             ...lock
    pthread_cond_signal(&data_ready)
                                                             ...empty? no
    pthread_mutex_unlock(&lock);
                                                             ...dequeue
                                                             ...unlock
Consume() {
                                                             return
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
         pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread_mutex_unlock(&lock)
                                      Oiterations: Produce() called before Consume()
    return item;
                                       iteration: Produce() signalled, probably
                                       + iterations: spurious wakeup or ...?
```

```
Thread 1
                                                                   Thread 2
pthread_mutex_t lock;
                                                               Consume()
pthread_cond_t data_ready;
                                                               ...lock
UnboundedOueue buffer;
                                                               ...empty? yes
                                                               ...unlock/start wait
Produce(item) {
                                                   Produce()
                                                                   waiting for
    pthread_mutex_lock(&lock);
                                                   ...lock
    buffer.engueue(item);
                                                                   data ready
                                                   ...enqueue
    pthread_cond_signal(&data_ready);
                                                   ...signal
                                                              stop wait
    pthread_mutex_unlock(&lock);
                                                   ...unlock
                                                              lock
                                                               ...empty? no
Consume() {
                                                               ...dequeue
    pthread_mutex_lock(&lock);
                                                               ...unlock
    while (buffer.empty()) {
         pthread_cond_wait(&data_ready, &loc
                                                              return
    item = buffer.dequeue();
    pthread_mutex_unlock(&lock)
                                      0 iterations: Produce() called before Consume()
    return item;
                                        iteration: Produce() signalled, probably
                                        + iterations: spurious wakeup or ...?
```

```
Thread 1
                                                         Thread 2
                                                                         Thread 3
pthread_mutex_t lock;
                                                    Consume()
pthread_cond_t data_ready;
                                                    ...lock
UnboundedOueue buffer;
                                                    ...empty? yes
                                                    ...unlock/start wait
Produce(item) {
                                        Produce()
                                                         waiting for
     pthread_mutex_lock(&lock);
                                        ..lock
                                                                        Consume()
     buffer.engueue(item);
                                                         data ready
                                        ...enqueue
                                                                         waiting for
     pthread_cond_signal(&data_rea
                                        ...signal
                                                    stop wait
     pthread_mutex_unlock(&lock);
                                                                            lock
                                                                        lock
                                        ...unlock
                                                         waiting for
                                                                        ...empty? no
Consume() {
                                                            lock
                                                                         ...dequeue
    pthread_mutex_lock(&lock);
                                                                         ...unlock
    while (buffer.empty()) {
                                                    ...lock
         pthread_cond_wait(&data_r
                                                                        return
                                                    ...empty? yes
                                                    ...unlock/start wait
     item = buffer.dequeue();
     pthread_mutex_unlock(&lock)
                                       0 iterations: Produce() called before Consume()
     return item;
                                         iteration: Produce() signalled, probably
                                          iterations: spurious wakeup or ...?
```

```
Thread 1
                                                            Thread 2
                                                                             Thread 3
pthread_mutex_t lock;
                                                       Consume()
pthread_cond_t data_ready;
                                                       ...lock
UnboundedOueue buffer;
                                                       ...empty? yes
                                                       ...unlock/start wait
in pthreads: signalled thread not
                                          Produce()
                                                            waiting for
    gaurenteed to hold lock next);
                                           ...lock
                                                                            Consume()
                                                            data ready
                 alternate design: a_rea ...enqueue ...signal
                                                                             waiting for
                                                       stop wait
                                                                                lock
                                                                            lock
                                          ...unlock
   signalled thread gets lock next
                                                            waiting for
                                                                             ...empty? no
        called "Hoare scheduling"
                                                               lock
                                                                             ...dequeue
   not done by pthreads, Java, ...
                                                                             ...unlock
                                                       ...lock
          pthread_cond_wait(&data_r
                                                                            return
                                                       ...empty? yes
     item = buffer.dequeue();
                                                       ...unlock/start wait
     pthread_mutex_unlock(&lock)
                                         0 iterations: Produce() called before Consume()
     return item;
                                           iteration: Produce() signalled, probably
                                             iterations: spurious wakeup or ...?
```

Hoare versus Mesa monitors

```
Hoare-style monitors signal 'hands off' lock to awoken thread
```

```
Mesa-style monitors

any eligible thread gets lock next

(maybe some other idea of priority?)
```

every current threading library I know of does Mesa-style

```
pthread mutex t lock;
pthread_cond_t data_ready; pthread_cond_t space_ready;
BoundedQueue buffer;
Produce(item) {
    pthread mutex lock(&lock);
    while (buffer.full()) { pthread_cond_wait(&space_ready, &lock); }
    buffer.engueue(item);
    pthread_cond_signal(&data_ready);
    pthread mutex unlock(&lock);
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    }
    item = buffer.dequeue();
    pthread_cond_signal(&space_ready);
    pthread_mutex_unlock(&lock);
    return item;
```

```
pthread mutex t lock;
pthread_cond_t data_ready; pthread_cond_t space_ready;
BoundedQueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
    while (buffer.full()) { pthread_cond_wait(&space_ready, &lock); }
    buffer.engueue(item);
    pthread_cond_signal(&data_ready);
    pthread mutex unlock(&lock);
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread_cond_signal(&space_ready);
    pthread_mutex_unlock(&lock);
    return item;
```

```
pthread mutex t lock;
pthread_cond_t data_ready; pthread_cond_t space_ready;
BoundedQueue buffer;
Produce(item) {
    pthread mutex lock(&lock);
    while (buffer.full()) { pthread_cond_wait(&space_ready, &lock); }
    buffer.enqueue(item);
    pthread cond signal (&data ready):
    pt correct (but slow?) to replace with:
Consum pthread_cond_broadcast(&space_ready);
       (just more "spurious wakeups")
        pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread_cond_signal(&space_ready);
    pthread_mutex_unlock(&lock);
    return item;
```

return item;

```
pthread_mutex_t lock;
pthread_cond_t data_ready; pthread_cond_t space_ready;
BoundedQueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
    while (buffer.full()) { pthread_cond_wait(&space_ready, &lock); }
    buffer.engueue(item);
    pthread_cond_signal(&data_ready);
                                              correct but slow to replace
    pthread mutex unlock(&lock);
                                              data ready and space ready
Consume() {
                                              with 'combined' condvar ready
    pthread_mutex_lock(&lock);
                                              and use broadcast
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock) (just more "spurious wakeups")
    item = buffer.dequeue();
    pthread_cond_signal(&space_ready);
    pthread_mutex_unlock(&lock);
```

monitor pattern

```
pthread mutex lock(&lock);
while (!condition A) {
    pthread_cond_wait(&condvar_for_A, &lock);
... /* manipulate shared data, changing other conditions */
if (set condition A) {
    pthread_cond_broadcast(&condvar_for_A);
   /* or signal, if only one thread cares */
if (set condition B) {
    pthread cond broadcast(&condvar for B);
    /* or signal, if only one thread cares */
pthread_mutex_unlock(&lock)
```

monitors rules of thumb

never touch shared data without holding the lock

keep lock held for entire operation:

verifying condition (e.g. buffer not full) up to and including manipulating data (e.g. adding to buffer)

create condvar for every kind of scenario waited for

always write loop calling cond_wait to wait for condition X

broadcast/signal condition variable every time you change X

monitors rules of thumb

never touch shared data without holding the lock

keep lock held for entire operation:

verifying condition (e.g. buffer not full) up to and including manipulating data (e.g. adding to buffer)

create condvar for every kind of scenario waited for

always write loop calling cond_wait to wait for condition X

broadcast/signal condition variable every time you change X

correct but slow to...

broadcast when just signal would work broadcast or signal when nothing changed use one condvar for multiple conditions

mutex/cond var init/destroy

```
pthread_mutex_t mutex;
pthread cond t cv;
pthread_mutex_init(&mutex, NULL);
pthread_cond_init(&cv, NULL);
// --OR--
pthread_mutex_t mutex = PTHREAD_MUTEX_INITIALIZER;
pthread cond t cv = PTHREAD COND INITIALIZER;
// and when done:
pthread cond destroy(&cv);
pthread mutex destroy(&mutex);
```

wait for both finished

```
// MISSING: init calls, etc.
pthread mutex t lock;
bool finished[2];
pthread_cond_t both_finished_cv;
void WaitForBothFinished() {
  pthread_mutex_lock(&lock);
 while (______
   pthread_cond_wait(&both_finished_cv, &lock);
  pthread_mutex_unlock(&lock);
void Finish(int index) {
  pthread_mutex_lock(&lock);
  finished[index] = true;
  pthread_mutex_unlock(&lock);
```

wait for both finished

```
A. finished[0] && finished[1]
// MISSING: init calls, etc.
                                  B. finished[0] || finished[1]
pthread mutex t lock;
                                  C. !finished[0] || !finished[1]
bool finished[2];
                                  D. finished[0] != finished[1]
pthread_cond_t both_finished_cv;
                                  E. something else
void WaitForBothFinished() {
  pthread_mutex_lock(&lock);
  while (______
   pthread_cond_wait(&both_finished_cv, &lock);
  pthread_mutex_unlock(&lock);
void Finish(int index) {
  pthread_mutex_lock(&lock);
  finished[index] = true;
  pthread_mutex_unlock(&lock);
```

wait for both finished

```
// MISSING: init calls, etc.
pthread mutex t lock;
                           A. pthread cond signal(&both finished cv)
bool finished[2];
                           B. pthread_cond_broadcast(&both_finished_cv)
pthread_cond_t both_fini
                           C. if (finished[1-index])
                                   pthread cond singal(&both finished cv);
void WaitForBothFinished D if (finished[1-index])
  pthread_mutex_lock(&lo
                                   pthread_cond_broadcast(&both_finished_cv);
                           E. something else
  while (
    pthread_cond_wait(&both_finished_cv, &lock);
  pthread_mutex_unlock(&lock);
void Finish(int index) {
  pthread_mutex_lock(&lock);
  finished[index] = true;
  pthread mutex unlock(&lock);
```

monitor exercise: barrier

suppose we want to implement a one-use barrier; fill in blanks:

```
struct BarrierInfo {
    pthread mutex t lock;
    int total_threads; // initially total # of threads
    int number_reached; // initially 0
};
void BarrierWait(BarrierInfo *b) {
    pthread mutex lock(&b->lock);
    ++b->number reached;
    if (b->number_reached == b->total_threads) {
    } else {
    pthread mutex unlock(&b->lock);
```

generalizing locks: semaphores

semaphore has a non-negative integer value and two operations:

P() or **down** or **wait**: wait for semaphore to become positive (>0), then decerement by 1

V() or **up** or **signal** or **post**: increment semaphore by 1 (waking up thread if needed)

P, V from Dutch: proberen (test), verhogen (increment)

semaphores are kinda integers

semaphore like an integer, but...

cannot read/write directly

down/up operaion only way to access (typically) exception: initialization

never negative — wait instead

down operation wants to make negative? thread waits

reserving books


```
suppose tracking copies of library book...
Semaphore free_copies = Semaphore(3);
void ReserveBook() {
    // wait for copy to be free
    free_copies.down();
    ... // ... then take reserved copy
void ReturnBook() {
    ... // return reserved copy
    free copies.up();
    // ... then wakekup waiting thread
```

suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book

Copy 1	
Copy 2	
Сору 3	
	_


free copies 3

suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book






suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book




free copies 2 after calling down to reserve

suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book



free copies 0 after calling down three times to reserve all copies


suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book





reserve book call down again start waiting...

suppose tracking copies of same library book non-negative integer count = # how many books used? up = give back book; down = take book



implementing mutexes with semaphores

```
struct Mutex {
    Semaphore s; /* with inital value 1 */
   /* value = 1 --> mutex if free */
    /* value = 0 --> mutex is busy */
MutexLock(Mutex *m) {
   m->s.down();
MutexUnlock(Mutex *m) {
   m->s.up();
```

implementing join with semaphores

```
struct Thread {
    Semaphore finish_semaphore; /* with initial value 0 */
   /* value = 0: either thread not finished OR already joined */
    /* value = 1: thread finished AND not joined */
};
thread join(Thread *t) {
    t->finish semaphore.down();
  assume called when thread finishes */
thread exit(Thread *t) {
    t->finish semaphore.up();
   /* tricky part: deallocating struct Thread safely? */
```

POSIX semaphores

```
#include <semaphore.h>
...
sem_t my_semaphore;
int process_shared = /* 1 if sharing between processes */;
sem_init(&my_semaphore, process_shared, initial_value);
...
sem_wait(&my_semaphore); /* down */
sem_post(&my_semaphore); /* up */
...
sem_destroy(&my_semaphore);
```

semaphore exercise

```
int value; sem t empty, ready; // with some initial values
void PutValue(int argument) {
    sem_wait(&empty);
    value = argument;
                        What goes in the blanks?
    sem_post(&ready);
                        A: sem_post(&empty) / sem_wait(&ready)
                        B: sem_wait(&ready) / sem_post(&empty)
                        C: sem_post(&ready) / sem_wait(&empty)
int GetValue() {
                        D: sem_post(&ready) / sem_post(&empty)
    int result:
                        E: sem_wait(&empty) / sem_post(&ready)
    result = value;
                        F: something else
    return result;
```

GetValue() waits for PutValue() to happen, retrieves value, then allows next

PutValue().

 $PutValue() \ waits \ for \ prior \ GetValue(), \ places \ value, \ then \ allows \ next \ GetValue().$

semaphore intuition

```
What do you need to wait for?
     critical section to be finished
     queue to be non-empty
     array to have space for new items
what can you count that will be 0 when you need to wait?
     # of threads that can start critical section now
     # of threads that can join another thread without waiting
     # of items in queue
     # of empty spaces in array
```

use up/down operations to maintain count

producer/consumer constraints

consumer waits for producer(s) if buffer is empty producer waits for consumer(s) if buffer is full any thread waits while a thread is manipulating the buffer

producer/consumer constraints

```
consumer waits for producer(s) if buffer is empty producer waits for consumer(s) if buffer is full any thread waits while a thread is manipulating the buffer
```

one semaphore per constraint:

```
sem_t full_slots; // consumer waits if empty
sem_t empty_slots; // producer waits if full
sem_t mutex; // either waits if anyone changing buffer
FixedSizedQueue buffer;
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 / * # thread that can use buffer at once */);
buffer.set_size(BUFFER_CAPACITY);
Produce(item) {
    sem_wait(&empty_slots); // wait until free slot, reserve it
    sem_wait(&mutex);
    buffer.enqueue(item);
    sem_post(&mutex);
    sem_post(&full_slots); // tell consumers there is more data
Consume() {
    sem_wait(&full_slots); // wait until queued item, reserve it
    sem wait(&mutex);
    item = buffer.dequeue();
    sem_post(&mutex);
    sem_post(&empty_slots); // let producer reuse item slot
    return item;
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, \dots, 1 /* # thread that can use buffer at once */);
buffer.set_size(BUFFER_CAPACITY);
Produce(item) {
    sem_wait(&empty_slots); // wait until free slot, reserve it
    sem_wait(&mutex);
    buffer.enqueue(item);
    sem_post(&mutex);
    sem_post(&full_slots); // tell consumers there is more data
Consume() {
    sem_wait(&full_slots); // wait until queued item, reserve it
    sem wait(&mutex);
    item = buffer.dequeue();
    sem_post(&mutex);
    sem_post(&empty_slots); // let producer reuse item slot
    return item;
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, \dots, 1 /* # thread that can use buffer at once */);
buffer.set_size(BUFFER_CAPACITY);
Produce(item) {
    sem_wait(&empty_slots); // wait until free slot, reserve it
    sem_wait(&mutex);
    buffer.enqueue(item);
    sem_post(&mutex);
    sem_post(&full_slots); // tell consumers there is more data
Consume() {
    sem_wait(&full_slots); // wait until queued item, reserve it
    sem wait(&mutex);
    item = buffer.dequeue();
    sem_post(&mutex);
    sem_post(&empty_slots); // let producer reuse item slot
    return item;
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 / * # thread that can use buffer at once */);
buffer.set_size(BUFFER_CAPACITY);
Produce(item) {
    sem wait(&empty slots); // wait until free slot. reserve it
    sem_wait(&mutex);
                            Can we do
    buffer.engueue(item);
                              sem wait(&mutex);
    sem_post(&mutex);
                              sem_wait(&empty_slots);
    sem_post(&full_slots);
                            instead?
Consume() {
    sem_wait(&full_slots); // wait until queued item, reserve it
    sem wait(&mutex);
    item = buffer.dequeue();
    sem_post(&mutex);
    sem_post(&empty_slots); // let producer reuse item slot
    return item;
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 / * # thread that can use buffer at once */);
buffer.set_size(BUFFER_CAPACITY);
Produce(item) {
    sem wait(&empty slots); // wait until free slot. reserve it
   sem_wait(&mutex);
                            Can we do
    buffer.enqueue(item);
                              sem wait(&mutex);
    sem_post(&mutex);
                              sem_wait(&empty_slots);
                                                            data
   sem_post(&full_slots);
                            instead?
Consume() {
                           No. Consumer waits on sem wait(&mutex)
   sem_wait(&full_slots);
                           so can't sem post(&empty slots)
   sem wait(&mutex);
   item = buffer.dequeue()
                           (result: producer waits forever
   sem_post(&mutex);
                           problem called deadlock)
   sem_post(&empty_slots);
    return item:
```

producer/consumer: cannot reorder mutex/empty

```
ProducerReordered() {
    // BROKEN: WRONG ORDER
    sem_wait(&mutex);
    sem_wait(&empty_slots);
    ...
    sem_post(&mutex);
```

```
Consumer() {
   sem_wait(&full_slots);

// can't finish until
   // Producer's sem_post(&mutex):
   sem_wait(&mutex);

...

// so this is not reached
   sem_post(&full_slots);
```

```
sem_init(&full_slots, ..., 0 /* # buffer slots initially used */);
sem_init(&empty_slots, ..., BUFFER_CAPACITY);
sem_init(&mutex, ..., 1 / * # thread that can use buffer at once */);
buffer.set_size(BUFFER_CAPACITY):
Produce(item) {
    sem_wait(&empty_slots); // wait until free slot, reserve it
    sem_wait(&mutex);
    buffer.enqueue(item);
    sem_post(&mutex);
   sem_post(&full_slots Can we do
                                                       more data
                           sem post(&full slots);
                           sem_post(&mutex);
Consume() {
    sem_wait(&full_slots
                                                       reserve it
                        instead?
    sem wait(&mutex);
    item = buffer.dequeu Yes — post never waits
    sem post(&mutex);
    sem_post(&empty_slots); // let producer reuse item slot
    return item;
```

producer/consumer summary

```
producer: wait (down) empty_slots, post (up) full_slots
consumer: wait (down) full_slots, post (up) empty_slots
```

two producers or consumers? still works!

transactions

```
transaction: set of operations that occurs atomically
idea: something higher-level handles locking, etc.:
BeginTransaction();
int FromOldBalance = GetBalance(FromAccount);
int ToOldBalance = GetBalance(ToAccount);
SetBalance(FromAccount, FromOldBalance - 100);
SetBalance(ToAccount, FromOldBalance + 100);
EndTransaction();
idea: library/database/etc. makes "transaction" happens all at
once
```

consistency / durability

"happens all at once" = could mean:

locking to make sure no other operations interfere (consistency) making sure on crash, no partial transaction seen (durability)

(some systems provide both, some provide only one)

we'll just talk about implementing consistency

implementing consistency: simple

simplest idea: only one run transaction at a time

implementing consistency: locking

everytime something read/written: acquire associated lock

on end transaction: release lock

if deadlock: undo everything, go back to BeginTransaction(), retry how to undo? one idea: keep list of writes instead of writing apply writes only at EndTransaction()

implementing consistency: locking

everytime something read/written: acquire associated lock

on end transaction: release lock

if deadlock: undo everything, go back to BeginTransaction(), retry how to undo? one idea: keep list of writes instead of writing apply writes only at EndTransaction()

implementing consistency: optimistic

on read: copy version # for value read

on write: record value to be written, but don't write yet

on end transaction:

acquire locks on everything make sure values read haven't been changed since read

if they have changed, just retry transaction

backup slides

cache tradeoffs briefly

deciding cache size, associativity, etc.?

lots of tradeoffs:

more cache hits v. slower cache hits? faster cache hits v. fewer cache hits? more cache hits v. slower cache misses? ...

details depend on programs run

how often is same block used again? how often is same index bits used?

simulation to assess impact of designs

exercise (1)

2-way set associative, LRU, write-allocate, writeback

index	valid	tag	value	dirty	valid	tag	value	dirty	LRU
0	1	001100	mem[0x30] mem[0x31]	0	1	010000	mem[0x40] mem[0x41]	* 1	0
1	1	011000	mem[0x62] mem[0x63]	0	1	001100	mem[0x32] mem[0x33]	* 1	1

for each of the following accesses, performed alone, would it require (a) reading a value from memory (or next level of cache) and (b) writing a value to the memory (or next level of cache)?

writing 1 byte to 0x33 reading 1 byte from 0x52 reading 1 byte from 0x50

exercise (2)

2-way set associative, LRU, write-no-allocate, write-through

index	valid	tag	value	valid	tag	value	LRU
0	1	001100	mem[0x30] mem[0x31]	1	010000	mem[0x40] mem[0x41]	0
1	1	011000	mem[0x62] mem[0x63]	1	001100	mem[0x32] mem[0x33]	1

for each of the following accesses, performed alone, would it require (a) reading a value from memory and (b) writing a value to the memory?

writing 1 byte to 0x33 reading 1 byte from 0x52 reading 1 byte from 0x50

thread versus process state

```
thread state
     registers (including stack pointer, program counter)
process state
     address space
     open files
     process id
     list of thread states
```

process info with threads

parent process info

```
thread 0: {PC = 0x123456, rax = 42, rbx = ...}
thread 1: {PC = 0x584390, rax = 32, rbx = ...}

page tables
open files
fd 0: ...
fd 1: ...
```

Linux idea: task_struct

Linux model: single "task" structure = thread

pointers to address space, open file list, etc.

pointers can be shared

e.g. shared open files: open fd 4 in one task → all sharing can use fd 4

```
fork()-like system call "clone": choose what to share
    clone(0, ...) — similar to fork()
    clone(CLONE_FILES, ...) — like fork(), but sharing open files
    clone(CLONE_VM, new_stack_pointer, ...) — like fork(),
    but sharing address space
```

Linux idea: task_struct

Linux model: single "task" structure = thread pointers to address space, open file list, etc.

pointers can be shared

e.g. shared open files: open fd 4 in one task ightarrow all sharing can use fd 4

```
fork()-like system call "clone": choose what to share
    clone(0, ...) — similar to fork()
    clone(CLONE_FILES, ...) — like fork(), but sharing open files
    clone(CLONE_VM, new_stack_pointer, ...) — like fork(),
    but sharing address space
```

advantage: no special logic for threads (mostly) two threads in same process = tasks sharing everything possible

aside: alternate threading models

we'll talk about kernel threads

OS scheduler deals directly with threads

alternate idea: library code handles threads

kernel doesn't know about threads w/in process

hierarchy of schedulers: one for processes, one within each process

not currently common model — awkward with multicore

atomic read-modfiy-write

really hard to build locks for atomic load store and normal load/stores aren't even atomic...

...so processors provide read/modify/write operations

one instruction that atomically reads and modifies and writes back a value

used by OS to implement higher-level synchronization tools

x86 atomic exchange

```
lock xchg (%ecx), %eax
atomic exchange
temp ← M[ECX]
M[ECX] \leftarrow EAX
\mathsf{EAX} \leftarrow \mathsf{temp}
...without being interrupted by other processors, etc.
```

implementing atomic exchange

make sure other processors don't have cache block probably need to be able to do this to keep caches in sync

do read+modify+write operation

higher level tools

```
usually we won't use atomic operations directly
instead rely on OS/standard libraries using them
(along with context switching, disabling interrupts, ...)
OS/standard libraries will provide higher-level tools like...
pthread join
locks (pthread mutex)
...and more
```

backup slides

backup slides

using atomic exchange?

if two cores try at once, only one should do it

example: OS wants something done by whichever core tries first

does not want it started twice!

```
int global flag = 0;
void DoThingIfFirstToTry() {
    int my value = 1;
    AtomicExchange(&my_value, &global_flag);
    if (my value == 0) {
        /* flag was zero before, so I was first!*/
        DoThing();
    } else {
        /* flag was already 1 when we exchanged */
        /* I was second, so some other core is handling it */
```

recall: pthread mutex


```
#include <pthread.h>
pthread_mutex_t some_lock;
pthread mutex init(&some lock, NULL);
// or: pthread_mutex_t some_lock = PTHREAD_MUTEX_INITIALIZER;
pthread mutex lock(&some lock);
pthread mutex unlock(&some lock);
pthread_mutex_destroy(&some_lock);
```

life homework even/odd

```
naive way has an operation that needs locking:
for (int time = 0; time < MAX ITERATIONS; ++time) {</pre>
    ... compute to grid ...
    swap(from grid, to grid);
but this alternative needs less locking:
Grid grids[2];
for (int time = 0; time < MAX ITERATIONS; ++time) {</pre>
    from grid = &grids[time % 2];
    to grid = &grids[(time % 2) + 1];
    ... compute to_grid ...
```

life homework even/odd

```
naive way has an operation that needs locking:
for (int time = 0; time < MAX ITERATIONS; ++time) {</pre>
    ... compute to grid ...
    swap(from grid, to grid);
but this alternative needs less locking:
Grid grids[2];
for (int time = 0; time < MAX_ITERATIONS; ++time) {</pre>
    from grid = &grids[time % 2];
    to_grid = &grids[(time % 2) + 1];
    ... compute to_grid ...
```



mfence

ret

movl \$0, the lock

lock variable in shared memory: the_lock

```
if 1: someone has the lock; if 0: lock is free to take
```

// for memory order reasons

// then, set the_lock to 0 (not taker

movl \$0, the lock

ret

lock variable in shared memory: the_lock

```
if 1: someone has the lock; if 0: lock is free to take
```

// then, set the_lock to 0 (not taker

136

lock variable in shared memory: the_lock

movl \$0, the lock

ret

lock variable in shared memory: the lock

```
if 1: someone has the lock; if 0: lock is free to take
acquire:
    movl $1, %eax
    lock xchg %eax, the_lock // swap %eax and the lock
                                      // sets the_lock to 1 (taken)
                                         sets "eax to prior val of t
                          release lock by setting it to 0 (not taken)
    test %eax, %eax
    ine acquire
                          allows looping acquire to finish
    ret
release:
    mfence
                               // for memory order reasons
                               // then, set the_lock to 0 (not taker
```

lock variable in shared memory: the_lock

```
if 1: someone has the lock; if 0: lock is free to take
acquire:
    movl $1, %eax
    lock xchg %eax, the_lock // swap %eax and the lock
                                      // sets the_lock to 1 (taken)
                       Intel's manual says:
    test %eax, %eax
                       no reordering of loads/stores across a lock
    ine acquire
    ret
                        or mfence instruction
release:
```

exercise: spin wait

consider implementing 'waiting' functionality of pthread_join

```
thread calls ThreadFinish() when done
```

```
complete code below:
finished: .quad 0
```

ThreadFinish:

ret
ThreadWaitForFinish:

lock xchg %eax, finished cmp \$0, %eax
____ ThreadWaitForFinish ret

A. mfence; mov \$1, finished C. mov \$0, %eax E. je B. mov \$1, finished; mfence D. mov \$1, %eax F. jne

spinlock problems

lock abstraction is not powerful enough lock/unlock operations don't handle "wait for event" common thing we want to do with threads solution: other synchronization abstractions

spinlocks waste CPU time more than needed want to run another thread instead of infinite loop solution: lock implementation integrated with scheduler

spinlocks can send a lot of messages on the shared bus more efficient atomic operations to implement locks

spinlock problems

lock abstraction is not powerful enough lock/unlock operations don't handle "wait for event" common thing we want to do with threads

spinlocks waste CPU time more than needed

solution: other synchronization abstractions

want to run another thread instead of infinite loop solution: lock implementation integrated with scheduler

spinlocks can send a lot of messages on the shared bus more efficient atomic operations to implement locks

mutexes: intelligent waiting

want: locks that wait better example: POSIX mutexes

instead of running infinite loop, give away CPU

lock = go to sleep, add self to list sleep = scheduler runs something else

unlock = wake up sleeping thread

mutexes: intelligent waiting

want: locks that wait better example: POSIX mutexes

instead of running infinite loop, give away CPU

lock = go to sleep, add self to list
sleep = scheduler runs something else

unlock = wake up sleeping thread

better lock implementation idea

shared list of waiters

spinlock protects list of waiters from concurrent modification

 $lock = use \ spinlock \ to \ add \ self \ to \ list, \ then \ wait \ without \ spinlock$

unlock = use spinlock to remove item from list

better lock implementation idea

shared list of waiters

spinlock protects list of waiters from concurrent modification

lock = use spinlock to add self to list, then wait without spinlock unlock = use spinlock to remove item from list

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

spinlock protecting lock_taken and wait_queue
only held for very short amount of time (compared to mutex itself)

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

tracks whether any thread has locked and not unlocked

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

list of threads that discovered lock is taken and are waiting for it be free these threads are not runnable

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

```
LockMutex(Mutex *m) {
                                            UnlockMutex(Mutex *m) {
 LockSpinlock(&m->guard_spinlock);
                                               LockSpinlock(&m->guard_spinlock);
 if (m->lock_taken) {
                                               if (m->wait_queue not empty) {
   put current thread on m->wait_queue
                                                remove a thread from m->wait_queue
   mark current thread as waiting
                                                mark thread as no longer waiting
   /* xv6: myproc()->state = SLEEPING; */
                                                /* xv6: myproc()->state = RUNNABLE; *,
   UnlockSpinlock(&m->guard_spinlock);
                                              } else {
   run scheduler (context switch)
                                                 m->lock_taken = false;
 } else {
   m->lock taken = true:
                                              UnlockSpinlock(&m->guard_spinlock);
   UnlockSpinlock(&m->guard_spinlock);
```

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

instead of setting lock_taken to false choose thread to hand-off lock to

```
LockMutex(Mutex *m) {
                                            UnlockMutex(Mutex *m) {
 LockSpinlock(&m->guard_spinlock);
                                               LockSpinlock(&m->guard_spinlock);
 if (m->lock_taken) {
                                               if (m->wait_queue not empty) {
   put current thread on m->wait_queue
                                                remove a thread from m->wait_queue
   mark current thread as waiting
                                                mark thread as no longer waiting
   /* xv6: myproc()->state = SLEEPING; */
                                                /* xv6: myproc()->state = RUNNABLE; *,
   UnlockSpinlock(&m->guard_spinlock);
                                              } else {
   run scheduler (context switch)
                                                 m->lock_taken = false;
 } else {
   m->lock taken = true:
                                              UnlockSpinlock(&m->guard_spinlock);
   UnlockSpinlock(&m->guard_spinlock);
```

```
struct Mutex {
     SpinLock guard_spinlock;
     bool lock taken = false;
     WaitQueue wait queue;
};
subtly: if UnlockMutex runs here on another core
need to make sure scheduler on the other core doesn't switch to thread
while it is still running (would 'clone' thread/mess up registers)
                                            UnlockMutex(Mutex *m) {
LockMutex(Mutex ^m) {
  LockSpinlock(&m->guard_spinlock);
                                              LockSpinlock(&m->guard_spinlock);
  if (m->lock_taken) {
                                              if (m->wait_queue not empty) {
                                                remove a thread from m->wait_queue
    put current thread on m->wait_queue
    mark current thread as waiting
                                                mark thread as no longer waiting
   /* xv6: myproc()->state = SLEEPING; */
                                                /* xv6: myproc()->state = RUNNABLE; *,
    UnlockSpinlock(&m->guard_spinlock);
                                              } else {
    run scheduler (context switch)
                                                 m->lock_taken = false;
  } else {
    m->lock taken = true:
                                              UnlockSpinlock(&m->guard_spinlock);
    UnlockSpinlock(&m->guard_spinlock);
```

```
struct Mutex {
    SpinLock guard_spinlock;
    bool lock_taken = false;
    WaitQueue wait_queue;
};
```

```
LockMutex(Mutex *m) {
                                            UnlockMutex(Mutex *m) {
 LockSpinlock(&m->guard_spinlock);
                                              LockSpinlock(&m->guard_spinlock);
 if (m->lock_taken) {
                                              if (m->wait_queue not empty) {
                                                remove a thread from m->wait_queue
   put current thread on m->wait_queue
   mark current thread as waiting
                                                mark thread as no longer waiting
   /* xv6: myproc()->state = SLEEPING; */
                                                /* xv6: myproc()->state = RUNNABLE; *,
   UnlockSpinlock(&m->guard_spinlock);
                                              } else {
   run scheduler (context switch)
                                                 m->lock_taken = false;
 } else {
   m->lock_taken = true;
                                              UnlockSpinlock(&m->guard_spinlock);
   UnlockSpinlock(&m->guard_spinlock);
```

mutex and scheduler subtly

core 0 (thread A)	core 1 (thread B)	
start LockMutex		
acquire spinlock		
discover lock taken		
enqueue thread A		
thread A set not runnable		
release spinlock	start UnlockMutex	
·	thread A set runnable	
	finish UnlockMutex	
	run scheduler	
	scheduler switches to A	
	with old verison of registers	
thread A runs scheduler		l
finally saving registers		
10513613	1	

Linux soln.: track 'thread running' separately from 'thread runnable'

xy6 coln: hold schodular lock until throad A cayos registers

mutex and scheduler subtly

core 0 (thread A)	core 1 (thread B)	
start LockMutex		
acquire spinlock		
discover lock taken		
enqueue thread A		
thread A set not runnable		
release spinlock	start UnlockMutex	
·	thread A set runnable	
	finish UnlockMutex	
	run scheduler	
	scheduler switches to A	
	with old verison of registers	
thread A runs scheduler	300000	
finally saving registers		

Linux soln.: track 'thread running' separately from 'thread runnable'

xy6 coln: hold schodular lock until throad A cayos registers

mutex efficiency

'normal' mutex **uncontended** case:

lock: acquire + release spinlock, see lock is free

unlock: acquire + release spinlock, see queue is empty

not much slower than spinlock

implementing locks: single core

intuition: context switch only happens on interrupt timer expiration, I/O, etc. causes OS to run

solution: disable them reenable on unlock

implementing locks: single core

intuition: context switch only happens on interrupt timer expiration, I/O, etc. causes OS to run

solution: disable them reenable on unlock

x86 instructions:

cli — disable interrupts
sti — enable interrupts

```
Lock() {
    disable interrupts
}
```

```
Unlock() {
    enable interrupts
}
```

```
Lock() {
    disable interrupts
}

problem: user can hang the system:
    Lock(some_lock);
    while (true) {}
```

```
Lock() {
                             Unlock() {
    disable interrupts
                                  enable interrupts
problem: user can hang the system:
            Lock(some lock);
            while (true) {}
problem: can't do I/O within lock
            Lock(some lock);
             read from disk
                 /* waits forever for (disabled) interrupt
                    from disk IO finishing */
```

```
Lock() {
    disable interrupts
}
```

```
Unlock() {
    enable interrupts
}
```

```
Lock() {
    disable interrupts
}
```

```
Unlock() {
    enable interrupts
}
```

```
Lock() {
    disable interrupts
}
```

```
Unlock() {
    enable interrupts
}
```

```
Unlock() {
Lock() {
    disable interrupts
                                 enable interrupts
problem: nested locks
        Lock(milk lock);
        if (no milk) {
            Lock(store lock);
            buy milk
            Unlock(store lock);
            /* interrupts enabled here?? */
        Unlock(milk lock);
```

C++ containers and locking

can you use a vector from multiple threads?

...question: how is it implemented?

C++ containers and locking

can you use a vector from multiple threads?

...question: how is it implemented? dynamically allocated array reallocated on size changes

C++ containers and locking

can you use a vector from multiple threads?

```
...question: how is it implemented?
dynamically allocated array
reallocated on size changes
```

can access from multiple threads ...as long as not append/erase/etc.?

assuming it's implemented like we expect...

but can we really depend on that? e.g. could shrink internal array after a while with no expansion save memory?

C++ standard rules for containers

multiple threads can read anything at the same time can only read element if no other thread is modifying it

can safely add/remove elements if no other threads are accessing container

(sometimes can safely add/remove in extra cases)

exception: vectors of bools — can't safely read and write at same time

might be implemented by putting multiple bools in one int

a simple race

a simple race

if loads/stores atomic, then possible results:

A:1 B:1 — both moves into x and y, then both moves into eax execute

A:0 B:1 — thread A executes before thread B

A:1 B:0 — thread B executes before thread A

a simple race: results

my desktop, 100M trials:

	,	• •	
frequency	result		
99 823 739	A:0 B:1	('A executes before B')	
171161	A:1 B:0	('B executes before A')	
		('execute moves into x+y first')	
394	A:0 B:0	???	
	99 823 739 171 161 4 706	171 161 A:1 B:0	

a simple race: results

my desktop, 100M trials:

frequency	result	
99823739	A:0 B:1	('A executes before B')
171161	A:1 B:0	('B executes before A')
4706	A:1 B:1	('execute moves into x+y first')
394	A:0 B:0	???

why reorder here?

thread A: faster to load y right now!

...rather than wait for write of x to finish

why load/store reordering?

fast processor designs can execute instructions out of order

goal: do something instead of waiting for slow memory accesses, etc.

more on this later in the semester

GCC: preventing reordering example (1)

```
void Alice() {
    int one = 1;
    __atomic_store(&note_from_alice, &one, __ATOMIC_SEQ_CST);
    do {
    } while (__atomic_load_n(&note_from_bob, __ATOMIC_SEQ_CST));
    if (no milk) {++milk:}
Alice:
  movl $1, note from alice
  mfence
.L2:
  movl note from bob, %eax
  testl %eax, %eax
  ine .L2
```

GCC: preventing reordering example (2)

```
void Alice() {
    note from alice = 1;
    do {
        __atomic_thread_fence(__ATOMIC_SEQ_CST);
    } while (note from bob);
    if (no milk) {++milk;}
Alice:
  movl $1, note_from_alice // note_from_alice <- 1</pre>
.L3:
 mfence // make sure store is visible to other cores before
          // on x86: not needed on second+ iteration of loop
  cmpl $0, note from bob // if (note from bob == 0) repeat for
  ine .L3
  cmpl $0, no_milk
```

exercise: fetch-and-add with compare-and-swap

exercise: implement fetch-and-add with compare-and-swap

```
compare_and_swap(address, old_value, new_value) {
    if (memory[address] == old_value) {
        memory[address] = new_value;
        return true; // x86: set ZF flag
    } else {
        return false; // x86: clear ZF flag
    }
}
```

solution

```
void
acquire(struct spinlock *lk)
  pushcli(); // disable interrupts to avoid deadlock.
  // The xchg is atomic.
 while(xchg(&lk->locked, 1) != 0)
 // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that the critical section's memory
  // references happen after the lock is acquired.
  sync synchronize();
  . . .
```

```
void
acquire(struct spinlock *lk)
  pushcli(); // disable interrupts to avoid deadlock.
  // The xchq is atomic.
  while(xchg(&lk->locked, 1) != 0)
  // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that the critical section's memory
    don't let us be interrupted after while have the lock
    problem: interruption might try to do something with the lock
    ...but that can never succeed until we release the lock
    ...but we won't release the lock until interruption finishes
```

```
void
acquire(struct spinlock *lk)
  pushcli(); // disable interrupts to avoid deadlock.
  // The xchq is atomic.
 while(xchg(&lk->locked, 1) != 0)
 // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that the critical section's memory
  // references happen after the lock is acquired.
  sync synchronize();
  . . .
```

xchg wraps the lock xchg instruction same loop as before

```
void
acquire(struct spinlock *lk)
  pushcli(); // disable interrupts to avoid deadlock.
  // The xchq is atomic.
  while(xchg(&lk->locked, 1) != 0)
  // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that the critical section's memory
  // references happen after the lock is acquired.
    svnc svnchronize():
  ··· avoid load store reordering (including by compiler)
     on x86, xchg alone is enough to avoid processor's reordering
     (but compiler may need more hints)
```

```
void
release(struct spinlock *lk)
  // Tell the C compiler and the processor to not move loads or sto
 // past this point, to ensure that all the stores in the critical
 // section are visible to other cores before the lock is released
 // Both the C compiler and the hardware may re-order loads and
 // stores; __sync_synchronize() tells them both not to.
  sync synchronize();
 // Release the lock, equivalent to lk->locked = 0.
  // This code can't use a C assignment, since it might
  // not be atomic. A real OS would use C atomics here.
  asm volatile("movl $0, %0" : "+m" (lk->locked) : );
 popcli();
```

```
void
release(struct spinlock *lk)
  // Tell the C compiler and the processor to not move loads or sto
  // past this point, to ensure that all the stores in the critical
  // section are visible to other cores before the lock is released
  // Both the C compiler and the hardware may re-order loads and
  // stores; __sync_synchronize() tells them both not to.
 sync synchronize();
  // Release the lock, equivalent to lk->locked = 0.
  // This code can't use a C assignment, since it might
  // not be atomic. A real OS would use C atomics here.
  asm volatile("movl $0, %0" : "+m" (lk->locked) : );
  popcli turns into instruction to tell processor not to reorder
         plus tells compiler not to reorder
```

```
void
release(struct spinlock *lk)
  // Tell the C compiler and the processor to not move loads or sto
 // past this point, to ensure that all the stores in the critical
 // section are visible to other cores before the lock is released
 // Both the C compiler and the hardware may re-order loads and
 // stores; sync synchronize() tells them both not to.
  sync synchronize();
 // Release the lock, equivalent to lk->locked = 0.
 // This code can't use a C assignment, since it might
  // not be atomic. A real OS would use C atomics here.
  asm volatile("movl $0, %0" : "+m" (lk->locked) : );
 popcli();
          turns into mov of constant 0 into lk->locked
```

```
void
release(struct spinlock *lk)
  // Tell the C compiler and the processor to not move loads or sto
 // past this point, to ensure that all the stores in the critical
  // section are visible to other cores before the lock is released
 // Both the C compiler and the hardware may re-order loads and
 // stores; sync synchronize() tells them both not to.
  sync synchronize();
  // Release the lock, equivalent to lk->locked = 0.
  // This code can't use a C assignment, since it might
  // not be atomic. A real OS would use C atomics here.
  asm volatile("movl $0, %0" : "+m" (lk->locked) : );
 popcli().
        reenable interrupts (taking nested locks into account)
```

fetch-and-add with CAS (1)

```
compare-and-swap(address, old_value, new_value) {
    if (memory[address] == old_value) {
        memory[address] = new_value;
        return true;
    } else {
        return false;
long my_fetch_and_add(long *pointer, long amount) { ... }
implementation sketch:
    fetch value from pointer old
    compute in temporary value result of addition new
    try to change value at pointer from old to new
    [compare-and-swap]
    if not successful, repeat
```

fetch-and-add with CAS (2)

```
long my_fetch_and_add(long *p, long amount) {
    long old_value;
    do {
        old_value = *p;
    } while (!compare_and_swap(p, old_value, old_value + amount);
    return old_value;
}
```

exercise: append to singly-linked list

ListNode is a singly-linked list assume: threads *only* append to list (no deletions, reordering) use compare-and-swap(pointer, old, new): atomically change *pointer from old to new return true if successful return false (and change nothing) if *pointer is not old void append to list(ListNode *head, ListNode *new last node) {

some common atomic operations (1)

```
// x86: emulate with exchange
test and set(address) {
    old_value = memory[address];
    memory[address] = 1;
    return old value != 0; // e.g. set ZF flag
// x86: xchq REGISTER, (ADDRESS)
exchange(register, address) {
    temp = memory[address];
    memory[address] = register;
    register = temp;
```

some common atomic operations (2)

```
// x86: mov OLD_VALUE, %eax; lock cmpxchq NEW_VALUE, (ADDRESS)
compare-and-swap(address, old_value, new_value) {
    if (memory[address] == old_value) {
        memory[address] = new_value;
        return true; // x86: set ZF flag
    } else {
        return false; // x86: clear ZF flag
// x86: lock xaddl REGISTER, (ADDRESS)
fetch-and-add(address, register) {
    old value = memory[address];
    memory[address] += register;
    register = old value;
```

common atomic operation pattern

```
try to do operation, ...

detect if it failed

if so, repeat
```

atomic operation does "try and see if it failed" part

cache coherency states

extra information for each cache block overlaps with/replaces valid, dirty bits

stored in each cache

update states based on reads, writes and heard messages on bus

different caches may have different states for same block

MSI state summary

Modified value may be different than memory and I am the only one who has it

Shared value is the same as memory

Invalid I don't have the value; I will need to ask for it

MSI scheme

from state	hear read	hear write	read	write			
Invalid			to Shared	to Modified			
Shared		to Invalid		to Modified			
Modified	to Shared	to Invalid					
blue: transition requires sending message on bus							

MSI scheme

```
from state hear read hear write read write

Invalid — to Shared to Modified
Shared — to Invalid — to Modified
Modified to Shared to Invalid — —
blue: transition requires sending message on bus
```

example: write while Shared must send write — inform others with Shared state then change to Modified

MSI scheme

```
from state hear read hear write read write

Invalid — to Shared to Modified

Shared — to Invalid — to Modified

Modified to Shared to Invalid — —

blue: transition requires sending message on bus
```

example: write while Shared

must send write — inform others with Shared state then change to Modified


example: hear write while Shared

change to Invalid


can send read later to get value from writer

example: write while Modified nothing to do — no other CPU can have a copy


MSI example



MSI example




MSI example




CPU1 writes 102 to 0xA300

MSI example




CPU2 reads 0xA300

MSI example



MSI example



MSI: update memory

to write value (enter modified state), need to invalidate others can avoid sending actual value (shorter message/faster)

"I am writing address X" versus "I am writing Y to address X"

MSI: on cache replacement/writeback

still happens — e.g. want to store something else

changes state to invalid

requires writeback if modified (= dirty bit)

cache coherency exercise

```
modified/shared/invalid; all initially invalid; 32B blocks, 8B
read/writes
     CPU 1: read 0x1000
     CPU 2: read 0x1000
     CPU 1: write 0x1000
     CPU 1: read 0x2000
```

CPU 2: read 0x1000 CPU 2: write 0x2008

CPU 1:

CPU 3: read 0x1008

Q1: final state of 0x1000 in caches? Modified/Shared/Invalid for CPU 1/2/3 CPU 1: CPU 2: CPU 3:

Q2: final state of 0x2000 in caches?

Modified/Shared/Invalid for CPU 1/2/3 CPU 2:

172

why load/store reordering?

fast processor designs can execute instructions out of order

goal: do something instead of waiting for slow memory accesses, etc.

more on this later in the semester

C++: preventing reordering

to help implementing things like pthread_mutex_lock

C++ 2011 standard: atomic header, std::atomic class prevent CPU reordering and prevent compiler reordering also provide other tools for implementing locks (more later)

could also hand-write assembly code compiler can't know what assembly code is doing

C++: preventing reordering example

```
#include <atomic>
void Alice() {
    note_from_alice = 1;
    do {
        std::atomic thread fence(std::memory order seg cst);
    } while (note from bob);
    if (no milk) {++milk;}
Alice:
  movl $1, note_from_alice // note_from_alice <- 1</pre>
.L2:
  mfence // make sure store visible on/from other cores
  cmpl $0, note from bob // if (note from bob == 0) repeat fence
  jne .L2
  cmpl $0, no milk
```

C++ atomics: no reordering

```
std::atomic<int> note_from_alice, note_from_bob;
void Alice() {
    note_from_alice.store(1);
    do {
    } while (note from bob.load());
    if (no milk) {++milk;}
Alice:
  movl $1, note_from alice
  mfence
.L2:
  movl note from bob, %eax
  testl %eax, %eax
  ine .L2
```

GCC: built-in atomic functions

used to implement std::atomic, etc.

predate std::atomic

builtin functions starting with __sync and __atomic

these are what xv6 uses

aside: some x86 reordering rules

```
each core sees its own loads/stores in order (if a core stores something, it can always load it back)
```

stores from other cores appear in a consistent order (but a core might observe its own stores too early)

causality:

```
if a core reads X=a and (after reading X=a) writes Y=b, then a core that reads Y=b cannot later read X=older value than a
```

how do you do anything with this?

difficult to reason about what modern CPU's reordering rules do typically: don't depend on details, instead:

special instructions with stronger (and simpler) ordering rules often same instructions that help with implementing locks in other ways

special instructions that restrict ordering of instructions around them ("fences")


loads/stores can't cross the fence


spinlock problems

lock abstraction is not powerful enough lock/unlock operations don't handle "wait for event" common thing we want to do with threads solution: other synchronization abstractions


spinlocks waste CPU time more than needed want to run another thread instead of infinite loop solution: lock implementation integrated with scheduler

spinlocks can send a lot of messages on the shared bus more efficient atomic operations to implement locks







CPU2 read-modify-writes lock (to see it is still locked)



CPU3 read-modify-writes lock (to see it is still locked)



CPU2 read-modify-writes lock (to see it is still locked)



CPU3 read-modify-writes lock (to see it is still locked)

"I want to modify lock" CPU1 CPU₂ CPU3 MEM1 address value state address value state address value state lock unlocked Modified lock Invalid lock Invalid

CPU1 sets lock to unlocked

"I want to modify lock" CPU1 CPU₂ CPU3 MEM1 address value state address value state address value state lock Invalid lock locked Modified lock Invalid

some CPU (this example: CPU2) acquires lock

test-and-set problem: cache block "ping-pongs" between caches each waiting processor reserves block to modify could maybe wait until it determines modification needed — but not typical implementation

each transfer of block sends messages on bus


...so bus can't be used for real work like what the processor with the lock is doing


test-and-test-and-set (pseudo-C)

```
acquire(int *the_lock) {
    do {
        while (ATOMIC-READ(the_lock) == 0) { /* try again */ }
    } while (ATOMIC-TEST-AND-SET(the_lock) == ALREADY_SET);
}
```


test-and-test-and-set (assembly)

```
acquire:
   cmp $0, the_lock  // test the lock non-atomically
          // unlike lock xchg --- keeps lock in Shared state!
   ine acquire
               // try again (still locked)
   // lock possibly free
   // but another processor might lock
   // before we get a chance to
   // ... so try wtih atomic swap:
   movl $1, %eax <- 1
   lock xchg %eax, the lock // swap %eax and the lock
         // sets the lock to 1
         // sets %eax to prior value of the lock
   test %eax, %eax // if the lock wasn't 0 (someone else
                     // try again
   jne acquire
   ret
```







CPU2 reads lock (to see it is still locked)



CPU1 writes back lock value, then CPU2 reads it



CPU3 reads lock (to see it is still locked)




CPU2, CPU3 continue to read lock from cache no messages on the bus

"I want to modify lock" CPU2 CPU3 CPU1 MEN address value state address value state address value state lock unlocked Modified lock Invalid lock Invalid

CPU1 sets lock to unlocked

"I want to modify lock"



some CPU (this example: CPU2) acquires lock (CPU1 writes back value, then CPU2 reads + modifies it)

couldn't the read-modify-write instruction...

notice that the value of the lock isn't changing...

and keep it in the shared state

maybe — but extra step in "common" case (swapping different values)

more room for improvement?

can still have a lot of attempts to modify locks after unlocked

there other spinlock designs that avoid this

ticket locks

MCS locks

...

MSI extensions

real cache coherency protocols sometimes more complex:

separate tracking modifications from whether other caches have copy

send values directly between caches (maybe skip write to memory) send messages only to cores which might care (no shared bus)

too much milk

roommates Alice and Bob want to keep fridge stocked with milk:

time	Alice	Bob
3:00	look in fridge. no milk	
3:05	leave for store	
3:10	arrive at store	look in fridge. no milk
3:15	buy milk	leave for store
3:20	return home, put milk in fridge	arrive at store
3:25		buy milk
3:30		return home, put milk in fridge

how can Alice and Bob coordinate better?

too much milk "solution" 1 (algorithm)

```
leave a note: "I am buying milk"
     place before buying, remove after buying
    don't try buying if there's a note
\approx setting/checking a variable (e.g. "note = 1")
    with atomic load/store of variable
if (no milk) {
     if (no note) {
          leave note;
          buy milk;
          remove note;
```

```
leave a note: "I am buying milk"
     place before buying, remove after buying
    don't try buying if there's a note
\approx setting/checking a variable (e.g. "note = 1")
    with atomic load/store of variable
if (no milk) {
     if (no note) {
          leave note;
          buy milk;
          remove note;
exercise: why doesn't this work?
```

too much milk "solution" 1 (timeline)

```
Alice
                                    Bob
if (no milk) {
    if (no note) {
                            if (no milk) {
                                if (no note) {
        leave note;
        buy milk;
        remove note;
                                    leave note;
                                    buy milk;
                                    remove note;
```

intuition: leave note when buying or checking if need to buy

```
leave note;
if (no milk) {
    if (no note) {
       buy milk;
    }
}
remove note;
```

too much milk: "solution" 2 (timeline)

```
Alice
leave note;
if (no milk) {
    if (no note) {
        buy milk;
    }
}
remove note;
```

too much milk: "solution" 2 (timeline)

```
Alice
leave note;
if (no milk) {
   if (no note) { ← but there's always a note buy milk;
   }
}
remove note;
```

too much milk: "solution" 2 (timeline)

"solution" 3: algorithm

```
intuition: label notes so Alice knows which is hers (and vice-versa)
    computer equivalent: separate noteFromAlice and noteFromBob
    variables
            Alice
                                                      Bob
                                       leave note from Bob;
leave note from Alice;
                                       if (no milk) {
if (no milk) {
    if (no note from Bob) {
                                            if (no note from Alice
         buy milk
                                                buy milk
remove note from Alice;
                                       remove note from Bob;
```

too much milk: "solution" 3 (timeline)

```
Alice
                                      Bob
leave note from Alice
if (no milk) {
                              leave note from Bob
    if (no note from Bob) {
                              if (no milk) {
                                  if (no note from Alice) {
                              remove note from Bob
```

remove note from Alice

too much milk: is it possible

is there a solutions with writing/reading notes? \approx loading/storing from shared memory

yes, but it's not very elegant

```
Alice
leave note from Alice
while (note from Bob) {
    do nothing
}
if (no milk) {
    buy milk
}
remove note from Alice
```

```
Bob
leave note from Bob
if (no note from Alice) {
    if (no milk) {
        buy milk
     }
}
remove note from Bob
```

```
Alice
                                             Bob
leave note from Alice
                                 leave note from Bob
while (note from Bob) {
                                 if (no note from Alice) {
    do nothing
                                     if (no milk) {
                                          buy milk
   (no milk) {
    buy milk
                                 remove note from Bob
remove note from Alice
exercise (hard): prove (in)correctness
```

```
Alice
                                             Bob
leave note from Alice
                                 leave note from Bob
while (note from Bob) {
                                 if (no note from Alice) {
    do nothing
                                     if (no milk) {
                                          buy milk
   (no milk) {
    buy milk
                                 remove note from Bob
remove note from Alice
exercise (hard): prove (in)correctness
```

```
Alice
                                             Bob
leave note from Alice
                                  leave note from Bob
while (note from Bob) {
                                  if (no note from Alice) {
    do nothing
                                      if (no milk) {
                                          buy milk
   (no milk) {
    buy milk
                                  remove note from Bob
remove note from Alice
exercise (hard): prove (in)correctness
exercise (hard): extend to three people
```

Peterson's algorithm

general version of solution

see, e.g., Wikipedia

we'll use special hardware support instead

mfence

x86 instruction mfence

make sure all loads/stores in progress finish

...and make sure no loads/stores were started early

fairly expensive

Intel 'Skylake': order 33 cycles + time waiting for pending stores/loads

mfence

x86 instruction mfence

make sure all loads/stores in progress finish

...and make sure no loads/stores were started early

fairly expensive

Intel 'Skylake': order 33 cycles + time waiting for pending stores/loads

aside: this instruction is did not exist in the original x86 so xv6 uses something older that's equivalent

modifying cache blocks in parallel

typical memory access — less than cache block e.g. one 4-byte array element in 64-byte cache block

what if two processors modify different parts same cache block?

4-byte writes to 64-byte cache block

typically how caches work — write instructions happen one at a time:


processor 'locks' 64-byte cache block, fetching latest version processor updates 4 bytes of 64-byte cache block later, processor might give up cache block

modifying things in parallel (code)

```
void *sum_up(void *raw_dest) {
    int *dest = (int *) raw_dest;
    for (int i = 0; i < 64 * 1024 * 1024; ++i) {
        *dest += data[i];
attribute ((aligned(4096)))
int array[1024]; /* aligned = address is mult. of 4096 */
void sum twice(int distance) {
    pthread t threads[2];
    pthread_create(&threads[0], NULL, sum_up, &array[0]);
    pthread_create(&threads[1], NULL, sum_up, &array[distance]);
    pthread_join(threads[0], NULL);
    pthread join(threads[1], NULL);
```

performance v. array element gap

(assuming sum_up compiled to not omit memory accesses)



false sharing

synchronizing to access two independent things

two parts of same cache block

solution: separate them

exercise (1)

```
int values[1024];
int results[2];
void *sum_front(void *ignored_argument) {
    results[0] = 0;
    for (int i = 0; i < 512; ++i)
        results[0] += values[i];
    return NULL;
}
void *sum_back(void *ignored_argument) {
    results[1] = 0;
    for (int i = 512; i < 1024; ++i)
        results[1] += values[i];
    return NULL;
int sum_all() {
    pthread_t sum_front_thread, sum_back_thread;
    pthread create(&sum front thread, NULL, sum front, NULL);
    pthread_create(&sum_back_thread, NULL, sum_back, NULL);
    pthread_join(sum_front_thread, NULL);
    pthread_join(sum_back_thread, NULL);
    return results[0] + results[1];
}
```

Where is false sharing likely to occur? How to fix?

exercise (2)

```
struct ThreadInfo { int *values; int start; int end; int result };
void *sum_thread(void *argument) {
    ThreadInfo *my info = (ThreadInfo *) argument;
    int sum = 0;
    for (int i = my_info->start; i < my_info->end; ++i) {
        my_info->result += my_info->values[i];
    return NULL;
int sum all(int *values) {
    ThreadInfo info[2]; pthread_t thread[2];
    for (int i = 0; i < 2; ++i) {
        info[i].values = values; info[i].start = i*512; info[i].end = (i+1)*512;
        pthread_create(&threads[i], NULL, sum_thread, (void *) &info[i]);
    for (int i = 0; i < 2; ++i)
        pthread_join(threads[i], NULL);
    return info[0].result + info[1].result;
}
```


Where is false sharing likely to occur?

connecting CPUs and memory

multiple processors, common memory

how do processors communicate with memory?

shared bus



one possible design

we'll revisit later when we talk about I/O

tagged messages — everyone gets everything, filters

contention if multiple communicators some hardware enforces only one at a time

shared buses and scaling

shared buses perform poorly with "too many" CPUs

so, there are other designs

we'll gloss over these for now

shared buses and caches


remember caches?

memory is pretty slow


each CPU wants to keep local copies of memory

what happens when multiple CPUs cache same memory?

the cache coherency problem



the cache coherency problem



CPU1 writes 101 to 0xA300?

producer/consumer signal?

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;
Produce(item) {
    pthread_mutex_lock(&lock);
    buffer.engueue(item);
    /* GOOD CODE: pthread_cond_signal(&data_ready); */
    /* BAD CODE: */
    if (buffer.size() == 1)
        pthread_cond_signal(&item);
    pthread_mutex_unlock(&lock);
Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    item = buffer.dequeue();
    pthread_mutex_unlock(&lock);
    return item;
```

bad case (setup)

thread 0	1	2	3
Consume():			
lock			
empty? wait on cv	Consume():		•
	lock		
	empty? wait on cv		
		Produce(): lock	
		lock	Produce():

bad case

thread 0	1	2	3
Consume(): lock			
empty? wait on cv	Consume(): lock empty? wait on cv		
		Produce():	
		lock	Produce(): wait for lock
wait for lock		$enqueue \ size = 1? \ signal$	
		unlock	gets lock
			enqueue size ≠ 1: don't signal unlock
gets lock dequeue			
	still waiting		

monitor exercise: ConsumeTwo

suppose we want producer/consumer, but...

but change Consume() to ConsumeTwo() which returns a pair of values

and don't want two calls to ConsumeTwo() to wait... with each getting one item

what should we change below?

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;

Produce(item) {
    pthread_mutex_lock(&lock);
    buffer.enqueue(item);
    pthread_cond_signal(&data_ready);
    pthread_mutex_unlock(&lock);
}

Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    }

item = buffer.dequeue();
    pthread_mutex_unlock(&lock);
    return item;
}

return item;
}
```

monitor exercise: ordering

suppose we want producer/consumer, but...

but want to ensure first call to Consume() always returns first

(no matter what ordering cond_signal/cond_broadcast use)

```
pthread_mutex_t lock;
pthread_cond_t data_ready;
UnboundedQueue buffer;

Produce(item) {
    pthread_mutex_lock(&lock);
    buffer.enqueue(item);
    pthread_cond_signal(&data_ready);
    pthread_mutex_unlock(&lock);
}

Consume() {
    pthread_mutex_lock(&lock);
    while (buffer.empty()) {
        pthread_cond_wait(&data_ready, &lock);
    }
    item = buffer.dequeue();
    pthread_mutex_unlock(&lock);
    return item;
}
```

Anderson-Dahlin and semaphores

Anderson/Dahlin complains about semaphores

"Our view is that programming with locks and condition variables is superior to programming with semaphores."

argument 1: clearer to have separate constructs for waiting for condition to be come true, and allowing only one thread to manipulate a thing at a time

arugment 2: tricky to verify thread calls up exactly once for every down

alternatives allow one to be sloppier (in a sense)

monitors with semaphores: locks

```
sem_t semaphore; // initial value 1

Lock() {
    sem_wait(&semaphore);
}

Unlock() {
    sem_post(&semaphore);
}
```

monitors with semaphores: [broken] cvs

start with only wait/signal:

```
sem_t threads_to_wakeup; // initially 0
Wait(Lock lock) {
    lock.Unlock();
    sem_wait(&threads_to_wakeup);
    lock.Lock();
}
Signal() {
    sem_post(&threads_to_wakeup);
}
```

monitors with semaphores: [broken] cvs

start with only wait/signal:

```
sem_t threads_to_wakeup; // initially 0
Wait(Lock lock) {
    lock.Unlock();
    sem_wait(&threads_to_wakeup);
    lock.Lock();
}
Signal() {
    sem_post(&threads_to_wakeup);
}
problem: signal wakes up non-waiting threads (in the far future)
```

monitors with semaphores: cvs (better)

start with only wait/signal:

```
sem t private lock; // initially 1
int num_waiters;
sem_t threads_to_wakeup; // initially 0
Wait(Lock lock) {
                                           Signal() {
  sem_wait(&private_lock);
                                             sem_wait(&private_lock);
                                             if (num waiters > 0) {
  ++num waiters;
  sem_post(&private_lock);
                                               sem_post(&threads_to_wakeup);
  lock.Unlock();
                                               --num_waiters;
  sem_wait(&threads_to_wakeup);
  lock.Lock();
                                             sem_post(&private_lock);
```

monitors with semaphores: broadcast

now allows broadcast:

```
sem_t private_lock; // initially 1
int num waiters;
sem_t threads_to_wakeup; // initially 0
Wait(Lock lock) {
                                          Broadcast() {
  sem_wait(&private_lock);
                                             sem_wait(&private_lock);
  ++num waiters;
                                             while (num_waiters > 0) {
  sem_post(&private_lock);
                                               sem_post(&threads_to_wakeup);
  lock.Unlock();
                                               --num waiters;
  sem_wait(&threads_to_wakeup);
  lock.Lock();
                                             sem_post(&private_lock);
```

pthread_mutex_t lock;

lock to protect shared state

```
pthread_mutex_t lock;
unsigned int count;
```

lock to protect shared state

shared state: semaphore tracks a count

```
pthread_mutex_t lock;
unsigned int count;
/* condition, broadcast when becomes count > 0 */
pthread_cond_t count_is_positive_cv;
```

lock to protect shared state shared state: semaphore tracks a count

add cond var for each reason we wait semaphore: wait for count to become positive (for down)

```
pthread_mutex_t lock;
unsigned int count;
/* condition, broadcast when becomes count > 0 */
pthread_cond_t count_is_positive_cv;
void down() {
    pthread_mutex_lock(&lock);
   while (!(count > 0)) {
        pthread_cond_wait(
            &count_is_positive_cv,
            &lock);
    count -= 1;
    pthread mutex unlock(&lock);
```

lock to protect shared state shared state: semaphore tracks a count

add cond var for each reason we wait semaphore: wait for count to become positive (for down)

wait using condvar; broadcast/signal when condition changes

```
pthread_mutex_t lock;
unsigned int count;
/* condition, broadcast when becomes count > 0 */
pthread_cond_t count_is_positive_cv;
void down() {
                                        void up() {
    pthread_mutex_lock(&lock);
                                            pthread_mutex_lock(&lock);
   while (!(count > 0)) {
                                            count += 1;
        pthread_cond_wait(
                                            /* count must now be
            &count_is_positive_cv,
                                               positive, and at most
            &lock);
                                               one thread can go per
                                               call to Up() */
                                            pthread_cond_signal(
    count -= 1:
    pthread_mutex_unlock(&lock);
                                                &count is positive cv
                                            pthread_mutex_unlock(&lock);
lock to protect shared state
```

add cond var for each reason we wait semaphore: wait for count to become positive (for down)

shared state: semaphore tracks a count

wait using condvar; broadcast/signal when condition changes

binary semaphores

binary semaphores — semaphores that are only zero or one

as powerful as normal semaphores

exercise: simulate counting semaphores with binary semaphores (more than one) and an integer

counting semaphores with binary semaphores

via Hemmendinger, "Comments on 'A correct and unrestrictive implementation of general semaphores' " (1989); Barz, "Implementing semaphores by binary semaphores" (1983) // assuming initialValue > 0 BinarySemaphore mutex(1); int value = initialValue ; BinarvSemaphore gate(1 /* if initialValue >= 1 */); /* gate = # threads that can Down() now */ void Down() { void Up() { gate.Down(); mutex.Down(); // wait, if needed value += 1; mutex.Down(); **if** (value == 1) { value -= 1; gate.Up(); **if** (value > 0) { // because down should finish now gate.Up(); // but could not before // because next down should finish // now (but not marked to before) mutex.Up(); mutex.Up();

gate intuition/pattern

```
pattern to allow one thread at a time:
sem_t gate; // 0 = closed; 1 = open
ReleasingThread() {
    ... // finish what the other thread is waiting for
   while (another thread is waiting and can go) {
        sem_post(&gate) // allow EXACTLY ONE thread
        ... // other bookkeeping
WaitingThread() {
    ... // indicate that we're waiting
    sem_wait(&gate) // wait for gate to be open
    ... // indicate that we're not waiting
```