

Invitation Card Editor — UI/UX Design Spec

Target user: 50+, low technical confidence
Feel: Premium, luxurious, modern, Canva/Adobe Express-simple
Platform: Offline Android, Flutter

1. Visual Design System

Color Theme — "Warm Ivory & Gold"

A theme that reads as premium stationery, not a tech app.

Role	Color	Hex
Background	Warm ivory/cream	#FBF7F0
Primary accent	Deep champagne gold	#C6A15B
Secondary accent	Soft charcoal	#2E2A26

Role	Color	Hex
Text (primary)	Near-black warm gray	#3A3532
Text (secondary/hints)	Muted taupe	#8C8275
Success/confirm	Muted sage green	#7A9471
Danger/delete	Soft terracotta red	#B5654F
Card surfaces	Pure white	#FFFFFF

No pure black, no neon colors — everything slightly warmed, like fine paper and foil.

Typography

- **Headings/branding:** An elegant serif (e.g., Playfair Display) — signals "invitation," not "app."
- **UI labels/buttons:** A clean, highly legible sans-serif (e.g., Inter or Nunito Sans) at a **minimum 16sp**, scalable to 20sp — this is non-negotiable for the 50+ audience.
- Generous line spacing and letter spacing throughout; nothing condensed.

Iconography

- Line icons (not filled), 2px stroke, rounded caps — soft and elegant rather than sharp/technical.
- **Every icon is paired with a text label.** No icon-only buttons anywhere in the app. This is the single most important accessibility decision for this audience.

Buttons

- Large touch targets: minimum 56dp height.
- Primary buttons: solid gold fill, charcoal text, subtle rounded corners (12dp radius), soft drop shadow to feel "pressable."
- Secondary buttons: outlined, gold border, transparent fill.
- Destructive actions (delete): terracotta outline, always require confirmation dialog.

Animation Philosophy

- Subtle and slow (250–350ms), never flashy or bouncy — this should feel calm, not gamified.
- Screen transitions: gentle horizontal slide or soft cross-fade.
- Button press: slight scale-down (0.97x) + shadow lift, like pressing a real card.

- Success actions (save, export): a soft gold checkmark animation with a gentle "settle" motion, plus a brief haptic tap.
 - No spinning loaders where avoidable — use a calm pulsing gold dot instead.
-

2. Screen-by-Screen Design

Screen 1 — Home / My Invitations (Library)

The app opens directly here. This is "home base."

- **Top bar:** App name in serif logo-type, centered. Small settings gear icon (top-right, labeled "Settings" beneath it).
- **Body:** A grid of card thumbnails — each past invitation the user has created or imported, shown as a real preview thumbnail with a soft shadow (like photos on a table).
 - Each thumbnail has: title text below it (editable), last-edited date in small muted text.
 - Tap thumbnail → opens Editor with that invitation.
 - Long-press or a small "⋮" labeled "Options" → menu: Rename, Duplicate, Delete, Export, Print.

- **Empty state** (first launch): centered illustration of an elegant blank card, with text "Create your first invitation" and one large gold button.
- **Bottom area:** One large, unmissable primary button, pinned: **" + New Invitation"** (gold, full-width, 56dp tall).

Screen 2 — New Invitation (Source Selection)

Opens as a bottom sheet or full screen when "+ New Invitation" is tapped.

Three large, clearly labeled option cards (not small icons):

1. **"Upload a File"** — upload icon + text — accepts PDF, JPG, PNG.
2. **"Start from a Template"** — template icon + text — opens Template Library (Screen 3).
3. **"Blank Card"** — blank page icon + text — opens Editor with an empty canvas.

Each option card is large (full-width, ~100dp tall), tappable anywhere on the card, with a one-line description underneath (e.g., "Choose a PDF or photo of your invitation").

Screen 3 — Template Library

- Grid of pre-designed invitation templates (birthday, wedding, anniversary, baby shower, holiday, blank).
- Category filter as large horizontal pill tabs at top (labeled, not icon-only): "All," "Wedding," "Birthday," "Holiday," "My Saved Templates."
- Tapping a template → opens directly in Editor, pre-loaded.
- "My Saved Templates" tab shows templates the user has saved from their own past designs.

Screen 4 — The Editor (core screen)

This is the most important screen and needs the most restraint.

Layout:

- **Top bar:** Back arrow (labeled "Back"), invitation title (tap to rename), and a single labeled **"Save"** button (top-right, always visible).
- **Canvas (center, most of screen):** The invitation image/PDF page shown at a comfortable zoom, with pinch-to-zoom and drag-to-pan enabled.
- **Bottom toolbar:** A single row of large, labeled icons — no more than 4-5 at once, to avoid overwhelm:
 - **"Add Text"**
 - **"Voice Type"** (microphone icon)

- **"Templates"** (jump to template library)
- **"Print / Export"**
- **"Menu"** (overflow: undo/redo, page settings, help)

Adding text (tap "Add Text" or tap empty canvas area):

- A text box appears on the canvas with a soft gold outline and 4 corner handles (drag to resize) plus a rotate handle.
- Tapping into the text box opens a **floating formatting panel** that slides up from the bottom (not a cramped toolbar):
 - **Font** — large scrollable list of font names, each rendered in its own actual font so the user can see, not guess.
 - **Size** — a simple large +/- stepper with a live preview, not a tiny slider.
 - **Color** — a row of large circular color swatches (curated palette, ~12 elegant colors) plus one "More Colors" option.
 - **Alignment** — left/center/right, shown as labeled buttons.
 - **Bold/Italic** — clearly labeled toggle buttons.
- A **microphone button sits directly inside the text box itself**, so voice typing is discoverable

exactly where text is created, not buried in a menu.

Voice typing flow:

- Tap the mic icon → it turns solid gold and gently pulses while listening.
- A caption strip appears above the keyboard area showing live transcribed text.
- Tap mic again (or a labeled "Done" button) to stop — text is inserted into the box.
- If no speech is detected, a warm, non-technical message: "I didn't catch that — try again?" with a retry button.

Moving/deleting elements:

- Tap any text box once to select it (gold outline + handles appear).
- A small labeled toolbar appears just above the selected box: **"Delete," "Duplicate," "Bring to Front."**
- Delete always shows a one-tap-undo snackbar at the bottom ("Text deleted. Undo") rather than a scary confirmation dialog — safer for accidental taps, less scary for cautious users.

Screen 5 — Save as Template Dialog

Triggered from the editor's overflow menu ("Save as Template").

- Simple centered dialog: "Name this template," one text field, "Save" and "Cancel" buttons.
- Confirmation: brief gold checkmark animation, dialog closes.

Screen 6 — Export / Print

Opens as a bottom sheet from the "Print / Export" button.

- **"Save as PDF"** — large labeled button with a document icon. Tapping shows a brief progress state, then a success screen: "Saved!" with the file name and two follow-up buttons — **"Open"** and **"Share."**
- **"Print"** — large labeled button with a printer icon. Opens Android's native print dialog directly (no custom print UI needed — Android handles printer selection).
- Both options shown together as two large stacked cards rather than tiny buttons, so the choice is unmistakable.

Screen 7 — Settings

Simple list, generously spaced, each row with an icon + label + short description:

- **Text Size** — app-wide UI text scaling (Small / Medium / Large) — important for this audience.
 - **Default Export Location**
 - **App Theme** — Light (default) / Warm Dark, in case of preference.
 - **Help & Tutorial** — replays a short onboarding walkthrough.
 - **About** — version, credits.
-

3. Onboarding (first launch only)

3 short slides, skippable, each with one illustration, one sentence, and a "Next" button (final slide says "Get Started"):

1. "Turn any invitation into your own design."
 2. "Tap anywhere to add text — even use your voice."
 3. "Save, print, or share when you're ready."
-

4. Complete User Flow (happy path)

Launch App
→ Home (Library)

- Tap "+ New Invitation"
- Choose: Upload File / Template / Blank
 - [Upload] Pick PDF/JPG/PNG from device → Editor opens with file loaded
 - [Template] Browse Template Library → tap one → Editor opens pre-filled
 - [Blank] Editor opens with empty canvas
- Editor
 - Tap canvas or "Add Text" → text box appears
 - Tap text box → formatting panel slides up (font/size/color/align)
 - Optionally tap mic → speak → text inserted
 - Drag/resize/rotate text box as needed
 - Tap "Save" (top bar) → returns to Home, thumbnail updated
 - OR tap "Print/Export" → choose Save as PDF or Print → done
 - OR open menu → "Save as Template" → name it → saved to Template Library
 - Home
 - Tap any past invitation → reopens in Editor
 - "... " on a thumbnail → Rename / Duplicate / Delete / Export / Print

5. Accessibility & Usability Notes for 50+ Users

- Minimum text size 16sp everywhere; user-adjustable up to 20sp+ in Settings.
- Every icon labeled with text — never rely on icon meaning alone.
- Touch targets ≥ 48 dp, ideally 56dp for primary actions.
- Destructive actions use undo-snackbars over scary confirmation dialogs where safe to do so (delete text); irreversible actions (delete whole invitation) still get a confirmation dialog.
- High color contrast between text and background (WCAG AA minimum).
- No gestures required beyond tap, drag, and pinch-zoom — no swipe-menus or hidden gestures.
- Calm, slow animations — nothing that feels rushed or game-like.
- Consistent button placement across screens (primary action always bottom or top-right) so muscle memory builds quickly.

This is the full design. Nothing here is code — it's the blueprint we'll build screen-by-screen once you

confirm.