

CUSPARSE Library

PG-05329-032_V02 August, 2010 CUSPARSE Library PG-05329-032_V02

Published by NVIDIA Corporation 2701 San Tomas Expressway Santa Clara, CA 95050

Notice

ALL NVIDIA DESIGN SPECIFICATIONS, REFERENCE BOARDS, FILES, DRAWINGS, DIAGNOSTICS, LISTS, AND OTHER DOCUMENTS (TOGETHER AND SEPARATELY, "MATERIALS") ARE BEING PROVIDED "AS IS". NVIDIA MAKES NO WARRANTIES, EXPRESSED, IMPLIED, STATUTORY, OR OTHERWISE WITH RESPECT TO THE MATERIALS, AND EXPRESSLY DISCLAIMS ALL IMPLIED WARRANTIES OF NONINFRINGEMENT, MERCHANTABILITY, AND FITNESS FOR A PARTICULAR PURPOSE.

Information furnished is believed to be accurate and reliable. However, NVIDIA Corporation assumes no responsibility for the consequences of use of such information or for any infringement of patents or other rights of third parties that may result from its use. No license is granted by implication or otherwise under any patent or patent rights of NVIDIA Corporation. Specifications mentioned in this publication are subject to change without notice. This publication supersedes and replaces all information previously supplied. NVIDIA Corporation products are not authorized for use as critical components in life support devices or systems without express written approval of NVIDIA Corporation.

Trademarks

NVIDIA, CUDA, and the NVIDIA logo are trademarks or registered trademarks of NVIDIA Corporation in the United States and other countries. Other company and product names may be trademarks of the respective companies with which they are associated.

Copyright

© 2005–2010 by NVIDIA Corporation. All rights reserved.

Table of Contents

1. CUSPARSE Library	5
CUSPARSE Formats	
Sparse Vector Format	6
Matrix Formats	7
Dense Format	7
Coordinate Format (COO)	8
Compressed Sparse Row Format (CSR)	9
Compressed Sparse Column Format (CSC)	10
CUSPARSE Types	12
cusparseHandle_t	
cusparseMatrixType_t	
cusparseFillMode_t	
cusparseDiagType_t	
cusparseIndexBase_t	
cusparseMatDescr_t	
cusparseOperation_t	
cusparseDirection_t	
cusparseStatus_t	
·	14
cusparseStatus_t	14 17
cusparseStatus_t	14 17 18
cusparseStatus_t	14 17 18
cusparseStatus_t 2. CUSPARSE Functions CUSPARSE Helper Functions. cusparseCreate() cusparseDestroy().	14 17 18 18
cusparseStatus_t 2. CUSPARSE Functions CUSPARSE Helper Functions. cusparseCreate() cusparseDestroy(). cusparseGetVersion()	14 17 18 18 19
cusparseStatus_t 2. CUSPARSE Functions CUSPARSE Helper Functions. cusparseCreate() cusparseDestroy(). cusparseGetVersion() cusparseSetKernelStream()	14 17 18 18 19 19
cusparseStatus_t 2. CUSPARSE Functions CUSPARSE Helper Functions. cusparseCreate() cusparseDestroy(). cusparseGetVersion() cusparseSetKernelStream() cusparseCreateMatDescr().	14 17 18 19 19 20 20
cusparseStatus_t 2. CUSPARSE Functions CUSPARSE Helper Functions. cusparseCreate() cusparseDestroy(). cusparseGetVersion() cusparseSetKernelStream() cusparseCreateMatDescr() cusparseDestroyMatDescr()	14 17 18 18 19 19 20 21
cusparseStatus_t 2. CUSPARSE Functions CUSPARSE Helper Functions. cusparseCreate() cusparseDestroy(). cusparseGetVersion() cusparseSetKernelStream() cusparseCreateMatDescr() cusparseDestroyMatDescr() cusparseSetMatType()	14 17 18 19 19 20 20 21 21
cusparseStatus_t 2. CUSPARSE Functions CUSPARSE Helper Functions. cusparseCreate() cusparseDestroy(). cusparseGetVersion() cusparseSetKernelStream() cusparseCreateMatDescr() cusparseDestroyMatDescr()	14 17 18 19 19 20 20 21 21
cusparseStatus_t 2. CUSPARSE Functions CUSPARSE Helper Functions. cusparseCreate() cusparseDestroy(). cusparseGetVersion() cusparseSetKernelStream() cusparseCreateMatDescr() cusparseDestroyMatDescr() cusparseSetMatType() cusparseGetMatType().	14 17 18 19 19 20 21 21 21
cusparseStatus_t 2. CUSPARSE Functions CUSPARSE Helper Functions. cusparseCreate() cusparseDestroy(). cusparseGetVersion() cusparseSetKernelStream() cusparseCreateMatDescr() cusparseDestroyMatDescr() cusparseSetMatType() cusparseGetMatType() cusparseSetMatFillMode()	14 17 18 18 19 20 20 21 21 21 22
cusparseStatus_t 2. CUSPARSE Functions CUSPARSE Helper Functions. cusparseCreate() cusparseDestroy(). cusparseGetVersion() cusparseSetKernelStream() cusparseCreateMatDescr() cusparseDestroyMatDescr() cusparseSetMatType() cusparseGetMatType() cusparseGetMatFillMode() cusparseGetMatFillMode()	14 17 18 18 19 20 20 21 21 22 22
cusparseStatus_t 2. CUSPARSE Functions CUSPARSE Helper Functions. cusparseCreate() cusparseDestroy(). cusparseGetVersion() cusparseSetKernelStream() cusparseCreateMatDescr() cusparseDestroyMatDescr() cusparseSetMatType(). cusparseGetMatType(). cusparseSetMatFillMode() cusparseGetMatFillMode() cusparseSetMatDiagType().	14 17 18 18 19 20 21 21 21 22 22 23

Naming Convention for the Sparse Level Functions	24
Sparse Level 1 Functions cusparse{S,D,C,Z}axpyi cusparse{S,D,C,Z}doti cusparse{C,Z}dotci cusparse{S,D,C,Z}gthr cusparse{S,D,C,Z}gthrz cusparse{S,D,C,Z}gthrz cusparse{S,D}roti cusparse{S,D,C,Z}sctr	25 26 28 29 30 32
Sparse Level 2 Function	
Sparse Level 3 Function	
Format Conversion Functions cusparse{S,D,C,Z}nnz cusparse{S,D,C,Z}dense2csr cusparse{S,D,C,Z}csr2dense cusparse{S,D,C,Z}dense2csc cusparse{S,D,C,Z}csc2dense cusparse{S,D,C,Z}csc2dense cusparse{S,D,C,Z}csr2csc cusparseXcoo2csr cusparseXcsr2coo	40 42 44 45 47 49 51
A. CUSPARSE Library Example	55
B. CUSPARSE Fortran Bindings	65

CHAPTER

1

CUSPARSE Library

The NVIDIA[®] CUDA[™] CUSPARSE library contains a set of basic linear algebra subroutines used for handling sparse matrices and is designed to be called from C or C⁺⁺. These subroutines can be classified in four categories:

- Level 1 routines include operations between a vector in sparse format and a vector in dense format.
- □ Level 2 routines include operations between a matrix in sparse format and a vector in dense format.
- □ Level 3 routines include operations between a matrix in sparse format and a set of vectors (tall matrix) in dense format.
- Conversion routines that allow conversion between different matrix formats.

The library is written using the CUDA parallel programming model and takes advantage of the computational resources of the NVIDIA graphics processor (GPU). The CUSPARSE API assumes that the input and output data reside in GPU (device) memory, not in CPU (host) memory, unless CPU memory is specifically indicated by the string HostPtr being part of the parameter name of a function (for example, *resultHostPtr in cusparse{S,D,C,Z}doti on page 26).

It is the responsibility of the user to allocate memory and to copy data between GPU memory and CPU memory using standard CUDA runtime API routines, such as, <code>cudaMalloc()</code>, <code>cudaFree()</code>, <code>cudaMemcpy()</code>, and <code>cudaMemcpyAsync()</code>. (The CUDA runtime API is part of the CUDA Toolkit from NVIDIA.) The library is currently designed to run only on single-GPU systems; it does not autoparallelize across multiple GPUs.

Note: The CUSPARSE library requires hardware with at least 1.1 compute capability. Please see *NVIDIA CUDA C Programming Guide*, Appendix A for the list of all compute capabilities.

CUSPARSE Formats

CUSPARSE supports a Sparse Vector Format and Matrix Formats.

Index Base Format

The library supports zero- and one-based indexing.

Sparse Vector Format

Sparse vectors are represented with two arrays.

- One data array contains all the non-zero values from the equivalent array in dense format.
- One integer index array contains the position of the corresponding non-zero value in the equivalent array in dense format.

For example, this 7×1 dense vector can be stored as a one-based or a zero-based sparse vector.

One-based:
$$\begin{bmatrix} 1.0 & 2.0 & 3.0 & 4.0 \\ 1 & 4 & 5 & 7 \end{bmatrix}$$

Zero-based:
$$\begin{bmatrix} 1.0 & 2.0 & 3.0 & 4.0 \\ 0 & 3 & 4 & 6 \end{bmatrix}$$

Note: It is assumed that the indices are provided in an increasing order and that each index appears only once.

Matrix Formats

The matrix formats are the following:

- □ Dense Format on page 7
- □ Coordinate Format (COO) on page 8
- Compressed Sparse Row Format (CSR) on page 9
- Compressed Sparse Column Format (CSC) on page 10

Dense Format

The dense matrix X is represented by the following parameters (assuming it is stored in column-major format in memory):

- □ m (integer): the number of rows in the matrix.
- □ n (integer): the number of columns in the matrix.
- □ 1dX (integer): the leading dimension of X, which must be greater than or equal to m. If 1dX is greater than m, then X represents a submatrix of a larger idX × n matrix stored in memory.
- □ X (pointer): points to the data array containing the matrix elements. It is assumed that enough storage is allocated for X to hold at least 1dX * n matrix elements and that CUSPARSE library functions may access values outside of the m×n sub-matrix, but will never overwrite them.

Figure 1 on page 8 shows a schematic representation of the $m \times n$ dense matrix X (shaded area) with leading dimension 1dX greater than m and one-based indexing.




Figure 1. $m \times n$ Dense Matrix X with IdX > m

Please note that this format and notation is similar to the format and notation used in the NVIDIA CUDA CUBLAS library.

Coordinate Format (COO)

The $m \times n$ sparse matrix A is represented in COO format by the following parameters:

- nnz (integer): the number of non-zero elements in the matrix.
- □ cooValA (pointer): points to the data array of length nnz that holds all non-zero values of A in row-major format.
- cooRowIndA (pointer): points to the integer array of length nnz that contains the row indices of the corresponding elements in array cooValA.
- cooColIndA (pointer): points to the integer array of length nnz that contains the column indices of the corresponding elements in array cooValA.

Note: It is assumed that the indices are given in row-major format (first sorted by row indices and then within the same row by column indices) and that each pair of row and column indices appears only once.

Consider the following 4×5 matrix A.

This is how it is stored in COO zero-based format.

cooValA =
$$\begin{bmatrix} 1.0 & 4.0 & 2.0 & 3.0 & 5.0 & 7.0 & 8.0 & 9.0 & 6.0 \end{bmatrix}$$

cooRowIndA = $\begin{bmatrix} 0 & 0 & 1 & 1 & 2 & 2 & 2 & 3 & 3 \end{bmatrix}$
cooColIndA = $\begin{bmatrix} 0 & 1 & 1 & 2 & 0 & 3 & 4 & 2 & 4 \end{bmatrix}$

And this is the COO one-based format.

cooValA =
$$\begin{bmatrix} 1.0 & 4.0 & 2.0 & 3.0 & 5.0 & 7.0 & 8.0 & 9.0 & 6.0 \end{bmatrix}$$

cooRowIndA = $\begin{bmatrix} 1 & 1 & 2 & 2 & 3 & 3 & 4 & 4 \end{bmatrix}$
cooColIndA = $\begin{bmatrix} 1 & 2 & 2 & 3 & 1 & 4 & 5 & 3 & 5 \end{bmatrix}$

Compressed Sparse Row Format (CSR)

The only difference between the COO and CSR formats is that the array containing the row indices is compressed in CSR format.

The $m \times n$ sparse matrix A is represented in CSR format by the following parameters:

- nnz (integer): the number of non-zero elements in the matrix.
- csrValA (pointer): points to the data array of length nnz that holds all non-zero values of A in row-major format.
- csrRowPtrA (pointer): points to the integer array of length m+1 that holds indices pointing to the array csrColIndA/csrValA. For the first m entries, csrRowPtrA(i) contains the index of the first non-zero element in the ith row, while the last entry, csrRowPtrA(m), contains nnz+csrRowPtrA(0). In general, csrRowPtrA(0) is 0 or 1 depending on whether zero- or one-based format is used, respectively.

 csrColIndA (pointer): points to the integer array of length nnz that holds the column indices of the corresponding elements in csrValA.

Note: It is assumed that the indices are given in row-major format (first sorted by row indices and then within the same row by column indices) and that each pair of row and column indices appears only once.

Again, consider the 4×5 matrix A.

It is stored in CSR zero-based format as shown.

csrValA =
$$\begin{bmatrix} 1.0 & 4.0 & 2.0 & 3.0 & 5.0 & 7.0 & 8.0 & 9.0 & 6.0 \end{bmatrix}$$

csrRowPtrA = $\begin{bmatrix} 0 & 2 & 4 & 7 & 9 \end{bmatrix}$
csrColIndA = $\begin{bmatrix} 0 & 1 & 1 & 2 & 0 & 3 & 4 & 2 & 4 \end{bmatrix}$

This is the CSR one-based format.

csrValA =
$$\begin{bmatrix} 1.0 & 4.0 & 2.0 & 3.0 & 5.0 & 7.0 & 8.0 & 9.0 & 6.0 \end{bmatrix}$$

csrRowPtrA = $\begin{bmatrix} 1 & 3 & 5 & 8 & 10 \end{bmatrix}$
csrColIndA = $\begin{bmatrix} 1 & 2 & 2 & 3 & 1 & 4 & 5 & 3 & 5 \end{bmatrix}$

Compressed Sparse Column Format (CSC)

The $m \times n$ matrix A is represented in CSC format by the following parameters:

- nnz (integer): the number of non-zero elements in the matrix.
- □ cscValA (pointer): points to the data array of length nnz that holds all non-zero values of A in column-major format.
- □ cscRowIndA (pointer): points to the integer array of length nnz that holds the row indices of the corresponding elements in cscValA.

10 PG-05329-032_V02 NVIDIA

cscColPtrA (pointer): points to the integer array of length n+1 that holds indices pointing to array cscRowIndA/cscValA. For the first n entries, cscColPtrA(i) contains the index of the first non-zero element in the ith column, while the last entry, csrColPtrA(n), contains nnz+csrColPtrA(0). In general, cscColPtrA(0) is 0 or 1 depending on whether zero- or one-based format is used, respectively.

Note: It is assumed that the indices are given in column-major format (first sorted by column indices and then within the same column by row indices) and that each pair of row and column indices appears only once.

Also note that matrix A in CSR format has exactly the same memory layout as its transpose in CSC format (and vice-versa).

Consider the 4×5 matrix A one more time.

The CSC zero-based storage format is below.

cscValA =
$$\begin{bmatrix} 1.0 & 5.0 & 4.0 & 2.0 & 3.0 & 9.0 & 7.0 & 8.0 & 6.0 \end{bmatrix}$$

cscRowIndA = $\begin{bmatrix} 0 & 2 & 0 & 1 & 1 & 3 & 2 & 2 & 3 \end{bmatrix}$
cscColPtrA = $\begin{bmatrix} 0 & 2 & 4 & 6 & 7 & 9 \end{bmatrix}$

And, this is the CSC one-based format.

cscValA =
$$\begin{bmatrix} 1.0 & 5.0 & 4.0 & 2.0 & 3.0 & 9.0 & 7.0 & 8.0 & 6.0 \end{bmatrix}$$

cscRowIndA = $\begin{bmatrix} 1 & 3 & 1 & 2 & 2 & 4 & 3 & 3 & 4 \end{bmatrix}$
cscColPtrA = $\begin{bmatrix} 1 & 3 & 5 & 7 & 8 & 10 \end{bmatrix}$

PG-05329-032_V02 NVIDIA

CUSPARSE Types

The library supports the following data types: float, double, cuComplex, and cuDoubleComplex. The first two are standard C data types, the second two are exported from cuComplex.h.

The CUSPARSE library provides these types:

```
    cusparseHandle_t on page 12
    cusparseMatrixType_t on page 12
    cusparseFillMode_t on page 13
    cusparseDiagType_t on page 13
    cusparseIndexBase_t on page 13
    cusparseMatDescr_t on page 13
    cusparseOperation_t on page 14
```

cusparseDirection_t on page 14

□ cusparseStatus_t on page 14

cusparseHandle_t

This is a pointer type to an opaque CUSPARSE context, which the user must initialize by calling <code>cusparseCreate()</code> prior to calling any other library function. The handle created and returned by <code>cusparseCreate()</code> must be passed to every CUSPARSE function.

cusparseMatrixType_t

This type indicates the type of matrix stored in sparse storage.

```
typedef enum {
   CUSPARSE_MATRIX_TYPE_GENERAL=0,
   CUSPARSE_MATRIX_TYPE_SYMMETRIC=1,
   CUSPARSE_MATRIX_TYPE_HERMITIAN=2,
   CUSPARSE_MATRIX_TYPE_TRIANGULAR=3
} cusparseMatrixType t;
```

cusparseFillMode_t

This type indicates if the lower or upper part of a matrix is stored in sparse storage.

```
typedef enum {
   CUSPARSE_FILL_MODE_LOWER=0,
   CUSPARSE_FILL_MODE_UPPER=1
} cusparseFillMode_t;
```

cusparseDiagType_t

This type indicates if the matrix diagonal entries are equal to one.

```
typedef enum {
    CUSPARSE_DIAG_TYPE_NON_UNIT=0,
    CUSPARSE_DIAG_TYPE_UNIT=1
} cusparseDiagType_t;
```

cusparseIndexBase_t

This type indicates if the base of the matrix indices is zero or one.

```
typedef enum {
    CUSPARSE_INDEX_BASE_ZERO=0,
    CUSPARSE_INDEX_BASE_ONE=1
} cusparseIndexBase_t;
```

cusparseMatDescr_t

This structure is used to describe the shape and properties of a matrix.

```
typedef struct {
    cusparseMatrixType_t MatrixType;
    cusparseFillMode_t FillMode;
    cusparseDiagType_t DiagType;
    cusparseIndexBase_t IndexBase;
} cusparseMatDescr t;
```

cusparseOperation_t

Indicates which operations need to be performed with the sparse matrix.

```
typedef enum {
    CUSPARSE_OPERATION_NON_TRANSPOSE=0,
    CUSPARSE_OPERATION_TRANSPOSE=1,
    CUSPARSE_OPERATION_CONJUGATE_TRANSPOSE=2
} cusparseOperation t;
```

cusparseDirection_t

Indicates whether the elements of a matrix should be parsed by rows or by columns (regardless of row- or column-major storage format).

```
typedef enum {
   CUSPARSE_DIRECTION_ROW=0,
   CUSPARSE_DIRECTION_COLUMN=1
} cusparseDirection_t;
```

cusparseStatus_t

This is a status type returned by the library functions and can have the following defined values:

```
typedef enum{
```

```
CUSPARSE_STATUS_SUCCESS=0,
CUSPARSE_STATUS_NOT_INITIALIZED=1,
CUSPARSE_STATUS_ALLOC_FAILED=2,
CUSPARSE_STATUS_INVALID_VALUE=3,
CUSPARSE_STATUS_ARCH_MISMATCH=4,
CUSPARSE_STATUS_MAPPING_ERROR=5,
CUSPARSE_STATUS_EXECUTION_FAILED=6,
CUSPARSE_STATUS_INTERNAL_ERROR=7,
CUSPARSE_STATUS_MATRIX_TYPE_NOT_SUPPORTED=8,
} cusparseStatus_t;
```

The status values are explained in the following table:

CUSPARSE Status Definitions

CUSPARSE_STATUS_SUCCESS

The operation completed successfully.

CUSPARSE_STATUS_NOT_INITIALIZED

The CUSPARSE library was not initialized. This is usually caused by the lack of a prior **cusparseCreate()** call, or by an error in CUDA or in the hardware setup.

To correct: call **cusparseCreate()** prior to the function call; and check that the hardware, an appropriate version of the driver, and the CUSPARSE library are correctly installed.

CUSPARSE_STATUS_ALLOC_FAILED

Resource allocation failed inside the CUSPARSE library. This is usually caused by a **cudaMalloc()** failure.

To correct: prior to the function call, deallocate previously allocated memory as much as possible.

CUSPARSE_STATUS_INVALID_VALUE

An unsupported value or parameter was passed to the function (a negative vector size, for example).

To correct: ensure that all the parameters being passed have valid values.

CUSPARSE_STATUS_ARCH_MISMATCH

Function requires a feature absent from the device architecture; usually caused by the lack of support for atomic operations or double precision. To correct: compile and run the application on a device with appropriate compute capability, which is 1.1 for 32-bit atomic operations and 1.3 for double precision.

CUSPARSE STATUS MAPPING ERROR

An access to GPU memory space failed, which is usually caused by a failure to bind a texture.

To correct: prior to the function call, unbind any previously bound textures.

CUSPARSE_STATUS_EXECUTION_FAILED

The GPU program failed to execute. This is often caused by a launch failure of the kernel on the GPU, which can be caused by multiple reasons. To correct: check that the hardware, an appropriate version of the driver, and the CUSPARSE library are correctly installed.

CUSPARSE Status Definitions (continued)

CUSPARSE_STATUS_INTERNAL_ERROR

An internal CUSPARSE operation failed. This error is usually caused by a **cudaMemcpyAsync()** failure.

To correct: check that the hardware, an appropriate version of the driver, and the CUSPARSE library are correctly installed.

CUSPARSE_STATUS_MATRIX_TYPE_NOT_SUPPORTED

The matrix type is not supported by this function. This is usually caused by passing an invalid matrix descriptor to the function.

To correct: check that the fields in **cusparseMatDescr_t *descrA** were set correctly.

CHAPTER

2

CUSPARSE Functions

This chapter discusses the CUSPARSE functions, which are divided into five groups, and the naming convention used for Sparse Level 1, Level 2, and Level 3 functions.

- CUSPARSE Helper Functions on page 18
- □ Naming Convention for the Sparse Level Functions on page 24
- □ Sparse Level 1 Functions on page 24
- □ Sparse Level 2 Function on page 34
- □ Sparse Level 3 Function on page 37
- □ Format Conversion Functions on page 40

CUSPARSE Helper Functions

The CUSPARSE helper functions are as follows:

- □ cusparseCreate() on page 18
- □ cusparseDestroy() on page 19
- □ cusparseGetVersion() on page 19
- □ cusparseSetKernelStream() on page 20
- cusparseCreateMatDescr() on page 20
- □ cusparseDestroyMatDescr() on page 21
- □ cusparseSetMatType() on page 21
- □ cusparseGetMatType() on page 21
- □ cusparseSetMatFillMode() on page 22
- □ cusparseGetMatFillMode() on page 22
- cusparseSetMatDiagType() on page 22
- □ cusparseGetMatDiagType() on page 23
- □ cusparseSetMatIndexBase() on page 23
- □ cusparseGetMatIndexBase() on page 24

cusparseCreate()

```
cusparseStatus_t
cusparseCreate( cusparseHandle_t *handle )
```

Initializes the CUSPARSE library and creates a handle on the CUSPARSE context. This function must be called before any other CUSPARSE API function is invoked. It allocates hardware resources necessary for accessing the GPU.

Note: The CUSPARSE library requires hardware with at least 1.1 compute capability. Please see *NVIDIA CUDA C Programming Guide*, Appendix A for the list of all compute capabilities.

Output

handle initialized pointer to a CUSPARSE context

Status Returnedi

CUSPARSE_STATUS_SUCCESS	CUSPARSE library initialized successfully
CUSPARSE_STATUS_NOT_INITIALIZED	if an error with CUDA or the hardware setup has been detected
CUSPARSE_STATUS_ALLOC_FAILED	
CUSPARSE_STATUS_ARCH_MISMATCH	if device compute capability is less than 1.1

i. See also CUSPARSE Status Definitions on page 15.

cusparseDestroy()

cusparseStatus_t cusparseDestroy(cusparseHandle_t handle)

Releases CPU side resources used by the CUSPARSE library. The release of GPU side resources may be deferred until the application shuts down.

Input

handle handle to a CUSPARS	handle to a CUSPARSE context	
Status Returned ⁱ		
CUSPARSE_STATUS_SUCCESS	CUSPARSE library shut down successfully	

i. See also CUSPARSE Status Definitions on page 15.

cusparseGetVersion()

cusparseStatus_t
cusparseGetVersion(
 cusparseHandle_t handle, int *version)

Returns the version number of the CUSPARSE library.

Input

handle	handle to a CUSPARSE context
Output	
version	integer version number of the library

Ctatue	Returned ¹
Status	Returned

Status Returned	
CUSPARSE_STATUS_SUCCESS	CUSPARSE library version was returned successfully
CUSPARSE_STATUS_NOT_INITIALIZED	

i. See also CUSPARSE Status Definitions on page 15.

cusparseSetKernelStream()

cusparseStatus_t
cusparseSetKernelStream(
 cusparseHandle_t handle, cudaStream_t streamId)

Sets the CUSPARSE stream in which the kernels will run.

Input

handle handle to a CUSPARSE context		
Status Returned ⁱ		
CUSPARSE_STATUS_SUCCESS	if stream provided has been set properly	
CUSPARSE_STATUS_NOT_INITIALIZED		

i. See also CUSPARSE Status Definitions on page 15.

cusparseCreateMatDescr()

cusparseStatus_t
cusparseCreateMatDescr(cusparseMatDescr_t *descrA)

Initializes the MatrixType and IndexBase fields of the matrix descriptor to the default values CUSPARSE_MATRIX_TYPE_GENERAL and CUSPARSE_INDEX_BASE_ZERO, while leaving other fields uninitialized.

Input

•	
descrA descriptor of the matrix A	
Status Returned	
CUSPARSE_STATUS_SUCCESS	matrix descriptor initialized successfully
CUSPARSE_STATUS_ALLOC_FAILED	if resources could not be allocated for the matrix descriptor

cusparseDestroyMatDescr()

cusparseStatus_t

cusparseDestroyMatDescr(cusparseMatDescr_t descrA)

Releases the memory allocated for the matrix descriptor.

Input

descrA descriptor of the matrix A	
Status Returned	
CUSPARSE_STATUS_SUCCESS	matrix descriptor destroyed successfully

cusparseSetMatType()

cusparseStatus_t
cusparseSetMatType(

cusparseMatDescr_t descrA, cusparseMatrixType_t type)

Sets the MatrixType field of the matrix descriptor descrA.

Input

-		
type	one of the enumerated mat	rix types
Output		
descrA	descriptor of the matrix A	
Status	Returned	
CUSPARS	E_STATUS_SUCCESS	MatrixType field was set successfully
CUSPARS	E_STATUS_INVALID_VALUE	if invalid value was passed in the type parameter

cusparseGetMatType()

```
cusparseMatrixType_t
```

cusparseGetMatType(const cusparseMatDescr_t descrA)

Returns the MatrixType field of the matrix descriptor descrA.

Input

descrA descriptor of the matrix A

Status Returned

one of the enumerated matrix types

cusparseSetMatFillMode()

```
cusparseStatus_t
cusparseSetMatFillMode(
    cusparseMatDescr_t descrA, cusparseFillMode_t fillMode )
```

Sets the **FillMode** field of the matrix descriptor descrA.

Input

mput		
fillMode one of the enumerated matrix types		
Output		
descrA descriptor of the matrix A		
Status Returned		
CUSPARSE_STATUS_SUCCESS	FillMode field was set successfully	
CUSPARSE_STATUS_INVALID_VALUE	if invalid value was passed in the	

fillMode parameter

cusparseGetMatFillMode()

```
cusparseFillMode_t
cusparseGetMatFillMode( const cusparseMatDescr_t descrA )
```

Returns the FillMode field of the matrix descriptor descrA.

Input

descrA descriptor of the matrix A

Status Returned

one of the enumerated fill-in types

cusparseSetMatDiagType()

Input

diagType one of the enumerated diagonal modes

PG-05329-032_V02 NVIDIA

Output	
descrA descriptor of the matrix A	
Status Returned	
CUSPARSE_STATUS_SUCCESS	DiagType field was set successfully
CUSPARSE_STATUS_INVALID_VALUE	if invalid value was passed in the diagType parameter

cusparseGetMatDiagType()

cusparseDiagType_t
cusparseGetMatDiagType(const cusparseMatDescr_t descrA)

Returns the **DiagType** field of the matrix descriptor descrA.

Input

descrA descriptor of the matrix A

Status Returned

one of the enumerated diagonal modes

cusparseSetMatIndexBase()

cusparseStatus_t
cusparseSetMatIndexBase(

cusparseMatDescr_t descrA, cusparseIndexBase_t base)

Sets the **IndexBase** field of the matrix descriptor descrA.

Input

base	one of the enumerated index base modes	
Output		
descrA	descriptor of the matrix A	
Status	Returned	
CUSPARS	E_STATUS_SUCCESS	IndexBase field was set successfully
CUSPARS	E_STATUS_INVALID_VALUE	if invalid value was passed in the base parameter

cusparseGetMatIndexBase()

cusparseIndexBase_t
cusparseGetMatIndexBase(const cusparseMatDescr_t descrA)

Returns the **IndexBase** field of the matrix descriptor descrA.

Input

descrA descriptor of the matrix A

Status Returned

one of the enumerated index base modes

Naming Convention for the Sparse Level Functions

Most of the CUSPARSE functions are available for data types float, double, cuComplex, and cuDoubleComplex. The Sparse Level 1, Level 2, and Level 3 functions follow this naming convention:

cusparse<T>[<sparse data format>]<operation>[<sparse data format>]

with <T> being S, D, C, Z, or X corresponding to the data types float, double, cuComplex, cuDoubleComplex, or no type, respectively. All these functions have the return type cusparseStatus_t.

Sparse Level 1 Functions

The Level 1 functions are the following:

- □ cusparse{S,D,C,Z}axpyi on page 25
- □ cusparse{S,D,C,Z}doti on page 26
- □ cusparse{C,Z}dotci on page 28
- □ cusparse{S,D,C,Z}gthr on page 29
- □ cusparse{S,D,C,Z}gthrz on page 30
- □ cusparse{S,D}roti on page 32
- □ cusparse{S,D,C,Z}sctr on page 33

cusparse{S,D,C,Z}axpyi

```
cusparseStatus_t
cusparseSaxpyi(
    cusparseHandle_t handle, int nnz,
    float alpha, const float *xVal,
    const int *xInd, float *y,
    cusparseIndexBase t idxBase )
cusparseStatus t
cusparseDaxpyi(
    cusparseHandle_t handle, int nnz,
    double alpha, const double *xVal,
    const int *xInd, double *y,
    cusparseIndexBase_t idxBase )
cusparseStatus t
cusparseCaxpyi(
    cusparseHandle t handle, int nnz,
    cuComplex alpha, const cuComplex *xVal,
    const int *xInd, cuComplex *y,
    cusparseIndexBase_t idxBase )
cusparseStatus_t
cusparseZaxpvi(
    cusparseHandle_t handle, int nnz,
    cuDoubleComplex alpha, const cuDoubleComplex *xVal,
    const int *xInd, cuDoubleComplex *y,
    cusparseIndexBase t idxBase )
```

Multiplies the vector x in sparse format by the constant alpha and adds the result to the vector y in dense format; that is, it overwrites y with alpha *x + y.

```
For i = 0 to nnz-1
```

```
y[xInd[i]-idxBase] = y[xInd[i]-idxBase] + alpha * xVal[i]
```

Input

```
handle handle to a CUSPARSE context

nnz number of elements of the vector x

alpha constant multiplier

xVal nnz non-zero values of vector x

xInd nnz indices corresponding to non-zero values of vector x
```

PG-05329-032_V02 **25** NVIDIA

Input (continued) initial vector in dense format idxBase CUSPARSE_INDEX_BASE_ZERO or CUSPARSE_INDEX_BASE_ONE Output result (unchanged if nnz == 0) У Status Returned¹ **CUSPARSE STATUS SUCCESS** CUSPARSE_STATUS_NOT_INITIALIZED CUSPARSE_STATUS_INVALID_VALUE if idxBase is neither CUSPARSE INDEX BASE ZERO nor CUSPARSE INDEX BASE ONE CUSPARSE_STATUS_ARCH_MISMATCH if the D or Z variants of the function were invoked on a device that does not support double precision. function failed to launch on GPU CUSPARSE_STATUS_EXECUTION_FAILED

i. See also CUSPARSE Status Definitions on page 15.

cusparse{S,D,C,Z}doti

```
cusparseStatus_t
cusparseSdoti(
    cusparseHandle t handle, int nnz,
    const float *xVal, const int *xInd,
    const float *y, float *resultHostPtr,
    cusparseIndexBase t idxBase )
cusparseStatus t
cusparseDdoti(
    cusparseHandle t handle, int nnz,
    const double *xVal, const int *xInd,
    const float *y, double *resultHostPtr,
    cusparseIndexBase t idxBase )
cusparseStatus_t
cusparseCdoti(
    cusparseHandle_t handle, int nnz,
    const cuComplex *xVal, const int *xInd,
    const float *y, cuComplex *resultHostPtr,
    cusparseIndexBase_t idxBase )
```

26 PG-05329-032_V02 NVIDIA

```
cusparseStatus_t
cusparseZdoti(
    cusparseHandle_t handle, int nnz,
    const cuDoubleComplex *xVal, const int *xInd,
    const float *y, cuDoubleComplex *resultHostPtr,
    cusparseIndexBase_t idxBase )
```

Returns the dot product of a vector x in sparse format and vector y in dense format.

For i = 0 to nnz-1

resultHostPtr += xVal[i] * y[xInd[i - idxBase]]

Input

_	
idxBase	CUSPARSE_INDEX_BASE_ZERO or CUSPARSE_INDEX_BASE_ONE
resultHostPtr	pointer where to write the result in host memory
у	vector in dense format
xInd	nnz indices corresponding to non-zero values of vector x
xVal	nnz non-zero values of vector x
nnz	number of elements of the vector x
handle	handle to a CUSPARSE context

Output

resultHostPtr	updated host memory with dot product
	(zero if nnz == 0)

Status Returnedi

CUSPARSE_STATUS_SUCCESS
CUSPARSE_STATUS_NOT_INITIALIZED
CUSPARSE_STATUS_ALLOC_FAILED
CUSPARSE_STATUS_INVALID_VALUE

if idxBase is neither

CUSPARSE_INDEX_BASE_ZERO nor CUSPARSE_INDEX_BASE_ONE

CUSPARSE_STATUS_ARCH_MISMATCH if the D or Z variants of the

function were invoked on a device that does not support double

precision.

CUSPARSE_STATUS_EXECUTION_FAILED CUSPARSE_STATUS_INTERNAL_ERROR

function failed to launch on GPU

i. See also CUSPARSE Status Definitions on page 15.

cusparse{C,Z}dotci

```
cusparseStatus_t
cusparseCdotci(
    cusparseHandle_t handle, int nnz,
    const cuComplex *xVal, const int *xInd,
    const cuComplex *y, cuComplex *resultHostPtr,
    cusparseIndexBase_t idxBase )

cusparseStatus_t
cusparseZdotci(
    cusparseHandle_t handle, int nnz,
    const cuDoubleComplex *xVal, const int *xInd,
    const cuComplex *y, cuDoubleComplex *resultHostPtr,
    cusparseIndexBase_t idxBase )
```

Returns the dot product of a complex conjugate of vector x in sparse format and complex vector y in dense format.

It computes the sum for i = 0 to nnz-1 of

```
resultHostPtr += \overline{xVal[i]} * y[xInd[i-idxBase]]
```

Input

handle	handle to a CUSPARSE context
nnz	number of elements of the vector x
xVal	nnz non-zero values of vector x
xInd	nnz indices corresponding to non-zero values of vector x
у	vector in dense format
resultHostPtr	pointer where to write the result in host memory
idxBase	CUSPARSE_INDEX_BASE_ZERO or CUSPARSE_INDEX_BASE_ONE

Output

resultHostPtr	undated bact mamany with dat anadyst
LESUTTHOSTELL.	updated host memory with dot product
	(
	(zero if nnz == 0)
	(20.0 2. 12 0)

Status Returnedi

```
CUSPARSE_STATUS_SUCCESS
CUSPARSE_STATUS_NOT_INITIALIZED
CUSPARSE_STATUS_ALLOC_FAILED
```

CUSPARSE_STATUS_INVALID_VALUE

if idxBase is neither
CUSPARSE_INDEX_BASE_ZERO nor
CUSPARSE_INDEX_BASE_ONE

Status Returned ^I (continued)	
CUSPARSE_STATUS_ARCH_MISMATCH	if the D or Z variants of the function were invoked on a device that does not support double precision.
CUSPARSE_STATUS_EXECUTION_FAILED	function failed to launch on GPU
CUSPARSE_STATUS_INTERNAL_ERROR	

i. See also CUSPARSE Status Definitions on page 15.

cusparse{S,D,C,Z}gthr

```
cusparseStatus_t
cusparseSgthr(
    cusparseHandle t handle, int nnz,
    const float *y, float *xVal,
    const int *xInd, cusparseIndexBase_t idxBase )
cusparseStatus_t
cusparseDgthr(
    cusparseHandle_t handle, int nnz,
    const double *y, double *xVal,
    const int *xInd, cusparseIndexBase t idxBase )
cusparseStatus t
cusparseCgthr(
    cusparseHandle_t handle, int nnz,
    const cuComplex *y, cuComplex *xVal,
    const int *xInd, cusparseIndexBase_t idxBase )
cusparseStatus t
cusparseZgthr(
    cusparseHandle_t handle, int nnz,
    const cuDoubleComplex *y, cuDoubleComplex *xVal,
    const int *xInd, cusparseIndexBase t idxBase )
```

Gathers the elements of the vector y listed by the index array xInd into the array xVal.

Input

handle	handle to a CUSPARSE context
nnz	number of elements of the vector x
у	vector in dense format, of size greater than or equal to $max(xInd) - idxBase + 1$

Input ((continu	ied)
IIIPGL (10u,

xVal	pre-allocated array i or equal to nnz	in device memory of size greater than
xInd	nnz indices correspo	onding to non-zero values of vector x
idxBase	CUSPARSE_INDEX_BAS	SE_ZERO or CUSPARSE_INDEX_BASE_ONE
Output		
xVal updated vector of nnz elements (unchanged if nnz == 0)		
Status Returned ⁱ		
CUSPARSE_STATUS_SUCCESS		
CUSPARSE_STATUS_NOT_INITIALIZED		
CUSPARSE_STATU	S_INVALID_VALUE	if idxBase is neither CUSPARSE_INDEX_BASE_ZERO nor CUSPARSE_INDEX_BASE_ONE
CUSPARSE_STATU	S_ARCH_MISMATCH	if the D or Z variants of the function were invoked on a device that does not support double precision.
CUSPARSE_STATU	S_EXECUTION_FAILED	function failed to launch on GPU

i. See also CUSPARSE Status Definitions on page 15.

cusparse{S,D,C,Z}gthrz

```
cusparseStatus_t
cusparseHandle_t handle, int nnz, float *y,
   float *xVal, const int *xInd,
   cusparseIndexBase_t idxBase )

cusparseStatus_t
cusparseOgthrz(
   cusparseHandle_t handle, int nnz, double *y,
   double *xVal, const int *xInd,
   cusparseIndexBase_t idxBase )

cusparseStatus_t
cusparseStatus_t
cusparseCgthrz(
   cusparseHandle_t handle, int nnz, cuComplex *y,
   cuComplex *xVal, const int *xInd,
   cusparseIndexBase t idxBase )
```

```
cusparseStatus_t
cusparseZgthrz(
    cusparseHandle_t handle, int nnz, cuDoubleComplex *y,
    cuDoubleComplex *xVal, const int *xInd,
    cusparseIndexBase_t idxBase )
```

Gathers the elements of the vector y listed by the index array xInd into the vector x, and zeroes those elements in the vector y.

Input

handle	handle to a CUSPARSE context
nnz	number of elements of the vector x
у	vector in dense format, of size greater than or equal to $max(xInd) - idxBase + 1$
xVal	nnz non-zero values of vector x
xInd	nnz indices corresponding to non-zero values of vector x
idxBase	CUSPARSE_INDEX_BASE_ZERO or CUSPARSE_INDEX_BASE_ONE

Output

xVal	nnz non-zero values of vector x (unchanged if nnz == 0)
xInd	nnz indices corresponding to non-zero values of vector x (unchanged if nnz == 0)
У	vector in dense format (unchanged if nnz == 0)

Status Returnedi

CUSPARSE_STATUS_SUCCESS	
CUSPARSE_STATUS_NOT_INITIALIZED	
CUSPARSE_STATUS_INVALID_VALUE	if idxBase is neither CUSPARSE_INDEX_BASE_ZERO nor CUSPARSE_INDEX_BASE_ONE
CUSPARSE_STATUS_ARCH_MISMATCH	if the D or Z variants of the function were invoked on a device that does not support double precision.
CUSPARSE_STATUS_EXECUTION_FAILED	function failed to launch on GPU

i. See also CUSPARSE Status Definitions on page 15.

cusparse{S,D}roti

```
cusparseStatus_t
cusparseSroti(
    cusparseHandle_t handle, int nnz, float *xVal,
    const int *xInd, float *y, float c,
    float s, cusparseIndexBase_t idxBase )

cusparseStatus_t
cusparseDroti(
    cusparseHandle_t handle, int nnz, double *xVal,
    const int *xInd, double *y, double c,
    double s, cusparseIndexBase t idxBase )
```

Applies Givens rotation, defined by values c and s, to vectors x in sparse and y in dense format.

For i = 0 to nnz-1

```
y[xInd[i]-idxBase] = c * y[xInd[i]-idxBase] - s * xVal[i]
x[i] = c * xVal[i] + s * y[xInd[i]-idxBase]
```

Input

•	
handle	handle to a CUSPARSE context
nnz	number of elements of the vector x
xVal	nnz non-zero values of vector x
xInd	nnz indices corresponding to non-zero values of vector x
у	vector in dense format
С	scalar
S	scalar
idxBase	CUSPARSE_INDEX_BASE_ZERO or CUSPARSE_INDEX_BASE_ONE

Output

xVal	updated nnz non-zero values of vector x (unchanged if nnz == 0)
xInd	updated nnz indices corresponding to non-zero values of vector x (unchanged if nnz == 0)
у	updated vector in dense format (unchanged if nnz == 0)

Status Returnedi

CUSPARSE_STATUS_SUCCESS

CUSPARSE_STATUS_NOT_INITIALIZED

ed)

CUSPARSE_STATUS_INVALID_VALUE	if idxBase is neither CUSPARSE_INDEX_BASE_ZERO nor CUSPARSE_INDEX_BASE_ONE
CUSPARSE_STATUS_ARCH_MISMATCH	if the D or Z variants of the function were invoked on a device that does not support double precision.
CUSPARSE_STATUS_EXECUTION_FAILED	function failed to launch on GPU

i. See also CUSPARSE Status Definitions on page 15.

cusparse{S,D,C,Z}sctr

```
cusparseStatus_t
cusparseSsctr(
    cusparseHandle_t handle, int nnz,
    const float *xVal, const int *xInd,
    float *y, cusparseIndexBase t idxBase )
cusparseStatus t
cusparseDsctr(
    cusparseHandle_t handle, int nnz,
    const double *xVal, const int *xInd,
    double *y, cusparseIndexBase_t idxBase )
cusparseStatus t
cusparseCsctr(
    cusparseHandle t handle, int nnz,
    const cuComplex *xVal, const int *xInd,
    cuComplex *y, cusparseIndexBase_t idxBase )
cusparseStatus_t
cusparseZsctr(
    cusparseHandle_t handle, int nnz,
    const cuDoubleComplex *xVal, const int *xInd,
    cuDoubleComplex *y, cusparseIndexBase t idxBase )
```

Scatters the vector x in sparse format into the vector y in dense format. It modifies only the elements of y whose indices are listed in the array xInd.

Input

handle	handle to a CUSPARSE context
nnz	number of elements of the vector x

PG-05329-032_V02 NVIDIA 33

Input (continι	ied)
IIIPGL (10u,

xVal	nnz non-zero values o	of vector x	
xInd	nnz indices correspor	nnz indices corresponding to non-zero values of vector x	
у	<u>*</u>	pre-allocated vector in dense format, of size greater than or equal to max(xInd) – idxBase + 1	
idxBase	CUSPARSE_INDEX_BASE	_ZERO or CUSPARSE_INDEX_BASE_ONE	
Output			
у	updated vector in dense forma	nt (unchanged if nnz == 0)	
CUSPARSE	Returned ⁱ E_STATUS_SUCCESS E_STATUS_NOT_INITIALIZED		
CUSPARSE	STATUS_INVALID_VALUE	if idxBase is neither CUSPARSE_INDEX_BASE_ZERO nor CUSPARSE_INDEX_BASE_ONE	
CUSPARSE	STATUS_ARCH_MISMATCH	if the D or Z variants of the function were invoked on a device that does not support double precision.	
CUSPARSE	_STATUS_EXECUTION_FAILED	function failed to launch on GPU	
CUSPARSE	E_STATUS_EXECUTION_FAILED	function failed to launch on GPU	

i. See also CUSPARSE Status Definitions on page 15.

Sparse Level 2 Function

There is one Level 2 function.

cusparse{S,D,C,Z}csrmv

```
cusparseStatus_t
cusparseScsrmv(
    cusparseHandle_t handle, cusparseOperation_t transA,
    int m, int n, float alpha,
    const cusparseMatDescr_t *descrA,
    const float *csrValA,
    const int *csrRowPtrA, const int *csrColIndA,
    const float *x, float beta,
    float *y )
```

```
cusparseStatus_t
cusparseDcsrmv(
    cusparseHandle t handle, cusparseOperation t transA,
    int m, int n, double alpha,
    const cusparseMatDescr t *descrA,
    const double *csrValA,
    const int *csrRowPtrA, const int *csrColIndA,
    const double *x, double beta,
    double *y )
cusparseStatus t
cusparseCcsrmv(
    cusparseHandle_t handle, cusparseOperation_t transA,
    int m, int n, cuComplex alpha,
    const cusparseMatDescr t *descrA,
    const cuComplex *csrValA,
    const int *csrRowPtrA, const int *csrColIndA,
    const cuComplex *x, cuComplex beta,
    cuComplex *y )
cusparseStatus_t
cusparseZcsrmv(
    cusparseHandle t handle, cusparseOperation t transA,
    int m, int n, cuDoubleComplex alpha,
    const cusparseMatDescr_t *descrA,
    const cuDoubleComplex *csrValA,
    const int *csrRowPtrA, const int *csrColIndA,
    const cuDoubleComplex *x, cuDoubleComplex beta,
    cuDoubleComplex *v )
```

Performs one of the matrix-vector operations

```
y = alpha * op(A) * x + beta * y,
where op(A) = A, op(A) = A^T, or op(A) = A^H.
```

A is an $m \times n$ matrix in CSR format, defined by the three arrays csrValA, csrRowPtrA, and csrColIndA; alpha and beta are scalars, and x and y are vectors in dense format.

Input

1	
handle	handle to a CUSPARSE context
transA	specifies op(A). If transA ==
	$\overline{\text{CUSPARSE_OPERATION_NON_TRANSPOSE}}$, $\operatorname{op}(A) = A$. This is
	the only operation supported at the moment.

Input (continued)

m	specifies the number of rows of matrix A; m must be at least zero
n	specifies the number of columns of matrix A; n must be at least zero
alpha	scalar multiplier applied to $op(A) * x$
descrA	descriptor of matrix A. The only MatrixType supported is CUSPARSE_MATRIX_TYPE_GENERAL. IndexBase constants CUSPARSE_INDEX_BASE_ZERO and CUSPARSE_INDEX_BASE_ONE are supported.
csrValA	array of nnz elements, where nnz is the number of non-zero elements and can be obtained from $csrRowPtrA(m) - csrRowPtrA(0)$
csrRowPtrA	array of m+1 index elements
csrColIndA	array of nnz column indices
x	vector of n elements if $op(A) = A$, and m elements if
	$op(A) = A^{T} or op(A) = A^{H}$
beta	scalar multiplier applied to y. If beta is zero, y does not have to be a valid input.
у	vector of m elements if $op(A) = A$, and n elements if
	$op(A) = A^{T} or op(A) = A^{H}$

Output

у	updated according to $y = alpha * op(A) * x + beta * y$
---	---

Status Returnedi

CUSPARSE_STATUS_SUCCESS

CUSPARSE_STATUS_NOT_INITIALIZED

CUSPARSE_STATUS_ALLOC_FAILED

CUSPARSE_STATUS_INVALID_VALUE

CUSPARSE_STATUS_ARCH_MISMATCH if the D or Z variants of the

> function were invoked on a device that does not support double

precision.

CUSPARSE_STATUS_EXECUTION_FAILED

function failed to launch on GPU

CUSPARSE_STATUS_INTERNAL_ERROR

CUSPARSE_STATUS_MATRIX_TYPE_NOT_SUPPORTED

i. See also CUSPARSE Status Definitions on page 15.

Sparse Level 3 Function

There is one Level 3 function.

cusparse{S,D,C,Z}csrmm

```
cusparseStatus t
cusparseScsrmm(
    cusparseHandle t handle, cusparseOperation t transA,
    int m, int n, int k, float alpha,
    const cusparseMatDescr t *descrA,
    const float *csrValA,
    const int *csrRowPtrA, const int *csrColIndA,
    const float *B, int ldb,
    float beta, float *C, int ldc )
cusparseStatus t
cusparseDcsrmm(
    cusparseHandle t handle, cusparseOperation t transA,
    int m, int n, int k, double alpha,
    const cusparseMatDescr t *descrA,
    const double *csrValA,
    const int *csrRowPtrA, const int *csrColIndA,
    const double *B, int ldb,
    double beta, double *C, int ldc )
cusparseStatus_t
cusparseCcsrmm(
    cusparseHandle t handle, cusparseOperation t transA,
    int m, int n, int k, cuComplex alpha,
    const cusparseMatDescr_t *descrA,
    const cuComplex *csrValA,
    const int *csrRowPtrA, const int *csrColIndA,
    const cuComplex *B, int ldb,
    cuComplex beta, cuComplex *C, int ldc )
```

```
cusparseStatus_t
cusparseZcsrmm(
    cusparseHandle_t handle, cusparseOperation_t transA,
    int m, int n, int k, cuDoubleComplex alpha,
    const cusparseMatDescr_t *descrA,
    const cuDoubleComplex *csrValA,
    const int *csrRowPtrA, const int *csrColIndA,
    const cuDoubleComplex *B, int ldb,
    cuDoubleComplex beta, cuDoubleComplex *C, int ldc )
```

Performs one of these matrix-matrix operations:

```
C = alpha * op(A) * B + beta * C,
where op(A) = A, op(A) = A^T, or op(A) = A^H;
```

and alpha and beta are scalars. B and C are dense matrices stored in column-major format, A is an $m \times k$ matrix in CSR format, defined by the three arrays csrValA, csrRowPtrA and csrColIndA.

Input

handle	handle to a CUSPARSE context
transA	specifies op(A). If transA == $CUSPARSE_OPERATION_NON_TRANSPOSE$, op(A) = A. This is the only operation supported at the moment.
m	number of rows of matrix A; m must be at least zero.
n	number of columns of matrices B and C; n must be at least zero.
k	number of columns of matrix A; k must be at least zero.
alpha	scalar multiplier applied to $op(A) * B$
descrA	descriptor of matrix A. The only MatrixType supported is CUSPARSE_MATRIX_TYPE_GENERAL. IndexBase constants CUSPARSE_INDEX_BASE_ZERO and CUSPARSE_INDEX_BASE_ONE are supported.
descrA csrValA	CUSPARSE_MATRIX_TYPE_GENERAL. IndexBase constants CUSPARSE_INDEX_BASE_ZERO and
	CUSPARSE_MATRIX_TYPE_GENERAL. IndexBase constants CUSPARSE_INDEX_BASE_ZERO and CUSPARSE_INDEX_BASE_ONE are supported. array of nnz elements, where nnz is the number of non-zero elements and can be obtained from
csrValA	CUSPARSE_MATRIX_TYPE_GENERAL. IndexBase constants CUSPARSE_INDEX_BASE_ZERO and CUSPARSE_INDEX_BASE_ONE are supported. array of nnz elements, where nnz is the number of non-zero elements and can be obtained from csrRowPtrA(m) - csrRowPtrA(0)
csrValA csrRowPtrA	CUSPARSE_MATRIX_TYPE_GENERAL. IndexBase constants CUSPARSE_INDEX_BASE_ZERO and CUSPARSE_INDEX_BASE_ONE are supported. array of nnz elements, where nnz is the number of non-zero elements and can be obtained from csrRowPtrA(m) - csrRowPtrA(0) array of m+1 index elements

Input (continued)

1db	leading dimension of B.
100	It must be at least $max(1, k)$ if $op(A) = A$, and at least
	$max(1, m)$ if $op(A) = A^T$ or $op(A) = A^H$.
beta	scalar multiplier applied to C. If beta is zero, C does not have to be a valid input.
С	array of dimension (1dc, n)
ldc	leading dimension of C. It must be at least $max(1, m)$ if $op(A) = A$, and at least
	$max(1, k)$ if $op(A) = A^T$ or $op(A) = A^H$.
Output	
С	updated according to alpha * op(A) * B + beta * C
Status F	Returned ⁱ
CUSPARSE	_STATUS_SUCCESS
CUSPARSE	E_STATUS_NOT_INITIALIZED
CUSPARSE_STATUS_ALLOC_FAILED	
CUCRARGE CTATUS TANAL TO MALUE	

CUSPARSE_STATUS_INVALID_VALUE

CUSPARSE_STATUS_ARCH_MISMATCH if the D or Z variants of the

function were invoked on a device that does not support double

precision.

CUSPARSE_STATUS_EXECUTION_FAILED function failed to launch on GPU

CUSPARSE_STATUS_INTERNAL_ERROR

CUSPARSE_STATUS_MATRIX_TYPE_NOT_SUPPORTED

i. See also CUSPARSE Status Definitions on page 15.

Format Conversion Functions

The format conversion functions are listed below:

- □ cusparse{S,D,C,Z}nnz on page 40
- □ cusparse{S,D,C,Z}dense2csr on page 42
- □ cusparse{S,D,C,Z}csr2dense on page 44
- □ cusparse{S,D,C,Z}dense2csc on page 45
- □ cusparse{S,D,C,Z}csc2dense on page 47
- □ cusparse{S,D,C,Z}csr2csc on page 49
- □ cusparseXcoo2csr on page 51
- □ cusparseXcsr2coo on page 52

cusparse{S,D,C,Z}nnz

```
cusparseStatus_t
cusparseSnnz(
    cusparseHandle t handle, cusparseDirection t dirA,
    int m, int n, const cusparseMatDescr t *descrA,
    const float *A, int lda, int *nnzPerVector,
    int *nnzHostPtr )
cusparseStatus_t
cusparseDnnz(
    cusparseHandle t handle, cusparseDirection t dirA,
    int m, int n, const cusparseMatDescr t *descrA,
    const double *A, int lda, int *nnzPerVector,
    int *nnzHostPtr )
cusparseStatus t
cusparseCnnz(
    cusparseHandle t handle, cusparseDirection t dirA,
    int m, int n, const cusparseMatDescr_t *descrA,
    const cuComplex *A, int lda, int *nnzPerVector,
    int *nnzHostPtr )
```

cusparseStatus_t cusparseZnnz(

cusparseHandle_t handle, cusparseDirection_t dirA,
int m, int n, const cusparseMatDescr_t *descrA,
const cuDoubleComplex *A, int lda, int *nnzPerVector,
int *nnzHostPtr)

Computes the number of non-zero elements per row or column and the total number of non-zero elements.

Input

handle	handle to a CUSPARSE context
dirA	CUSPARSE_DIRECTION_ROW OR CUSPARSE_DIRECTION_COLUMN indicates whether to count the number of non-zero elements per row or per column, respectively.
m	number of rows of the matrix A; m must be at least zero.
n	number of columns of matrix A; n must be at least zero.
descrA	descriptor of matrix A. The only MatrixType supported is CUSPARSE_MATRIX_TYPE_GENERAL. IndexBase constants CUSPARSE_INDEX_BASE_ZERO and CUSPARSE_INDEX_BASE_ONE are supported.
Α	array of dimension (lda, n)
lda	leading dimension of A
nnzPerVector	array of integers of size $m \times n$ to be filled
nnzHostPtr	pointer (in the host memory) to an integer to be filled
Output	
nnzPerVector	array of size m or n, containing number of non-zero elements per row or column, respectively
nnzHostPtr	pointer (in the host memory) to an integer containing the total number of non-zero elements

Status Returnedi

CUSPARSE_STATUS_SUCCESS

CUSPARSE_STATUS_NOT_INITIALIZED

CUSPARSE_STATUS_ALLOC_FAILED

CUSPARSE_STATUS_INVALID_VALUE

CUSPARSE_STATUS_ARCH_MISMATCH if the D or Z variants of the

function were invoked on a device that does not support double

precision.

CUSPARSE_STATUS_EXECUTION_FAILED function failed to launch on GPU

Status Returnedⁱ (continued)

CUSPARSE_STATUS_INTERNAL_ERROR

CUSPARSE_STATUS_MATRIX_TYPE_NOT_SUPPORTED

i. See also CUSPARSE Status Definitions on page 15.

cusparse{S,D,C,Z}dense2csr

```
cusparseStatus t
cusparseSdense2csr(
    cusparseHandle_t handle, int m, int n,
    const cusparseMatDescr t *descrA,
    const float *A, int lda,
    const int *nnzPerRow, float *csrValA,
    int *csrRowPtrA, int *csrColIndA )
cusparseStatus t
cusparseDdense2csr(
    cusparseHandle t handle, int m, int n,
    const cusparseMatDescr_t *descrA,
    const double *A, int lda,
    const int *nnzPerRow, double *csrValA,
    int *csrRowPtrA, int *csrColIndA )
cusparseStatus t
cusparseCdense2csr(
    cusparseHandle t handle, int m, int n,
    const cusparseMatDescr t *descrA,
    const cuComplex *A, int lda,
    const int *nnzPerRow, cuComplex *csrValA,
    int *csrRowPtrA, int *csrColIndA )
cusparseStatus t
cusparseZdense2csr(
    cusparseHandle_t handle, int m, int n,
    const cusparseMatDescr t *descrA,
    const cuDoubleComplex *A, int lda,
    const int *nnzPerRow, cuDoubleComplex *csrValA,
    int *csrRowPtrA. int *csrColIndA )
```

Converts the matrix A in dense format into a matrix in CSR format. All the parameters are pre-allocated by the user, and the arrays are filled

42 PG-05329-032_V02 NVIDIA

in based on nnzPerRow (which can be pre-computed with cusparse{S,D,C,Z}nnz()).

Input

handle	handle to a CUSPARSE context	
m	number of rows of the matrix A; m must be at least zero.	
n	number of columns of matrix A; n must be at least zero.	
descrA	descriptor of matrix A. The only MatrixType supported is CUSPARSE_MATRIX_TYPE_GENERAL. IndexBase constants CUSPARSE_INDEX_BASE_ZERO and CUSPARSE_INDEX_BASE_ONE are supported.	
Α	array of dimension (1da, n)	
lda	leading dimension of A	
nnzPerRow	array of size m containing the number of non-zero elements per row	
csrValA	array of nnz elements to be filled	
csrRowPtrA	array of m+1 index elements	
csrColIndA	array of nnz column indices, corresponding to the non-zero elements in the matrix	
Output		
csrValA	updated array of nnz elements, where nnz is the number of non-zero elements in the matrix	
csrRowPtrA	updated array of m+1 index elements	
csrColIndA	updated array of nnz column indices, corresponding to the non-zero elements in the matrix	
•		

Status Returnedⁱ

CUSPARSE_STATUS_SUCCESS

CUSPARSE_STATUS_NOT_INITIALIZED

CUSPARSE_STATUS_ALLOC_FAILED

CUSPARSE_STATUS_INVALID_VALUE

CUSPARSE_STATUS_ARCH_MISMATCH

if the **D** or **Z** variants of the

function were invoked on a device that does not support double

precision.

CUSPARSE_STATUS_EXECUTION_FAILED

function failed to launch on GPU

CUSPARSE_STATUS_INTERNAL_ERROR

CUSPARSE_STATUS_MATRIX_TYPE_NOT_SUPPORTED

i. See also CUSPARSE Status Definitions on page 15.

cusparse{S,D,C,Z}csr2dense

```
cusparseStatus_t
cusparseScsr2dense(
    cusparseHandle t handle, int m, int n,
    const cusparseMatDescr t *descrA,
    const float *csrValA,
    const int *csrRowPtrA, const int *csrColIndA,
    float *A, int lda )
cusparseStatus t
cusparseDcsr2dense(
    cusparseHandle t handle, int m, int n,
    const cusparseMatDescr t *descrA,
    const double *csrValA,
    const int *csrRowPtrA, const int *csrColIndA,
    double *A, int lda )
cusparseStatus t
cusparseCcsr2dense(
    cusparseHandle_t handle, int m, int n,
    const cusparseMatDescr t *descrA,
    const cuComplex *csrValA,
    const int *csrRowPtrA, const int *csrColIndA,
    cuComplex *A, int lda )
cusparseStatus_t
cusparseZcsr2dense(
    cusparseHandle t handle, int m, int n,
    const cusparseMatDescr_t *descrA,
    const cuDoubleComplex *csrValA,
    const int *csrRowPtrA, const int *csrColIndA,
    cuDoubleComplex *A, int lda )
```

Converts the matrix in CSR format defined by the three arrays csrValA, csrRowPtrA, and csrColIndA into a matrix A in dense format. The dense matrix A is filled in with the values of the sparse matrix and with zeros elsewhere.

Input

handle	handle to a CUSPARSE context
m	number of rows of the matrix A; m must be at least zero.
n	number of columns of matrix A; n must be at least zero.

PG-05329-032_V02 NVIDIA

Input (continued)

descrA	CUSPARSE_MATRIX_ CUSPARSE_INDEX_B	descriptor of matrix A. The only MatrixType supported is CUSPARSE_MATRIX_TYPE_GENERAL. IndexBase constants CUSPARSE_INDEX_BASE_ZERO and CUSPARSE_INDEX_BASE_ONE are supported.	
csrValA	zero elements and	array of nnz elements, where nnz is the number of non- zero elements and can be obtained from csrRowPtrA(m) - csrRowPtrA(0)	
csrRowPtrA	array of m+1 index	array of m+1 index elements	
csrColIndA	array of nnz colum	array of nnz column indices	
Α	array of dimension	array of dimension (1da, n)	
lda	leading dimension	leading dimension of A	
Output			
A updated array filled in with values defined in the sparse matrix, and zeros elsewhere			
Status Return	ed ⁱ		
CUSPARSE_STATE	JS_SUCCESS		
CUSPARSE_STATUS_NOT_INITIALIZED			
CUSPARSE_STATI	JS_INVALID_VALUE		
CUSPARSE_STAT	JS_ARCH_MISMATCH	if the D or Z variants of the function were invoked on a device that does not support double precision.	

function failed to launch on GPU

i. See also CUSPARSE Status Definitions on page 15.

CUSPARSE_STATUS_MATRIX_TYPE_NOT_SUPPORTED

cusparse{S,D,C,Z}dense2csc

CUSPARSE_STATUS_EXECUTION_FAILED

```
cusparseStatus_t
cusparseSdense2csc(
   cusparseHandle_t handle, int m, int n,
   const cusparseMatDescr_t *descrA,
   const float *A, int lda,
   const int *nnzPerCol, float *cscValA,
   int *cscRowIndA, int *cscColPtrA )
```

```
cusparseStatus_t
cusparseDdense2csc(
    cusparseHandle t handle, int m, int n,
    const cusparseMatDescr t *descrA,
    const double *A, int lda,
    const int *nnzPerCol, double *cscValA,
    int *cscRowIndA, int *cscColPtrA )
cusparseStatus t
cusparseCdense2csc(
    cusparseHandle_t handle, int m, int n,
    const cusparseMatDescr_t *descrA,
    const cuComplex *A, int lda,
    const int *nnzPerCol, cuComplex *cscValA,
    int *cscRowIndA, int *cscColPtrA )
cusparseStatus_t
cusparseZdense2csc(
    cusparseHandle_t handle, int m, int n,
    const cusparseMatDescr_t *descrA,
    const cuDoubleComplex *A, int lda,
    const int *nnzPerCol, cuDoubleComplex *cscValA,
    int *cscRowIndA, int *cscColPtrA )
```

Converts the matrix A in dense format into a matrix in CSC format. All the parameters are pre-allocated by the user, and the arrays are filled in based on nnzPerCol (which can be pre-computed with cusparse{S,D,C,Z}nnz()).

Input

•	
handle	handle to a CUSPARSE context
m	number of rows of the matrix A; m must be at least zero.
n	number of columns of matrix A; n must be at least zero.
descrA	descriptor of matrix A. The only MatrixType supported is CUSPARSE_MATRIX_TYPE_GENERAL. IndexBase constants CUSPARSE_INDEX_BASE_ZERO and CUSPARSE_INDEX_BASE_ONE are supported.
Α	array of dimension (lda, n)
lda	leading dimension of A
nnzPerCol	array of size n containing the number of non-zero elements per column
cscValA	array of nnz elements to be filled

Input (continued)

cscRowIndA		array of nnz row indices, corresponding to the non-zero elements in the matrix	
cscColPtrA	array with n+1 inde	array with n+1 index elements	
Output			
cscValA	updated array of nn of non-zero elemen	z elements, where nnz is the number ts in the matrix	
cscRowIndA		updated array of nnz row indices, corresponding to the non-zero elements in the matrix	
cscColPtrA	updated array with	updated array with n+1 index elements	
Status Return	ed ⁱ		
CUSPARSE_STATU	JS_SUCCESS		
CUSPARSE_STATU	JS_NOT_INITIALIZED		
CUSPARSE_STATU	JS_ARCH_MISMATCH	if the D or Z variants of the function were invoked on a device that does not support double precision.	
CUSPARSE STATUS EXECUTION FAILED		function failed to launch on GPU	

i. See also CUSPARSE Status Definitions on page 15.

CUSPARSE_STATUS_MATRIX_TYPE_NOT_SUPPORTED

cusparse{S,D,C,Z}csc2dense

```
cusparseStatus_t
cusparseScsc2dense(
    cusparseHandle_t handle, int m, int n,
    const cusparseMatDescr_t *descrA,
    const float *cscValA,
    const int *cscRowIndA, const int *cscColPtrA,
    float *A, int lda )

cusparseStatus_t
cusparseDcsc2dense(
    cusparseHandle_t handle, int m, int n,
    const cusparseMatDescr_t *descrA,
    const double *cscValA,
    const int *cscRowIndA, const int *cscColPtrA,
    double *A, int lda )
```

```
cusparseStatus_t
cusparseCcsc2dense(
    cusparseHandle_t handle, int m, int n,
    const cusparseMatDescr_t *descrA,
    const cuComplex *cscValA,
    const int *cscRowIndA, const int *cscColPtrA,
    cuComplex *A, int lda )

cusparseStatus_t
cusparseZcsc2dense(
    cusparseHandle_t handle, int m, int n,
    const cusparseMatDescr_t *descrA,
    const cuDoubleComplex *cscValA,
    const int *cscRowIndA, const int *cscColPtrA,
    cuDoubleComplex *A, int lda )
```

Converts the matrix in CSC format defined by the three arrays cscValA, cscColPtrA, and cscRowIndA into matrix A in dense format. The dense matrix A is filled in with the values of the sparse matrix and with zeros elsewhere.

Input

handle	handle to a CUSPARSE context	
m	number of rows of the matrix A; m must be at least zero.	
n	number of columns of matrix A; n must be at least zero.	
descrA	descriptor of matrix A. The only MatrixType supported is CUSPARSE_MATRIX_TYPE_GENERAL. IndexBase constants CUSPARSE_INDEX_BASE_ZERO and CUSPARSE_INDEX_BASE_ONE are supported.	
cscValA	array of nnz elements, where nnz is the number of non-zero elements and can be obtained from cscColPtrA(m) – cscColPtrA(0)	
cscRowIndA	array of nnz row indices	
cscColPtrA	array of n+1 index elements	
Α	array of dimension (1da, n)	
lda	leading dimension of A	

A updated array filled in with values defined in the sparse matrix and zeros elsewhere

Status Returnedi

```
CUSPARSE_STATUS_NOT_INITIALIZED

CUSPARSE_STATUS_INVALID_VALUE

CUSPARSE_STATUS_ARCH_MISMATCH if the D or Z variants of the function were invoked on a device that does not support double precision

CUSPARSE_STATUS_EXECUTION_FAILED function failed to launch on GPU

CUSPARSE_STATUS_MATRIX_TYPE_NOT_SUPPORTED
```

i. See also CUSPARSE Status Definitions on page 15.

cusparse{S,D,C,Z}csr2csc

```
cusparseStatus_t
cusparseScsr2csc(
    cusparseHandle_t handle, int m, int n,
    const float *csrVal, const int *csrRowPtr,
    const int *csrColInd, float *cscVal,
    int *cscRowInd, int *cscColPtr,
    int copyValues, int base )
cusparseStatus_t
cusparseDcsr2csc(
    cusparseHandle_t handle, int m, int n,
    const double *csrVal,
    const int *csrRowPtr,
    const int *csrColInd, double *cscVal,
    int *cscRowInd, int *cscColPtr,
    int copyValues, int base )
cusparseStatus t
cusparseCcsr2csc(
    cusparseHandle_t handle, int m, int n,
    const cuComplex *csrVal, const int *csrRowPtr,
    const int *csrColInd, cuComplex *cscVal,
    int *cscRowInd, int *cscColPtr,
    int copyValues, int base )
```

```
cusparseStatus_t
cusparseZcsr2csc(
    cusparseHandle_t handle, int m, int n,
    const cuDoubleComplex *csrVal, const int *csrRowPtr,
    const int *csrColInd, cuDoubleComplex *cscVal,
    int *cscRowInd, int *cscColPtr,
    int copyValues, int base )
```

Converts the matrix in CSR format defined with the three arrays csrVal, csrRowPtr, and csrColInd into matrix A in CSC format defined by arrays cscVal, cscRowInd, and cscColPtr. The resulting matrix can also be seen as the transpose of the original sparse matrix. This routine can also be used to convert a matrix in CSC format into a matrix in CSR format.

Input

handle	handle to a CUSPARSE context
m	number of rows of the matrix A; m must be at least zero.
n	number of columns of matrix A; n must be at least zero.
descrA	descriptor of matrix A. The only MatrixType supported is CUSPARSE_MATRIX_TYPE_GENERAL. IndexBase constants CUSPARSE_INDEX_BASE_ZERO and CUSPARSE_INDEX_BASE_ONE are supported.
csrVal	array of nnz elements, where nnz is the number of non-zero elements and can be obtained from $csrRowPtrA(m) - csrRowPtrA(0)$
csrRowPtr	array of m+1 indices
csrColInd	array of nnz column indices
cscVal	array of nnz elements, where nnz is the number of non- zero elements and can be obtained from csrColPtr(m) – csrColPtr(0)
cscRowInd	array of nnz row indices
cscColPtr	array of n+1 indices
copyValues	if zero, cscVal array is not filled
base	base index: CUSPARSE_INDEX_BASE_ZERO or CUSPARSE_INDEX_BASE_ONE
Output	
cscVal	if copyValues is non-zero, updated array
cscColPtr	updated array of n+1 index elements
cscRowInd	updated array of nnz row indices,

Status Returnedi

```
CUSPARSE_STATUS_NOT_INITIALIZED

CUSPARSE_STATUS_ALLOC_FAILED

CUSPARSE_STATUS_INVALID_VALUE

CUSPARSE_STATUS_ARCH_MISMATCH

if the D or Z variants of the function were invoked on a device that does not support double precision.

CUSPARSE_STATUS_EXECUTION_FAILED

CUSPARSE_STATUS_INTERNAL_ERROR
```

i. See also CUSPARSE Status Definitions on page 15.

cusparseXcoo2csr

```
cusparseStatus_t
cusparseXcoo2csr(
    cusparseHandle_t handle, const int *cooRowInd,
    int nnz, int m, int *csrRowPtr,
    cusparseIndexBase t idxBase )
```

Converts the array containing the uncompressed row indices (corresponding to COO format) into an array of compressed row pointers (corresponding to CSR format).

It can also be used to convert the array containing the uncompressed column indices (corresponding to COO format) into an array of column pointers (corresponding to CSC format).

Input

handle	handle to a CUSPARSE context
cooRowInd	array of row indices
nnz	number of non-zeros of the matrix in COO format; this is also the length of array cooRowInd
m	number of rows of the matrix A; m must be at least zero.
csrRowPtr	array of row pointers
idxBase	base index: CUSPARSE_INDEX_BASE_ZERO or CUSPARSE_INDEX_BASE_ONE
Output	
csrRowPtr	updated array of m+1 index elements

Status Returnedi

CUSPARSE_STATUS_SUCCESS	
CUSPARSE_STATUS_NOT_INITIALIZED	
CUSPARSE_STATUS_INVALID_VALUE	if idxBase is neither CUSPARSE_INDEX_BASE_ZERO nor CUSPARSE_INDEX_BASE_ONE
CUSPARSE_STATUS_EXECUTION_FAILED	function failed to launch on GPU

i. See also CUSPARSE Status Definitions on page 15.

cusparseXcsr2coo

```
cusparseStatus_t
cusparseXcsr2coo(
    cusparseHandle_t handle, const int *csrRowPtr,
    int nnz, int m, int *cooRowInd,
    cusparseIndexBase_t idxBase )
```

Converts the array containing the compressed row pointers (corresponding to CSR format) into an array of uncompressed row indices (corresponding to COO format).

It can also be used to convert the array containing the compressed column pointers (corresponding to CSC format) into an array of uncompressed column indices (corresponding to COO format).

Input

handle	handle to a CUSPARSE context	
csrRowPtr	array of compressed row pointers	
nnz	number of non-zeros of the matrix in COO format; this is also the length of array cooRowInd	
m	number of rows of the matrix A; m must be at least zero.	
cooRowInd	array of uncompressed row indices	
idxBase	base index: CUSPARSE_INDEX_BASE_ZERO or CUSPARSE_INDEX_BASE_ONE	
Output		
cooRowInd	updated array of nnz index elements	
Status Returned ⁱ		
CUSPARSE_STATUS_SUCCESS		

52 PG-05329-032_V02 NVIDIA

CUSPARSE_STATUS_NOT_INITIALIZED

Status Returnedⁱ (continued)

CUSPARSE_STATUS_INVALID_VALUE	if idxBase is neither CUSPARSE_INDEX_BASE_ZERO nor CUSPARSE_INDEX_BASE_ONE
CUSPARSE_STATUS_EXECUTION_FAILED	function failed to launch on GPU

i. See also CUSPARSE Status Definitions on page 15.

APPENDIX



CUSPARSE Library Example

Example A.1 on page 56 demonstrates an application of the CUSPARSE library. The example performs these actions:

- 1. Creates a sparse test matrix in COO format.
- **2.** Creates a sparse and dense vector.
- 3. Allocates GPU memory and copies the matrix and vectors into it.
- 4. Initializes the CUSPARSE library.
- **5.** Creates and sets up the matrix descriptor.
- **6.** Converts the matrix from COO to CSR format.
- 7. Exercises Level 1 routines.
- **8.** Exercises Level 2 routines.
- **9.** Exercises Level 3 routines.

Example A.1. CUSPARSE Library Example

```
#include <stdio.h>
#include <stdlib.h>
#include <cuda runtime.h>
#include "cusparse.h"
#define CLEANUP(s)
                                                      ١
do {
    printf ("%s\n", s);
    if (yHostPtr)
                            free(yHostPtr);
    if (zHostPtr)
                            free(zHostPtr);
    if (xIndHostPtr)
                            free(xIndHostPtr);
    if (xValHostPtr)
                            free(xValHostPtr);
    if (cooRowIndexHostPtr) free(cooRowIndexHostPtr);\
    if (cooColIndexHostPtr) free(cooColIndexHostPtr);\
                            free(cooValHostPtr);
    if (cooValHostPtr)
    if (y)
                            cudaFree(y);
                                                      ١
    if(z)
                            cudaFree(z);
                                                      \
    if (xInd)
                            cudaFree(xInd);
                                                      ١
    if (xVal)
                            cudaFree(xVal);
    if (csrRowPtr)
                            cudaFree(csrRowPtr);
                                                      ١
    if (cooRowIndex)
                            cudaFree(cooRowIndex);
                                                      ١
    if (cooColIndex)
                            cudaFree(cooColIndex);
    if (cooVal)
                            cudaFree(cooVal);
    if (handle)
                            cusparseDestroy(handle); \
    fflush (stdout);
} while (0)
int main(){
    cudaError t cudaStat1,cudaStat2,cudaStat3,cudaStat4,cudaStat5,cudaStat6;
    cusparseStatus_t status;
    cusparseHandle_t handle=0;
    cusparseMatDescr_t descra=0;
    int *
           cooRowIndexHostPtr=0;
    int *
             cooColIndexHostPtr=0;
    double * cooValHostPtr=0;
    int * cooRowIndex=0;
```

56 PG-05329-032_V02 NVIDIA

```
int *
        cooColIndex=0:
double * cooVal=0;
        xIndHostPtr=0;
double * xValHostPtr=0;
double * yHostPtr=0;
int *
        xInd=0;
double * xVal=0;
double * y=0;
int *
        csrRowPtr=0;
double * zHostPtr=0;
double * z=0;
int     n, nnz, nnz_vector, i, j;
printf("testing example\n");
/* create the following sparse test matrix in COO format */
/* |1.0
           2.0 3.0
      4.0
   15.0
          6.0 7.0
       8.0
              9.0 */
n=4; nnz=9;
cooRowIndexHostPtr = (int *) malloc(nnz*sizeof(cooRowIndexHostPtr[0]));
cooColIndexHostPtr = (int *) malloc(nnz*sizeof(cooColIndexHostPtr[0]));
                  = (double *)malloc(nnz*sizeof(cooValHostPtr[0]));
cooValHostPtr
if ((!cooRowIndexHostPtr) || (!cooColIndexHostPtr) || (!cooValHostPtr)){
   CLEANUP("Host malloc failed (matrix)");
   return EXIT FAILURE;
cooRowIndexHostPtr[0]=0; cooColIndexHostPtr[0]=0; cooValHostPtr[0]=1.0;
cooRowIndexHostPtr[1]=0; cooColIndexHostPtr[1]=2; cooValHostPtr[1]=2.0;
cooRowIndexHostPtr[2]=0; cooColIndexHostPtr[2]=3; cooValHostPtr[2]=3.0;
cooRowIndexHostPtr[3]=1; cooColIndexHostPtr[3]=1; cooValHostPtr[3]=4.0;
cooRowIndexHostPtr[4]=2; cooColIndexHostPtr[4]=0; cooValHostPtr[4]=5.0;
cooRowIndexHostPtr[5]=2; cooColIndexHostPtr[5]=2; cooValHostPtr[5]=6.0;
cooRowIndexHostPtr[6]=2; cooColIndexHostPtr[6]=3; cooValHostPtr[6]=7.0;
cooRowIndexHostPtr[7]=3; cooColIndexHostPtr[7]=1; cooValHostPtr[7]=8.0;
cooRowIndexHostPtr[8]=3; cooColIndexHostPtr[8]=3; cooValHostPtr[8]=9.0;
```

```
//print the matrix
printf("Input data:\n");
for (i=0; i<nnz; i++){
    printf("cooRowIndexHostPtr[%d]=%d ",i,cooRowIndexHostPtr[i]);
    printf("cooColIndexHostPtr[%d]=%d ",i,cooColIndexHostPtr[i]);
    printf("cooValHostPtr[%d]=%f \n",i,cooValHostPtr[i]);
}
/* create a sparse and dense vector */
/* xVal= [100.0 200.0 400.0] (sparse)
   xInd= [0
               1
                      3
   y = [10.0 20.0 30.0 40.0 | 50.0 60.0 70.0 80.0] (dense) */
nnz vector = 3;
xIndHostPtr = (int *) malloc(nnz vector*sizeof(xIndHostPtr[0]));
xValHostPtr = (double *)malloc(nnz vector*sizeof(xValHostPtr[0]));
yHostPtr = (double *)malloc(2*n
                                       *sizeof(yHostPtr[0]));
zHostPtr = (double *)malloc(2*(n+1) *sizeof(zHostPtr[0]));
if((!xIndHostPtr) || (!xValHostPtr) || (!yHostPtr) || (!zHostPtr)){
    CLEANUP("Host malloc failed (vectors)");
    return EXIT FAILURE;
}
yHostPtr[0] = 10.0; xIndHostPtr[0]=0; xValHostPtr[0]=100.0;
yHostPtr[1] = 20.0; xIndHostPtr[1]=1; xValHostPtr[1]=200.0;
yHostPtr[2] = 30.0;
yHostPtr[3] = 40.0; xIndHostPtr[2]=3; xValHostPtr[2]=400.0;
yHostPtr[4] = 50.0;
yHostPtr[5] = 60.0;
yHostPtr[6] = 70.0;
vHostPtr[7] = 80.0;
//print the vectors
for (j=0; j<2; j++){}
    for (i=0; i< n; i++){}
        printf("yHostPtr[%d,%d]=%f\n",i,j,yHostPtr[i+n*j]);
    }
}
for (i=0; i<nnz_vector; i++){</pre>
    printf("xIndHostPtr[%d]=%d ",i,xIndHostPtr[i]);
```

```
printf("xValHostPtr[%d]=%f\n".i.xValHostPtr[i]);
}
/* allocate GPU memory and copy the matrix and vectors into it */
cudaStat1 = cudaMalloc((void**)&cooRowIndex,nnz*sizeof(cooRowIndex[0]));
cudaStat2 = cudaMalloc((void**)&cooColIndex,nnz*sizeof(cooColIndex[0]));
cudaStat3 = cudaMalloc((void**)&cooVal,
                                            nnz*sizeof(cooVal[0]));
cudaStat4 = cudaMalloc((void**)&y,
                                            2*n*sizeof(y[0]));
cudaStat5 = cudaMalloc((void**)&xInd,nnz vector*sizeof(xInd[0]));
cudaStat6 = cudaMalloc((void**)&xVal,nnz vector*sizeof(xVal[0]));
if ((cudaStat1 != cudaSuccess) ||
    (cudaStat2 != cudaSuccess) ||
    (cudaStat3 != cudaSuccess) ||
    (cudaStat4 != cudaSuccess) ||
    (cudaStat5 != cudaSuccess) ||
    (cudaStat6 != cudaSuccess)) {
    CLEANUP("Device malloc failed");
    return EXIT FAILURE;
}
cudaStat1 = cudaMemcpy(cooRowIndex, cooRowIndexHostPtr,
                       (size t)(nnz*sizeof(cooRowIndex[0])),
                       cudaMemcpyHostToDevice);
cudaStat2 = cudaMemcpy(cooColIndex, cooColIndexHostPtr,
                       (size t)(nnz*sizeof(cooColIndex[0])),
                       cudaMemcpyHostToDevice);
cudaStat3 = cudaMemcpy(cooVal,
                                    cooValHostPtr,
                       (size t)(nnz*sizeof(cooVal[0])),
                       cudaMemcpyHostToDevice);
cudaStat4 = cudaMemcpy(y,
                                    vHostPtr,
                       (size t)(2*n*sizeof(y[0])),
                       cudaMemcpyHostToDevice);
cudaStat5 = cudaMemcpy(xInd,
                                    xIndHostPtr,
                       (size t)(nnz vector*sizeof(xInd[0])),
                       cudaMemcpyHostToDevice);
cudaStat6 = cudaMemcpy(xVal,
                                    xValHostPtr,
                       (size t)(nnz vector*sizeof(xVal[0])),
                       cudaMemcpyHostToDevice);
```

```
if ((cudaStat1 != cudaSuccess) ||
    (cudaStat2 != cudaSuccess) ||
    (cudaStat3 != cudaSuccess) ||
    (cudaStat4 != cudaSuccess) ||
    (cudaStat5 != cudaSuccess) ||
    (cudaStat6 != cudaSuccess)) {
    CLEANUP("Memcpy from Host to Device failed");
    return EXIT FAILURE;
}
/* initialize cusparse library */
status= cusparseCreate(&handle);
if (status != CUSPARSE STATUS SUCCESS) {
    CLEANUP("CUSPARSE Library initialization failed");
    return EXIT_FAILURE;
}
/* create and setup matrix descriptor */
status= cusparseCreateMatDescr(&descra);
if (status != CUSPARSE STATUS SUCCESS) {
    CLEANUP("Matrix descriptor initialization failed");
    return EXIT FAILURE;
cusparseSetMatType(descra,CUSPARSE MATRIX TYPE GENERAL);
cusparseSetMatIndexBase(descra,CUSPARSE INDEX BASE ZERO);
/* exercise conversion routines (convert matrix from COO 2 CSR format) */
cudaStat1 = cudaMalloc((void**)&csrRowPtr,(n+1)*sizeof(csrRowPtr[0]));
if (cudaStat1 != cudaSuccess) {
    CLEANUP("Device malloc failed (csrRowPtr)");
    return EXIT FAILURE;
status= cusparseXcoo2csr(handle,cooRowIndex,nnz,n,
                         csrRowPtr,CUSPARSE INDEX BASE ZERO);
if (status != CUSPARSE STATUS SUCCESS) {
    CLEANUP("Conversion from COO to CSR format failed");
```

```
return EXIT FAILURE;
//csrRowPtr = [0 3 4 7 9]
/* exercise Level 1 routines (scatter vector elements) */
status= cusparseDsctr(handle, nnz vector, xVal, xInd,
                      &y[n], CUSPARSE_INDEX_BASE_ZERO);
if (status != CUSPARSE STATUS SUCCESS) {
    CLEANUP("Scatter from sparse to dense vector failed");
    return EXIT FAILURE;
//y = [10\ 20\ 30\ 40\ |\ 100\ 200\ 70\ 400]
/* exercise Level 2 routines (csrmv) */
status= cusparseDcsrmv(handle,CUSPARSE OPERATION NON TRANSPOSE, n, n, 2.0,
                       descra, cooVal, csrRowPtr, cooColIndex, &y[0],
                       3.0, &y[n]);
if (status != CUSPARSE STATUS SUCCESS) {
    CLEANUP("Matrix-vector multiplication failed");
    return EXIT FAILURE;
}
/* print intermediate results (y) */
//y = [10\ 20\ 30\ 40\ |\ 680\ 760\ 1230\ 2240]
cudaMemcpy(yHostPtr, y, (size_t)(2*n*sizeof(y[0])), cudaMemcpyDeviceToHost);
printf("Intermediate results:\n");
for (j=0; j<2; j++){}
    for (i=0; i< n; i++){}
        printf("yHostPtr[%d,%d]=%f\n",i,j,yHostPtr[i+n*j]);
}
/* exercise Level 3 routines (csrmm) */
cudaStat1 = cudaMalloc((void**)&z, 2*(n+1)*sizeof(z[0]));
if (cudaStat1 != cudaSuccess) {
    CLEANUP("Device malloc failed (z)");
    return EXIT FAILURE;
```

```
}
cudaStat1 = cudaMemset((void *)z,0, 2*(n+1)*sizeof(z[0]));
if (cudaStat1 != cudaSuccess) {
    CLEANUP("Memset on Device failed");
    return EXIT FAILURE;
}
status= cusparseDcsrmm(handle, CUSPARSE_OPERATION_NON_TRANSPOSE, n, 2, n,
                       5.0, descra, cooVal, csrRowPtr, cooColIndex, y, n,
                       0.0, z, n+1);
if (status != CUSPARSE STATUS SUCCESS) {
    CLEANUP("Matrix-matrix multiplication failed");
    return EXIT FAILURE;
}
/* print final results (z) */
cudaStat1 = cudaMemcpy(zHostPtr, z,
                       (size t)(2*(n+1)*sizeof(z[0])),
                       cudaMemcpyDeviceToHost);
if (cudaStat1 != cudaSuccess) {
    CLEANUP("Memcpy from Device to Host failed");
    return EXIT FAILURE;
}
//z = [950 \ 400 \ 2550 \ 2600 \ 0 \ | \ 49300 \ 15200 \ 132300 \ 131200 \ 0]
printf("Final results:\n");
for (j=0; j<2; j++){
    for (i=0; i< n+1; i++){
        printf("z[%d,%d]=%f\n",i,j,zHostPtr[i+(n+1)*j]);
    }
}
/* check the results */
/* Notice that CLEANUP() contains a call to cusparseDestroy(handle) */
if ((zHostPtr[0] != 950.0)
                               П
    (zHostPtr[1] != 400.0)
    (zHostPtr[2] != 2550.0)
                               Ш
    (zHostPtr[3] != 2600.0)
                             - 11
                               Ш
    (zHostPtr[4] != 0.0)
```

```
(zHostPtr[5] != 49300.0)
        (zHostPtr[6] != 15200.0) ||
        (zHostPtr[7] != 132300.0) ||
        (zHostPtr[8] != 131200.0) ||
        (zHostPtr[9] != 0.0)
        (yHostPtr[0] != 10.0)
        (yHostPtr[1] != 20.0)
        (yHostPtr[2] != 30.0)
                                  Ш
        (yHostPtr[3] != 40.0)
                                  Ш
                                  Ш
        (yHostPtr[4] != 680.0)
        (yHostPtr[5] != 760.0)
                                  | | |
        (yHostPtr[6] != 1230.0) ||
        (yHostPtr[7] != 2240.0)){
       CLEANUP("example test FAILED");
        return EXIT FAILURE;
    }
   else{
       CLEANUP("example test PASSED");
        return EXIT_SUCCESS;
    }
}
```

APPENDIX

B

CUSPARSE Fortran Bindings

CUSPARSE is implemented using the C-based CUDA toolchain, and it thus provides a C-style API that makes interfacing to applications written in C or C++ trivial. There are also many applications implemented in Fortran that would benefit from using CUSPARSE, and therefore a CUSPARSE Fortran interface has been developed.

Unfortunately, Fortran-to-C calling conventions are not standardized and differ by platform and toolchain. In particular, differences may exist in the following areas:

- symbol names (capitalization, name decoration)
- □ argument passing (by value or reference)
- passing of pointer arguments (size of the pointer)

To provide maximum flexibility in addressing those differences, the CUSPARSE Fortran interface is provided in the form of wrapper functions, which are written in C and are located in the file cusparse_fortran.c. This file also contains a few additional wrapper functions (for cudaMalloc(), cudaMemset(), and so on) that can be used to allocate memory on the GPU.

The CUSPARSE Fortran wrapper code is provided as an example only and needs to be compiled into an application for it to call the

CUSPARSE API functions. Providing this source code allows users to make any changes necessary for a particular platform and toolchain.

The CUSPARSE Fortran wrapper code has been used to demonstrate interoperability with the compilers g95 0.91 (on 32-bit and 64-bit Linux) and g95 0.92 (on 32-bit and 64-bit Mac OS X). In order to use other compilers, users have to make any changes to the wrapper code that may be required.

The direct wrappers, intended for production code, substitute device pointers for vector and matrix arguments in all CUSPARSE functions. To use these interfaces, existing applications need to be modified slightly to allocate and deallocate data structures in GPU memory space (using CUDA_MALLOC() and CUDA_FREE()) and to copy data between GPU and CPU memory spaces (using the CUDA_MEMCPY routines). The sample wrappers provided in cusparse_fortran.c map device pointers to the OS-dependent type size_t, which is 32 bits wide on 32-bit platforms and 64 bits wide on a 64-bit platforms.

One approach to dealing with index arithmetic on device pointers in Fortran code is to use C-style macros and to use the C preprocessor to expand them. On Linux and Mac OS X, preprocessing can be done by using the option '-cpp' with g95 or gfortran. The function **GET_SHIFTED_ADDRESS()**, provided with the CUSPARSE Fortran wrappers, can also be used, as shown in Example B.1., "Fortran 77 CUSPARSE Library Example" on page 67.

Example B.1 shows Example A.1 on page 56 implemented in Fortran 77 on the host. This example should be compiled with ARCH_64 defined as 1 on a 64-bit OS system and as undefined on a 32-bit OS system. For example, on g95 or gfortran, it can be done directly on the command line using the option '-cpp -DARCH_64=1'.

Example B.1. Fortran 77 CUSPARSE Library Example

```
program cusparse fortran example
      implicit none
      integer cuda malloc
      external cuda_free
      integer cuda memcpy c2fort int
      integer cuda memcpy c2fort real
      integer cuda memcpy fort2c int
      integer cuda memcpy fort2c real
      integer cuda memset
      integer cusparse create
      external cusparse destroy
      integer cusparse_get_version
      integer cusparse create mat descr
      external cusparse destroy mat descr
      integer cusparse_set_mat_type
      integer cusparse get mat type
      integer cusparse get mat fill mode
      integer cusparse_get_mat_diag_type
      integer cusparse_set_mat_index_base
      integer cusparse get mat index base
      integer cusparse xcoo2csr
      integer cusparse dsctr
      integer cusparse dcsrmv
      integer cusparse_dcsrmm
      external get shifted address
#if ARCH 64
      integer*8 handle
      integer*8 descrA
      integer*8 cooRowIndex
      integer*8 cooColIndex
      integer*8 cooVal
      integer*8 xInd
      integer*8 xVal
      integer*8 y
```

Example B.1. Fortran 77 CUSPARSE Library Example (continued)

```
integer*8 z
      integer*8 csrRowPtr
      integer*8 ynp1
#else
      integer*4 handle
      integer*4 descrA
      integer*4 cooRowIndex
      integer*4 cooColIndex
      integer*4 cooVal
      integer*4 xInd
      integer*4 xVal
      integer*4 y
      integer*4 z
      integer*4 csrRowPtr
      integer*4 ynp1
#endif
      integer status
      integer cudaStat1,cudaStat2,cudaStat3
      integer cudaStat4,cudaStat5,cudaStat6
      integer n, nnz, nnz vector
      parameter (n=4, nnz=9, nnz_vector=3)
      integer cooRowIndexHostPtr(nnz)
      integer cooColIndexHostPtr(nnz)
      real*8 cooValHostPtr(nnz)
      integer xIndHostPtr(nnz vector)
      real*8 xValHostPtr(nnz vector)
      real*8 yHostPtr(2*n)
      real*8 zHostPtr(2*(n+1))
      integer i, j
      integer version, mtype, fmode, dtype, ibase
      real*8 dzero,dtwo,dthree,dfive
      real*8 epsilon
```

Example B.1. Fortran 77 CUSPARSE Library Example (continued)

```
write(*,*) "testing fortran example"
      predefined constants (need to be careful with them)
c
      dzero = 0.0
      dtwo = 2.0
      dthree= 3.0
      dfive = 5.0
c
      create the following sparse test matrix in COO format
      (notice one-based indexing)
C
               2.0 3.0
C
      11.0
          4.0
c
      15.0
               6.0 7.0
c
           8.0
                   9.01
c
      cooRowIndexHostPtr(1)=1
      cooColIndexHostPtr(1)=1
      cooValHostPtr(1)
      cooRowIndexHostPtr(2)=1
      cooColIndexHostPtr(2)=3
      cooValHostPtr(2)
                           =2.0
      cooRowIndexHostPtr(3)=1
      cooColIndexHostPtr(3)=4
      cooValHostPtr(3)
      cooRowIndexHostPtr(4)=2
      cooColIndexHostPtr(4)=2
      cooValHostPtr(4)
                           =4.0
      cooRowIndexHostPtr(5)=3
      cooColIndexHostPtr(5)=1
      cooValHostPtr(5)
                           =5.0
      cooRowIndexHostPtr(6)=3
      cooColIndexHostPtr(6)=3
      cooValHostPtr(6)
                           =6.0
      cooRowIndexHostPtr(7)=3
      cooColIndexHostPtr(7)=4
      cooValHostPtr(7)
                           =7.0
      cooRowIndexHostPtr(8)=4
```

Example B.1. Fortran 77 CUSPARSE Library Example (continued)

```
cooColIndexHostPtr(8)=2
      cooValHostPtr(8)
                           =8.0
     cooRowIndexHostPtr(9)=4
     cooColIndexHostPtr(9)=4
     cooValHostPtr(9)
     print the matrix
C
     write(*,*) "Input data:"
     do i=1,nnz
        write(*,*) "cooRowIndexHostPtr[",i,"]=",cooRowIndexHostPtr(i)
        write(*,*) "cooColIndexHostPtr[",i,"]=",cooColIndexHostPtr(i)
        write(*,*) "cooValHostPtr[", i,"]=",cooValHostPtr(i)
     enddo
c
     create a sparse and dense vector
     xVal= [100.0 200.0 400.0]
                                  (sparse)
C
     xInd= Γ0
                  1
                         3
C
          = [10.0 20.0 30.0 40.0 | 50.0 60.0 70.0 80.0] (dense)
C
     (notice one-based indexing)
c
     yHostPtr(1) = 10.0
     yHostPtr(2) = 20.0
     yHostPtr(3) = 30.0
     yHostPtr(4) = 40.0
     yHostPtr(5) = 50.0
     yHostPtr(6) = 60.0
     yHostPtr(7) = 70.0
     yHostPtr(8) = 80.0
     xIndHostPtr(1)=1
     xValHostPtr(1)=100.0
     xIndHostPtr(2)=2
     xValHostPtr(2)=200.0
     xIndHostPtr(3)=4
     xValHostPtr(3)=400.0
     print the vectors
C
     do j=1,2
```

Example B.1. Fortran 77 CUSPARSE Library Example (continued)

```
do i=1,n
           write(*,*) "yHostPtr[",i,",",j,"]=",yHostPtr(i+n*(j-1))
         enddo
      enddo
      do i=1,nnz vector
         write(*,*) "xIndHostPtr[",i,"]=",xIndHostPtr(i)
         write(*,*) "xValHostPtr[",i,"]=",xValHostPtr(i)
     enddo
     allocate GPU memory and copy the matrix and vectors into it
C
c
     cudaSuccess=0
     cudaMemcpyHostToDevice=1
c
     cudaStat1 = cuda malloc(cooRowIndex,nnz*4)
      cudaStat2 = cuda malloc(cooColIndex,nnz*4)
      cudaStat3 = cuda malloc(cooVal,
                                          nnz*8)
      cudaStat4 = cuda malloc(y,
                                          2*n*8)
      cudaStat5 = cuda malloc(xInd,nnz vector*4)
      cudaStat6 = cuda malloc(xVal,nnz vector*8)
     if ((cudaStat1 /= 0) .OR.
          (cudaStat2 /= 0) .OR.
     $
          (cudaStat3 /= 0) .OR.
     $
         (cudaStat4 /= 0) .OR.
         (cudaStat5 /= 0) .OR.
          (cudaStat6 /= 0)) then
         write(*,*) "Device malloc failed"
        write(*,*) "cudaStat1=",cudaStat1
        write(*,*) "cudaStat2=",cudaStat2
         write(*,*) "cudaStat3=",cudaStat3
         write(*,*) "cudaStat4=",cudaStat4
         write(*,*) "cudaStat5=",cudaStat5
         write(*,*) "cudaStat6=",cudaStat6
         stop
     endif
     cudaStat1 = cuda memcpy fort2c int(cooRowIndex,cooRowIndexHostPtr,
```

Example B.1. Fortran 77 CUSPARSE Library Example (continued)

```
nnz*4,1)
cudaStat2 = cuda memcpy fort2c int(cooColIndex,cooColIndexHostPtr,
                                    nnz*4,1)
cudaStat3 = cuda_memcpy_fort2c_real(cooVal,
                                                cooValHostPtr,
                                     nnz*8,1)
cudaStat4 = cuda memcpy fort2c real(y,
                                             yHostPtr,
                                      2*n*8,1)
cudaStat5 = cuda memcpy fort2c int(xInd,
                                                xIndHostPtr,
                                    nnz_vector*4,1)
cudaStat6 = cuda memcpy fort2c real(xVal,
                                                xValHostPtr,
                                     nnz vector*8,1)
if ((cudaStat1 /= 0) .OR.
     (cudaStat2 /= 0) .OR.
$
     (cudaStat3 /= 0) .OR.
    (cudaStat4 /= 0) .OR.
    (cudaStat5 /= 0) .OR.
     (cudaStat6 /= 0)) then
    write(*,*) "Memcpy from Host to Device failed"
    write(*,*) "cudaStat1=",cudaStat1
    write(*,*) "cudaStat2=",cudaStat2
   write(*,*) "cudaStat3=",cudaStat3
    write(*,*) "cudaStat4=",cudaStat4
    write(*,*) "cudaStat5=",cudaStat5
    write(*,*) "cudaStat6=",cudaStat6
    call cuda free(cooRowIndex)
    call cuda free(cooColIndex)
    call cuda free(cooVal)
    call cuda_free(xInd)
    call cuda free(xVal)
    call cuda free(y)
    stop
endif
 initialize cusparse library
```

72 PG-05329-032_V02 NVIDIA

c

Example B.1. Fortran 77 CUSPARSE Library Example (continued)

```
c
      CUSPARSE_STATUS_SUCCESS=0
      status = cusparse create(handle)
      if (status /= 0) then
         write(*,*) "CUSPARSE Library initialization failed"
         call cuda free(cooRowIndex)
         call cuda free(cooColIndex)
         call cuda free(cooVal)
         call cuda free(xInd)
         call cuda_free(xVal)
         call cuda free(y)
         stop
     endif
C
      get version
c
      CUSPARSE STATUS SUCCESS=0
      status = cusparse_get_version(handle, version)
      if (status /= 0) then
         write(*,*) "CUSPARSE Library initialization failed"
         call cuda free(cooRowIndex)
         call cuda free(cooColIndex)
         call cuda free(cooVal)
         call cuda_free(xInd)
         call cuda free(xVal)
         call cuda free(y)
         call cusparse_destroy(handle)
         stop
      endif
      write(*,*) "CUSPARSE Library version",version
c
      create and setup the matrix descriptor
c
     CUSPARSE_STATUS_SUCCESS=0
     CUSPARSE_MATRIX_TYPE_GENERAL=0
c
     CUSPARSE INDEX BASE ONE=1
c
      status= cusparse create mat descr(descrA)
      if (status /= 0) then
```

Example B.1. Fortran 77 CUSPARSE Library Example (continued)

```
write(*,*) "Creating matrix descriptor failed"
         call cuda free(cooRowIndex)
         call cuda free(cooColIndex)
         call cuda free(cooVal)
         call cuda free(xInd)
         call cuda free(xVal)
         call cuda free(y)
         call cusparse destroy(handle)
         stop
      endif
      status = cusparse set mat type(descrA,0)
      status = cusparse set mat index base(descrA,1)
      print the matrix descriptor
C
      mtvpe = cusparse get mat type(descrA)
      fmode = cusparse_get_mat_fill_mode(descrA)
      dtype = cusparse get mat diag type(descrA)
      ibase = cusparse get mat index base(descrA)
      write (*,*) "matrix descriptor:"
      write (*,*) "t=",mtype,"m=",fmode,"d=",dtype,"b=",ibase
      exercise conversion routines: convert matrix from COO 2 CSR format
C
c
      cudaSuccess=0
     CUSPARSE STATUS SUCCESS=0
c
c
      CUSPARSE_INDEX_BASE_ONE=1
      cudaStat1 = cuda malloc(csrRowPtr,(n+1)*4)
      if (cudaStat1 /= 0) then
         call cuda free(cooRowIndex)
         call cuda free(cooColIndex)
         call cuda free(cooVal)
         call cuda free(xInd)
         call cuda free(xVal)
         call cuda free(y)
         call cusparse destroy mat descr(descrA)
         call cusparse destroy(handle)
```

Example B.1. Fortran 77 CUSPARSE Library Example (continued)

```
write(*,*) "Device malloc failed (csrRowPtr)"
         stop
      endif
      status= cusparse_xcoo2csr(handle,cooRowIndex,nnz,n,
                                csrRowPtr,1)
      if (status /= 0) then
         call cuda free(cooRowIndex)
         call cuda free(cooColIndex)
         call cuda_free(cooVal)
         call cuda free(xInd)
         call cuda free(xVal)
         call cuda free(y)
         call cuda free(csrRowPtr)
         call cusparse destroy mat descr(descrA)
         call cusparse_destroy(handle)
         write(*,*) "Conversion from COO to CSR format failed"
         stop
      endif
      csrRowPtr = [0 3 4 7 9]
c
c
      exercise Level 1 routines (scatter vector elements)
c
      CUSPARSE STATUS SUCCESS=0
     CUSPARSE INDEX BASE ONE=1
c
      call get_shifted_address(y,n*8,ynp1)
      status= cusparse_dsctr(handle, nnz_vector, xVal, xInd,
                             ynp1, 1)
      if (status /= 0) then
         call cuda_free(cooRowIndex)
         call cuda free(cooColIndex)
         call cuda free(cooVal)
         call cuda_free(xInd)
         call cuda free(xVal)
         call cuda free(y)
         call cuda free(csrRowPtr)
```

Example B.1. Fortran 77 CUSPARSE Library Example (continued)

```
call cusparse_destroy_mat_descr(descrA)
         call cusparse destroy(handle)
         write(*,*) "Scatter from sparse to dense vector failed"
         stop
      endif
      y = [10 \ 20 \ 30 \ 40 \ | \ 100 \ 200 \ 70 \ 400]
c
      exercise Level 2 routines (csrmv)
C
C
      CUSPARSE_STATUS_SUCCESS=0
c
      CUSPARSE OPERATION NON TRANSPOSE=0
      status= cusparse dcsrmv(handle, 0, n, n, dtwo,
                              descrA, cooVal, csrRowPtr, cooColIndex,
                              y, dthree, ynp1)
      if (status /= 0) then
         call cuda_free(cooRowIndex)
         call cuda free(cooColIndex)
         call cuda free(cooVal)
         call cuda free(xInd)
         call cuda free(xVal)
         call cuda free(y)
         call cuda_free(csrRowPtr)
         call cusparse destroy mat descr(descrA)
         call cusparse destroy(handle)
         write(*,*) "Matrix-vector multiplication failed"
         stop
      endif
c
      print intermediate results (y)
c
      y = [10 \ 20 \ 30 \ 40 \ | \ 680 \ 760 \ 1230 \ 2240]
      cudaSuccess=0
C
      cudaMemcpyDeviceToHost=2
c
      cudaStat1 = cuda memcpy c2fort real(yHostPtr, y, 2*n*8, 2)
      if (cudaStat1 /= 0) then
         call cuda free(cooRowIndex)
```

Example B.1. Fortran 77 CUSPARSE Library Example (continued)

```
call cuda_free(cooColIndex)
         call cuda free(cooVal)
         call cuda free(xInd)
         call cuda free(xVal)
         call cuda free(y)
         call cuda free(csrRowPtr)
         call cusparse destroy mat descr(descrA)
         call cusparse destroy(handle)
         write(*,*) "Memcpy from Device to Host failed"
      endif
      write(*,*) "Intermediate results:"
      do j=1,2
         do i=1,n
             write(*,*) "yHostPtr[",i,",",j,"]=",yHostPtr(i+n*(j-1))
         enddo
      enddo
      exercise Level 3 routines (csrmm)
c
      cudaSuccess=0
C
     CUSPARSE_STATUS_SUCCESS=0
c
c
      CUSPARSE OPERATION NON TRANSPOSE=0
      cudaStat1 = cuda malloc(z, 2*(n+1)*8)
      if (cudaStat1 /= 0) then
         call cuda free(cooRowIndex)
         call cuda free(cooColIndex)
         call cuda_free(cooVal)
         call cuda_free(xInd)
         call cuda free(xVal)
         call cuda free(y)
         call cuda free(csrRowPtr)
         call cusparse destroy mat descr(descrA)
         call cusparse destroy(handle)
         write(*,*) "Device malloc failed (z)"
```

Example B.1. Fortran 77 CUSPARSE Library Example (continued)

```
stop
 endif
 cudaStat1 = cuda memset(z, 0, 2*(n+1)*8)
 if (cudaStat1 /= 0) then
    call cuda free(cooRowIndex)
    call cuda free(cooColIndex)
    call cuda free(cooVal)
    call cuda free(xInd)
    call cuda_free(xVal)
    call cuda free(y)
    call cuda free(z)
    call cuda_free(csrRowPtr)
    call cusparse destroy mat descr(descrA)
    call cusparse destroy(handle)
    write(*,*) "Memset on Device failed"
    stop
 endif
 status= cusparse_dcsrmm(handle, 0, n, 2, n, dfive,
$
                         descrA, cooVal, csrRowPtr, cooColIndex,
                         y, n, dzero, z, n+1)
 if (status /= 0) then
    call cuda free(cooRowIndex)
    call cuda free(cooColIndex)
    call cuda_free(cooVal)
    call cuda free(xInd)
    call cuda free(xVal)
    call cuda free(y)
    call cuda_free(z)
    call cuda free(csrRowPtr)
    call cusparse_destroy_mat_descr(descrA)
    call cusparse_destroy(handle)
    write(*,*) "Matrix-matrix multiplication failed"
    stop
 endif
```

Example B.1. Fortran 77 CUSPARSE Library Example (continued)

```
c
     print final results (z)
c
     cudaSuccess=0
     cudaMemcpyDeviceToHost=2
c
     cudaStat1 = cuda memcpy c2fort real(zHostPtr, z, 2*(n+1)*8, 2)
     if (cudaStat1 /= 0) then
        call cuda free(cooRowIndex)
        call cuda free(cooColIndex)
        call cuda_free(cooVal)
        call cuda free(xInd)
        call cuda free(xVal)
        call cuda_free(y)
        call cuda free(z)
        call cuda free(csrRowPtr)
        call cusparse_destroy_mat_descr(descrA)
        call cusparse_destroy(handle)
        write(*,*) "Memcpy from Device to Host failed"
        stop
     endif
     z = [950\ 400\ 2550\ 2600\ 0\ |\ 49300\ 15200\ 132300\ 131200\ 0]
c
     write(*,*) "Final results:"
     do j=1,2
        do i=1,n+1
           write(*,*) "z[",i,",",j,"]=",zHostPtr(i+(n+1)*(j-1))
        enddo
     enddo
c
     check the results
     epsilon = 0.00000000000001
     .OR.
         (DABS(zHostPtr(2) - 400.0)
                                     .GT. epsilon)
                                                    .OR.
         (DABS(zHostPtr(3) - 2550.0)
                                                    .OR.
    $
                                     .GT. epsilon)
    $
         (DABS(zHostPtr(4) - 2600.0)
                                                    .OR.
                                     .GT. epsilon)
         (DABS(zHostPtr(5) - 0.0)
                                      .GT. epsilon)
                                                    .OR.
```

Example B.1. Fortran 77 CUSPARSE Library Example (continued)

```
$
          (DABS(zHostPtr(6) - 49300.0) .GT. epsilon)
                                                       OR.
     $
          (DABS(zHostPtr(7) - 15200.0) .GT. epsilon)
                                                       .OR.
    $
          (DABS(zHostPtr(8) - 132300.0).GT. epsilon)
                                                       .OR.
     $
          (DABS(zHostPtr(9) - 131200.0).GT. epsilon)
                                                       .OR.
    $
          (DABS(zHostPtr(10) - 0.0)
                                        .GT. epsilon)
                                                       .OR.
     $
          (DABS(yHostPtr(1) - 10.0)
                                        .GT. epsilon)
                                                       .OR.
          (DABS(yHostPtr(2) - 20.0)
                                        .GT. epsilon)
                                                       .OR.
    $
          (DABS(yHostPtr(3) - 30.0)
                                        .GT. epsilon)
                                                       .OR.
          (DABS(yHostPtr(4) - 40.0)
                                        .GT. epsilon)
                                                       .OR.
    $
          (DABS(yHostPtr(5) - 680.0)
                                        .GT. epsilon)
                                                       .OR.
    $
          (DABS(yHostPtr(6) - 760.0)
                                        .GT. epsilon)
                                                       .OR.
          (DABS(yHostPtr(7) - 1230.0) .GT. epsilon)
                                                       .OR.
          (DABS(yHostPtr(8) - 2240.0) .GT. epsilon)) then
          write(*,*) "fortran example test FAILED"
       else
          write(*,*) "fortran example test PASSED"
       endif
       deallocate GPU memory and exit
c
       call cuda free(cooRowIndex)
       call cuda_free(cooColIndex)
       call cuda free(cooVal)
       call cuda free(xInd)
       call cuda_free(xVal)
       call cuda free(y)
       call cuda free(z)
       call cuda free(csrRowPtr)
       call cusparse_destroy_mat_descr(descrA)
       call cusparse destroy(handle)
       stop
       end
```