ARP (Address Resolution Protocol) 和NTP (Network Time Protocol) 都属于广播通信。

ARP是局域网中的地址解析协议,利用这个协议,可以找出IP地址到MAC地址的映射关系。当主机A准备与主机B通信时,如果只知道主机B的IP地址,则主机A向整个全网发送一个ARP请求,询问IP地址为XXXX的主机,如果主机B收到就会产生回应。

NTP是网络时间协议。在支持广播的局域网中设置NTP协议,可以使NTP服务器每隔一个 固定的时间间隔,就向全网发送时间信息,客户端在收到时间信息后进行更新处理。

原理解析:

要进行广播通信,首先要理解广播地址。在IP地址中,如果最后一个数字是255,则一定是一个广播地址。

- 网络广播地址: 网络广播地址在没有进行子网划分的网络内广播,由于当强的网络均涉及子网划分,故此种地址很少存在
- 受限广播地址:以255.255.255.255组成的广播地址,在当前路由器均不转发此类 广播
- 子网广播地址:子网广播地址是一种常用的广播方式,它是指在一个具体的子网内进行广播,比如192.168是网络ID,那么192.168.1.255就是子网192.168.1的广播
- 全部子网广播地址:是指所有子网络的广播,以上一个为例,全部子网广播地址是 192.168.255.255

广播要采用UDP的方式,具体流程如下:

- 1. 创建UDP套接字
- 2. 设置套接字属性为SO BROADCAST,设置为广播地址
- 3. 设置广播地址为INADDR BROADCAST,同时也要指定发送端口
- 4. 进行数据收发操作

例子:



//bserver.c

#include <sys/types.h>

#include <stdio.h>

#include <sys/socket.h>

#include <stdlib.h>

#include <string.h>

#include <netdb.h>

#include <errno.h>

```
#define BUFFSIZE 200
#define PORT 5050
int main(int argc, char **argv)
int serversocket;
struct sockaddr in serveraddress, clientaddress;
int so_broadcast=1;
if((serversocket=socket(AF INET,SOCK DGRAM,0))<0){</pre>
perror("socket");
return 0;
}
if(setsockopt(serversocket,SOL SOCKET,SO BROADCAST,&so broadcast,sizeof(so broadcast))
<0){
perror("setsockopt");
return 0;
}
serveraddress.sin family=AF INET;
serveraddress.sin port=htons(INADDR ANY);
serveraddress.sin addr.s addr=htonl(INADDR BROADCAST);
if (bind(serversocket, (struct sockaddr*) &serveraddress, sizeof(struct sockaddr)) < 0) {</pre>
perror("bind");
return 0;
}
clientaddress.sin family=AF INET;
clientaddress.sin port=htons(PORT);
clientaddress.sin addr.s addr=htonl(INADDR BROADCAST);
while(1){
char buf[BUFFSIZE];
printf("please input your word:");
scanf("%s",buf);
if (sendto (serversocket, buf, strlen (buf), 0,
(struct sockaddr*) &clientaddress, sizeof(clientaddress)) < 0) {</pre>
perror("sendto");
return 0;
else
```

```
printf("send msg: %s\n",buf);
}
return 0;
//bclient.c
#include <sys/types.h>
#include <stdio.h>
#include <sys/socket.h>
#include <stdlib.h>
#include <string.h>
#include <netdb.h>
#include <errno.h>
int main(int argc, char **argv)
int clientsocket;
struct sockaddr_in serveraddress, clientaddress;
clientsocket=socket(AF INET,SOCK_DGRAM,0);
serveraddress.sin_family=AF_INET;
serveraddress.sin port=htons(5050);
serveraddress.sin_addr.s_addr=htonl(INADDR ANY);
int opt=1;
if(setsockopt(clientsocket, SOL SOCKET, SO REUSEADDR, &opt, sizeof(opt)) < 0) {</pre>
perror("setsockopt");
return 0;
}
if(bind(clientsocket,(struct sockaddr*)&serveraddress,sizeof(struct sockaddr))!=0){
perror("bind");
return 0;
}
char buf[200];
while(1){
memset (buf, 0,200);
int size=0;
size=recvfrom(clientsocket,buf,200,0,
(struct sockaddr*) &serveraddress, sizeof (serveraddress));
```

```
buf[size]='\0';
    printf("IP:%s msg:%s\n",inet_ntoa(clientaddress.sin_addr),buf);

    if(strcmp(buf,"quit")==0) {
        printf("system quit!\n");
        close(clientsocket);
        return 0;
    }
}

return 0;
}
```

(我在测试的时候只能发送不收接收,折磨了我半天,后来才想到是Linux防火墙的问题。。)