Lecture.10.Virtual.Memory.txt

- Virtual Memory
 - Separation of user logical memory from physical memory
 - Logical address space can therefore be much larger than physical address space
 - The memory management unit (MMU) is used to correlate logical and physical addresses
 - Allows address spaces to be shared by several processes
 - Virtual address space is the logical view of how processes are stored in memory
 - If there is not enough space in memory, paging or segmentation is used
 - Segments are considered as huge pages
 - Virtual memory can be implemented via:
 - Demand paging
 - Demand segmentation
- Virtual Memory That Is Larger Than Physical Memory
 - i.e. Diagram of Virtual Memory

page 0
 page 1
 page 2
*
*
*
ĺ
İ İ
j page v j
ii

- Data moves from virtual memory to physical memory to backing store
 - It can also move from backing store to physical memory
 - This is mostly a concept
- Virtual Address Space

Memory

- Logical address space for stack to start at max and grow "down", while heap grows "up"
 - Heap is dynamically allocated memory
 - The heap and stack grow toward each other
- Enables sparse address spaces with holes left for growth,


dynamically linked libraries, etc.

- System libraries shared via mapping into virtual address space
 - This virtual address space is used for all processes that require the system library
- i.e. Diagram

Max |-----|
| stack |
|--||---|
| || |
| \/ |
| /\ |
| ---||--|
heap
data

code

- Shared Library Using VM
 - i.e. Diagram




- $\mbox{-}$ In the diagram above, both processes, P1 and P2, share data
 - They share data on the same virtual address space
- Demand Paging

- The entire process is swapping pages in and out
 - Could bring entire process into memory at load time
 - Or bring a page into memory only when it is needed
- If page is needed, reference to it
 - An invalid reference -> Abort
 - If it is not-in-memory -> Bring it to memory
- Page Table When Some Pages Are Not In Main Memory
 - i.e. Diagram of Logical Memory

0	Α	
1	B	
2	C	
_		
3	ן ט	
4	—— E	
5	F	
6	G	
7	Н	
	Logi	cal
	Memo	ry
		-

- i.e. Diagram of Page Table



Page Table

- i.e. Diagram of Physical Memory

```
0 |
```

		l l				
	1					
	2	 				
:	3	 				
	4	 A				
!	5	 				
(6	 C				
	7	 				
;	8	 				
9	9	 F				
1	0	 				
1	1	 				
1	2					
1	3					
1	4	 				
1.	5	 				
- i.e	ľ	Physica Memory Diagran	f Ba	ckin	g Sto	re
		 	 	j	 	
		 	 A 		 B 	
		 C 	 D 		 E 	
 		 F	 G	 	 H	

į				į
į	jj	jj	ii	į
j				-i

- In the diagrams above, Page 0 (that holds 'A') in the page table is mapped to frame 4, and the valid-invalid bit is set to 'v'
- This process is located at address 4, inside physical memory
 In the diagrams above, Page 1 (that holds 'B') in the page table is not mapped to any frame
 - Thus, 'B' is not inside physical memory
 - Instead, 'B' is inside the backing store
 - If you wanted to run process 'B', it is the job of the operating system to copy 'B' from the backing store into physical memory
- With each page table entry a valid-invalid bit is associated
 - Indicates if the page has a corresponding frame in physical memory
- During MMU address translation, if valid-invalid bit in page table entry is invalid -> page fault exception

- Demand Paging

- Get the bad virtual address that caused the page fault
- Allocate a physical page
 - Find the page in the backing store
- Call the file system to copy the page from the disk to the physical page in memory
 - Copy page from backing store into physical memory
- Update the page table
- Re-execute the instruction
- Steps In Handling A Page Fault
 - Assume that process 'M' is being loaded, and it is not already in physical memory
 - The steps are:
 - 1. Reference
 - Try to look for 'M' in page table
 - 2. Trap
 - Since 'M' is not in the page table, a trap is created by the operating system (OS)
 - 3. Page is on backing store
 - The OS locates 'M' in the backing store
 - Backing store is the hard drive (HDD)
 - 4. Bring in missing page
 - 'M' is copied into physical memory
 - 5. Reset page table
 - The page table is updated with new information

- New information is 'M' and its location
- 6. Restart instruction
 - When the instruction is restarted, it will be properly executed this time
- Note: It is the job of the operating system to handle page faults
- Free Frame List
 - When a page fault occurs, the operating system must bring the desired page from secondary storage into main memory
 - Most operating systems maintain a free frame list
 - This is a pool of free frames for satisfying such requests
 - The list contains all free frames in physical memory
 - New data from the backing store is copied into these free frames
 - Then, the page table is updated with information that contains the translation of logical to physical address
 - Zero-fill-on-demand
 - The content of the frames zeroed-out before being allocated
 - When a system starts up, all available memory is placed on the free frame list
- Performance Of Demand Paging
 - Moving page(s) into main memory takes time
 - There are 3 major activities:
 - 1. Service the interrupt
 - 2. Read the page
 - 3. Restart the process
 - Page fault rate: 0 <= p <= 1</pre>
 - If the page fault rate is very low, then the system will run quickly
 - A high page fault rate slows down the system
 - Effective Access Time (EAT)
 - EAT = (1 p) * memory access +
 - p * (page fault overhead + swap page out
 - + swap page in)
 - If `p` is 1, then `1 -p` is cancelled out
 - Only the second part needs to be calculated
 - This is the page fault overhead of swap page out and swap page in
 - If `p` is 0, then there is no fault
 - EAT = Memory access time
 - Demand Paging Example
 - For memory access time = 200ns, and average page fault service time is 8ms
 - EAT = (1 p) * 200ns + p * 8000000ns
 - For p = 0, E = 200ns
 - For p = 1 / 10000, EAT = 8us --> Slowdown by a factor of 40
 - This demonstrates why it is important to not have a page fault, because it dramatically slows down the system

- Even a small value of `p` can drastically slow down the system
- Basic Page Replacement
 - When a page fault occurs, we need to:
 - Find the location of the desired page on disk
 - Then, find a free frame
 - If there is a free frame, use it
 - If there is no free frame, use a page replacement algorithm to select a victim frame and write victim frame to disk
 - Bring the desired page into the (newly) free frame and update the page and frame tables
 - Restart the instruction that caused the trap
- Page Replacement
 - Assuming that the physical memory is full, the page replacement steps are:
 - 1. Swap out victim page
 - This is the page that will be rewritten
 - 2. Change to invalid
 - The old page is no longer in physical memory, so its valid-invalid bit is set to 'i'
 - 3. Swap desired page in
 - 4. Reset page table for new page
- Page & Frame Replacement Algorithms
 - FIFO
 - First in, first out
 - OPT
 - Optimal algorithm
 - This is not possible to implement in reality, but good to have for reference
 - Other algorithms are compared to the optimal algorithm
 - LRU
 - Least recently used
 - LFU
 - Least frequently used
 - MFU
 - Most frequently used
 - Depending on the scenario, some algorithms work better than others
 - Page replacement algorithms move pages from secondary storage into main memory
- First In First Out (FIFO) Algorithm
 - Reference string: 7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1
 - These numbers represent data
 - i.e. Processes
 - 3 frames

- 3 pages can be in memory at a time per process
- In the FIFO algorithm, the first frame is used for the replacement
 - This algorithm is very simple to implement, but it is not effective
- i.e. FIFO Diagram

Reference string (part 1)

	7	0	1			3						3		1	•	•
-																١
į	7	7	•	2		2	2	4	4	4	0			0	0	İ
-																ļ
		0	0	0		3	3	3	2	2	2			1	1	l
1-																I
į	ĺ		1	1	İ	1		0			3			3	2	
-																l
ĺ	*	*					*								*	
-																l
H	it			-							•					

Reference string (part 2)

	•	•		
j j	İ	7	7	
j j	İ	1	0	
j j	İ	2	2	
	 			 *
 Hit				

- 15 page faults in total
 - Count the asterisks in the diagram above
- Adding more frames can cause more page faults
 - This is known as Belady's Anomaly
- FIF0: Belady's Anomaly
 - Belady's anomaly states that adding more frames can cause more page faults
 - Thus, a bad replacement choice increases the page-fault rate and slows down process execution
 - i.e. Table of Page Faults

 Number Of Frames	Number Of Page Faults
1	12
j 2	12
3	9
4	10

5	5	
6	5	I
7	5	I
		ı

- The reference string for this table is:
 - 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
- According to the table above, increasing the number of frames from 3 to 4 also increases the number of page faults from 9 to 10
- Optimal Algorithm
 - Replace page that will not be used for longest period of time
 - How do you know this?
 - We don't, because we can't see the future
 - Used for measuring how well your algorithm performs
 - This algorithm yields the best possible result
 - No algorithm can be better than the optimal algorithm
 - i.e. Optimal Algorithm Diagram

Reference string (part 1)

					, i		-									
	7	0	1	2	0	3	0	4	2	3	0	3	2	1	2	
																l
	7	7	7	2	İ	2		2			2			2		İ
																l
ĺ		0	0	0		0		4	İ	İ	0			0		İ
																l
			1	1		3		3			3			1		İ
																l
	*	*	*	*		*		*	İ	İ	*			*		İ
																l
	Hit	-	•	•									-			•

Reference string (part 2)

1101	-1 -11		rı TIIÇ	y (pu
0	1	7	0	1
ĺ		7		İ
		0		
		1		
		*		
Hit				

- Only 9 page faults
 - This is the best possible outcome
- Least Recently Used (LRU) Algorithm
 - Replace page that has not been used in the most amount of time
 - Associate time of last use with each page
 - The idea behind LRU is that if a page has not been recently

used, then it won't be used again in the future

i.e. LRU Diagram

Reference string (part 1)

			:	י יוי ע		-,									
7	0	1	2	0	3	0	4	2	3	0	3	2	1	2	
															ĺ
7	7	j 7	2	j	2		4	4	4	0		İ	1	į į	ĺ
	0	j 0	j 0	ĺ	0		0	0	3	3		ĺ	3	ĺ	ĺ
İ	ĺ	1	1	j	3		3	2	2	2		İ	2	į į	ĺ
*	*	 *	 *	ĺ	*		*	*	*	*		ĺ	*	ĺ	ĺ
Hit	•					•									

Reference string (part 2)

The reflect of the ting (par											
0	1	7	0	1							
1		1		į į							
0		0		į į							
2		7		ĺĺ							
*		*		ĺĺ							
Hi+											

Hit

- 12 page faults
 - Better than FIFO, but worse than OPT
 - Generally good algorithm, and frequently used

- LRU Algorithm

- There are two ways to implement the LRU algorithm
 - Counter Implementation
 - Every page entry has a counter
 - Every time a page is referenced, copy the clock into the counter
 - In this way, we always have the "time" of the last reference to each page.
 - When a page needs to be changed, look at the counters to find smallest value
 - Stack Implementation
 - Keep a stack of page numbers in a double link form
 - Whenever a page is referenced, it is removed from the stack and put on the top
- Stack Implementation
 - i.e. Stack Diagram
 - 4 7 0 7 1 0 1 2 1 2 7 1 2

2	7
1	j 2 j
j ø j	1
j 7 j	j 0 j
4	j 4 j
stack	stack
before	after
'a'	'b'
_	_

- The least recently used page is always at the bottom
- LRU and OPT are cases of stack algorithms that don't have Belady's Anomaly
- Approximaion Of LRU: Clock Algorithm
 - LRU needs special hardware
 - Reference bit algorithm
 - With each page associate a bit, initially = 0
 - When page is referenced bit set to 1
 - 8 bit shift registers contain the history of page use for the last eight time periods
 - If the shift register contains 00000000, for example, then the page has not been used for eight time periods
 - Second chance algorithm
 - If page to be replaced has reference bit = 0
 - Then, replace it
 - If reference bit = 1, then set reference bit to 0, leave page in memory, replace next page, subject to same rules
- Second Chance (Clock) Page Replacement Algorithm
 - Looks like a circular queue of pages
 - If next victim's reference bit is 1, then it is set to 0
 - If next victim's reference bit is 0, it is replaced
- Counting Algorithms
 - Other page replacement algorithms require a counter
 - Keep a counter of the number of references that have been made to each page
 - Least frequently used (LFU) algorithm
 - Replaces page with smallest count
 - The rationale is that if a page has not been used for an extended period of time, it may not be used again
 - Thus, it is better to replace it
 - Most frequently used (MFU) algorithm
 - Based on the argument that the page with the smallest count

was probably just brought in, and has yet to be used

- Thus, it will be used again, so it is better to keep it in memory
- Page Buffering Algorithms
 - Algorithms can be improved by always keeping a pool of free frames
 - Read page into free frame and select victim to evict and add to free pool
 - Possibly, keep list of modified pages. Whenever the paging device is idle, a modified page is selected and is written to secondary storage
 - Possibly, keep free frame contents intact and note what is in them
 - If referenced again before reused, no need to load contents again from disk
 - This is used to improve performance, and is heavily used in operating systems
 - All of these algorithms have OS guessing about future page access
 - There is no guarantee about future page access, only probability
- Thrashing & Working Set Model
 - Thrashing occurs when a process spends more time paging than executing
 - The memory becomes as slow as the hard drive (HDD)
 - Trashing may significantly decrease performance, and waste time moving data between secondary and primary storage
 - One way to prevent trashing is through the use of a working set model
 - Working set model
 - Basis: Locality
 - Working set window (WSW)
 - A time frame
 - If the frame is inside the WSW, then it is not removed
 Even if the frame is marked as a victim
 - Working set (WS)
 - A set of pages referenced in the time frame
 - Working set size (WSS)
 - Number of pages in WS
 - Page replacement can be determined by working set model
 - A working set model can prevent thrashing
- Trashing & Working Set
 - How does the system detect thrashing?
 - The system can detect thrashing by evaluating the level of CPU utilization compared with the level of multiprogramming
 - If the CPU is extremely busy, then something is not

correct, because a few threads should not take up all the processing time

- This implies that there is thrashing
- Is it possible for a process to have two working sets, one for representing data and another representing code?
 Yes
 - In fact, many processors provide 2 TLBs for this very reason
 - As an example, the code being accessed by a process may retain the same working set (WS) for a long time
 - However, the data the code accesses may change, thus reflecting a change in the WS for the data accesses

- End

- Operating systems are among the most complex pieces of software ever developed!