ttyname(3) — Linux manual page

NAME | SYNOPSIS | DESCRIPTION | RETURN VALUE | ERRORS | ATTRIBUTES | CONFORMING TO | NOTES | SEE ALSO | COLOPHON

Search online pages

TTYNAME(3)

Linux Programmer's Manual

TTYNAME(3)

NAME top

ttyname, ttyname_r - return name of a terminal

SYNOPSIS

top

```
#include <unistd.h>
char *ttyname(int fd);
int ttyname r(int fd, char *buf, size t buflen);
```

DESCRIPTION top

The function **ttyname**() returns a pointer to the null-terminated pathname of the terminal device that is open on the file descriptor fd, or NULL on error (for example, if fd is not connected to a terminal). The return value may point to static data, possibly overwritten by the next call. The function **ttyname_r**() stores this pathname in the buffer buf of length buflen.

RETURN VALUE top

The function **ttyname**() returns a pointer to a pathname on success. On error, NULL is returned, and *errno* is set to indicate the error. The function **ttyname_r**() returns 0 on success, and an error number upon error.

ERRORS top

EBADF Bad file descriptor.

ENODEV fd refers to a slave pseudoterminal device but the corresponding pathname could not be found (see NOTES).

ENOTTY fd does not refer to a terminal device.

ERANGE (ttyname_r()) buflen was too small to allow storing the pathname.

ATTRIBUTES top

For an explanation of the terms used in this section, see attributes(7).

Interface	Attribute	Value
ttyname()	Thread safety	MT-Unsafe race:ttyname
ttyname_r()	Thread safety	MT-Safe

CONFORMING TO

POSIX.1-2001, POSIX.1-2008, 4.2BSD.

NOTES top

A process that keeps a file descriptor that refers to a pts(4) device open when switching to another mount namespace that uses a different /dev/ptmx instance may still accidentally find that a device path of the same name for that file descriptor exists. However, this device path refers to a different device and thus can't be used to access the device that the file descriptor refers to. Calling ttyname() or ttyname_r() on the file descriptor in the new mount namespace will cause these functions to return NULL and set errno to ENODEV.

SEE ALSO top

tty(1), fstat(2), ctermid(3), isatty(3), pts(4)

COLOPHON top

This page is part of release 5.13 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

Linux 2021-03-22 TTYNAME(3)

Pages that refer to this page: ctermid(3), getttyent(3), getutent(3), isatty(3), openpty(3), ptsname(3), ttyslot(3)

Copyright and license for this manual page

HTML rendering created 2021-08-27 by Michael Kerrisk, author of *The Linux Programming Interface*, maintainer of the Linux *man-pages* project.

For details of in-depth Linux/UNIX system programming training courses that I teach, look here.

Hosting by jambit GmbH.

