

PERSONAL PROTECTIVE EQUIPMENT

Job Performance Requirements

NFPA 1010

6.1.2

6.3.1*

6.3.2*

Note: All objectives in this section are testable.

Performance Objective

Subject: PPE

Task: Donning

Note: All attachments (Buttons, Clips, Snaps, Velcro, Zippers) shall be fastened.

Procedure:

1. Don the protective hood, keeping it on top of head.
2. With pants in place over the boots, step into the boots, pull up pants and place suspenders on shoulders. Fasten attachments.
3. Put on the coat with thumbs through the gauntlets and fasten attachments. Pull up the collar and secure.
4. Slide the hood down from head around the neck.
5. Don the helmet with earflaps down and outside the collar. Properly attach and adjust chinstrap, then lower face shield/goggles.
6. Don the gloves with the wristlet over the coat wristlet.

Performance Objective

Subject: PPE

Task: _____ ~~-Detect~~ Check Self Contained Breathing Apparatus (**SCBA**) for Proper Function

Note: If any of the following procedures are faulty, then the SCBA shall be placed "out of service" until the issues are corrected.

Procedure:

1. Check and verify the air cylinder has been hydrostatically tested (as per ~~manufacturers~~ manufacturers' recommendations).
2. Check the air cylinder, ensuring valve is operational and pressure is at least 90% capacity; if less than 90%, it is recommend changing cylinder.
3. Check the harness assembly, ~~ensuring to establish~~ all straps and attachments are functional.
4. Ensure the high-pressure hose fitting has an "O" ring present for a proper seal when connecting to the air cylinder valve. For quick disconnects, ~~detect~~ check the operation of the locking sleeve on the female quick disconnect and the male shaft (particularly the locking ridge) for signs of wear.
5. Securely attach the air cylinder to the harness assembly.
6. Inspect the high-pressure hose fitting and air cylinder valve assembly for signs of wear. Properly attach the high-pressure hose fitting to the air cylinder valve, ensuring the connection is secure prior to pressurizing.
7. Slowly open the air cylinder valve until low-pressure alarm activates, then open quickly. ~~open the valve and demonstrate and~~ Check for and establish:
 - a. No audible or visual air leaks are present,
 - b. Low-pressure alarm functions correctly,
 - c. Personal Alert Safety System (**PASS**) device activation,
 - d. Air cylinder and Independent/Remote Pressure Gauge (**IPG or RPG**) readings are within ~~manufactures~~ manufacturers' recommendation,
 - e. Regulator ensuring all valves (Bypass, Mainline) are functional.

Performance Objective

Subject: PPE

Task: Don SCBA utilizing the “over the head” method

Note: SCBA should be checked and ~~detected~~ inspected prior to use.

Procedure:

1. Kneel at the end of the air cylinder opposite the valve.
2. Slowly open valve until low air alarm activates, then open quickly. ~~open valve demonstrates.~~
3. ~~Pressure gauge numerical reading shall be announced.~~ Announce cylinder pressure gauge reading
4. Announce ~~the~~ PASS device ~~is activated~~ activation (PASS device should be integrated).
5. ~~IPG/RPG (Independent/Remote Pressure Gauge) numerical reading shall be announced.~~ Announce Independent/Remote Pressure Gauge (IPG or RPG) reading
6. Spread the harness shoulder straps out on both sides of cylinder.
7. With hands placed on cylinder inside of the harness straps, lift SCBA overhead and rest on upper portion of your back.
8. With harness straps freely hanging, remove hands from cylinder and extend arms ~~demonstrates~~ bringing hands through and on the outside of harness straps.
9. Fasten and adjust all straps.

Commented [TM1]: Changes are in blue.

Performance Objective

Subject: PPE

Task: Don SCBA utilizing the “coat” method

Note: The following procedure pertains to left side mounted regulators. If the regulator is right side mounted, utilize this procedure grasping the right strap first. SCBA should be checked and ~~detected~~ inspected prior to use.

Procedure:

1. Kneel at the air cylinder valve end.
2. Slowly open valve until low air alarm activates, then quickly open. ~~valve.~~
3. ~~Pressure gauge numerical reading shall be announced~~ Announce cylinder pressure gauge reading.
4. Announce ~~the~~ PASS device ~~is~~ activated (PASS device should be integrated).
5. ~~IPG/RPG (Independent/Remote Pressure Gauge) numerical reading shall be announced.~~ Announce Independent/Remote Pressure Gauge (IPG or RPG) reading
6. Spread the harness shoulder straps out on both sides of cylinder.
7. Grasp the upper left strap with the left hand holding the Regulator hose and the lower left strap with the right hand.
8. Lift the SCBA and swing it onto your back.
9. While maintaining contact with left hand on left strap, release the right hand and extend the right arm through the right strap.
10. Fasten and adjust all straps.

Performance Objective

Subject: PPE

Task: Don SCBA utilizing **the** apparatus “seat mounted” method

Note: SCBA should be checked and ~~detected~~ **inspected** prior to use.

Procedure:

1. SCBA should be mounted onto seat rack.
2. ~~Pressure gauge numerical reading shall be announced.~~ Announce cylinder pressure gauge reading
3. Pull SCBA forward to remove from seat mount.

Note: Another method is to extend arms through shoulder straps, lean forward to remove SCBA from seat mount, then fasten and adjust all straps.

4. Slowly open valve until low air alarm activates, then **open** quickly. ~~open valve demonstrates.~~
5. Announce ~~the~~ PASS device ~~is activated~~ **activation** (PASS device should be integrated).
6. ~~IPG/RPG (Independent/Remote Pressure Gauge) numerical reading shall be announced.~~ Announce Independent/Remote Pressure Gauge (IPG or RPG) reading
7. Extend arms through shoulder straps.

8. Fasten and adjust all straps.

Performance Objective

Subject: PPE

Task: Don Facemask utilizing ~~the "chin"~~ "chin first" method

Note: Facemask should be checked and ~~-detected~~ inspected prior to use.

Procedure:

1. ~~With fingers inserted through the strap~~ Insert fingers through the straps.
lace your chin into the chin cup. Pull the head harness back and spread the webbing around your head, ensuring the harness is centered and positioned on the back of your head.
2. Ensure any obstructions are not impeding the seal of the facemask (Hair, straps...).
3. Tighten the straps by pulling them backward, evenly, and simultaneously in the following order: Chin, Temple, Top (if necessary).
4. Perform an ~~-seal~~ inhalation check by pulling the wristlet down exposing your palm, place your palm demonstrates covering the regulator fitting and inhale. Any failing result shall be corrected before continuing.

Formatted: Font: 14 pt

5. Perform an exhalation valve check by placing your palm demonstrates covering the regulator fitting and exhale. Any failing result shall be corrected before continuing.

Note: Steps 4 and 5 can be performed by connecting regulator to the facemask as the manufacturer recommends.

6. Pull the protective hood up, covering your head and any exposed skin. Ensure the exhalation valve and your vision is unobscured.
7. Place the helmet on your head, pulling the earflaps down and over the coat collar. Ensure the chinstrap is snug under the chin.

Performance Objective

Subject: PPE

Task: Don Facemask utilizing the “ball cap” method

Note: Facemask should be checked and ~~detected~~ inspected prior to use.

Procedure:

1. ~~With fingers inserted through the straps ,~~ Insert fingers through the straps. pull the head harness back and spread the webbing centered around your head. This will leave the facemask on top of the head.
2. While placing ~~a one~~ hand on the webbing ~~,~~ holding it to your head. Use your ~~with the~~ other hand to grasp the facemask and bring it down over the face ~~placing place~~ your chin in the cup.
3. Ensure any obstructions are not impeding the seal of the facemask (Hair, straps...).

Formatted: Font: 14 pt

4. Tighten the straps by pulling them backward, evenly, and simultaneously in the following order: Chin, Temple, Top (if necessary).
5. Perform an ~~seal~~ inhalation check by pulling the wristlet down exposing your palm, place your palm ~~demonstrates covering~~ over the regulator fitting and inhale. Any failing result shall be corrected before continuing.
6. Perform an exhalation valve check by placing your palm ~~demonstrates covering~~ the regulator fitting and exhale. Any failing result shall be corrected before continuing.

Note: Steps 5 and 6 can be performed by connecting regulator to the facemask as the manufacturer recommends.

7. Pull the protective hood up, covering your head and any exposed skin. Ensure the exhalation valve and your vision ~~is unobscured~~ are not obscured.
8. Place the helmet on your head, pulling the earflaps down and over the coat collar. Ensure the chinstrap is snug under the chin.

Formatted: Font: 14 pt

Performance Objective

Subject: PPE

Task: Doff Facemask

Procedure:

1. Remove the helmet and pull the protective hood down around your neck.
2. Loosen the straps evenly and simultaneously in the following order: Top (if necessary), Temple, Chin.
3. Grasp the facemask and lift it over your head. Ensure all straps are fully extended.

Note: It is NOT necessary or required to present facemask to the examiner.

4. Place the helmet on your head, pulling the earflaps down and over the coat collar. Ensure the chinstrap is snug under the chin.

Performance Objective

Subject: PPE

Task: Changing Air Cylinder on SCBA

Procedure:

1. Close cylinder valve.
2. Bleed air from high-pressure hose line.
3. Disconnect high-pressure coupling from cylinder.
4. Detach and remove cylinder from harness assembly.
5. ~~Detect~~ **Inspect** replacement air cylinder, ensuring bottle is at least 90% capacity.
6. ~~Detect~~ **Inspect** high-pressure hose fitting for the presence of a serviceable "O" ring. For quick disconnects, ~~detect~~ **inspect** the operation of the locking sleeve on

the female quick disconnect and the male shaft (particularly the locking ridge) for signs of wear.

7. Place the cylinder in the harness assembly and connect high-pressure hose fitting to the air cylinder valve.
8. Securely attach the air cylinder ~~in~~ to the harness assembly, ensuring no movement of the cylinder.
9. Slowly opens air cylinder valve until low-pressure alarm activates, then open quickly ~~open valve demonstrates~~ checking for and ensure:
 - a. No audible or visual air leaks are present,
 - b. Low-pressure alarm functions correctly,
 - c. PASS device activates,
 - d. Air cylinder and Independent/Remote Pressure Gauge (IPG or RPG) readings are within manufacture's recommendation,
 - e. Regulator ~~ensuring all~~ valve (Bypass, Mainline) are functional.
10. Don SCBA.

Formatted: Space After: 10 pt

Formatted: Space After: 10 pt