# University Physics with Modern Physics Electromagnetism Notes

# Chris Doble

## December 2022

# Contents

<b>21</b>	Elec	tric Charge and Electric Field	3
	21.1	Electric Charge	3
	21.2	Conductors, Insulators, and Incuded Charges	4
	21.3	Coulomb's Law	4
	21.4	Electric Field and Electric Forces	4
	21.5	Electric-Field Calculations	5
	21.6	Electric Field Lines	5
			6
22	Gau	ss's Law	6
	22.1	Calculating Electric Flux	6
	22.2	Gauss's Law	6
			6
	22.4	Charges on Conductors	7
23	Elec	etric Potential	7
	23.1	Electric Potential Energy	7
	23.2	Electric Potential	8
			8
	23.5	Potential Gradient	9
24	Cap	acitance and Dielectrics	9
	$24.\bar{1}$	Capacitors and Capacitance	9
	24.2	Capacitors in Series and Parallel	9
		Energy Storage in Capacitors and Electric-Field Energy 1	0
		Dielectrics	0
		Molecular Model of Induced Charge	1
		Gauss's Law in Dielectrics	2

<b>25</b>	Current, Resistance, and Electromotive	
	Force	<b>12</b>
	25.1 Current	12
	25.2 Resistivity	12
	25.3 Resistance	13
	25.4 Electromotive Force and Circuits	13
	25.5 Energy and Power in Electric Circuits	14
	25.6 Theory of Metallic Conduction	15
26	Direct-Current Circuits	<b>15</b>
	26.1 Resistors in Series and Parallel	15
	26.2 Kirchhoff's Rules	15
	26.3 Electrical Measuring Instruments	16
	26.4 R-C Circuits	17
27	Magnetic Field and Magnetic Forces	18
	27.1 Magnetism	18
	27.2 Magnetic Field	18
	27.3 Magnetic Field Lines and Magnetic Flux	19
	27.4 Motion of Charge Particles in a Magnetic Field	19
	27.5 Applications of Motion of Charged Particles	20
	27.6 Magnetic Force on a Current-Carrying Conductor	20
	27.7 Force and Torque on a Current Loop	20
	27.9 The Hall Effect	20
28	Sources of Magnetic Field	<b>21</b>
	28.1 Magnetic Field of a Moving Charge	21
	28.2 Magnetic Field of a Current Element	21
	28.3 Magnetic Field of a Straight Current-Carrying Conductor	21
	28.4 Force Between Parallel Conductors	21
	28.5 Magnetic Field of a Circular Current Loop	22
	28.6 Ampere's Law	22
	28.7 Applications of Ampere's Law	22
	28.8 Magnetic Materials	23
29	Electromagnetic Induction	24
	29.2 Faraday's Law	24
	29.3 Lenz's Law	25
	29.4 Motional Emf	25
	29.5 Induced Electric Fields	25
	29.6 Eddy Currents	26
	29.7 Displacement Current and Maxwell's Equations	26

30	Indu	actance	27
	30.1	Mutual Inductance	27
			28
	30.3	Magnetic-Field Energy	28
			29
	30.5	The L-C Circuit	29
	30.6	The L-R-C Series Circuit	30
31	Alte	ernating Current	30
		_	30
			31
			32
	31.4	Power in Alternating-Current Circuits	33
	31.5	Resonance in Alternating-Current Circuits	34
	31.6	Transformers	35
32	Elec	tromagnetic Waves	35
	32.1	Maxwell's Equations and Electromagnetic Waves	35
		Plane Electromagnetic Waves and The Speed of	
		Light	35
	32.3	Sinusoidal Electromagnetic Waves	36
			37
	32.5	Standing Electromagnetic Waves	37

# 21 Electric Charge and Electric Field

## 21.1 Electric Charge

- Electrons have a much smaller mass than neutrons and protons
- Neutrons and protons have a very similar mass
- Electrons and protons have the same magnitude of charge
- The number of protons in an atom determins its **atomic number**
- If an electron is added to a neutral atom it becomes a **negative ion**, if one is removed it becomes a **positive ion** this is called **ionisation**
- The **principle of conservation of charge** states that the algebraic sum of all the electric charges in any closed system is constant
- The electron or proton's magnitude of charge is a natural unit of charge every observable amount of electric charge is an integer multiple of this

## 21.2 Conductors, Insulators, and Incuded Charges

- Conductors pemit easy movement of charge, insulators do not
- Holding a charged object near an uncharged object causes free electrons in the latter to move away/towards the former, resulting in a net charge on either side this is called **induced charge**

#### 21.3 Coulomb's Law

- The SI unit of charge is called one **coulomb** (1 C) and is defined such that  $1.602176634 \times 10^{-19}$  C is equal to the charge of an electron or proton
- Coulomb's law describes the electric force between two point charges

$$F = \frac{1}{4\pi\epsilon_0} \frac{|q_1 q_2|}{r^2}$$

where the **electric constant**  $\epsilon_0 = 8.854 \times 10^{-12} \,\mathrm{C}^2/\mathrm{N} \cdot \mathrm{m}^2$ ,  $q_1$  and  $q_2$  are the magnitudes of the charges, and r is the distance between them

- The electric force is always directed along the line between the two charges, attracting opposite charges and repelling like charges
- $\frac{1}{4\pi\epsilon_0}$  can be approximated as  $9.0 \times 10^9 \,\mathrm{N}\cdot\mathrm{m}^2/\mathrm{C}^2$
- The principle of superposition of forces also applies to electric charges

#### 21.4 Electric Field and Electric Forces

- The electric force on a charged object is exerted by the electric field created by other charged objects
- We can determine if there is an electric field at a point by placing a test charge  $q_0$  there and seeing if it experiences an electric force the electric field at that point (the electric force per unit charge) is then given by

$$\mathbf{E} = rac{\mathbf{F}}{q_0}$$

• Rearranging, the force experienced by a charge  $q_0$  at a point is given by

$$\mathbf{F} = q_0 \mathbf{E}$$

• When considering an electric field produced by a point charge, the location of the point charge is called the **source point** and the location at which we're trying to determine the field is called the **field point** 

• The electric field produced by a point charge is given by

$$\mathbf{E} = \frac{1}{4\pi\epsilon_0} \frac{q}{r^2} \hat{\mathbf{r}}$$

where q is the charge of the point charge, r is the distance between the source and field points, and  $\hat{\mathbf{r}}$  is the unit vector from the source to the field point

- Unlike Coulomb's law this equation doesn't use the absolute value of q meaning that the electric fields of positive charges point away from the charge, while those of negative charges point towards them
- ullet In electrostatics, the electric field inside the material of a conductor (but not holes within the material) is ullet

#### 21.5 Electric-Field Calculations

• The **principle of superposition of electric fields** states that the total electric field at a point *P* is the vector sum of the fields at *P* due to each point charge in the charge distribution

$$\mathbf{E} = \mathbf{E}_1 + \mathbf{E}_2 + \cdots$$

- For a line charge distribution the **linear charge density** is represented by  $\lambda$  (the charge per unit length, measured in C/m)
- For a surface charge distribution the **surface charge density** is represented by  $\sigma$  (the charge per unit area, measured in C/m<sup>2</sup>)
- For a volume charge distribution the volume charge density is represented by  $\rho$  (the charge per unit volume, measured in C/m<sup>3</sup>)
- $\bullet$  The electric field of an infinitely long line charge along the y-axis is

$$E = \frac{\lambda}{2\pi\epsilon_0 r}$$

#### 21.6 Electric Field Lines

- An electric field line is a line drawn through space such that its tangent at any point is in the direction of the electric field vector at that point
- Fewer lines are drawn in areas where the electric field is weak and more lines are drawn in areas where it's strong

## 21.7 Electric Dipoles

- An **electric dipole** is a pair of point charges of equal magnitude q and opposite sign separated by a distance d
- ullet The net force on an electric dipole in a uniform electric field is  $oldsymbol{0}$
- The **electric dipole moment p** of an electric dipole is a vector directed from the negative charge to the positive charge with magnitude qd
- The net torque on an electric dipole in a uniform electric field is  $\mathbf{p} \times \mathbf{E}$  or  $qEd\sin\phi$  where  $\phi$  is the angle between the electric dipole and the electric field
- The potential energy of an electric dipole in a uniform electric field is

$$U = -\mathbf{p} \cdot \mathbf{E}$$

## 22 Gauss's Law

## 22.1 Calculating Electric Flux

 $\bullet$  The electric flux of a uniform electric field through a flat surface A is

$$\Phi_E = \mathbf{E} \cdot \mathbf{A}$$

where  $\mathbf{A}$  is normal to A and has a magnitude equal to its area

 $\bullet$  The electric flux of a nonuniform electric field through a curved surface A is

$$\Phi_E = \int \mathbf{E} \cdot \mathbf{dA}$$

#### 22.2 Gauss's Law

• Gauss's law states that the total electric flux through a closed surface is equal to the total electric charge enclosed by the surface divided by  $\epsilon_0$ 

$$\Phi_E = \oint \mathbf{E} \cdot \mathbf{dA} = rac{Q_{ ext{enc}}}{\epsilon_0}$$

## 22.3 Applications of Gauss's Law

- Gauss's law can be used in two ways:
  - If we know the charge distribution and it has enough symmetry to let us evaluate the integral in Gauss's law, we can find the field
  - If we know the field, we can use Gauss's law to find the charge distribution

- Under electrostatics, excess charge always lies of the surface of a conductor
- The electric field of an infinite line charge is

$$\mathbf{E} = \frac{1}{4\pi\epsilon_0} \frac{2\lambda}{r} \hat{\mathbf{r}}$$

## 22.4 Charges on Conductors

- If there is excess charge at rest on a conductor, all of that charge must lie on the surface of the conductor and the electric field inside the conductor must be zero. If there is a cavity inside the conductor, the net charge on the cavity walls equals the amount of charge enclosed by the cavity
- Charges outside a conductor have no effect on the interior of the conductor, even if it has a cavity inside this is why Faraday cages work
- At the surface of a conductor, the component of the electric field that is perpendicular to the surface is

$$E_{\perp} = \frac{\sigma}{\epsilon_0}$$

### 23 Electric Potential

### 23.1 Electric Potential Energy

• The electric potential energy of two point charges is

$$U = \frac{1}{4\pi\epsilon_0} \frac{q_1 q_2}{r}$$

• The electric potential energy of a point charge  $q_0$  and a collection of charges  $q_1, q_2$ , etc. is

$$U = \frac{q_0}{4\pi\epsilon_0} \left( \frac{q_1}{r_1} + \frac{q_2}{r_2} + \cdots \right) = \frac{q_0}{4\pi\epsilon_0} \sum_i \frac{q_i}{r_i}$$

- For every electric field due to a static charge distribution, the force exterted by that field is conservative
- The total electric potential energy of a collection of charges  $q_1$ ,  $q_2$ , etc. is

$$U = \frac{1}{4\pi\epsilon_0} \sum_{i < j} \frac{q_i q_j}{r_{ij}}$$

where  $r_{ij}$  is the distance between  $q_i$  and  $q_j$ 

#### 23.2 Electric Potential

- Potential is potential energy per unit charge
- The unit of potential is the **volt**, equal to 1 joule per coulomb
- The potential difference between two points  $V_{ab} = V_a V_b$  is called the potential of a with respect to b and equals the amount of work done by the electric force when a unit (1 C) of charge moves from a to b
- The electric potential due to a point charge is

$$V = \frac{1}{4\pi\epsilon_0} \frac{q}{r}$$

• The electric potential due to a collection of point charges is

$$V = \frac{1}{4\pi\epsilon_0} \sum_{i} \frac{q_i}{r_i}$$

• The electric potential due to a continuous charge distribution is

$$V = \frac{1}{4\pi\epsilon_0} \int \frac{dq}{r}$$

• The electric potential difference between two points is given by

$$V_a - V_b = \int_a^b \mathbf{E} \cdot d\mathbf{l} = \int_a^b E \cos \phi \, dl$$

- Positive charges tend to "fall" from high- to low-potential regions while negative charges do the opposite
- When a particle with charge  $e = 1.602 \times 10^{-19} \,\mathrm{C}$  moves between two points with a potential difference of  $1 \,\mathrm{V} = 1 \,\mathrm{J/C}$  the change in energy is  $U_a U_b = q V_{ab} = (1.602 \times 10^{-19} \,\mathrm{C})(1 \,\mathrm{J/C}) = 1.602 \times 10^{-19} \,\mathrm{J}$  which is called 1 **electron volt**

#### 23.4 Equipotential Surfaces

- An **equipotential surface** is a three-dimensional surface on which the electric potential is the same at every point
- Because electric potential energy doesn't change as a test charge moves over an equipotential surface, the electric field can do no work and thus field lines and equipotential surfaces are always perpendicular
- When all charges are at rest, the surface of a conductor is an equipotential surface
- When all charges are at rest, the entire solid volume of a conductor is at the same potential

#### 23.5 Potential Gradient

• The relationship between  $\mathbf{E}$  and V is given by

$$\mathbf{E} = -\nabla V = -\left(\frac{\partial V}{\partial x}\hat{\mathbf{i}} + \frac{\partial V}{\partial y}\hat{\mathbf{j}} + \frac{\partial V}{\partial z}\hat{\mathbf{k}}\right)$$

• If E has a radial component  $E_r$  with respect to an axis or a point and r is the distance from that axis or point, then

$$E_r = -\frac{\partial V}{\partial r}$$

## 24 Capacitance and Dielectrics

## 24.1 Capacitors and Capacitance

- Any two conductors separated by an insulator (or a vacuum) form a **capacitor**
- The capacitance of a capacitor measures its ability to store charge

$$C = \frac{Q}{V_{AB}}$$

• Capacitance is measured in **farads** where

$$1 \, \mathrm{F} = 1 \, \mathrm{C/V}$$

• The capacitance of a parallel plate capacitor in a vacuum is

$$C = \epsilon_0 \frac{A}{d}$$

#### 24.2 Capacitors in Series and Parallel

- In a series connection, the magnitude of charge on all plates is the same
- The **equivalent capacitance** of a combination of capacitors is the capacitance of a single capacitor that would have equivalent behaviour
- In a series connection, the reciprocal of the equivalent capacitance equals the sum of the reciprocals of the individual capacitances

$$\frac{1}{C_{\text{eq}}} = \frac{1}{C_1} + \frac{1}{C_2} + \cdots$$

meaning the equivalent capacitance is always less than any individual capacitance

- In a parallel connection, the potential difference is the same for all capacitors
- In a parallel connection, the equivalent capacitance equals the sum of the individual capacitances

$$C_{\text{eq}} = C_1 + C_2 + \cdots$$

meaning the equivalent capacitance is always greater than any individual capacitance  $\,$ 

# 24.3 Energy Storage in Capacitors and Electric-Field Energy

• The potential energy stored in a capacitor is

$$U = \frac{Q^2}{2C} = \frac{1}{2}CV^2 = \frac{1}{2}QV$$

• The **energy density** of a parallel plate capacitor is its energy per unit volume

$$u = \frac{\frac{1}{2}CV^2}{Ad} = \frac{1}{2}\epsilon_0 E^2$$

#### 24.4 Dielectrics

- **Dielectrics** are nonconducting materials
- Most capacitors have a dielectric material between their plates because
  - 1. It preserves the distance between the plates
  - 2. It increases the maximum potential difference between the plates by avoiding **dielectric breakdown** when the material between the plates becomes ionized and becomes conductive this happens more easily for air
  - 3. It increases the capacitance by decreasing the potential difference for a given charge
- The dielectric constant of a material is defined as

$$K = \frac{C}{C_0}$$

where  $C_0$  is the capacitance of a capacitor with vacuum between the plates and C is the capacitance of the same capacitor with the material between the plates

• If  $E_0$  is the magnitude of the electric field between the plates of a parallel plate capacitor when separated by a vacuum and E is the magnitude when separated by a dielectric then

$$E = \frac{E_0}{K}$$

• The electric field (and electric potential) are reduced because the dielectric becomes **polarized** and an induced surface charge appears of magnitude

$$\sigma_i = \sigma \left( 1 - \frac{1}{K} \right)$$

• The **permittivity** of a dielectric is defined as

$$\epsilon = K\epsilon_0$$

• The capacitance of a parallel plate capacitor with dielectric between the plates is thus

$$C = KC_0 = K\epsilon_0 \frac{A}{d} = \epsilon \frac{A}{d}$$

and the electric energy density is

$$u = \frac{1}{2}K\epsilon_0 E^2 = \frac{1}{2}\epsilon E^2$$

• The maximum electric-field magnitude that a material can withstand without the occurrence of breakdown is called its **dielectric strength** and is denoted  $E_m$ 

## 24.5 Molecular Model of Induced Charge

- If a material is comprised of polar molecules where the net charge of the molecule is 0 but the charge isn't distributed equally, electric fields cause the molecules to rotate which induces a charge
- Even if a material isn't comprised of polar molecules, electric fields cause molecules' positive and negative charges to separate slightly resulting in a dipole which again experiences a torque
- The charges in conductors are free to move so they're known as **free charges** while the charges in dielectrics aren't so they're known as **bound charges**

## 24.6 Gauss's Law in Dielectrics

• Gauss's Law in a dielectric material relates the flux of  $K\mathbf{E}$  through the surface to the amount of free (not bound) charge enclosed by the surface

$$\oint K\mathbf{E} \cdot d\mathbf{A} = \frac{Q_{\text{encl-free}}}{\epsilon_0}$$

• This shows that filling a volume with a dielectric with relative permittivity K reduces the magnitude of the electric field by a factor of 1/K

# 25 Current, Resistance, and Electromotive Force

#### 25.1 Current

- A current is any motion of charge from one region to another
- $\bullet$  The **drift velocity v<sub>d</sub>** of a current is the velocity of its particles
- While a current may come about through the movement of negative and/or
  positive charges, conventional current dictates that by convention we
  describe currents as if they were carried by positive charges
- The unit of current is the **ampere** which is defined to be one coulomb per second

$$1 A = 1 C/s$$

- The **charge concentration** *n* is the number of moving charged particles per unit volume
- The current through an area is given by

$$I = \frac{dQ}{dt} = n|q|v_dA$$

• The current density is the current per unit cross-sectional area

$$J = nqv_d$$

#### 25.2 Resistivity

• The resistivity  $\rho$  of a material is defined by **Ohm's law** 

$$\rho = \frac{E}{I}$$

• The unit of resistivity is ohm-meters  $(\Omega m)$ 

- The reciprocal of resistivity is **conductivity**
- Materials that obey Ohm's law are called **ohmic** or **linear** conductors
- Materials that don't obey Ohm's law are called nonohmic or nonlinear conductors
- The resistivity of a metallic conductor nearly always increases with increasing temperature

$$\rho(T) = \rho_0[1 + \alpha(T - T_0)]$$

where  $\rho_0$  is the resistivity at reference temperature  $T_0$  and  $\alpha$  is the **temperature coefficient of resistivity** 

- The resistivity of semiconductors decreases with increasing temperature
- Some materials exhibit **superconductivity** where their resistivity drops to 0 below a critical temperature

#### 25.3 Resistance

• The ratio of the voltage and current in a conductor is called its **resistance** 

$$R = \frac{V}{I} = \frac{\rho L}{A}$$

where  $\rho$  is the resistivity of the conductor, L is its length, and A is its cross-sectional area

- If  $\rho$  is constant (as in ohmic materials), then R is also constant
- The unit of resistance is the ohm

$$1\Omega = 1V/A$$

 Because the resistivity of a material varies with temperature, so too does the resistance of a specific conductor

$$R(T) = R_0[1 + \alpha(T - T_0)]$$

• A device made to have a specific resistance is called a **resistor** 

#### 25.4 Electromotive Force and Circuits

• When a charge goes around a complete circuit and returns to its starting position its electric potential energy must be the same, but it experienced losses due to resistance along the way

- Electromotive force or emf  $\mathcal{E}$  is the influence that makes current flow from lower to higher potential in a circuit and restores its original potential energy
- A device that provides emf is called a source of emf
- The SI unit of emf is the volt
- In an ideal source of emf
  - The potential difference between its terminals is constant regardless of the current passing through it
  - $-\mathcal{E} = V = IR$
- Real sources of emf have **internal resistance** r that reduce the **terminal voltage**

$$V_{ab} = \mathcal{E} - Ir$$

• Real sources of emf can be modelled as an ideal source of emf  ${\mathcal E}$  in series with a resistor r

#### 25.5 Energy and Power in Electric Circuits

• Power is the time rate change of energy transfer

$$P = VI$$

where V is the voltage across a circuit element and I is the current in it

• The SI unit of power is the watt

$$1 \, \mathrm{W} = 1 \, \mathrm{J/s}$$

• If the circuit element is a resistor then V = IR and

$$P = VI = I^2R = \frac{V^2}{R}$$

• If the circuit element is a source of emf outputting power then

$$P = VI = (\mathcal{E} - Ir)I = \mathcal{E}I - I^2r$$

where the  $\mathcal{E}I$  term is the power generated by the element and the  $I^2r$  term is the power dissipated by its internal resistance

• If the circuit element is a source of emf consuming power (charging) then

$$P = VI = (\mathcal{E} + Ir)I = \mathcal{E}I + I^2r$$

where the terms are the same as above

## 25.6 Theory of Metallic Conduction

- The average time between collisions of an electron and positive ions is called the **mean free time**  $\tau$
- The resistivity of a metal can be approximated as

$$\rho = \frac{m}{ne^2\tau}$$

where m is the mass of an electron, n is the number of free electrons per unit volume, e is the charge of an electron, and  $\tau$  is the mean free time

### 26 Direct-Current Circuits

#### 26.1 Resistors in Series and Parallel

- Circuit elements connected one after another with a single current path between them are said to be connected in series
- The current is the same for all circuit elements connected in series
- Circuit elements connected such there is an alternate current path for each element are said to be connected in **parallel**
- The potential difference / voltage is the same for all circuit elements connected in parallel
- For any combination of resistors we can always find a single resistor that could replace the combination and result in the same current and potential difference the resistance of this resistor is called the **equivalent resistance**
- The equivalent resistance of a series combination of resistors equals the sum of the individual resistances

$$R_{\rm eq} = R_1 + R_2 + \cdots$$

• The reciprocal of the equivalent resistance of a parallel combination of resistors equals the sum of the reciprocals of the individual resistances

$$\frac{1}{R_{\rm eq}} = \frac{1}{R_1} + \frac{1}{R_2} + \cdots$$

#### 26.2 Kirchhoff's Rules

- A **junction** in a circuit is a point where three or more conductors meet
- A loop is any closed conducting path

• **Kirchhoff's junction rule** states that the sum of the currents into any junction equals zero

$$\sum I = 0$$

• Kirchhoff's loop rule states that the sum of the potential differences around any loop equals zero

$$\sum V = 0$$

 Kirchhoff's rules can be used to analyse circuits by following these steps PROBLEM-SOLVING STRATEGY 26.2 Kirchhoff's Rules

**IDENTIFY** the relevant concepts: Kirchhoff's rules are useful for analyzing any electric circuit.

SET UP the problem using the following steps:

- 1. Draw a circuit diagram, leaving room to label all quantities, known and unknown. Indicate an assumed direction for each unknown current and emf. (Kirchhoff's rules will yield the magnitudes and directions of unknown currents and emfs. If the actual direction of a quantity is opposite to your assumption, the resulting quantity will have a negative sign.)
- As you label currents, it's helpful to use Kirchhoff's junction rule, as in Fig. 26.9, so as to express the currents in terms of as few quantities as possible.
- 3. Identify the target variables.


**EXECUTE** the solution as follows:

 Choose any loop in the network and choose a direction (clockwise or counterclockwise) to travel around the loop as you apply Kirchhoff's loop rule. The direction need not be the same as any assumed current direction.

- Travel around the loop in the chosen direction, adding potential differences algebraically as you cross them. Use the sign conventions of Fig. 26.8.
- 3. Equate the sum obtained in step 2 to zero in accordance with the loop rule.
- 4. If you need more independent equations, choose another loop and repeat steps 1-3; continue until you have as many independent equations as unknowns or until every circuit element has been included in at least one loop.
- 5. Solve the equations simultaneously to determine the unknowns.
- 6. You can use the loop-rule bookkeeping system to find the potential V<sub>ab</sub> of any point a with respect to any other point b. Start at b and add the potential changes you encounter in going from b to a; use the same sign rules as in step 2. The algebraic sum of these changes is V<sub>ab</sub> = V<sub>a</sub> V<sub>b</sub>.

**EVALUATE** your answer: Check all the steps in your algebra. Apply steps 1 and 2 to a loop you have not yet considered; if the sum of potential drops isn't zero, you've made an error somewhere.

Figure 26.9 Applying the junction rule to point a reduces the number of unknown currents from three to two.



## 26.3 Electrical Measuring Instruments

- Many common devices measure current or potential difference with a d'Arsonval galvanometer which reports values via the deflection of a pointer
- $\bullet$  The maximum deflection is called full-scale deflection and occurs at a particular current  $I_{\rm fs}$
- The device also has a resistance  $R_c$
- A device that measures the current passing through it is called an ammeter
- An ideal ammeter would have 0 resistance so it doesn't affect the rest of the circuit, but real ammeters have a small, finite resistance

 An ammeter can be adjusted to measure currents larger than its full-scale reading by connecting a resistor in parallel so some current passes through the resistor — this is called a shunt resistor and obeys the relation

$$I_{\rm fs}R_{\rm c} = (I_{\rm a} - I_{\rm fs})R_{\rm sh}$$

where  $I_{\rm fs}$  is the device's full-scale current,  $R_{\rm c}$  is its coil resistance,  $I_{\rm a}$  is the desired full-scale current, and  $R_{\rm sh}$  is the resistance of the shunt resistor

- A device that measures the potential difference between two probes / terminals is called a voltmeter
- An ideal voltmeter would have infinite resistance so it doesn't affect the rest of the circuit, but real voltmeters have large, finite resistance
- A voltmeter can be adjusted to measure potential differences larger than its full-scale reading by connecting a resistor in series with it so the voltage drops before reaching the voltmeter this obeys the relation

$$V_{\rm V} = I_{\rm fs}(R_{\rm c} + R_{\rm s})$$

where  $V_{\rm V}$  is the desired full-scale voltage,  $I_{\rm fs}$  is the device's full-scale current,  $R_{\rm c}$  is its coil resistance, and  $R_{\rm s}$  is the resistance of the resistor

- If you measure the current and voltage across an element simulateneously either the ammeter will be measuring the current across both the element and the voltmeter, or the voltmeter will be measuring the potential difference across both the element and the ammeter either way you need to correct one of the measurements
- A device that measures resistance is called an **ohmmeter**
- A **potentiometer** is a device that can be used to measure an unknown emf via a known emf and a sliding contact attached to a resistor

#### 26.4 R-C Circuits

- A circuit that has a resistor and a capacitor in series is called an R-C circuit
- When charging the capacitor in an R-C circuit, the charge on the capacitor is given by

$$q = C\mathcal{E}(1 - e^{-t/RC}) = Q_{\rm f}(1 - e^{-t/RC})$$

and the current in the circuit is given by

$$i = \frac{\mathcal{E}}{R}e^{-t/RC} = I_0 e^{-t/RC}$$

- At t = RC the capacitor has reached 1 1/e of its final value and the current has decreased to 1/e of its original value this product  $\tau = RC$  is a measure of how quickly the capacitor charges and is called the **time** constant or the relaxation time
- When discharging the capacitor in an R-C circuit, the charge on the capacitor is given by

$$q = Q_0 e^{-t/RC}$$

and the current in the circuit is given by

$$i = -\frac{Q_0}{RC}e^{-t/RC} = I_0e^{-t/RC}$$

## 27 Magnetic Field and Magnetic Forces

- Electric forces act on electric charges whether they are moving or not but magnetic forces acts only on moving charges
- Electric forces arise in two stages: (1) a charge produces an electric field in the space around it, and (2) a second charge responds to this field
- Magnetic forces also arise in two stages: (1) a moving charge or a collection of moving charges (i.e. a current) produces a magnetic field, and (2) a second moving charge or current responds to this field

## 27.1 Magnetism

• There is no experimental evidence that magnetic monopoles exist

## 27.2 Magnetic Field

- ullet Magnetic fields are vector fields represented by the symbol  ${\bf B}$
- The direction of the field is the direction the North pole of a compass would point at that position
- $\bullet\,$  For any magnet,  ${\bf B}$  points out of its North pole towards its South pole
- The magnetic force on a moving charged particle is given by

$$\mathbf{F} = q\mathbf{v} \times \mathbf{B}$$

• The unit of magnetic fields is the tesla where

$$1 \text{ tesla} = 1 \text{ T} = 1 \text{ N/A m}$$

or the gauss where

$$1 G = 1 \times 10^{-4} T$$

• When a charged particle moves through a region where both electric and magnetic fields are present the total force is the vector sum of the electric and magnetic forces

$$\mathbf{F} = q(\mathbf{E} + \mathbf{v} \times \mathbf{E})$$

this is called the Lorentz force

## 27.3 Magnetic Field Lines and Magnetic Flux

- Magnetic field lines are to magnetic fields what electric field lines are to electric fields, however they don't show the force that would be exerted on a moving charge because that depends on the charge's velocity
- The magnetic flux through a surface is given by

$$\Phi_B = \int \mathbf{B} \cdot d\mathbf{A}$$

• Magnetic flux uses the unit weber where

$$1 \,\mathrm{Wb} = 1 \,\mathrm{T} \,\mathrm{m}^2 = 1 \,\mathrm{N} \,\mathrm{m/A}$$

• Gauss's law for magnetism states that the total magnetic flux through a closed surface is 0

$$\oint \mathbf{B} \cdot d\mathbf{A} = 0$$

• Sometimes we need to calculate the magnetic flux through an open surface in which case the direction of  $d\mathbf{A}$  is ambiguous — in these scenarios we choose one direction to be positive and use that consistently

## 27.4 Motion of Charge Particles in a Magnetic Field

- Magnetic forces do no work on point charges because they are always perpendicular to the charges' velocity
- The motion of a charge particle affected only by a magnetic force is always motion with constant speed
- The radius of a circular orbit in a magentic field is given by

$$R = \frac{mv}{|q|B},$$

the angular speed is given by

$$\omega = \frac{|q|B}{m},$$

and the frequency is given by

$$f = \frac{\omega}{2\pi} = \frac{|q|B}{2\pi m}$$

## 27.5 Applications of Motion of Charged Particles

• The speed for which there is no deflection in a velocity selector is

$$v = \frac{E}{B}$$

## 27.6 Magnetic Force on a Current-Carrying Conductor

• The magnetic force on a straight wire segment is given by

$$\mathbf{F} = I\mathbf{l} \times \mathbf{B}$$

where l is the vector length of the segment (points in the current direction)

• The magnetic force on a non-straight wire segment is given by

$$\mathbf{F} = I \int d\mathbf{l} \times \mathbf{B}$$

## 27.7 Force and Torque on a Current Loop

- The net force on a current loop in a uniform magnetic field is zero, however the net torque is not in general equal to zero
- The **magnetic dipole moment** or **magnetic moment** of a current loop is a vector perpendicular to the plane of the loop with direction determined by the current around the loop and right hand rule with magnitude

$$\mu = IA$$

- A current loop or any any other object that experiences a magnetic torque in a magnetic field is called a **magnetic dipole**
- The magnetic torque experienced by a current loop is given by

$$\tau = \mu \times \mathbf{B}$$

• The potential energy of a magnetic dipole in a magnetic field is

$$U = -\boldsymbol{\mu} \cdot \mathbf{B}$$

ullet A coil consisting of N planar loops close together is called a **solenoid** and its magnetic moment, potential energy, and torque are all multiplied by a factor of N

#### 27.9 The Hall Effect

• The Hall effect is described by the equation

$$nq = \frac{-J_x B_y}{E_z}$$

where  $E_z$  is the induced electrostatic field in the conductor

## 28 Sources of Magnetic Field

## 28.1 Magnetic Field of a Moving Charge

• The magnetic field due to a point charge with constant velocity is

$$\mathbf{B} = \frac{\mu_0}{4\pi} \frac{q\mathbf{v} \times \hat{\mathbf{r}}}{r^2}$$

where  $\mu_0$  is called the **magnetic constant** 

•  $\mu_0$  is approximately equal to  $4\pi \times 10^{-7} \,\mathrm{T}\,\mathrm{m/A}$ 

## 28.2 Magnetic Field of a Current Element

• The **principle of superposition of magnetic fields** states that the total magnetic field caused by several moving charges is the vector sum of the fields caused by the individual charges

• The **Biot-Savart law** gives the magnetic field generated by a constant current

$$\mathbf{B} = \frac{\mu_0}{4\pi} \int \frac{I \, d\mathbf{l} \times \hat{\mathbf{r}}}{r^2}$$

# 28.3 Magnetic Field of a Straight Current-Carrying Conductor

• The magnetic field near a long, straight, current-carrying conductor has direction as described by the right-hand rule and magnitude

$$B = \frac{\mu_0 I}{2\pi r}$$

#### 28.4 Force Between Parallel Conductors

• The magnetic force per unit length between two long, straight, parallel, current-carrying conductors is

$$\frac{F}{L} = \frac{\mu_0 II'}{2\pi r}$$

• Two parallel conductors carrying current in the same direction attract each other

• Two parallel conductors carrying current in opposite directions repel each other

## 28.5 Magnetic Field of a Circular Current Loop

• The magnetic field on the axis of a current carrying loop is directed perpendicular to the plane of the loop as described by the right-hand rule and has magnitude

$$B = \frac{\mu_0 I a^2}{2 \left(x^2 + a^2\right)^{3/2}}$$

- ullet The magnetic field of a coil consisting of N loops has magnitude N times that of a single loop
- Magnetic dipoles are also generators of magnetic fields with the magnetic field along the axis of  $\mu$  having the same direction as  $\mu$  and magnitude

$$B = \frac{\mu_0 \mu}{2\pi \left(x^2 + a^2\right)^{3/2}}$$

## 28.6 Ampere's Law

• Ampere's law relates the line integral of the magnetic field around a closed path to the net current enclosed by that path. If the currents are steady and no time-varying electric fields are present then

$$\oint \mathbf{B} \cdot d\mathbf{l} = \mu_0 I_{\text{encl}}$$

## 28.7 Applications of Ampere's Law

• The magnetic field of a long cylindrical conductor is

$$B = \frac{\mu_0 I}{2\pi} \frac{r}{R^2}$$

inside the conductor and

$$B = \frac{\mu_0 I}{2\pi r}$$

outside the conductor

• The magnetic field outside a solenoid is 0 and inside is

$$B = \mu_0 nI$$

where n is the number of windings per unit length

• The magnetic field outside a toroidal solenoid is 0 and inside is

$$B = \frac{\mu_0 NI}{2\pi r}$$

where N is the number of turns of wire

## 28.8 Magnetic Materials

• The **Bohr magneton** is a physical constant that represents the minimum magnetic moment and has the value

$$\mu_B = 9.274 \times 10^{-24} \,\mathrm{A} \,\mathrm{m}^2 = 9.274 \times 10^{-24} \,\mathrm{J/T}$$

- All magnetic moments must be an integer multiple of the Bohr megneton
- Some materials have atoms with net magnetic moments. In the presence of an external magnetic field these atoms experience a torque causing them to align with the field, generating a field of their own that increases the overall field strength. Such materials are called **paramagnetic materials**.
  - The **magnetization** of a material is the density of magnetic moments

$$\mathbf{M} = rac{oldsymbol{\mu}_{ ext{total}}}{V}$$

where V is the volume of the material

- The additional magnetic field of a paramagnetic material is

$$\mu_0 \mathbf{M} = \mu_0 \frac{\boldsymbol{\mu}_{\text{total}}}{V}$$

If a current-carrying conductor is surrounded by paramagnetic material the total magnetic field is

$$\mathbf{B} = \mathbf{B}_0 + \mu_0 \mathbf{M}$$

- The result of this additional magnetic field is that the total magnetic field is increased by a dimensionless factor  $K_m$  called the **relative permeability** of the material
- Most equations can be adapted by multiplying by  $K_m$
- To simplify this, the **permeability**  $\mu = K_m \mu_0$  can be used instead
- The amount by which the relative permeability of a material differs from unity is called the magnetic susceptibility

$$\chi_m = K_m - 1$$

Curie's law describes how paramagnetic susceptibility is inversely proportional to temperature

$$M = C\frac{B}{T}$$

where C is a material-specific constant and T is the absolute temperature of the material

- **Diamagnetic materials** oppose external magnetic fields, meaning they have a negative susceptibility and a relative permeability less than 1
  - Diamagnetic materials are effectively temperature independent
- Ferromagnetic materials contain "domains" in which atomic magnetic moments are aligned
  - Applying an external magnetic field causes domains aligned with the field to grow and other domains to shrink
  - As the magnitude of the external field is increased a point is reached where almost all atomic magnetic moments in the material are aligned with the field. Further increases to the magnitude of the field won't change the magnetization of the material — this is called saturation magnetization
  - When a material is magnetized to saturation then the external field is reduced to zero, some magnetization remains — this behaviour is called hysterisis

Figure 28.29 Hysteresis loops. The materials of both (a) and (b) remain strongly magnetized when B<sub>0</sub> is reduced to zero. Since (a) is also hard to demagnetize, it would be good for permanent magnets. Since (b) magnetizes and demagnetizes more easily, it could be used as a computer memory material. The material of (c) would be useful for transformers and other alternating-current devices where zero hysteresis would be optimal.

(a)

(a)

(b)

(c)

(c)

(a)

(b)

(c)

(d)

(e)

(e)

(e)

(f)

(f)

(f)

(hysterial field in the opposite direction is needed to reduce the magnetization to zero.

(hysterial field is reduced to zero; magnetization remains.

(hysterial is reduced to zero; magnetization remains.

(hysterial is reduced to zero; magnetization to saturation by an external field of the saturation and demagnetization in the reversed external field gives the material a magnetization in the reversed deternal field gives the material and magnetization in the reverse direction.

(b)

(c)

(c)

(d)

(e)

(e)

(e)

(f)

(f)

(f)

(hysterial is reduced to zero; magnetization remains.

(g)

(hysterial is reduced to zero; magnetization remains.

(hysterial is reduced to zero; magnetization remains.

(hysterial is reduced to zero; magnetization remains.

(hysterial field is reduced to zero; magnetiza

netization to zero

# 29 Electromagnetic Induction

## 29.2 Faraday's Law

• Faraday's law states that the induced emf in a closed loop equals the negative of the time rate change of the magnetic flux through the loop

$$\mathcal{E} = -\frac{d\Phi_B}{dt}$$

- The direction of induced emf is described by the right hand rule with the thumb in the direction of the area vector a positive emf is in the direction of the fingers, a negative emf is in the opposite direction
- A coil of N loops has N times the magnetic flux and thus experiences N times the induced emf

#### 29.3 Lenz's Law

- Lenz's law states that the direction of any magnetic induction effect is such as to oppose the cause of the effect
- If the change in flux is due to a changing magnetic field, the magnetic field resulting from the induced emf tries to "undo" the original change
- If the change in flux is due to changing area of the circuit, the current resulting from the induced emf experiences a magnetic force that tries to "undo" the original change

#### 29.4 Motional Emf

• Emf generated as a result of the conductor moving is called **motional emf** and has magnitude

$$\mathcal{E} = vBL$$

for a straight conductor of length L and

$$\mathcal{E} = \oint (\mathbf{v} \times \mathbf{B}) \cdot d\mathbf{l}$$

for any conductor where  ${\bf v}$  is the velocity of the infinitesimal conductor element and  ${\bf B}$  is the magnetic field at its location

### 29.5 Induced Electric Fields

- A changing magnetic field induces an electric field circumferential around the direction of the change
- Unlike electrostatic fields, induced electric fields or nonelectrostatic fields are non-conservative
- An alternative form of Faraday's law tells us the nature of the induced electric field

$$\oint \mathbf{E} \cdot d\mathbf{l} = -\frac{d\Phi_B}{dt}$$

- Faraday's law describes two separate situations
  - When a conductor moves through a static magnetic field, the magnetic force on the conductor's charge carriers induces an emf that opposes the movement
  - When a magnetic field changes in a static conductor, an electric field is induced and hence an emf that opposes the change in flux

## 29.6 Eddy Currents

Induced currents can circulate through the body of a conducting material as opposed to around a well-defined circuit. These are called eddy currents


## 29.7 Displacement Current and Maxwell's Equations

• Ampere's law in the form

$$\oint \mathbf{B} \cdot d\mathbf{l} = \mu_0 I_{\text{encl}}$$

breaks in the case of a charging capacitor. If the integration surface is taken to intersect the wire at a higher potential then  $I_{\rm encl}=i_c$  (the conduction current) but if the integration path is kept the same and the integration surface changed to pass between the plates of the capacitor then  $I_{\rm encl}=0$ 

Figure **29.22** Parallel-plate capacitor being charged. The conduction current through the plane surface is  $i_C$ , but there is no conduction current through the surface that bulges out to pass between the plates. The two surfaces have a common boundary, so this difference in  $I_{\text{encl}}$  leads to an apparent contradiction in applying Ampere's law.



 $\bullet$  The generalized form of Ampere's law introduces a  ${\bf displacement}$   ${\bf current}$ 

$$i_D = \epsilon_0 \frac{d\Phi_E}{dt}$$

to account for the changing electric field between the plates of the capacitor

$$\oint \mathbf{B} \cdot d\mathbf{l} = \mu_0 (i_C + i_D)_{\text{encl}}$$

where  $i_C$  is the conduction current and  $i_D$  is the displacement current

- The displacement current actually exists and produces corresponding magnetic fields of its own
- Maxwell's equations describe all of the relationships between electric and magnetic fields

- Gauss's law for **E** 

$$\oint \mathbf{E} \cdot d\mathbf{A} = \frac{Q_{\text{encl}}}{\epsilon_0}$$

- Gauss's law for  ${f B}$ 

$$\oint \mathbf{B} \cdot d\mathbf{A} = 0$$

- Faraday's law

$$\oint \mathbf{E} \cdot d\mathbf{l} = -\frac{d\Phi_B}{dt}$$

- Generalized Ampere's law

$$\oint \mathbf{B} \cdot d\mathbf{l} = \mu_0 (i_C + i_D)_{\text{encl}} = \mu_0 (i_C + \epsilon_0 \frac{d\Phi_E}{dt})_{\text{encl}}$$

#### 30 Inductance

#### 30.1 Mutual Inductance

• The **mutual inductance** of two coils is a proportionality constant that determines how much emf is generated in one coil from a changing current in the other coil

$$\mathcal{E}_1 = -M \frac{di_2}{dt}$$
 and  $\mathcal{E}_2 = -M \frac{di_1}{dt}$ 

 Providing there isn't a magnetic material with a non-constant relative permeability present the mutual inductance only depends on the geometry of the two coils

$$M = \frac{N_2 \Phi_{B2}}{i_1} = \frac{N_1 \Phi_{B1}}{i_2}$$

where  $N_n$  is the number of turns in coil n,  $\Phi_{Bn}$  is the magnetic flux through a single loop of coil n, and  $i_n$  is the current through coil n

• The SI unit of mutual inductance is the henry

$$1 H = 1 Wb/A$$

## 30.2 Self-inductance and Inductors

- A current in a single isolated circuit establishes a magnetic field that causes a magnetic flux through the same circuit. This flux changes as the current changes, inducing an emf in the circuit. This self-induced emf opposes the change in current that caused it
- The **self-inductance** of a coil is

$$L = \frac{N\Phi_B}{i}$$

where N is the number of loops in the coil,  $\Phi_B$  is the average magnetic flux through each loop, and i is the current

• The magnitude of self-induced emf can be calculated by rearranging the self-inductance

$$\begin{split} \frac{N\Phi_B}{i} &= L\\ N\Phi_B &= Li\\ N\frac{d\Phi_B}{dt} &= L\frac{di}{dt}\\ \Rightarrow \mathcal{E} &= -N\frac{d\Phi_B}{dt} = -L\frac{di}{dt} \end{split}$$

- An **inductor** or **choke** is a device designed to have a particular self-inductance
- The potential difference between the terminals of an inductor is

$$V = L \frac{di}{dt}$$

• The self inductance of a solenoid is

$$L = \frac{\mu_0 A N^2}{l}$$

#### 30.3 Magnetic-Field Energy

• The energy stored in an inductor is given be

$$U = \frac{1}{2}LI^2$$

• The magnetic energy density in vacuum is

$$u = \frac{B^2}{2\mu_0}$$

and in a material is

$$u = \frac{B^2}{2\mu}$$

## 30.4 The R-L Circuit

- When an inductor is introduced into a circuit, the voltages, currents, and capacitor charges are in general functions of time rather than constants. However Kirchhoff's rules still apply at each moment in time
- An R-L circuit contains a resistor and an inductor in series
- After connecting a source of emf to an R-L circuit the current is

$$i = \frac{\mathcal{E}}{R}(1 - e^{-(R/L)t})$$

and its rate of change is

$$\frac{di}{dt} = \frac{\mathcal{E}}{L}e^{-(R/L)t}$$

• After disconnecting a source of emf from an R-L circuit the current is

$$i = I_0 e^{-(R/L)t}$$

and its rate of change is

$$\frac{di}{dt} = -\frac{I_0 R}{L} e^{-(R/L)t}$$

where  $I_0$  is its original current

• The time constant of an R-L circuit is the time it takes for the circuit to increase to 63% of its final current after connecting a source of emf or decrease to 37% of its original current after disconnecting a source of emf

$$\tau = \frac{L}{R}$$

#### 30.5 The L-C Circuit

- An L-C circuit contains an inductor and a capacitor in series
- The circuit oscillates as in simple harmonic motion, with the capacitor's charge playing the role of elastic/gravitational potential energy and the current through the inductor playing the role of kinetic energy
- The charge of the capacitor in an L-C circuit is given by

$$q = Q\cos(\omega t + \phi)$$

and thus the current is given by

$$i = -\omega Q \sin(\omega t + \phi)$$

where

$$\omega = \sqrt{\frac{1}{LC}}$$

#### 30.6 The L-R-C Series Circuit

- An L-R-C series circuit is one where an inductor, resistor, and capacitor are in series
- The circuit oscillates as in damped harmonic motion
- The terms underdamped, critically damped, and overdamped apply the same as they do in mechanical damped harmonic oscillation
- The angular frequency of an L-R-C circuit is

$$\omega' = \sqrt{\frac{1}{LC} - \frac{R^2}{4L^2}}$$

## 31 Alternating Current

## 31.1 Phasors and Alternating Currents

• An ac source is any device that supplies a sinusoidally varying voltage

$$v = V \cos \omega t$$

or current

$$i = I \cos \omega t$$

where v and i are the instantaneous voltage and current and V and I are the voltage and current amplitude, respectively

- In a **phasor diagram** the value of a quantity that varies sinusoidally with time is represented by the projection onto a horizontal axis of a vector known as a **phasor** which has length equal to the amplitude of the quantity and constant angular speed  $\omega$
- The **rectified average current** is defined such that after any whole number of cycles, the total charge that flows is the same as if the current was constant with a value equal to

$$I_{\rm rav} = \frac{2}{\pi} I \approx 0.637I$$

• The **root-mean-square current** is obtained by squaring the current, taking the average value of the squared current, and taking the square root of that average. For ac currents

$$I_{\rm rms} = \frac{I}{\sqrt{2}}$$

and

$$V_{\rm rms} = \frac{V}{\sqrt{2}}$$

#### 31.2 Resistance and Reactance

- Reactance is the opposition presented to alternating current by inductance or capacitance. It is similar to resistance in that it results in a smaller current for the same applied voltage, but it doesn't result in the dissipation of electrical energy as heat.
- The amplitude of voltage across a resistor in an ac circuit is

$$V_R = IR$$

and the instantaneous voltage is

$$v_R = iR = (IR)\cos\omega t = V_R\cos\omega t$$

so the voltage is in phase with the current

• The amplitude of voltage across an inductor in an ac circuit is

$$V_L = I\omega L$$

and the instantaneous voltage is

$$v_L = L \frac{di}{dt}$$

$$= L \frac{d}{dt} (I \cos \omega t)$$

$$= -I\omega L \sin \omega t$$

$$= I\omega L \cos \left(\omega t + \frac{\pi}{2}\right)$$

$$= V_L \cos \left(\omega t + \frac{\pi}{2}\right)$$

so the voltage is out of phase with the current, leading it by 90°.

• The inductive reactance of an inductor is defined as

$$X_L = \omega L$$

which lets the amplitude of voltage be written in the same form as that of a resistor

$$V_L = IX_L$$

• The inductive reactance is a measure of the self-induced emf that opposes any change in current — greater angular frequency  $\omega$  or inductance L results in greater opposition

• The ampltitude of voltage across a capacitor in an ac circuit is

$$V_C = \frac{I}{\omega C}$$

and the instantaneous voltage is

$$v_C = \frac{1}{\omega C} \sin \omega t$$
$$= \frac{1}{\omega C} \cos \left(\omega t - \frac{\pi}{2}\right)$$
$$= V_C \cos \left(\omega t - \frac{\pi}{2}\right)$$

so the voltage is out of phase with the current, lagging it by 90°.

• The capacitive reactance of a capacitor is defined as

$$X_C = \frac{1}{\omega C}$$

which lets the amplitude of voltage be written in the same form as that of a resistor

$$V_C = IX_C$$

• The capacitive reactance is measure of the voltage produced by the build up of charge on the plates of the capacitor which opposes current — greater angular frequency  $\omega$  or capacitance C results in less opposition

#### 31.3 The L-R-C Series Circuit

- An L-R-C series circuit is one that contains an inductor, a resistor, and a capacitor in series
- In the phasor diagram for such a circuit, the inductor phasor leads the current phasor by  $90^{\circ}$ , the resistor phasor is parallel with it, and the capacitor phasor lags by  $90^{\circ}$
- The instantaneous voltage of any ac circuit is equal to the projection of the vector sum of the components' phasors
- The **impedance** Z of an ac circuit is a measure of its opposition to ac current due to the combined effect of resistance and reactance. It is defined as the ratio of the voltage amplitude to the current amplitude in the circuit

$$Z = \frac{V}{I} \Rightarrow V = IZ$$

• The impedance of an L-R-C series circuit is

$$Z = \sqrt{R^2 + (X_L - X_C)^2} = \sqrt{R^2 + [\omega L - (1/\omega C)]^2}$$

• The phase angle of voltage with respect to current in an L-R-C series circuit is

$$\tan\phi = \frac{X_L - X_C}{R} = \frac{\omega L - 1/\omega C}{R}$$

- The equations above are valid if a component is missing from an L-R-C series circuit
  - If the resistor is missing, set R=0
  - If the inductor is missing, set L=0
  - If the capacitor is mising, set  $C = \infty$
- The above equations deal with ampitudes, but they can be modified to deal with rms values by dividing current and voltage by  $\sqrt{2}$
- Kirchhoff's rules hold at each instance in an ac circuit

## 31.4 Power in Alternating-Current Circuits

• The instantaneous power delivered to an ac circuit element is

$$p = vi$$

• The average power delivered to an ac circuit consisting only of a resistor is

$$P_{\rm av} = \frac{1}{2}VI = \frac{V}{\sqrt{2}}\frac{I}{\sqrt{2}} = V_{\rm rms}I_{\rm rms}$$

• Because  $V_{\rm rms} = I_{\rm rms} R$ , the above can also be expressed as

$$P_{\rm av} = I_{\rm rms}^2 R = \frac{V_{\rm rms}^2}{R} = V_{\rm rms} I_{\rm rms}$$

- Because the voltage across an inductor leads the current by  $90^{\circ}$ , half the time the product vi is positive and half the time it's negative and thus the average power delivered to an inductor is 0
- When the voltage across an inductor is positive the magnetic field is being established and when it's negative the magnetic field is collapsing, returning energy back to the circuit
- Because the voltage across a capacitor lags the current by  $90^{\circ}$ , half the time the product vi is positive and half the time it's negative and thus the average power delivered to a capacitor is 0
- When the voltage across a capacitor is positive charge is building up on the plates and when it's negative the charge is returning to the circuit

• The instantaneous power delivered to a circuit is

$$p = vi$$

$$= [V \cos(\omega t + \phi)][I \cos \omega t]$$

$$= [V(\cos \omega t \cos \phi - \sin \omega t \sin \phi)][I \cos \omega t]$$

$$= VI \cos \phi \cos^2 \omega t - VI \sin \phi \cos \omega t \sin \omega t$$

• The average value of  $\cos^2 \omega t$  over one cycle is  $\frac{1}{2}$  and  $\cos \omega t \sin \omega t$  is equal to  $\frac{1}{2} \sin 2\omega t$ , the average value of which over one cycle is 0 so

$$P_{\rm av} = \frac{1}{2} V I \cos \phi = V_{\rm rms} I_{\rm rms} \cos \phi$$

- In other words, the average power delivered to a circuit is equal to  $\frac{1}{2}I$  times  $V\cos\phi$  which is the projection of the voltage phasor onto the current phasor, i.e. only the component of the voltage that is in phase with the current contributes to power
- The factor  $\cos \phi$  is called the **power factor** of the circuit
- The power factor of an L-R-C circuit is equal to R/Z

#### 31.5 Resonance in Alternating-Current Circuits

• As the angular frequency  $\omega$  of an ac source increases,  $X_C$  decreases and  $X_L$  increases. For one value they're equal meaning  $Z = \sqrt{R^2 + (X_L - X_C)^2}$  is minimised and I = V/Z is maximised. This behaviour is called **resonance** and the angular frequency at which Z is minimised and I is maximised is called the **resonance** angular frequency


$$\omega_0 = \frac{1}{\sqrt{LC}}$$

• At the resonance angular frequency  $V_C = IX_C$  and  $V_L = IX_L$  are equal and opposite, meaning  $V = V_R$  and all power in the circuit is delivered to the resistor

### 31.6 Transformers

• A transformer uses magnetic induction to change a source voltage.

The induced emf *per turn* is the same in both coils, so we adjust the ratio of terminal voltages by adjusting the ratio of turns:  $\frac{V_2}{V_1} = \frac{N_2}{N_1}$ 



• The ratio of terminal voltages in a transformer is given by

$$\frac{V_2}{V_1} = \frac{N_2}{N_1}$$

- If  $N_2 > N_1$  then  $V_2 > V_1$  and it's called a step-up transformer. If  $N_2 < N_1$  then  $V_2 < V_1$  and it's called a step down transformer.
- The power delivered to both windings is equal

$$V_1I_1 = V_2I_2$$

# 32 Electromagnetic Waves

### 32.1 Maxwell's Equations and Electromagnetic Waves

- All electromagnetic waves originate from the acceleration of charges
- The phrase "electromagnetic radiation" is used intechangably with "electromagnetic waves"

# 32.2 Plane Electromagnetic Waves and The Speed of Light

• A plane wave is one where, at any instant, the fields are uniform over any plane perpendicular to the direction of propagation

- Electromagnetic waves are **transverse**, i.e. both **E** and **B** are perpendicular to the direction of propagation of the wave. The fields are also perpendicular to each other
- The direction of propagation is the direction of  $\mathbf{E} \times \mathbf{B}$
- There is a definite ratio between the magnitudes of the fields of an electromagnetic wave: E = cB
- Electromagnetic waves travel in a vacuum with a definite and unchanging speed
- Unlike mechanical waves that require the particles of a medium to transmit a wave, electromagnetic waves require no medium
- The **E** and **B** fields obey the superposition principle in waves just as in static situations
- Because the magnitudes of the **E** and **B** fields must be related in the ratio E = cB the periodic variations of the two fields in a periodic travelling wave must be in phase
- A wave in which E is always parallel to a certain axis is said to be linearly polarized along that axis

#### 32.3 Sinusoidal Electromagnetic Waves

ullet The magnitudes of the  ${f E}$  and  ${f B}$  fields in a sinusoidal electromagnetic wave are given by

$$E = E_{\text{max}}\cos(kx - \omega t)$$

and

$$B = B_{\text{max}}\cos(kx - \omega t)$$

where  $k=2\pi/\lambda$  is the wave number,  $\lambda$  is the wavelength, and  $\omega$  is the angular frequency

- For a wave travelling in the +x direction, **E** is in the +y direction and **B** is in the +z direction
- For waves travelling in a dielectric, E = vB and  $B = \epsilon \mu vE$  where  $\epsilon = K\epsilon_0$ ,  $\mu = K_m \mu_0$ , and

$$v = \frac{1}{\sqrt{\epsilon \mu}} = \frac{1}{\sqrt{KK_m}} \frac{1}{\sqrt{\epsilon_0 \mu_0}} = \frac{c}{\sqrt{KK_m}}$$

• The ratio of the speed of light c to the speed of light in a material is known as the **index of refraction**. If  $K_m \approx 1$  then

$$n = \frac{c}{v} = \sqrt{KK_m} \approx \sqrt{K}$$

## 32.4 Energy and Momentum in Electromagnetic Waves

• The energy density of an electromagnetic wave in a vacuum is

$$u = \epsilon_0 E^2$$

 $\bullet$  The **Poynting vector** has units W/m<sup>2</sup> and it describes the magnitude and direction of the energy flow rate of an electromagnetic wave

$$\mathbf{S} = \frac{1}{\mu_0} \mathbf{E} \times \mathbf{B}$$

• The Poynting vector is a function of both position and time and because the frequencies of typical electromagnetic waves are so high the Poynting vector varies rapidly. It's often more appropriate to look at the magnitude of its average value which is known as **intensity** 

$$I = \frac{E_{\text{max}}B_{\text{max}}}{2\mu_0} = \frac{E_{\text{max}}^2}{2\mu_0 c} = \frac{1}{2}\sqrt{\frac{\epsilon_0}{\mu_0}}E_{\text{max}}^2 = \frac{1}{2}\epsilon_0 c E_{\text{max}}^2$$

- The equations for the Poynting vector and intensity can be modified for the case of an electromagnetic wave in a dielectric by replacing c with v,  $\epsilon_0$  with  $\epsilon$ , and  $\mu_0$  with  $\mu$
- Electromagnetic waves have momentum density

$$\frac{dp}{dV} = \frac{EB}{\mu_0 c^2} = \frac{S}{c^2}$$

• The momentum flow rate per unit area of an electromagnetic wave is

$$\frac{1}{A}\frac{dp}{dt} = \frac{S}{c} = \frac{EB}{\mu_0 c}$$

and the average rate of momentum transfer per unit area can be obtained by replacing S with  $S_{\rm av}=I$ 

• The momentum of electromagnetic waves is responsible for **radiation pressure** the magnitude of which is

$$p_{\rm rad} = \frac{I}{c}$$

when the wave is completely absorbed and

$$p_{\rm rad} \frac{2I}{c}$$

when it's completely reflected

### 32.5 Standing Electromagnetic Waves

• The superposition of an incident wave and a reflected wave form a **standing wave**