

Script bash
Copy/paste this code and save it as setup-zram.sh

Then, use these commands to install Zram with persistence.

```
sudo cp setup-zram.sh /usr/local/bin/setup-zram.sh
sudo chmod +x /usr/local/bin/setup-zram.sh
sudo /usr/local/bin/setup-zram.sh
```

```
#-----Beginning script-----
#!/bin/bash
#by triki1

set -euo pipefail

# modprobe/swapon/
export PATH="/usr/sbin:/sbin:/usr/bin:/bin:${PATH}"

# --- Configuration ---
SIZE="2G"
DEVICE="/dev/zram0"
PRIORITY=100

echo "==> Setup ZRAM swap (${SIZE}) sur ${DEVICE}"

# 1. Charger le module zram
if ! lsmod | grep -q '^zram'; then
    echo "Chargement du module zram..."
    modprobe zram num_devices=1
fi

# 2. Si zram0 existe déjà et est actif en swap, on désactive proprement
avant de reconfigurer
if swapon --show=NAME --noheadings | grep -q "^${DEVICE}$"; then
    echo "Désactivation du swap existant sur ${DEVICE}..."
    swapoff "${DEVICE}"
fi

# 3. Réinitialiser le device s'il a déjà une taille configurée
if [ -e "/sys/block/zram0/disksize" ]; then
    CURRENT_SIZE=$(cat /sys/block/zram0/disksize)
    if [ "${CURRENT_SIZE}" != "0" ]; then
        echo "Reset du device zram0..."
        echo 1 > /sys/block/zram0/reset
```

```
fi
fi
```

```
# 4. Si zram0 n'existe pas du tout, on le crée
if [ ! -e "/sys/block/zram0" ]; then
    echo 1 > /sys/class/zram-control/hot_add
fi
```

```
# 5. Configurer l'algorithme de compression
if [ -e "/sys/block/zram0/comp_algorithm" ]; then
    if grep -q "zstd" /sys/block/zram0/comp_algorithm; then
        echo "zstd" > /sys/block/zram0/comp_algorithm
        echo "Algorithme de compression : zstd"
    fi
fi
```

```
# 6. Définir la taille
echo "${SIZE}" > /sys/block/zram0/disksize
```

```
# 7. Créer et activer le swap
mkswap "${DEVICE}"
swapon -p "${PRIORITY}" "${DEVICE}"
```

```
echo "==> ZRAM configuré avec succès : "
swapon --show
```

```
#----- End -----
```
