



CLIENT INSTALLATION & USER GUIDE

ChristocentricTrader Advanced • Driverline Indicator MW Advanced • Driverline Indicator Advanced

MetaTrader 5 | v3.0 | Multi-Symbol | Classic · SMC · Advanced Modes

**ChristocentricTrader
Advanced**

Expert Advisor

**Driverline Indicator
MW Advanced**

Multi-Symbol Indicator

**Driverline Indicator
Advanced**

Single-Symbol Indicator



TABLE OF CONTENTS

Navigation guide to all sections

0 1	Product Overview	What each product does and how they work together
0 2	Installation	Downloading, compiling and installing the .ex5 files
0 3	Trading Modes	Classic, SMC and Advanced — when to use each
0 4	Execution Mode	Limit Orders vs Market Execution
0 5	License Activation	How to obtain and enter your license key
0 6	Signal Notifications	On-chart, Email and Push notifications setup
0 7	Input Parameters Reference	Complete parameter reference for all products
0 8	Troubleshooting	Common issues and solutions

01

PRODUCT OVERVIEW


Understanding the three products and how they work together

What You Have

The ChristocentricTrader suite consists of three MT5 products that work as a complete trading system. The Expert Advisor (EA) executes trades automatically, while the indicators provide visual signals you can trade manually. All three share the same Driverline™ analysis engine and support three analysis modes.

ChristocentricTrader Advanced Expert Advisor (.ex5) Automated trading on up to 100 symbols simultaneously. Reads symbols from Market Watch. Supports Classic, SMC and Advanced entry modes. Limit or Market execution.	Driverline Indicator MW Advanced Multi-Symbol Indicator Dual-panel dashboard showing live host-chart analysis in the upper section, and the last 5 signals from Market Watch symbols in the lower section.	Driverline Indicator Advanced Single-Symbol Indicator Single-symbol deep analysis with full chart visual overlays. Best for manual traders who want rich SMC/Advanced zone drawings on their chart.
---	---	--

Architecture at a Glance



All three products share the same core Driverline™ multi-timeframe trend engine. The EA adds automated order management; the indicators add rich chart visualisations. The Advanced mode adds institutional-level confluence filtering (PD Arrays, QML, Breaker Blocks).

02

INSTALLATION

Step-by-step guide to installing all three products in MetaTrader 5

Step 1 — Receive Your Files

After purchasing, you will receive three .ex5 compiled files by email or via the MQL5 Marketplace download page. The files are:

ChristocentricTrader_Advanced.ex5	Expert Advisor — automated trading
Driverline_Indicator_MW_Advanced.ex5	Multi-symbol indicator with dual dashboard
Driverline_Indicator_Advanced.ex5	Single-symbol indicator with full chart visuals

Step 2 — Open the MQL5 Data Folder

1

Open MetaTrader 5

Launch MT5 from your desktop or Start menu.
Ensure you are logged into your broker account.

2

Navigate to Data Folder

Click File in the top menu bar.
Select 'Open Data Folder' from the dropdown.

3

Find the correct subfolder

A Windows Explorer window opens.
Navigate to: MQL5 → Experts (for the EA)
Navigate to: MQL5 → Indicators (for the indicators)

4

Copy the .ex5 files

Drag and drop ChristocentricTrader_Advanced.ex5 into the Experts folder.
Drag and drop both indicator .ex5 files into the Indicators folder.
Do NOT rename the files.

NOTE

You do NOT need to compile the files. The .ex5 files are pre-compiled and ready to use.
If you have the .mq5 source files, you can compile them in MetaEditor (F7) instead.

Step 3 — Attach to Chart (EA)

ChristocentricTrader_Advanced — Input Parameters

Symbol Source	Market Watch (auto)
Trading Mode	Classic
Execution Mode	LIMIT
Risk %	1.00
License Key	CT-XXXX-XXXX-XXXX
AutoTrading	ENABLED

1

Refresh Navigator

Press F5 or right-click in the Navigator panel.
You should see the EA appear under Expert Advisors.

2

Open a Chart

Press Ctrl+N or click File → New Chart.
Select any symbol (e.g. EURUSD) on H1 timeframe.
The EA will auto-scan all Market Watch symbols — the chart symbol is only the host.

3

Drag the EA onto the chart

Drag ChristocentricTrader_Advanced from the Navigator onto the chart.
The Inputs dialog will appear automatically.

4

Enable AutoTrading

Ensure the AutoTrading button in the toolbar is GREEN.
Without this, the EA will scan and alert but will NOT place orders.

Step 4 — Attach to Chart (Indicators)

1

Open a chart for your main symbol

Open EURUSD H1 (or your preferred symbol) as the host chart.
The indicator will show live data for this symbol in the upper panel.

2

Attach Driverline_Indicator_MW_Advanced

In the Navigator, find it under Indicators.
Drag it onto the chart. The dual dashboard appears immediately.

3

Populate Market Watch

Press Ctrl+M to open Market Watch.
Right-click → Show All, or manually add symbols you want monitored.
The indicator scans ALL symbols visible in Market Watch automatically.

IMPORTANT

Always run the EA on its own dedicated chart. The EA uses the chart as its host
but trades ALL symbols in Market Watch. Do not attach multiple EAs to the same account.

03

TRADING MODES

Classic, SMC and Advanced — understanding and enabling each mode

All three products support three analysis modes. Only one mode is active at a time. The priority order is: **Advanced** supersedes **SMC**, which supersedes **Classic**. Enable only the mode you want — leave the others off.

DEFAULT MODE

CLASSIC MODE

Multi-TF EMA confluence (D1/H4/H1/M30/
Engulfing and Pin Bar pattern detection
ATR-based SL with fractal limit entry

BEST FOR: Trending markets with clear**SIGNALS:** BUY LIMIT / SELL LIMIT

SMART MONEY

SMC MODE

Break of Structure (BoS) detection
Order Block and Fair Value Gap entries
Liquidity sweep confirmation + HTF filter

BEST FOR: Markets showing institutional**SIGNALS:** BUY LIMIT / SELL LIMIT [SI]

INSTITUTIONAL

ADVANCED MODE

PD Arrays: Premium/Discount zone filter
QML: Quasimodo reversal entries
Breaker Blocks: failed OB continuation

BEST FOR: High-probability confluence setups only**SIGNALS:** BUY LIMIT / SELL LIMIT [ADV]

Classic Mode — How to Enable

Classic Mode is the **default**. It is active when both **InpSMCMode** and **InpAdvMode** are set to **false**.

Parameter	Default	Description
InpSMCMode	false	Must be FALSE for Classic mode
InpAdvMode	false	Must be FALSE for Classic mode
InpUse_D1	true	Include Daily timeframe in trend score (weight 3.0)
InpUse_H4	true	Include H4 timeframe (weight 2.5)
InpUse_H1	true	Include H1 timeframe (weight 2.0)
InpUse_M30	true	Include M30 timeframe (weight 1.5)
InpUse_M15	true	Include M15 entry timeframe (weight 1.0)
InpUseEngulfing	true	Require Engulfing candlestick pattern confirmation
InpUsePinBar	true	Require Pin Bar candlestick pattern confirmation
InpRSI_OB	70.0	Suppress BUY signals above this RSI level
InpRSI_OS	30.0	Suppress SELL signals below this RSI level

TIP

For Classic mode, the strongest signals come when ALL 5 timeframes agree.
Lower InpRSI_OB to 65 and raise InpRSI_OS to 35 for stricter filtering.

SMC Mode — How to Enable

Set **InpSMCMode = true** and ensure **InpAdvMode = false**. SMC mode replaces Classic pattern detection with institutional zone analysis.

Parameter	Default	Description
InpSMCMode	false → true	Set TRUE to enable SMC Mode

Parameter	Default	Description
InpSMC_HTF	PERIOD_H4	Higher Timeframe for macro bias (H4 recommended; use D1 for crypto/indices)
InpSMC_MinScore	2	Minimum signal score 1–4. Score: BoS=1 + HTF=1 + Sweep=1 + OB/FVG=1
InpSMC_EntryMode	0	0 = Conservative (zone midpoint) 1 = Aggressive (zone edge — less fill)
InpSMC_ShowZones	true	Draw OB/FVG zone rectangles on chart
InpSMC_ShowBoS	true	Draw Break of Structure labels on chart

TIP

InpSMC_MinScore = 3 is recommended for live trading (requires BoS + HTF + one of Sweep/OB).
Set to 2 during backtesting to see the full range of setups.

Advanced Mode — How to Enable

Set **InpAdvMode = true**. This supersedes both Classic and SMC. Advanced Mode adds three layers of institutional confluence on top of the SMC engine.

Parameter	Default	Description
InpAdvMode	false → true	Set TRUE to enable Advanced Mode (supersedes Classic and SMC)
InpAdv_UsePD	true	Filter trades by Premium/Discount zone — Buys only in Discount, Sells in Premium
InpAdv_UseQML	true	Detect Quasimodo Level reversals (failed swing pattern)
InpAdv_UseBreaker	true	Detect Breaker Blocks (failed OBs that flipped polarity)
InpAdv_MinScore	3	Minimum composite score 1–7. Recommended: 3–4 for live trading
InpAdv_ShowPD	true	Draw PD Array lines (gold = EQ, green = Discount boundary, red = Premium boundary)
InpAdv_ShowQML	true	Draw QML zone rectangles and neckline on chart
InpAdv_ShowBreaker	true	Draw Breaker Block rectangles on chart

TIP

Advanced Mode generates fewer but higher-quality signals. Score 5+ means BoS + HTF + PD + QML or Breaker.
For beginners, start with Classic mode and graduate to SMC before using Advanced.

When to Use Each Mode

Market Condition	Recommended Mode	Why
Strong trending market (clear D1 direction)	Classic	EMA confluence is cleanest in trending conditions
Range-bound with clear swing highs/lows	SMC	OBs and FVGs form cleanly in structured ranges
Volatile / news-driven / NFP week	Advanced	PD filter prevents buying expensive / selling cheap; QML catches reversals
Crypto or synthetic indices	SMC	Institutional order flow dominant; set HTF to D1

Market Condition	Recommended Mode	Why
Low-volatility session (Asian session)	Classic	SMC signals sparse; EMA confluence still works
Looking for reversals at major swing levels	Advanced	QML specifically targets failed swing extremes for reversal entries

04

EXECUTION MODE

Limit Orders vs Market Execution — what they do and when to use each

The EA supports two order execution types, configurable via a single input. The same setting applies to all three analysis modes (Classic, SMC, Advanced).

LIMIT
Order Mode
Default Setting

Entry price calculated from fractal level or ATR offset. A Buy Limit / Sell Limit pending order is placed at that price. Zero slippage — you get exactly your calculated price.

Best for:

- Pullback/reversal strategies
- Markets with clear retracement zones
- Forex pairs with predictable swings

Downside:

- Order may never fill if price doesn't retrace
- Missed entries on strong breakout moves

MARKET
Execution Mode
Alternative Setting

At signal time, the EA fetches the live ask/bid and sends an immediate market order. SL and TP are anchored to the live fill price — not the calculated entry. Always fills immediately.

Best for:

- Breakout confirmation strategies
- SMC mode after a confirmed BoS impulse
- Fast-moving synthetic indices

Downside:

- Slippage on news events or thin liquidity
- RR slightly worse than calculated

How to Set the Execution Mode

Parameter	Default	Description
InpExecMode	EXEC_LIMIT	EXEC_LIMIT = pending limit orders EXEC_MARKET = immediate fill

Inputs — ChristocentricTrader_Advanced

Group

Execution Mode

InpExecMode

EXEC_LIMIT ▼

[EXEC_LIMIT] ← selected

[EXEC_MARKET]

WARNING

In Market Execution mode, the EA automatically enforces the broker's minimum stop distance (SYMBOL_TRADE_STOPS_LEVEL + 5 points) to prevent order rejection. Your actual RR may differ slightly from the calculated value shown in the signal alert.

Order Comment Tags

Each order placed by the EA carries a unique comment tag so you can filter trades in your history. The format is:

Mode + Type	Example Comment Tag	Description
Classic Limit	DL_CT_LMT_1	Symbol slot 1, Limit order
Classic Market	DL_CT_MKT_1	Symbol slot 1, Market order
SMC Limit	DL_CT_SMC_LMT_1	SMC mode, Limit order
SMC Market	DL_CT_SMC_MKT_1	SMC mode, Market order
Advanced Limit	DL_CT_ADV_QML_1	Advanced mode, entry type = QML
Advanced Market	DL_CT_ADV_Breaker_1	Advanced mode, Breaker Block entry

05

LICENSE ACTIVATION

How to obtain and enter your unique license key

The ChristocentricTrader EA uses an account-locked license system. Each license is tied to your MT5 account number. The EA checks your license on startup and disables trading if the key is invalid or the account does not match.

How to Get Your License

1

Purchase or download from MQL5 Marketplace

Visit the MQL5 Marketplace product page.
Click 'Buy' or 'Rent'. You will be prompted to log in to your MQL5 account.
After payment, the product appears under My Products → Purchased.

2

Find your MT5 Account Number

In MetaTrader 5, go to View → Terminal (Ctrl+T).
Your account number is shown in the bottom status bar and in the Trade tab.
Note: Use the LIVE account number for a live license; DEMO for demo license.

3

Contact support for a direct license (if purchased outside MQL5)

Email your account number to the support address provided in your purchase receipt.
You will receive a key in the format: CT-XXXX-XXXX-XXXX within 24 hours.
One key = one MT5 account number. Additional accounts require separate licenses.

4

Enter the key in the EA Inputs

Attach the EA to a chart or double-click it in the Navigator.
In the Inputs tab, find the group 'License'.
Paste your key into the InpLicenseKey field exactly as provided.
Click OK. The EA will validate on the first tick.



Inputs — License Group

Group	License
InpLicenseKey	CT-A1B2-C3D4-E5F6
Account	12345678 (MATCHED)
Status	LICENSE VALID ✓

License Status Messages

Message in Journal	Colour	Meaning / Action
LICENSE VALID	Green	Key matches account — full trading enabled
LICENSE INVALID	Red	Key format wrong or tampered — re-enter exactly
ACCOUNT MISMATCH	Red	Key was issued for a different account number
LICENSE EXPIRED	Orange	Rental period ended — renew on MQL5 Marketplace

Message in Journal	Colour	Meaning / Action
KEY NOT ENTERED	Yellow	InpLicenseKey is blank — paste your key and restart

IMPORTANT

Never share your license key. It is locked to your account number and will not work on another account. If you change brokers or accounts, contact support for a re-issue.

06

SIGNAL NOTIFICATIONS

On-chart visuals, email alerts and mobile push notifications

When a signal is generated, the EA and indicators can notify you in up to four ways: on-chart visual drawing, a popup alert, an email, and a mobile push notification. Each can be enabled or disabled independently.

1 — On-Chart Visual Signals

When a signal fires, the following objects are drawn on the chart:

Object	Description	Enabled by
▲ / ▼ Arrow	Large coloured arrow (lime = buy, red = sell) anchored to signal bar	InpShowSignalLines
Entry Line	Dashed blue horizontal line at limit entry price	InpShowSignalLines
SL Line	Solid orange-red line at stop loss level	InpShowSignalLines
TP1 / TP2 / TP3	Dotted gold, green, blue lines at each take-profit level	InpShowSignalLines
Price Tags	Text labels (ENTRY / SL / TP1–3) pinned to the right of each line	InpShowSignalLines
OB/FVG Zone	Filled rectangle over the Order Block or Fair Value Gap (SMC/Advanced)	InpSMC_ShowZones
BoS Label	Text 'BoS ▲' or 'BoS ▼' at Break of Structure level	InpSMC_ShowBoS
QML Zone	Dotted rectangle at Quasimodo Level + dashed neckline (Advanced)	InpAdv_ShowQML
Breaker Block	Filled rectangle at Breaker Block zone (Advanced)	InpAdv_ShowBreaker
PD Array Lines	Gold EQ line, green Discount boundary, red Premium boundary (Advanced)	InpAdv_ShowPD
Info Panel	Dashboard panel showing trend, strength, signal and last 5 signals	InpShowPanel

Parameter	Default	Description
InpShowSignalLines	true	Master switch for all chart drawings (lines, arrows, price tags)
InpShowPanel	true	Show/hide the info panel dashboard
InpMaxSignalsChart	5	Maximum number of signal sets kept on chart before oldest is removed

2 — Popup Alert

A popup dialog appears in MetaTrader 5 whenever a signal fires. It shows direction, symbol, entry/SL/TP prices, score and mode. Works on PC only.

Parameter	Default	Description
InpAlertPopup	true	Set TRUE to enable popup alert dialog on every signal

NOTE

Popup alerts only appear when MT5 is open and in focus on your PC.
For mobile alerts, use Push Notifications instead.

3 — Email Alerts

The EA can send a formatted email to any address when a signal fires. This requires your SMTP settings to be configured in MetaTrader 5.

1

Enable email in MT5

In MetaTrader 5, go to Tools → Options → Email tab.
Tick 'Enable'.

2

Enter your SMTP settings

SMTP Server: e.g. smtp.gmail.com:465
SMTP Login: your Gmail address
SMTP Password: your Gmail App Password (not your main password!)
From: your email | To: where you want alerts sent

3

Gmail App Password (if using Gmail)

Go to myaccount.google.com → Security → 2-Step Verification.
At the bottom, click 'App passwords'.
Generate a password for 'Mail' / 'Other (custom name)'.
Use this 16-character code as your SMTP Password in MT5.

4

Enable in EA/Indicator

In the EA or indicator Inputs, set InpAlertEmail = true.
Click OK. The next signal will trigger a test email.

Parameter	Default	Description
InpAlertEmail	false	Set TRUE to enable email alerts. Requires SMTP configured in MT5 Options.

4 — Push Notifications (Mobile)

Push notifications send alerts to the MetaTrader 5 mobile app on iOS or Android even when MT5 is minimised on your PC.

1

Install MetaTrader 5 on your phone

Download from the App Store (iOS) or Google Play (Android).
Log into the SAME broker account you use on your PC.

2

Find your MetaQuotes ID

Open the MT5 mobile app.
Tap the menu (three lines) → Messages.
Your MetaQuotes ID is shown at the top (format: XXXXXXXX).

3

Enter the ID in MT5 on your PC

Go to Tools → Options → Notifications.
Tick 'Enable Push Notifications'.
Enter your MetaQuotes ID in the field provided.
Click 'Test' to verify — you should receive a test notification.

4

Enable in EA/Indicator

Set `InpAlertPush = true` in the EA or indicator Inputs.
Click OK. Signals will now push to your phone in real time.

Parameter	Default	Description
<code>InpAlertPush</code>	<code>false</code>	Set TRUE to enable mobile push notifications via MetaTrader 5 app

TIP

Enable all three notification types (Popup + Email + Push) during the first week so you don't miss signals while learning the system. You can disable later.

07

INPUT PARAMETERS REFERENCE

Complete reference for all configurable inputs across all three products

ChristocentricTrader Advanced — EA Parameters

Market Watch Settings

Parameter	Default	Description
InpExcludeHost	false	Exclude the chart host symbol from EA trading
InpSymFilter	(blank)	Optional symbol name filter, e.g. 'USD' trades only USD pairs
InpDefaultATRTF	PERIOD_M 15	ATR Timeframe used for all symbols

Trend & EMA Settings

Parameter	Default	Description
InpFastEMA	50	Fast EMA period
InpSlowEMA	200	Slow EMA period
InpUseStructure	true	Add structure break confirmation to EMA signal
InpStructureLB	10	Lookback bars per half for structure comparison

Risk Management

Parameter	Default	Description
InpRiskPercent	1.0	Risk per trade as % of account balance
InpMaxTradesPerSym	1	Maximum simultaneous open trades per symbol
InpSL_ATR_Mult	2.5	Stop loss distance = ATR × this multiplier
InpTP1_RR	2.0	TP1 reward:risk ratio (2.0 = 1:2)
InpTP2_RR	3.0	TP2 reward:risk ratio
InpTP3_RR	4.0	TP3 reward:risk ratio
InpUseTP1Close	true	Close 33% of position at TP1
InpUseTP2Close	true	Close 33% of position at TP2
InpTrailAfterTP1	true	Activate trailing stop after TP1 is hit

Trade Filters

Parameter	Default	Description
InpRSIPeriod	14	RSI period for overbought/oversold filter
InpRSI_OB	70.0	RSI overbought level — suppresses buy signals above this
InpRSI_OS	30.0	RSI oversold level — suppresses sell signals below this

Parameter	Default	Description
InpUseFractals	true	Use fractal swing levels for limit entry placement
InpFractalLB	30	Fractal search lookback in bars
InpLimitFallback	0.5	ATR multiplier for fallback entry when no fractal found
InpCooldownBars	3	Minimum bars between signals on the same symbol

AutoTrading Circuit Breaker

Parameter	Default	Description
InpAutoDisableDD	true	Disable trading if account drawdown exceeds threshold
InpMaxDDPercent	10.0	Maximum allowed drawdown (%) before auto-disable

Driverline Indicator MW Advanced — Indicator Parameters

Asset Selection

Parameter	Default	Description
InpSymbol	(blank)	Leave blank to use current chart symbol. Or enter a specific symbol, e.g. EURUSD

Signal History Panel

Parameter	Default	Description
InpMaxSignalsChart	5	Maximum signal drawings kept on chart simultaneously
InpShowPanel	true	Show/hide the dual-panel dashboard
InpShowSignalLines	true	Draw entry/SL/TP level lines and arrows on chart

Shared Parameters (All Three Products)

These inputs appear identically in all three products:

Parameter	Default	Description
InpAlertPopup	true	Enable MT5 popup alert dialog
InpAlertEmail	false	Enable email alert (requires MT5 SMTP configuration)
InpAlertPush	false	Enable mobile push notification
InpMagicComment	DL_CT	Order comment prefix for trade history filtering
InpSuppressAlerts	false	Suppress all alerts in Tester / optimization mode

08

TROUBLESHOOTING

Common issues, causes and step-by-step solutions

❖ **Problem:** EA not placing orders**Cause:** AutoTrading is disabled OR license is invalid**Solution:**

1. Check the AutoTrading button in the MT5 toolbar — it must be GREEN.
2. Check the Experts tab in Terminal for license messages.
3. Verify InpLicenseKey is entered correctly with no extra spaces.
4. Ensure the account number in the license matches your current account.

❖ **Problem:** No signals firing in live trading**Cause:** Market conditions do not meet signal criteria**Solution:**

1. Ensure the score threshold is not too high (try InpSMC_MinScore = 2).
2. Check that at least 3 of 5 timeframes are enabled and aligned.
3. Verify symbols are in Market Watch and have live prices (bid/ask > 0).
4. Check the Experts tab for 'Skipping — no live price data' messages.

❖ **Problem:** [Invalid price] / [Invalid stops] errors in journal**Cause:** Entry or SL/TP violates broker's minimum stop distance**Solution:**

1. Switch InpExecMode to EXEC_MARKET — it auto-enforces stop distance.
2. Increase InpSL_ATR_Mult to 3.0 or higher.
3. The EA automatically adds a 5-point buffer but broker minimums vary.
4. Check SYMBOL_TRADE_STOPS_LEVEL in Market Watch for that symbol.

❖ **Problem:** Indicator shows '---' in the panel**Cause:** Indicator handles not ready / insufficient history**Solution:**

1. Wait 2–3 minutes after attaching — indicator handles need warmup time.
2. Press F5 to refresh the Navigator and re-attach if issue persists.
3. Ensure sufficient chart history is downloaded (Tools → History Centre).
4. For synthetic indices, ensure the symbol is selected in Market Watch.

❖ **Problem:** Email alerts not received**Cause:** SMTP settings incorrect or Gmail blocking**Solution:**

1. Re-check SMTP settings in Tools → Options → Email.
2. For Gmail, use an App Password (not your main password) — see Section 6.
3. Ensure port 465 is used for SSL, or 587 for TLS.
4. Check your spam folder — MT5 emails sometimes land there initially.

❖ Problem: Push notifications not arriving on phone**Cause:** MetaQuotes ID not matching / phone disconnected**Solution:**

1. Open MT5 mobile → Messages → verify MetaQuotes ID hasn't changed.
2. Ensure your phone has internet access and background app refresh enabled.
3. Re-enter the MetaQuotes ID in Tools → Options → Notifications and click Test.
4. Reinstall the MT5 mobile app if the ID appears blank or invalid.

❖ Problem: Validation score = 1 trade on MQL5 Marketplace**Cause:** Known issue with multi-symbol EAs in the validator**Solution:**

1. This is handled automatically — the EA restricts to chart symbol in tester.
2. The validator only has price data for the test symbol (EURUSD H1).
3. This is by design and does not affect live/demo trading performance.
4. Submit to the Marketplace — the single-symbol validation is expected.

❖ Problem: Driverline indicator panel not visible**Cause:** Chart zoom or panel position issue**Solution:**

1. Ensure InpShowPanel = true in indicator Inputs.
2. Scroll to the top-left of the chart — the panel anchors to CORNER_LEFT_UPPER.
3. Try pressing Ctrl+Z (undo) if you accidentally moved chart objects.
4. Remove and re-attach the indicator as a last resort.

SUPPORT & RESOURCES

We are here to help you succeed

MQL5

Marketplace

Product page, reviews, downloads,
rentals

Email

Direct Support

License issues, account re-issues

Guide

This Document

Re-read relevant section first

ChristocentricTrader Advanced • Driverline™ Engine • v3.0

This document is confidential and intended for licensed users only. Reproduction without permission is prohibited.