

HPE Performance Software — Message Passing Interface MPInside Reference Guide

Abstract:

This publication describes how to use the MPInside parameter to the mpiexec_mpt(1) command.

Part Number: 007-5780-005 Published: August 2017 Edition: Revision 5 © 2011, 2013-2014, 2016-2017, Hewlett Packard Enterprise Development LP

Notices

The information contained herein is subject to change without notice. The only warranties for Hewlett Packard Enterprise products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. Hewlett Packard Enterprise shall not be liable for technical or editorial errors or omissions contained herein.

Confidential computer software. Valid license from Hewlett Packard Enterprise required for possession, use, or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Links to third-party websites take you outside the Hewlett Packard Enterprise website. Hewlett Packard Enterprise has no control over and is not responsible for information outside the Hewlett Packard Enterprise website.

Acknowledgements

Excel, Microsoft, and Windows are registered trademarks or trademarks of Microsoft Corporation in the United States and/or othr countries.

Intel®, Intel® Itanium®, and Intel® Xeon® are registered trademarks of Intel Corporation or its subsidiaries in the U.S. and/or other countries.

Linux® is the registered trademark of Linus Torvalds in the U.S. and other countries.

NVIDIA® and the NVIDIA logo are trademarks and/or registered trademarks of NVIDIA Corporation in the U.S. and other countries.

Red Hat® and Red Hat® Enterprise Linux are registered trademarks of Red Hat, Inc., in the United States and other countries.

Record of Revision

Version	Description
001	June 2011 Original Printing.
002	November 2013 Rewrite to support MPInside 3.6.3.
003	May 2014 Revised to support MPInside 3.6.4.
004	May 2016 Revised to support MPInside 3.6.7.
005	August 2017 Supports the HPE Performance Software – Message Passing Interface 1.0 release, the HPE Performance Software – Message Passing Interface MPInside 4.0.0 release, and the MPT 2.16 release.

007–5780–005 iii

Contents

About This Documentation	•	•	•		•	X
HPE Performance Software Suite Publications and General MPI Information						X
HPE Websites						xii
Documentation Feedback		٠		•		xii
1. About MPInside					•	1
About Analyzing Program Performance With MPInside			•	•		1
About MPInside Overhead						2
Obtaining Additional MPInside Information						3
About Using a Spreadsheet Program with MPInside						4
Installing MPInside and Establishing the Computing Environment						4
Starting MPInside						5
About MPInside Terminology						6
About MPInside Environment Variables						8
2. Getting Started and Generating Default MPInside Reports	•					13
About Getting Started						13
About MPInside Example Programs						13
Analyzing a Program Using MPInside Defaults						14
Generating MPInside Statistics						14
Opening the mpinside_stats Report Within a Spreadsheet						15
Creating Graphics Within the Spreadsheet						16
(Optional) Creating Labels on the Spreadsheet's Charts						18
3. Comparing MPInside Statistics from Multiple Program Runs	S					19
007–5780–005						

νi

About Using Statistics From Multiple Program Runs			. 19
Gathering Data From Multiple Program Runs			. 19
Run 1 — Gathering Baseline Statistics			. 19
Run 2 — Simulating a Perfect Interconnect Environment			. 23
Run 3 — Analyzing the Amount of Time Spent Waiting			. 26
4. Using MPInside to Analyze Only Parts of a Program	•		. 29
Analyzing Subsets of a Program			. 29
5. Analyzing Call Stack Branches and Communication Stiffness .			. 35
About Call Stack Branches and Communication Stiffness			. 35
Interpreting the Call Stack Branch Output			. 35
Opening the Call Stack Branch Report			. 36
Branch Statistics			. 36
Ancestor Information			. 37
Partner Information			. 37
Branches With Partners			. 39
Branches Without Partners			. 39
Examples			. 40
Communication Stiffness			. 41
Generating Statistics to Analyze Call Stack Branches and Communication Stiffness			. 44
Run 1 — Obtaining Baseline Statistics			. 44
Run 2 — Simulating a Perfect Interconnect Environment			. 53
Run 3 — Evaluating Send Late Time			. 55
Run 4 — Examining the Call Stack Branches			. 57
Appendix A. MPInside Calculations			. 65
About MPInside and the Collective Functions			. 65
Interpreting the Statistics for the MPI_Bcast Collective Function	•	•	. 65

007-5780-005

HPE Performance Software -	 Message Passin 	g Interface	MPInside	Reference	Guide
-----------------------------------	------------------------------------	-------------	-----------------	-----------	-------

_																									
Index	•	•	•	•	•	•	•	•	•	•	•	•	•	•	•	•	•	•	•	•	•	•	•	•	67

007–5780–005 vii

Figures

Figure 1-1	Send Late Time	7
Figure 2-1	Stacked Area Plot — Running Times Per Rank of Various MPI Routines	17
Figure 5-1	Output for a Program With a Low Stiffness Rating	43
Figure 5-2	Output for a Program With a High Stiffness Rating	43

007–5780–005 ix

About This Documentation

This publication describes how to use the MPInside parameter to the mpiexec_mpt(1) command. When you use the MPInside parameter, you receive a report that contains an analysis of your MPI program

The default MPInside report, mpinside_stats, includes information about the time spent cumulatively in each MPI routine. This report also contains information about the amount of data transferred between ranks, in terms of both size and time.

The MPInside parameter interoperates with many environment variables that enable you to retrieve different types of data about your application. For example:

- An MPI program's performance problems often stem from a lack of synchronization during sends and receives. MPInside can help you determine which of the MPI send/receive pairs are not executing synchronously. MPInside measures this unsynchronized time for all of the MPI ranks and for all the MPI functions involved in the application. Its reports include information about the actual speeds the MPI engine attained during send/receive communication.
- MPInside reports can include information on a branch basis. A branch is an MPI function with all its ancestors in the calling sequence. MPInside provides the routine name and the source file line number for all the routines that define a branch.

HPE Performance Software Suite Publications and General MPI Information

The HPE Performance Software Suite Publications are as follows:

- The HPE Performance Software Message Passing Interface User Guide describes how to use the HPE Performance Software Message Passing Interface software.
- The HPE Performance Software Message Passing Interface MPInside Reference Guide describes how to use the MPInside parameter.
- The HPE Performance Software Message Passing Interface Cpuset Software Guide describes how to use cpusets.
- MPInside(3)

This man page lists all the MPInside environment variables that HPE supports.

007–5780–005 xi

• MPInside-exp(3)

This man page lists MPInside environment variables that HPE supports on an experimental basis. Use of these environment variables can generate unexpected results. The HPE Performance MPI documentation uses some of these experimental variables in examples and procedures.

- The HPE Performance Software Message Passing Interface release notes contain information about the specific software packages included in each product. The release notes are available in the following locations:
 - The HPE Performance MPI release notes are posted to the following SGI website:

https://support1-sgi.custhelp.com/app/answers/detail/a_id/6093

Note: To access documentation through the SGI customer portal, first log in, and then navigate to the link. You can log in at the following website:

https://support.sgi.com/login

- On the product media. The release notes reside in a text file in the /docs directory on the product media.
- On the system. After installation, the release notes and other product documentation reside in the

/opt/hpe/hpc/mpt/mpt-version_number/doc/README.relnotes directory.

For example, you can use the following rpm(8) command to retrieve the location of the Array Services release notes:

```
# rpm -qi sgi-arraysvcs
/usr/share/doc/packages/sgi-arraysvcs/README.relnotes
```

Use a text editor or other command to display the file that the ${\tt rpm}(8)$ command returns.

For information about the MPI standard, see the following:

 The Message Passing Interface Forum's website, which is as follows: http://www.mpi-forum.org/

xii 007–5780–005

- Using MPI 2nd Edition: Portable Parallel Programming with the Message Passing Interface (Scientific and Engineering Computation), by Gropp, Lusk, and Skjellum. ISBN-13: 978-0262571326.
- The University of Tennessee technical report. See reference [24] from *Using MPI: Portable Parallel Programming with the Message-Passing Interface*, by Gropp, Lusk, and Skjellum. ISBN-13: 978–0262571043.
- Journal articles in the following publications:
 - International Journal of Supercomputer Applications, volume 8, number 3/4, 1994
 - International Journal of Supercomputer Applications, volume 12, number 1/4, pages 1 to 299, 1998

HPE Websites

The following HPE websites might interest you:

- Hewlett Packard Enterprise Information Library: www.hpe.com/info/EIL
- Single Point of Connectivity Knowledge (SPOCK) Storage compatibility matrix: www.hpe.com/storage/spock
- Storage white papers and analyst reports: www.hpe.com/storage/whitepapers

Documentation Feedback

Hewlett Packard Enterprise is committed to providing documentation that meets your needs. To help us improve the documentation, send any errors, suggestions, or comments to Documentation Feedback (docsfeedback@hpe.com). When submitting your feedback, include the document title, part number, edition, and publication date located on the front cover of the document. For online help content, include the product name, product version, help edition, and publication date located on the legal notices page.

007–5780–005 xiii

About MPInside

This chapter contains the following topics:

- "About Analyzing Program Performance With MPInside" on page 1
- "About MPInside Overhead" on page 2
- "Obtaining Additional MPInside Information" on page 3
- "About Using a Spreadsheet Program with MPInside" on page 4
- "Installing MPInside and Establishing the Computing Environment" on page 4
- "Starting MPInside" on page 5
- "About MPInside Terminology" on page 6
- "About MPInside Environment Variables" on page 8

About Analyzing Program Performance With MPInside

The MPInside parameter invokes a Message Passing Interface (MPI) profiling tool. You can use MPInside to analyze the performance of an MPI application. MPInside provides information about the MPI communications. MPInside analyzes the process send actions and the process receive actions and generates data that reveals how closely the send and receive actions are synchronized. When you analyze the data, you can determine the areas in the application upon which you want to focus your optimization efforts.

As with any performance analysis tool, remember that MPInside provides data, hints, and clues. You need an initial hypothesis of your own to guide your path of inquiry. The statistics that MPInside generates can back up or disprove your hypothesis. Your own hypothesis combined with the data from multiple MPInside runs can guide you toward analyzing and modifying your program. When you run MPInside multiple times with different settings, the differences in the output can guide your tuning.

The information that MPInside generates includes the following:

- The size of each data request
- The number of data requests

- The size of the communicator used for MPI collective functions
- The number of times that each rank was the root of a collective function

For the preceding statistics, MPInside reports the size as the sum total for the full run.

MPInside can also provide more advanced information. For example, you can use MPInside to answer "what if" questions, such as what if the MPI environment (library and hardware) were perfect? That is, what if bandwidth were infinite and latency were zero? MPInside can also provide information about the relative lateness of a send posting with regard to the receive posting.

MPInside reports its timings on a *call stack branch*, or simply *branch*, basis. A branch is a sequence of calls. Specifically, a branch is an MPI function and all of its ancestors in the calling sequence. To analyze a program's branches, use the MPInside post processor called MPInside_post. For each rank, MPInside generates reports named mpinside_clstk.rank, where rank is the number of the rank. When you run the MPInside_post command, it generates reports named mpinside_clstk_post.rank, where rank is the number of the rank. The MPInside reports include the routine name for all the routines that define a branch. If you compile the program with -g, the reports also includes source line numbers.

For each CPU's branch that had a send/receive partnership with another CPU's branches, MPInside generates information about each send/receive partnership. MPInside defines each partner set with the following four numbers:

- Sending rank number
- · Sending CPU branch identification
- Percentage of time accounted to the partnership, in relation to the total execution wait time of the receiving branch
- Percentage of execution wait time attributed to the lack of synchronization

About MPInside Overhead

As with all profiling tools, MPInside generates some overhead when it runs. The overhead incurred with MPInside is negilible.

For example, problems occur if the application calls the MPI_Wait function billions of times with a null MPI_REQUEST_NULL request. With a null request, the MPI library returns to the application in about 0.2 microseconds, so these calls add approximately

200 seconds. Even when MPInside runs as lightly as possible, MPInside calls the timer upon entry and exit. MPInside updates the counter based on these two calls. For one instance, it takes about 0.3 microseconds to update the counter, so this action adds approximately 300 seconds. In this case, the action of updating the counter is more intrusive and more complicated than checking if the request is null, and that is what the MPI library is doing. In cases such as this, the program incurs approximately 500 seconds for the MPI_Wait function, and MPInside overhead is bigger than just the MPI function itself.

Check the size and request statistics gathered during the basic run, and use that information to find the problems in the application. When you examine your program in light of the existing statistics, make sure that the program does not call MPI Wait billions of times with a null request.

Obtaining Additional MPInside Information

In addition to this manual, you might want to examine the online information about MPI and MPInside.

The MPI and MPInside man(1) pages are as follows:

- MPI(1), which introduces the Message Passing Interface (MPI). This man(1) page is available in the HPE Performance Software — Message Passing Interface (HPE Performance MPI) software package. This man(1) page is not included in the MPI standard.
- MPInside(3), which introduces the MPInside parameter and explains the environment variables that you can set when you use MPInside.
- MPInside-exp(3), which lists environment variables that interoperate with the MPInside parameter. These are environment variables that HPE supports on an experimental basis. Use of these environment variables can generate unexpected results. The MPInside documentation uses some of these experimental variables in examples and procedures.
- mpiplace(1), which is a data placement tool.

In addition, the command help ouput contains some feature and usage information.

You can type the following commands to retrieve extended help output:

• pram -h

• MPInside post -h

About Using a Spreadsheet Program with MPInside

Because of the large amount of statistics that MPInside generates, HPE recommends that you use a spreadsheet program as an aid to understanding. HPE does not endorse or recommend any particular spreadsheet program, but the examples in this documentation use Microsoft Excel 2010.

Installing MPInside and Establishing the Computing Environment

MPInside is part of the HPE Performance Software — Message Passing Interface (HPE Performance MPI) software suite. The HPE Performance MPI installation process installs MPInside along with the rest of the HPE Performance MPI software.

The following procedure establishes the computing environment and ensures that you can retrieve the MPInside man(1) pages.

Procedure 1-1 To establish the computing environment

- 1. Log into your system.
- 2. Ensure that MPInside, at its current release level, is included in the list of directories that include executable programs.

The following example command displays the content of the \$PATH variable and shows that MPInside/version is not in the path:

% echo \$PATH

/opt/hpe/hpc/mpt/mpt-2.16/bin:/usr/local/bin:/usr/bin:/usr/bin:/usr/bin/X11:/usr/games

The following example commands add MPInside/4.0.0 to the \$PATH variable and verify success:

% module load MPInside/4.0.0

% echo \$PATH

/opt/hpe/hpc/MPInside/4.0.0/bin:/opt/hpe/hpc/mpt/mpt-2.16/bin:/usr/local/bin:
/usr/bin:/usr/bin/X11:/usr/games

To use a different release level, replace 4.0.0 with the release level you want to use.

3. Ensure that you can retrieve man(1) pages related to MPInside.

For example, the following commands show the correct paths to MPInside man(1) pages in the \$LD_LIBRARY_PATH variable and in the \$MANPATH variable:

% echo \$LD_LIBRARY_PATH

/opt/hpe/hpc/MPInside/4.0.0/lib:/opt/hpe/hpc/mpt/mpt-2.16/lib

% echo \$MANPATH

/opt/hpe/hpc/MPInside/4.0.0/man:/opt/hpe/hpc/mpt/mpt-2.16/man:/usr/share/man:
/usr/share/catman:/usr/catman:/usr/man

Starting MPInside

You can generate an MPInside report without recompiling or relinking your program. By default, MPInside creates a report called mpinside_stats. When you open the mpinside_stats report from inside a spreadsheet program, you can see the data displayed as a series of tables. When you convert the tables to graphics, it is easy to see the amount of time the program spends on communication.

The following procedure explains how to start MPInside.

Procedure 1-2 To start MPInside

1. (Conditional) Load the HPE Performance MPI libraries.

Complete this step if your MPI implementation is HPE Performance MPI.

The command is as follows:

- % module load mpt
- 2. Use the mpiexec mpt(1) command to start MPInside.

The mpiexec_mpt(1) command is designed for use in batch environments. The mpiexec mpt(1) command has the following format:

mpiexec_mpt -np processes MPInside program_name [program_args]

The arguments are as follows:

- For *processes*, specify the number of ranks used by the application.
- For *program_name*, specify the name of the binary program you want to analyze. The program must have been compiled. For example: a.out.

For program_args, specify any optional arguments that the program requires.

The mpiexec_mpt(1) command in this step is part of the HPE Performance MPI MPT package. Your implementation might have different commands, but you can still use the MPInside argument to generate MPInside statistics.

3. Analyze the information in the mpinside stats output file.

For information, see the following:

Chapter 2, "Getting Started and Generating Default MPInside Reports" on page 13

For example, in an HPE Performance MPI environment, to generate default MPInside statistics, run your compiled program and include the MPInside parameter on the mpiexec_mpt command line, as follows:

```
% module load mpt
% mpiexec mpt -np 128 MPInside ./a.out arg1
```

If your MPI environment is not HPE Performance MPI, use the MPINSIDE_LIB environment variable to load experimental, nondefault, package-specific libraries. The examples in this manual show how to use the MPINSIDE_LIB environment variable.

Note: HPE supports the following as experimental technology: the MPINSIDE_LIB environment variable, the X86 Intel MPI library, and the OpenMPI library. Use of this software can generate unexpected results.

About MPInside Terminology

The MPInside documentation and the MPInside reports use the following terms:

Function time The time before the call to the MPI function minus the

time when returning to the application. This time is equal to send late time + transfer time in Figure 1-1 on

page 7.

Transfer time The time when the data is actually being transferred

(see Figure 1-1 on page 7).

Function waiting time In Figure 1-1 on page 7, this time is equal to the

function time because MPI Recv is a blocking function.

For a nonblocking function, such as MPI_Irecv, function wait time is the time of the MPI_Wait function that "finished" the request (in the MPI sense) corresponding to this function.

Send late time (SLT)

Figure 1-1 on page 7 shows unsynchronized communication between a send/receive pair. In this communication, Rank 0 issues an MPI_Recv request at T_1 , but Rank 1 does not begin to send the data until T_2 . The time difference between T_2 and T_1 is called *send late time* (SLT). The actual send time is T_3 – T_2 . Network latency can affect SLT and send time.

In theory, there is a small amount of time between when Rank 1 starts the MPI_Send and when Rank 0 receives the first data item, but because this amount of time is negligible, this documentation does not address or acknowledge this time.




Figure 1-1 Send Late Time

Branch

A *branch* is a sequence of function calls in a user application that is terminated by an MPI function. A branch has a unique identification number. Such a number could differ from one CPU to the other even if both refer to exactly the same sequence of calls. The

007-5780-005

identification depends on the order they are encountered in the MPInside library.

For more information about branches, run the MPInside_post command after an MPInside run, and examine the mpinside_clstk_post.rank reports from an MPInside run.

About MPInside Environment Variables

The MPInside parameter interoperates with many environment variables that you can use to modify the default MPInside behavior. The MPInside documentation shows examples that use these environment variables to generate different types of MPInside reports. The MPInside(3) man page lists all the MPInside environment variables that are available to you.

Note: Depending on the shell you use, you might need to export the environment variables after you declare them. The examples in this manual do not show an export step. Consult your shell documentation for information about how to export variables.

The following list summarizes the environment variables that are used in the examples in this documentation:

• MPINSIDE CALLSTACK DEPTH integer_number

Unwinds the branch call stack to a depth of <code>integer_number</code>, and writes branch information and statistics to files named <code>mpinside clstk.rank</code>.

A *branch* is an MPI function and all of its ancestors in the calling sequence. The additional reports, one for each rank number, contain information about all the branches that end with a call to an MPI routine.

• MPINSIDE CROSS REFERENCE

When set along with MPINSIDE_CALLSTACK_DEPTH, this variable specifies that call stack branches include data about the ranks that participated on each end of the MPI routine. The additional cross referencing output includes the following:

- The total communication time attributable to the partner on each end of a given branch
- The total send late time for each branch/partner pair

• MPINSIDE EVAL COLLECTIVE WAIT

Specifies that MPInside perform the following tasks:

- Insert an MPI Barrier function before all MPI collective operations
- Record the time elapsed for the MPI Barrier function
- MPINSIDE EVAL SLT

Directs MPInside to measure the time for all send actions that are late (send late time (SLT)) compared to the MPI Recv-MPI Wait arrivals.

• MPINSIDE LITE

Reduces MpInside overhead to the absolute minimum. MpInside overhead is minimal in most environments, but when you use the MpInside_LITE environment variable, MpInside reduces its overhead to very minimal levels. This mode of operation can be useful for programs that perform many, small-sized function calls. The resulting report include timings but not size or request information.

Note: HPE supports the MPINSIDE_LITE environment variable as an experimental environment variable. Use of this environment variable can generate unexpected results.

• MPINSIDE MATRICES

Directs MPInside to print the transfer topology matrix files.

• MPINSIDE MODEL

Instructs MPInside to generate statistics that model how the program would perform in an environment with zero latency, infinite bandwidth, and no time spent in the MPI routines. This output is useful because it shows how much faster a program could run if each rank did the same computational work but adopted a more efficient communication pattern or ran on a system with better networking hardware.

• MPINSIDE OUTPUT PREFIX

Enables you to specify a custom prefix for the MPInside output report. By default, MPInside writes its report to mpinside_stats in the run directory. When you specify this environment variable, you can specify a full path to a

different directory, or you can specify a prefix other than mpinside. This environment variable is useful if you want to run MPInside several times and write the report to a differently named report each time.

• MPINSIDE PRINT ALL COLUMNS

Prints columns of MPInside statistics with a value of zero (0) when zero values are generated. By default, MPInside suppresses columns that contain all zeros. When this variable is set, MPInside output includes all columns of statistics that pertain to the environment variables that you set. Use this variable if you want to make sure that a particular column is printed. For example, if you want to run MPInside more than once, use this variable for each run. When you set this variable, you ensure that the output contains the same columns of data for all runs.

• MPINSIDE PRINT DIRTY

Prints data with full precision but no formatting. The report appears poorly formatted if you open it in an editor such as vi(1), but you can import the report into a spreadsheet with readable results.

• MPINSIDE SHOW READ WRITE

Generates additional columns in the MPInside report. These columns show the time, number of characters, and number of calls to libc I/O functions such as read(), write, open, and fread that the program calls directly. If the application calls one of the MPI I/O functions, such as MPI_File_read_at(), setting this variable causes MPInside to include information about the MPI File xxx functions in an additional set of five arrays.

To set this environment variable, specify a 1 as its argument or, for extended I/O reporting, specify a string of file names. For information about how to specify the string, see MPInside(3).

Note: HPE supports the MPINSIDE_SHOW_READ_WRITE environment variable as an experimental environment variable. Use of this environment variable can generate unexpected results.

MPINSIDE SIZE DISTRI

Generates a table that shows the total number of requests that the program generated at a given size for each type of MPI communication. Options to this environment variable enable you to generate a table that shows the total time spent per each request size and each type of communication.

The preceding list defines each of the environment variables very briefly. For more information, see the ${\tt MPInside}(3)$ man page.

Getting Started and Generating Default MPInside Reports

This chapter contains the following topics:

- "About Getting Started" on page 13
- "About MPInside Example Programs" on page 13
- "Analyzing a Program Using MPInside Defaults" on page 14

About Getting Started

The MPInside reports, mpinside_stats, mpinside_clstk.rank, and mpinside_clstk_post.rank, contain many statistics. MPInside writes these files as tab-separated text files.

Because the reports contain so many statistics, HPE recommends that you open the reports from within a spreadsheet. The example in this chapter explains how to generate a default mpinside_stats report and open it from within a spreadsheet.

The MPInside documentation shows how to open the mpinside_stats file from within Microsoft Excel 2010 on a Windows operating system, but you can use any spreadsheet program. On Linux platforms, you can open the reports in some spreadsheet programs by dragging and dropping the output file into an open spreadsheet program.

About MPInside Example Programs

HPE includes MPI examples and a script in the following directory:

/usr/share/doc/packages/MPInside-version_number/examples

The examples directory contains the following:

• A README file, which contains information about the example test provided and the output that it generates.

- The osu_allgather binary, which is an open source MPI latency microbenchmark.
- The osu allgather.c, which is the source file for the osu allgather binary.
- The collect_osu_allgather_statistics.sh script, which generates four files. The first is the mpinside_stats report. The second file contains rank-to-rank communication matrixes. The script also generates two call stack reports, one for each rank.

You can run the script interactively or you can submit it to a batch scheduler that is compatible with PBS. You can use this file to generate an MPI report for your own applications by replacing <code>osu_allgather</code> with the name of your application and setting the number of ranks appropriately.

When you run the script, it generates output files in the current working directory.

Analyzing a Program Using MPInside Defaults

The following procedures show how to run MPInside with your program and how to obtain a simple set of output statistics:

- "Generating MPInside Statistics" on page 14
- "Opening the mpinside stats Report Within a Spreadsheet" on page 15
- "Creating Graphics Within the Spreadsheet" on page 16

Generating MPInside Statistics

The MPInside analysis does not require you to recompile or relink your program. The following procedure explains how to run an MPI program and request MPInside statistics.

Procedure 2-1 To generate MPInside statistics

- 1. Type the following command to load the MPInside module:
 - % module load MPInside
- 2. (Optional) Set environment variables.

MPInside supports many environment variables. The environment variables affect the MPInside output with regard to formatting, comprehensiveness, file naming, and other aspects of performance analysis.

For information about the MPInside environment variables, see the MPInside(3) man page.

3. Type the mpiexec mpt command in the following format:

```
mpiexec mpt -np processes MPInside program_name [program_args]
```

For processes, specify the number of ranks used by the application.

For *program_name*, specify the name of the binary program you want to analyze. The program must have been compiled. For example: a.out.

For *program_args*, specify any arguments that the program requires. These arguments are optional and are not required by MPInside.

4. Verify that the mpiexec_mpt command finished, and locate the following file in the mpinside stats working directory.

By default, the report is named mpinside_stats. You can use the MPINSIDE_OUTPUT_PREFIX environment variable to specify a prefix other than mpinside.

5. Copy the mpinside_stats report to the computer that hosts the spreadsheet program you want to use.

Opening the mpinside stats Report Within a Spreadsheet

The following procedure explains how to open the mpinside_stats report within Microsoft Excel 2010.

Procedure 2-2 To open the mpinside stats report

- 1. Open the spreadsheet program.
- 2. Within the spreadsheet program, click **Data** > **From Text**.
- 3. On the **Import Text File** page, select **All files (*.*)** from the pull-down menu.
- 4. Navigate to and select the mpinside_stats report.
- 5. Click Import.

- 6. On the **Text Import Wizard Step 1 of 3** pop-up window, select **Delimited**, and click **Next**.
- On the Text Import Wizard Step 2 of 3 pop-up window, select Tab, and click Next.

Make sure that all the other boxes in this window are clear.

- 8. On the **Text Import Wizard Step 3 of 3** pop-up window, accept the defaults, and click **Finish**.
- 9. On the **Import Data** pop-up window, make sure that **Existing Worksheet** is selected, and click **OK**.

Creating Graphics Within the Spreadsheet

MPInside creates a large volume of data. It is easier to detect problem areas in your program if you create graphics within the spreadsheet. You can create a graphic from any data set in the spreadsheet. The example in this topic creates a graphic from the data for the first array.

The following procedure explains how to create graphics from the data in the mpinside_stats report within a spreadsheet program.

Procedure 2-3 To create graphics

1. Locate the data for the first array.

For example, in Microsoft Excel, complete the following steps:

- Press CTRL-f.
- Type CPU in the pop-up window's search field.
- Click Find Next.

This action positions the cursor in the CPU cell for the first array.

Within the spreadsheet, each column head is an abbreviation for an MPI function. At the top of the report, you can see an explanation for each column head.

2. Select all the data for the first array and create a graph.

In this step, your goal is to select all the columns from the **Compute** column through the rightmost column. The orientation of the resulting graphic should be rectangular (horizontal). For example:




Figure 2-1 Stacked Area Plot — Running Times Per Rank of Various MPI Routines

You can drag your mouse to highlight all the rows and columns of data, but if you have a lot of data, this can be error-prone and tedious.

To highlight all the data automatically, put your cursor in the **Compute** cell, and press the following keys simultaneously: Shift + End + down arrow.

007-5780-005

If this key combination does not work automatically, press Shift + End + down arrow to highlight all the rows, and then press Shift + End + right arrow to highlight all the columns.

- Click Insert > Area.
- 4. In the 2-D Area, click the Stacked Area icon.

The **Stacked Area** icon is the middle icon in the **2-D Area** row. If you hover over the middle icon, the **Stacked Area** label appears.

5. (Conditional) Reset the chart axes.

Complete this step if your chart data is difficult to analyze.

Depending on the spreadsheet program you use, your chart might have the wrong axes. Complete the following steps to flip the axes and display a more useful chart:

- Right click in the chart you created, and select **Select Data**.
- On the Select Data Source pop-up, click Switch Row/Column and click OK.

(Optional) Creating Labels on the Spreadsheet's Charts

Complete this procedure if you want to create labels on the charts you create within the spreadsheet.

The following procedure explains how to create labels on the Microsoft Excel 2010 charts within a spreadsheet.

Procedure 2-4 To create labels on the charts

- 1. Click in one of the charts you created.
- 2. Select one of the chart layouts from the Microsoft Excel ribbon.

For example, select Layout 6.

- 3. Click the **Chart Title** placeholder label, and type a name for your chart.
- 4. Click the **Axis Title** placeholder label, and type a name for the X axis. For example, MPI Ranks.
- 5. In the Category (Y) axis field, type a label. For example, Elapsed Time in Seconds.

Comparing MPInside Statistics from Multiple Program Runs

This chapter contains the following topics:

- "About Using Statistics From Multiple Program Runs" on page 19
- "Gathering Data From Multiple Program Runs" on page 19

About Using Statistics From Multiple Program Runs

MPInside interoperates with environment variables that you can use to modify MPInside's default output. For example, you can use these environment variables to model a different execution environment, to generate additional statistics, or to rename the report. When you use different environment variables for each program run, each program run generates slightly different statistics. When all the program runs are complete, you can compare the statistics.

This chapter contains a large example that shows how to use different environment variables for different programming runs to generate a suite of statistics for you to examine.

Gathering Data From Multiple Program Runs

The following topics each show one part of a large example that collects statistics from an MPI program over several program runs:

- "Run 1 Gathering Baseline Statistics" on page 19
- "Run 2 Simulating a Perfect Interconnect Environment" on page 23
- "Run 3 Analyzing the Amount of Time Spent Waiting" on page 26

Run 1 — Gathering Baseline Statistics

In this initial run, your goal is to gather statistics from a typical run in your typical programming environment.

The following procedure explains the environment variables to use when you run MPInside for the first time.

Procedure 3-1 To run MPInside

- 1. Type the following command to load the MPInside module:
 - % module load MPInside
- 2. Rename the MPInside report.

By default MPInside writes to the mpinside_stats report. If you want to run MPInside only once, there is no need to rename the report. However, in this example, you want to run MPInside multiple times and compare the results. In this case, if you permit MPInside to use the default report name, MPInside overwrites the mpinside_stats report in its successive runs. To preserve each successive run in a separate file, use different names for the report in each run.

Type the following command to rename the MPInside report to mpinside_baseline_stats:

- % setenv MPINSIDE OUTPUT PREFIX mpinside baseline
- 3. Type the following command to generate statistics on the request sizes:
 - % setenv MPINSIDE_SIZE_DISTRI T+12:0-11

By default, MPInside runs with the following specification: MPINSIDE_SIZE_DISTRI 12:0--0, and the statistics that MPInside generates show the accumulated total request sizes for all calls for rank zero (0). In this step, you specify the following:

T+ Generates additional statistics that describe how much time each type of MPI communication spent in transmitting or receiving a given request size. The statistics show the timings of the MPI functions, split by size. These statistics can expose bottlenecks in the program that occur for particular request sizes. The resulting statistics appear in a table with two axes, one for the communication type and one for the request size. You can look at both axes to determine the cause of an application's slowness. These statistics appear in the report after the request sizes.

In the transmission time report, time spent in MPI_Wait, MPI Waitall, MPI Waitany, and MPI Waitsome is added into

the row and column that corresponds to the previous nonblocking communication request, such as an MPI Isend, MPI Irecv call.

If the T+ option is not supplied, the MPInside statistics do not include the time spent in calls to MPI wait or MPI waitall.

- Specifies the number of rows in the report, excluding the row at the bottom that tabulates requests of size zero.
- 0-11 Includes statistics for ranks *first-last* in the report. In this example, you request statistics for 12 ranks. If you have 16 ranks and you want statistics for all ranks, specify 0-15.
- 4. Type the following commands to set additional environment variables:

```
% setenv MPINSIDE_SHOW_READ_WRITE
% setenv MPINSIDE PRINT ALL COLUMNS
```

% setenv MPINSIDE PRINT DIRTY

Note: HPE supports the MPINSIDE_SHOW_READ_WRITE environment variable as an experimental environment variable. Use of this environment variable can generate unexpected results.

5. (Conditional) Set the MPINSIDE_LIB environment variable to your MPI implementation.

Complete this step if your MPI implementation is something other than the HPE Performance Software — Message Passing Interface (HPE Performance MPI) implementation. The default setting is <code>MPINSIDE_LIB MPT</code>, which assumes that HPE Performance MPI is your MPI implementation.

If you use an implementation that is not the HPE Performance MPI implementation, type the one command from the following list that pertains to your implementation:

Command

MPI Implementation

% setenv MPINSIDE LIB IMPI

X86 Intel MPI

% setenv MPINSIDE LIB OPENMPI

OpenMPI

Note: HPE supports the following as experimental technology: the MPINSIDE_LIB environment variable, the X86 Intel MPI library, and the OpenMPI library. Use of this software can generate unexpected results.

6. Type the mpiexec mpt command in the following format:

```
mpiexec_mpt -np processes MPInside program_name [program_args]
```

For *processes*, specify the number of ranks used by the application.

For *program_name*, specify the name of the binary program you want to analyze. The program must have been compiled. For example: a.out.

For *program_args*, specify any arguments that the program requires. These arguments are optional and are not required by MPInside.

7. (Conditional) Repeat this programming run with a smaller set of environment variables.

Complete this step only if the preceding run completed in an excessively long period of time and you suspect that MPInside introduced overhead.

In most cases, MPInside incurs negligible overhead. However, if you notice that your program's run took noticeably longer to complete when MPInside was invoked, you might want to get an additional run. In this additional run, invoke MPInside with only minimal environment variables.

Make sure to retain the mpinside_baseline_stats report file. You do not want to overwrite mpinside_baseline_stats because it includes important information about the size and number of requests for which overhead does not matter. Type the following commands to repeat the programming run and request minimal MPInside operations:

• Load the MPInside module:

% module load MPInside

Specify the report name:

\$ setenv MPINSIDE_OUTPUT_PREFIX mpiniside_lite

- Specify minimal overhead:
 - % setenv MPINSIDE_LITE
- (Conditional) Specify your MPI library:
 - % setenv MPINSIDE LIB $oldsymbol{lib}$

This step is not needed if your library is HPE Performance MPI. The default *lib* is MPT. An earlier step in this procedure shows the nondefault *lib* specifications.

- Run the program with MPInside:
 - % mpiexec mpt -np processes MPInside program_name [program_args]

If this run, with MPINSIDE_LITE specified, is still noticeably longer than a run without MPInside involvement, you need to consider programming problems.

With a null request, the MPI library could return to the application in tens or hundreds of nanoseconds. For such calls, MPInside's accounting can take more processing time than the actions of the MPI library that you wanted to track. If these calls make up a substantial amount of the total MPI calls in your program, you might end up with an unrealistically long running time due to MPInside overhead, even when running in lite mode.

Note: HPE supports the following as experimental technology: the MPINSIDE_LITE environment variable and the MPINSIDE_LIB environment variable. Use of this software can generate unexpected results.

Run 2 — Simulating a Perfect Interconnect Environment

If the programming environment had a perfect network and perfect hardware, you might expect all message passing to occur perfectly, with no waiting. When you complete this run, you simulate a perfect environment. This run simulates the amount of waiting that occurs because of unbalanced loads, and that is independent of the MPI engine.

The following procedure explains the environment variables to use when you run MPInside for the second time.

Procedure 3-2 To run MPInside

- 1. Type the following command to load the MPInside module:
 - % module load MPInside
- 2. Type the following command to rename the MPInside report to mpinside_perfect_stats:
 - % setenv MPINSIDE_OUTPUT_PREFIX mpinside_perfect
- 3. Type the following command to specify the modeling of a perfect execution envionment:
 - % setenv MPINSIDE MODEL PERFECT+1.0

This environment variable uses the following parameter:

PERFECT+1.0 The 1.0 specifies that you want the CPU to run in

its typical mode, as you would expect it to run.

If you set this higher, for example, to 1.2, MPInside simulates a CPU that is 20% faster.

If you set this lower, for example, to 0.8, MPInside simulates a CPU that is 20% slower, or $\frac{1}{2}$

80% of its typical speed.

4. Type the following command to direct MPInside to print the transfer topology matrix files:

```
% setenv MPINSIDE_MATRICES EXA:-B:S
```

This environment variable uses the following parameters:

Includes the exact point-to-point transfers implied by the collective functions in the matrix files. Specify this parameter only when running with the HPE Performance MPI library. If you load your program with libraries other than the HPE Performance MPI library, use the PLA parameter.

- -B Include matrix files in the output in binary format only.
- S Separates the collective functions and the point to point matrices in the binary output.
- 5. (Conditional) Merge collectives and point-to-point matrixes into binary files.

Complete this step if you did not use the HPE Performance MPI libraries to compile your program.

The command is as follows:

- % setenv MPINSIDE MATRICES P2P:-B:M
- 6. Type the following commands to set additional environment variables:

```
% setenv MPINSIDE SHOW READ WRITE
```

- % setenv MPINSIDE PRINT ALL COLUMNS
- % setenv MPINSIDE PRINT DIRTY

Note: HPE supports the MPINSIDE_SHOW_READ_WRITE environment variable as an experimental environment variable. Use of this environment variable can generate unexpected results.

7. (Conditional) Set the MPINSIDE_LIB environment variable to your MPI implementation.

Complete this step if your MPI implementation is something other than HPE Performance MPI. The default setting is ${\tt MPINSIDE_LIB}$ ${\tt MPT}$, which assumes that HPE Performance MPI is your MPI implementation.

If you use an implementation that is not the HPE Performance MPI implementation, type the one command from the following list that pertains to your implementation:

Command	MPI I	mplementation
---------	-------	---------------

왕	setenv	${\tt MPINSIDE_LIB}$	IMPI	X86 Intel MPI
%	setenv	MPINSIDE_LIB	OPENMPI	OpenMPI

Note: HPE supports the MPINSIDE_LIB environment variable as experimental technology. Use of this software can generate unexpected results.

8. Type the mpiexec mpt command in the following format:

```
mpiexec_mpt -np processes MPInside program_name [program_args]
```

For *processes*, specify the number of ranks used by the application.

007-5780-005

For *program_name*, specify the name of the binary program you want to analyze. The program must have been compiled. For example: a.out.

For program_args, specify any arguments that the program requires.

Do not try to compare the statistics in this programming run's mpinside_perfect_stats report with the true time elapsed during the programming run. The MPInside times are simulated times, and MPInside performs more computations when it simulates a perfect environment

For example, if you pass the entire <code>mpiexec_mpt</code> command in this step to the <code>time(1)</code> command, the <code>time(1)</code> command returns the time elapsed during this <code>MPInside</code> programming run. Do not compare the timings in <code>mpinside_perfect_stats</code> with the output from the <code>time(1)</code> command.

Run 3 — Analyzing the Amount of Time Spent Waiting

In a perfect environment, CPUs would work constantly. The CPUs would pass data to each other as smoothly as the first runner in a relay race passes a baton to the next runner on the team. However, a CPU sometimes has to wait until the information in another CPU is available to be transferred. The run in this topic enables you to analyze the amount of time the CPUs spend waiting.

The following procedure explains the environment variables to use when you run MPInside for the wait analysis.

Procedure 3-3 To run MPInside

- 1. Type the following command to load the MPInside module:
 - % module load MPInside
- 2. Type the following command to rename the MPInside report to mpinside slt stats:
 - % setenv MPINSIDE OUTPUT PREFIX mpinside slt
- 3. Type the following commands to set environment variables:

```
% setenv MPINSIDE_EVAL_COLLECTIVE_WAIT
% setenv MPINSIDE_EVAL_SLT
% setenv MPINSIDE_SHOW_READ_WRITE
% setenv MPINSIDE_PRINT_ALL_COLUMNS
% setenv MPINSIDE_PRINT_DIRTY
```

Note: HPE supports the MPINSIDE_SHOW_READ_WRITE environment variable as an experimental environment variable. Use of this environment variable can generate unexpected results.

4. (Conditional) Set the MPINSIDE_LIB environment variable to your MPI implementation.

Complete this step if your MPI implementation is something other than HPE Performance MPI. The default setting is MPINSIDE_LIB MPT, which assumes that HPE Performance MPI is your MPI implementation.

If you use an implementation that is not the HPE Performance MPI implementation, type the one command from the following list that pertains to your implementation:

Command MPI I	mplementation
---------------	---------------

% setenv MPINSIDE_LIB IMPI X86 Intel MPI % setenv MPINSIDE_LIB OPENMPI OpenMPI

Note: HPE supports the MPINSIDE_LIB environment variable as experimental technology. Use of this software can generate unexpected results.

5. Type the mpiexec mpt command in the following format:

mpiexec mpt -np processes MPInside program_name [program_args]

For *processes*, specify the number of ranks used by the application.

For *program_name*, specify the name of the binary program you want to analyze. The program must have been compiled. For example: a.out.

For *program_args*, specify any arguments that the program requires.

007-5780-005

Using MPInside to Analyze Only Parts of a Program

This chapter contains the following topic:

"Analyzing Subsets of a Program" on page 29

Analyzing Subsets of a Program

In some cases, you do not need to, or want to, run MPInside against the entire application from MPI_Init() to MPI_Finalize(). This might be the case if you have already used MPInside to isolate programming problems and have determined the parts of your program that you want to change. You can also use the information in this topic if you are responsible for only parts of a program, not the entire program.

To create a targeted MPInside analysis, insert MPInside calls into your program and recompile your program. When the program runs, MPInside generates statistics for only the parts of the program that require deeper analysis. The set of calls you need to use depends on how much of your program you want MPInside to analyze.

The following procedure explains how to enable and disable the MPInside analysis to produce a targeted analysis.

Procedure 4-1 To reduce the amount of MPInside analysis

1. Determine the scope of the analysis that is needed.

Does one large part of your program require analysis? You can divide a program like this into three areas, as follows:

```
Initialization — no analysis needed
Computation — analysis needed
Finalization — no analysis needed
```

Do many small parts of your program require analysis? You can divide a program like this into two or more small areas, as follows:

```
Initialization — no analysis needed
Computation phase 1 — analysis needed
Computation phase 2 — no analysis needed
Computation phase 3 — analysis needed
```

```
Computation phase 4 — no analysis needed
Computation phase 5 — analysis needed
Finalization — no analysis needed
```

2. Open your program file and insert function calls to MPInside.

For a program with one large part that needs analysis, insert calls as follows:

· For a C program:

```
Initialization
(void) mpinside_start();
Computation — analysis needed
(void) mpinside_end();
Finalization
```

• For a Fortran program:

```
Initialization
Call mpinside_start
Computation — analysis needed
Call mpinside_end()
Finalization
```

For a program with many small parts that need analysis, insert calls as follows:

• For a C program:

```
Initialization — no analysis needed (void) mpinside_start();
Computation phase 1 — analysis needed mpinside_suspend()
Computation phase 2 — no analysis needed mpinside_resume()
Computation phase 3 — analysis needed mpinside_suspend()
Computation phase 4 — no analysis needed mpinside_resume()
Computation phase 5 — analysis needed (void) mpinside_end();
Finalization — no analysis needed
```

• For a Fortran program:

Initialization — no analysis needed

Call mpinside_start
Computation phase 1 — analysis needed
Call mpinside_suspend()
Computation phase 2 — no analysis needed
Call mpinside_resume()
Computation phase 3 — analysis needed
Call mpinside_suspend()
Computation phase 4 — no analysis needed
Call mpinside_resume()
Computation phase 5 — analysis needed
Call mpinside_end()
Finalization — no analysis needed

Note the following regarding the function calls:

- The mpinside_start(), mpinside_end(), mpinside_suspend(), and mpinside_resume() calls must involve all ranks. That is, these calls must be MPI COMM WORLD collective calls, or you may experience unexpected results.
- MPInside's analysis ends when it encounters an mpinside_end() call. If the program calls MPI_Finalize() before it calls mpinside_end(), the program ends as expected, and the MPInside report contains statistics through the MPI Finalize() call.
- If your program includes an mpinside_suspend() call toward the end, but does not includes an mpinside_end() call, the analysis continues from the last mpinside_suspend() call through to the MPI_Finalize() call.
- 3. Compile the program.
- 4. Link the program.

Make sure that the MPInside environment is properly set in order to be able to link your program with libMPInside_stub.so.

The example that follows this procedure contains a link step.

5. Type the following command to set the MPINSIDE_PARTIAL_EXPERIMENT environment variable:

% setenv MPINSIDE PARTIAL EXPERIMENT

This environment variable ensures that MPInside starts its analysis after it encounters the mpinside start() call.

For information about environment variables, see the MPInside(3) man page.

6. (Conditional) Set the MPINSIDE_LIB environment variable to your MPI implementation.

Complete this step if your MPI implementation is something other than the HPE Performance Software — Message Passing Interface (HPE Performance MPI) implementation. The default setting is MPINSIDE_LIB MPT, which assumes that HPE Performance MPI is your MPI implementation.

If you use an implementation that is not the HPE Performance MPI implementation, type the one command from the following list that pertains to your implementation:

Command	MPI Implementation	
% setenv MPINSIDE_LIB IMPI	X86 Intel MPI	
% setenv MPINSIDE_LIB OPENMPI	OpenMPI	

Note: HPE supports the MPINSIDE_LIB environment variable as experimental technology. Use of this software can generate unexpected results.

7. Type the following command to run your program:

```
% mpiexec_mpt -np processes program_name program_args
```

For example, the following commands link and run a C++ program that uses the HPE Performance MPI library:

• Load HPE's MPT module:

```
% module load mpt
```

• Load the MPInside module:

```
% module load MPInside
```

This step ensures that LD_LIBRARY_PATH includes the MPInside library's directory.

• Start the Intel C++ Compiler:

```
% icc -o prog_with_stub prog.c -l mpi -l MPInside_stub
```

• Run the program:

```
% mpiexec_mpt -np 128 ./prog_with_stub args
```

• Run the program with MPInside:

```
% mpiexec_mpt -np 128 MPInside ./prog_with_stub args
```

007-5780-005 33

Analyzing Call Stack Branches and Communication Stiffness

This chapter contains the following topics:

- "About Call Stack Branches and Communication Stiffness" on page 35
- "Interpreting the Call Stack Branch Output" on page 35
- "Communication Stiffness" on page 41
- "Generating Statistics to Analyze Call Stack Branches and Communication Stiffness" on page 44

About Call Stack Branches and Communication Stiffness

Certain environment variables enable you to generate call stack information and to generate information about communication *stiffness*. Communication within a program is said to be *stiff* when it contains serialized communication dependencies. MPInside can help you analyze these dependencies.

This chapter explains how to interpret the statistics that describe call stack branches and stiffness. This chapter also contains an example that shows the programming runs used to gather these statistics.

Note: Some of the output examples in this chapter are very wide. To accommodate inclusion in this documentation, some have been wrapped, and column alignment in examples might differ from your output.

Interpreting the Call Stack Branch Output

When you use the MPINSIDE_CALLSTACK_DEPTH environment variable, the MPInside report contains call stack information. Each mpinside_clstk.rank file is a call stack branch report. These reports list call stack branch information. Each branch consists of an MPI function, followed by all of its call stack ancestors. The report sorts the branches and provides data about the time spent in a particular MPI

function. The reports can also contain information about branch partners. The following topics explain the call stack branch reports:

- "Opening the Call Stack Branch Report" on page 36
- "Branch Statistics" on page 36
- "Ancestor Information" on page 37
- "Partner Information" on page 37

Opening the Call Stack Branch Report

Like the MPInside statistics report (mpinside_stats), the call stack branch report (mpinside_clstk.rank) is a tab-separated report that contains a very large amount of data. HPE recommends that you open the mpinside_clstk.rank file from a spreadsheet. For information about how to open this file in a spreadsheet, use the information in the following topic:

"Opening the mpinside stats Report Within a Spreadsheet" on page 15

Branch Statistics

The call stack branch contains columns of data for each function. You can interpret the column headings as follows:

Column Heading	Meaning
MPI_FUNCTION	The function name. For example, MPI_Allreduce or MPI_Send.
Branch ID	The unique branch identification number.
Receive Time(s)	The time spent on the receive function itself.
Self%	The percentage of the total execution time that is accountable to this branch.
	Specifically, this is a percentage accounting of how much time was spent on a certain branch out of the run time of the whole program.
Self totals	The sum of the Self% for all earlier branches plus the Self% for the current branch.

#Send reqs The number of send requests from this branch.

#Recv reqs The number of receive requests from this branch.

Ave MBs sent Average data amount sent, in Mbytes, from this branch.

For this column, and for the Ave MBs received column, the exact meaning depends on the specific MPI

function.

See the preamble of the MPInside report for information specific to the MPI function.

Ave MBs received Average data amount received, in Mbytes, from this

branch.

For this column, and for the Ave MBs sent column, the exact meaning depends on the specific MPI function.

Ave partner wait

time(s)

The Receive Time(s) column shows the time spent for the receive function itself. The Ave partner wait time(s) column shows the wait time associated with a request. For a function like MPI_Recv(), these two times are equal. For a function like MPI_Irecv(),

these two times are not equal.

Ancestor Information

If the MPINSIDE_CROSS_REFERENCE environment variable is set, the call stack branch output contains an additional line that appears after the columns of timing data. This additional line is headed by the keyword Ancestors. If the application was compiled with the -g option, MPInside prints the line number for each function at the end of the line for each routine in the Ancestors section.

Partner Information

Some branches have *partners*. Branch partners consist of complementary pairs of operations. The partner for a particular call stack is the corresponding call stack branch in one or more other ranks. The call stack in the other rank performs the corresponding action in that other rank. The partners are two halves of a communication pair.

For example, assume that one application uses three ranks, and the ranks contain the following calls:

• Rank 0

```
Main > func_a > MPI_Recv
Main > func b > MPI Recv
```

- Rank 1
- Rank 2

MPInside tracks the following for these calls:

- Two call stacks, one for each MPI Recv that is issued from Rank 0.
- Two, three, or four branch partners. Rank 0 issues the MPI_Recv functions. Rank 0's MPI_Recv calls could receive data from Rank 1, from Rank 2, or from both Rank 1 and from Rank 2. MPInside reports all branch partners, so the statistics report could show the following branch partners:

```
- Main > func_a > MPI_Recv and the returned data from Rank 1
```

- Main > func a > MPI Recv and the returned data from Rank 2
- Main > func b > MPI Recv and the returned data from Rank 1
- Main > func b > MPI Recv and the returned data from Rank 2

If rank 0 sends data to rank 1, then rank 0 has a call stack that ends with an $\texttt{MPI_Send}$ that partners with an $\texttt{MPI_Recv}$ call in rank 1.

The MPInside call stack branch output contains partner information, where appropriate, in the following format:

A: #B: C: D

- A The rank number of the partner that initiated the MPI_Send or MPI_Isend for this branch.
- B The MPI_Send or MPI_Isend branch identifier (ID) of the partner. You can find this ID in the mpinside clstk.rank report.
- *C* The percentage of receive or wait time that MPInside can attribute to rank *A* and MPI send branch #*B*.

D The percentage of MPI_Recv time for which the corresponding send arrived late (send late time) in *C*.

The partners connect the wait/receive branches to their corresponding request/send branches. MPInside generates partner information for the MPI_Recv, MPI_Wait, and MPI_Test functions. Partners for these functions are always MPI_Send, MPI_Isend, and so on. It is possible for an MPI_Recv, MPI_Wait, or MPI_Test branch to have several partners.

The following topics describe partners in more detail:

- "Branches With Partners" on page 39
- "Branches Without Partners" on page 39
- "Examples" on page 40

Branches With Partners

Wait branches connect, as partners, the send/recieve branches that initiate MPI requests. For all the send/receive branches that were connected to it, each wait branch reports the percentage of function waiting time to account to a particular send/receive branch in regard to the total execution time of a particular wait branch. For example, an MPI Wait branch is a wait branch as well as a MPI Recv branch.

Receive branches have send partners and are targets of wait branches. Each receive branch reports, for all the send branches that were with it, as follows:

- · The ranks of the sends
- · The send branch IDs
- The percentage of execution time (function waiting time) to account to this particular send branch in regard to the total wait time of this Recv branch.
- The percentage of time (send late time) such send branches were arriving late in regard to the matching receive posting.

Branches Without Partners

Some call stacks do not have partners.

Ordinary branches do not have partners nor are they targets of another branch. Collective function branches are of this type.

Send branches do not have partners. Send branches are targets of receive branches or wait branches.

Examples

The following two examples show MPInside output and include partner information after the ancestor information. For more information about this kind of output, see "Run 4 — Examining the Call Stack Branches" on page 57.

Note: The following output examples are very wide. The rightmost columns are wrapped and shown below the main body of the output for inclusion in this documentation.

Example 1. In the following output, in the Partners line at the end, the first 100.00 indicates that the branch spent 100% of its time partnering with rank 0, branch 2. The second 100.00 in this line indicates that 100% of the time was spent waiting on a late send.

```
MPI FUNCTION Branch ID Receive Time(s) Self% Self totals #Send regs #Recv regs Ave MBs sent
                                       39.72 39.7
  MPI Recv
             #258
                       2.003
                                                          Ω
                                                                      1
                                                                                 Ω
Ancestors: level 2 /home/bryce6/dthomas/MPInside/TESTS/example.c:20
           level 1 /home/bryce6/dthomas/MPInside/TESTS/example.c:38
            main /home/bryce6/dthomas/MPInside/TESTS/example.c:56
             libc start main ??:?
Partners 1 0: 0:#2:100.00:100.00
                                               ## The last two columns of output are as follows:
                                                Ave MBs received Ave partner wait time(s)
                                                                 2.003513
```

Example 2. In the MPI_Recv in following output, the report shows that this branch, with the level_2() call on line 20, was a partner to the matching MPI_Send from rank 0, branch 1. This MPI_Send was executed following the second call (line 20) of the level_2() routine. This partnership accounted for 100% of the MPI_Recv branch, and 99.88% of the time was just wait.

```
MPI_FUNCTION Branch ID Receive Time(s) Self% Self totals #Send reqs #Recv reqs Ave MBs sent
MPI Recv #257 1.026 20.34 60.1 0 1 0
```

```
Ancestors: level_2 /home/bryce6/dthomas/MPInside/TESTS/example.c:20
level_1 /home/bryce6/dthomas/MPInside/TESTS/example.c:37
main /home/bryce6/dthomas/MPInside/TESTS/example.c:56
__libc_start_main ??:?
Partners_1_0: 0:#1:100.00:99.88

## The last two columns of output are as follows:
Ave MBs received Ave partner wait time(s)
0 1.027300
```

Communication Stiffness

Communication stiffness measures an application's sensitivity to point-to-point communication dependency chains. Stiffness is a conceptual rating of how sensitive the running time of each rank is to waiting for other ranks to send the data that the rank needs to proceed.

MPInside measures the communication stiffness as a proxy for the performance effect of dependent communication chains in an MPI program. The stiffness rating is not an absolute timing. Stiffness does not describe, in terms of wall clock time, how fast a given application can run. An application's communication strategy is *stiff* if the ranks spend an unnecessary amount of time waiting for data before the ranks can proceed.

For example, consider a physical simulation that involves a rectangular region of space. The rectangle is a region of space composed of a one-dimensional set of n cubes, such that each of n ranks is responsible for the communication and computation that pertains to the particles in one cube. The following are different communication strategies:

- A communication strategy with an optimal (low) stiffness rating is one in which (1) a rank containing a particle moving out of its physically contained region sends that particle's data directly to the other rank that will contain the particle in the next time step and (2) each rank receives data only from ranks that will send them particles in this time step.
- In a less optimal strategy, rank 0 sends data about all of its outgoing particles to rank 1 before rank 1 can send data about its particles to rank 2, and then from rank 2 to rank 3, and so on. In this case, rank *n*-1 sends data to rank 0 before the end of the time step. With this programming strategy, each time step involves a

007–5780–005 41

chain of *n*-dependent MPI communications, which gives the application a higher stiffness rating.

Applications with dependency chains that affect performance have the following characteristics:

- · Poor scalability
- Transfers that introduce load imbalances

MPInside uses two numbers to calculate the stiffness rating. The first number is the SDC counter, which is the *Size of the Dependency Chain*. MPInside keeps an SDC counter for each rank. The second number is the TNSR counter. The TNSR counter is the sum of the *Total Number of Sends and Receives*. The TNSR number reflects the number of point-to-point operations performed by the rank. These numbers form the stiffness rating, as follows:

- When a send occurs, MPInside increments the SDC counter for that rank by one and includes the new value in the message header.
- When a receive completes, MPInside increments the SDC counter for the
 receiving rank by one. If the new value for the receiving rank is lower than the
 SDC value of the sending rank, MPInside assigns the SDC value of the sending
 rank to the receiving rank.
- The stiffness rating is the ratio of SDC/TNSR.

When you run the program with the following environment variables, the MPInside report includes a stiffness rating:

- MPINSIDE_EVAL_SLT
- MPINSIDE MODEL PERFECT+1.0

A stiffness rating of 1 is good and signifies very little communication stiffness. Higher numbers indicate a higher probability of dependency chains in the program and worsening communication stiffness.

Figure 5-1 on page 43 shows a program with an acceptable, or good, stiffness rating of 1. The value within each box shows SDC changes for each send/receive operation. The TNSR for each rank is 3.




Figure 5-1 Output for a Program With a Low Stiffness Rating

Figure 5-2 on page 43 shows a program with scalability problems. This program includes a bottleneck in that a token is passed back and forth. This program has a higher stiffness rating of 3.




Figure 5-2 Output for a Program With a High Stiffness Rating

007-5780-005 43

Generating Statistics to Analyze Call Stack Branches and Communication Stiffness

The following topics contain procedures that explain how to use the stiffness data in the MPInside report. The topics are as follows:

- "Run 1 Obtaining Baseline Statistics" on page 44
- "Run 2 Simulating a Perfect Interconnect Environment" on page 53
- "Run 3 Evaluating Send Late Time" on page 55
- "Run 4 Examining the Call Stack Branches" on page 57

Run 1 — Obtaining Baseline Statistics

The first run collects baseline statistics about how the program performs in a typical programming environment.

The following procedure explains the MPInside output for a particular C program called example.

Procedure 5-1 To create the program and generate output

1. Use a text editor to create the following C program, called program example:

```
MPI Status status;
13
14
      if(me % 2 == 0) {
15
        (void) sleep(load unbalance);
16
17
        (void) MPI Send (buff S, BUFF SZ/2, MPI INT,
18
               dest, 13, MPI_COMM_WORLD);
19
20
      else { // note Receive size is 2 time send size
21
        (void) MPI_Recv(buff_R, BUFF_SZ,MPI_INT,
               src, 13, MPI_COMM_WORLD, &status);
22
23
        (void) sleep(load_unbalance);
24
25
26
      (void) MPI_Allreduce(buff_S, buff_R, BUFF_SZ,
27
               MPI_INT, MPI_SUM, MPI_COMM_WORLD);
28
29
      if(me == 0) (void) sleep(1);
      (void) MPI Bcast(buff S, BUFF SZ/4, MPI INT,
30
              0, MPI COMM WORLD);
31
32
33 }
35 void level 1()
36 {
37
      level_2(1);
38
      level_2(2);
39 }
40
41 int
42 main(int argc, char **argv)
43 {
44
45
       (void) MPI Init(&argc,&argv);
46
       (void) MPI Comm size(MPI COMM WORLD, &World size);
47
       (void) MPI_Comm_rank(MPI_COMM_WORLD, &me);
48
49
       bzero(buff_S, BUFF_SZ * sizeof(int));
50
51
52
       dest = me + 1;
       src = me - 1;
```

007-5780-005 45

```
54
55     level_1();
56
57      (void) MPI_Finalize();
58 }
```

Note the following about the preceding program:

- This program runs a cascade of calls and then calls several MPI functions in the level 2() routine.
- After the program runs, MPInside writes the mpinside_stats report. The
 information in the mpinside_stats report about the work in routine
 level_2(int load_unbalance) shows that the sleep() routine calls
 introduce a huge load imbalance to the computation and add to the MPI
 function time.



Caution: The code example in this step is for illustrative purposes only and has not been evaluated for use in a production environment.

Type the following commands to compile the program and to generate baseline statistics:

```
% gcc -g -o example example.c -lmpi
% setenv MPINSIDE_ECHO_INPUT
% setenv MPINSIDE_PRINT_DIRTY
% setenv MPINSIDE_ADD_COLUMN_MEANING
% setenv MPINSIDE_SIZE_DISTRI T+12:0-3
```

3. (Conditional) Set the MPINSIDE_LIB environment variable to your MPI implementation.

Complete this step if your MPI implementation is something other than HPE Performance MPI. The default setting is MPINSIDE_LIB MPT, which assumes that HPE Performance MPI is your MPI implementation.

If you use an implementation that is not HPE Performance MPI, type the one command from the following list that pertains to your implementation:

Command MPI Implementation
% setenv MPINSIDE LIB IMPI X86 Intel MPI

% setenv MPINSIDE_LIB OPENMPI

OpenMPI

Note: HPE supports the MPINSIDE_LIB environment variable as experimental technology. Use of this software can generate unexpected results.

4. Type the following command to run the program with MPInside:

```
% mpiexec mpt -np 4 MPInside ./example
```

5. Open the mpinside stats report within a spreadsheet.

For information about how to open an mpinside_stats report from within a spreadsheet, see the following:

"Opening the mpinside stats Report Within a Spreadsheet" on page 15

6. (Optional) Scan the preamble.

#recvcnt:

#sendont:

The preamble in the mpinside_stats report contains metadata about the programming run and explains how MPInside calculates some of its statistics.

In example's case, you specified the MPINSIDE_ECHO_INPUT environment variable, so the preamble lists the environment variables you used during this program run. Otherwise, however, it does not contain a lot of program-specific information. The preamble for example is as follows:

```
MPInside 4.0.0 standard(May 6 2017 14:06:40) Input variables:
MPINSIDE PRINT DIRTY
                                     : Set
MPINSIDE ADD COLUMN MEANING
                                     : Set
MPINSIDE SIZE DISTRI
                                    : T+12:0-3
 >>> column meanings <<<<
MPI Init: MPI Init
        MPI_Recv
Recv:
Send:
         MPI Send
         MPI_Bcast:
                         Calls sending data+=comm sz, Calls receiving data++; Root: Bytes sent++: Bytes received+=count
Allreduce: MPI Allreduce: Calls sending data+=comm sz; Bytes received+=count, Calls receiving data++
#calls: Number of calls to the MPI function
#count: Number of bytes transfered (P2P functions)
              Sum of the communicator size for collective functions; Remote group size if intercomm
#comm sz:
```

007-5780-005 47

Bytes received parameter(collective functions, average for V functions)

Bytes sent parameter(collective functions, average for V functions)

#root: Number of time rank was root of the collective function

For information about how MPInside calculates the Bcast and Allreduce data, see Appendix A, "MPInside Calculations" on page 65.

7. Analyze the Communication time totals area of the report.

The statistics in this part of the report summarize timings, in seconds, for the whole program. The following is an example of this area:

>>>>	>>> Communication time totals (s) 0 1<<<<						
CPU	Compute	MPI_Init	Recv	Send	Bcast	Allreduce	
		General	Point-to-point	Point-to-point	Collective	Collective	
0000	5.002315	0.000218	0.000000	0.000025	0.000033	3.013441	
0001	3.004462	0.000201	3.004253	0.000000	2.000165	0.008992	
0002	3.007882	0.000219	0.000000	0.000048	2.000170	3.009974	
0003	3.004205	0.000195	3.007667	0.000000	2.000175	0.005770	

Take a look at this area and ask yourself the following questions:

Do the statistics seem balanced?

The rows show the number of seconds that each rank spends in the following specific activities:

- Total compute time
- Processing MPI Init functions
- Processing MPI Recv functions
- Processing MPI Send functions
- Processing MPI_Bcast functions
- Processing MPI Allreduce functions

In the case of program example, the mpinside_stats report shows that rank 0's computing time is much higher (at 5+ seconds) than the computing time for the other ranks (at 3+ seconds, each). In most cases, you want to design your program to balance computing time evenly across all ranks. In this case, the additional time is not expected, so this is something that you want to investigate.

What kind of communication traffic occurs between the ranks?

Generally, you want to balance the send times among the ranks. In program example, the send times are balanced between ranks 0 and 2, and the receive times are balanced between ranks 1 and 3. If, for example, ranks 0 and 2 sent the same amount of data but rank 0's send took longer to complete than rank 2's send, that might indicate network contention or load balancing problems.

In program example, note the sleep() routine that occurs before the MPI_Send() function in the level_2() routine for rank 0 and rank 2. The sleep() routine forces rank 1 and rank 3 to wait 3 seconds for the matching MPI_Recv(). A clearly asymmetric set of timings for the sends and receives suggests that the receivers might be spending a long time waiting for sends. In a larger program of, for example, 1000 ranks and more subtle imbalances, you could not conclude so quickly that a large MPI_Recv() time contributes so greatly to the load imbalance problem or to the performance of the pure transfers. Additional programming runs that use more advanced MPInside features can help you to find the causes of performance problems more easily.

8. Analyze the Bytes sent area of the report, which is as follows in program example:

>>>>	Bytes sen	t <<<<				
CPU	Compute	MPI_Init	Recv	Send	Bcast	Allreduce
				#bytes	#root	
0000		0	0	4096	2	0
0001		0	0	0	0	0
0002		0	0	4096	0	0
0003		0	0	0	0	0

The preceding output conveys the following information:

- Ranks 0 and 2 sent 4096 bytes using a call to MPI Send.
- Rank 0 sent out 2 bytes during calls to MPI Allreduce.
- Ranks 1 and 3 did not send any data during any calls to MPI Send.

With regard to the data for your program, does this match your expectations?

9. Analyze the Calls sending data area of the report, which is as follows in program example:

>>>> Calls sending data <<<<

CPU	Compute	MPI_Init	Recv	Send	Bcast	Allreduce
				#calls	#comm_sz	#comm_sz
0000		1	0	2	8	8
0001		1	0	0	8	8
0002		1	0	2	8	8
0003		1	0	0	8	8

The preceding output conveys the following information:

- Each rank called MPI init once.
- Ranks 0 and 2 called MPI_Send two times. These are point-to-point calls. No other ranks called MPI Send.
- From the listing, we know that program example performs collective operations with MPI_COMM_WORLD with four ranks. The 8s in the last two columns are the product of 2 X 4. In the MPI_Bcast column, this represents 2 ranks multiplied by 4 MPI_Bcast calls. In the MPI_Allreduce column, this represents 2 ranks multiplied by 4 MPI Allreduce calls.

With regard to the data for your program, does this match your expectations?

10. Analyze the Bytes received area of the report, which is as follows in program example:

>>>>	Bytes rec	eived <<<<				
CPU	Compute	MPI_Init	Recv	Send	Bcast	Allreduce
			#bytes		#bytes	#bytes
0000		0	0	0	2048	8192
0001		0	4096	0	2048	8192
0002		0	0	0	2048	8192
0003		0	4096	0	2048	8192

The preceding output conveys the following information:

- Ranks 1 and 3 received 4096 bytes of data.
- Ranks 0-4 (all ranks) received 2048 bytes from MPI_Bcast calls, which is the
 result of 1024 bytes received from each of the two MPI_Bcast calls that Rank
 0 initiated.
- The 8192 bytes that each rank received came from the two MPI_Allreduce calls. 4 ranks participated in each call, each contributing 1024 bytes of data.

11. Analyze the Calls receiving data area of the report, which is as follows in program example:

>>>>	Calls rec	eiving dat	a <<<<			
CPU	Compute	MPI_Init	Recv	Send	Bcast	Allreduce
			#calls		#calls	#calls
0000		0	0	0	2	2
0001		0	2	0	2	2
0002		0	0	0	2	2
0003		0	2	0	2	2

Ranks 1 and 3 each called MPI_Recv twice.

Each rank received data from two ${\tt MPI_Broadcast}$ calls and two ${\tt MPI_Allreduce}$ calls.

12. Examine the output in the SIZE HISTOGRAMS area of the report.

The MPINSIDE_SIZE_DISTRI environment variable generates the SIZE HISTOGRAMS area of the report. All times are in seconds. All units for non-timing tables are expressed as the number of calls. The following is the MPInside output for program example for Rank 0 and Rank 1:

>>> Rank 0	Sizes distribution	1 <<<	
Sizes	Send	Bcast	Allreduce
65536	0	0	0
32768	0	0	0
16384	0	0	0
8192	0	0	0
4096	0	0	2
2048	2	0	0
1024	0	2	0
512	0	0	0
256	0	0	0
128	0	0	0
64	0	0	0
32	0	0	0
0	0	0	0
>>> Rank 0	Size distribution	times (in	s) <<<
Sizes	Send	Bcast	Allreduce
65536	0.000000	0.000000	0.00000

007–5780–005 51

32768	0.000000	0.000000	0.000000
16384	0.000000	0.00000	0.00000
8192	0.000000	0.000000	0.000000
4096	0.000000	0.000000	3.013441
2048	0.000025	0.000000	0.000000
1024	0.000000	0.000033	0.000000
512	0.000000	0.000000	0.000000
256	0.000000	0.000000	0.000000
128	0.000000	0.00000	0.000000
64	0.000000	0.000000	0.000000
32	0.000000	0.00000	0.000000
0	0.000000	0.000000	0.000000
>>> Rank 1	Sizes distribution	n <<<	
Sizes	Recv	Bcast	Allreduce
65536	0	0	0
32768	0	0	0
16384	0	0	0
8192	0	0	0
4096	0	0	2
2048	2	0	0
1024	0	2	0
512	0	0	0
256	0	0	0
128	0	0	0
64	0	0	0
32	0	0	0
0	0	0	0
>>> Rank 1	Size distribution	times (in s) <<<
Sizes	Recv	Bcast	Allreduce
65536	0.000000	0.000000	0.000000
32768	0.000000	0.000000	0.000000
16384	0.000000	0.000000	0.000000
8192	0.000000	0.000000	0.000000
4096	0.000000	0.000000	0.008992
2048	3.004253	0.000000	0.000000
1024	0.000000	2.000165	0.000000
512	0.000000	0.000000	0.000000
256	0.000000	0.000000	0.000000
128	0.000000	0.000000	0.000000
64	0.000000	0.000000	0.000000
32	0.000000	0.00000	0.000000

```
0 0.000000 0.000000 0.000000
```

In the preceding output, look for numbers that are uneven. The block of information called Rank 0 Size distribution times shows an MPI_Allreduce of 4096 bytes that took 3+ seconds to complete, compared with MPI_Send and MPI_Bcast times of much less than a second. This indicates that you should look in your program for an MPI Allreduce with a 4K data payload.

Run 2 — Simulating a Perfect Interconnect Environment

If the programming environment had a perfect network and perfect hardware, you might expect all message passing to occur perfectly, with no waiting. When you complete this run, you simulate a perfect environment. This run simulates the amount of waiting that occurs because of unbalanced loads and that is independent of the MPI engine.

The following procedure explains the environment variables to use when you run MPInside for the second time.

Procedure 5-2 To simulate a perfect interconnect environment

- 1. Type the following command to load the MPInside module:
 - % module load MPInside
- 2. Type the following command to rename the MPInside report to mpinside perfect stats:
 - % setenv MPINSIDE_OUTPUT_PREFIX mpinside_perfect
- 3. Type the following commands to specify that you want to run MPInside in a way that simulates a perfect computing environment:

```
% setenv MPINSIDE_ECHO_INPUT
% setenv MPINSIDE_PRINT_DIRTY
% setenv MPINSIDE_ADD_COLUMN_MEANING
% setenv MPINSIDE MODEL PERFECT+1
```

4. (Conditional) Set the MPINSIDE_LIB environment variable to your MPI implementation.

Complete this step if your MPI implementation is something other than HPE Performance MPI. The default setting is MPINSIDE_LIB MPT, which assumes that HPE Performance MPI is your MPI implementation.

007–5780–005 53

If you use an implementation that is not HPE Performance MPI, type the one command from the following list that pertains to your implementation:

Command	MPI Implementation
% setenv MPINSIDE_LIB IMPI	X86 Intel MPI
% setenv MPINSIDE_LIB OPENMPI	OpenMPI

Note: HPE supports the MPINSIDE_LIB environment variable as experimental technology. Use of this software can generate unexpected results.

5. Type the following command to run the program with MPInside:

```
% mpiexec mpt -np 4 MPInside ./example
```

6. Compare the mpinside_perfect_stats report from this run to the mpinside stats report from the previous program run.

The preamble is nearly identical in both reports. The only difference is the echoed environment variables.

The Communication time totals area shows the time spent by the MPI function if the MPI engine operated in a perfect environment with zero latency and infinite bandwidth. The timings in this perfect environment are very similar to the baseline run. This simulation running time is a little shorter because of the huge load imbalance that is introduced with the sleep() function. The true transfer for the run is almost nothing in regard to the load imbalance. The statistics are as follows:

>>>>	>>> Communication time totals (s) 0 1<<<<						
CPU	Compute	MPI_Init	Recv	Send	Bcast	Allreduce	Stiffness
		General	Point-to-point	Point-to-point	${\tt Collective}$	Collective	None
0	5.0172	0.000131	0	0	0	3.020069	0
1	3.011644	0.000141	3.008671	0	2.008501	0.008452	0
2	3.012449	0.000144	0	0	2.008501	3.016319	0
3	3.016353	0.000136	3.012414	0	2.008501	0	0

In the preceding output, notice the new column, Stiffness. For information about communication stiffness, see the following:

"Communication Stiffness" on page 41

The Bytes sent, Calls sending data, Bytes received, and Calls receiving data areas are identical to the baseline statistics.

Run 3 — Evaluating Send Late Time

Send late time (SLT) refers to the amount of time a rank waits for data to be received from another rank. For more information about send late time, see "About MPInside Terminology" on page 6.

The following procedure shows a programming run that generates SLT statistics.

Procedure 5-3 To generate send time late statistics

- 1. Type the following command to load the MPInside module:
 - % module load MPInside
- 2. Type the following command to rename the MPInside report to mpinside slt stats:
 - % setenv MPINSIDE OUTPUT PREFIX mpinside slt
- 3. Type the following commands to specify that you want to run MPInside in a way that generates SLT statistics:

```
% setenv MPINSIDE_ECHO_INPUT
% setenv MPINSIDE_PRINT_DIRTY
% setenv MPINSIDE_ADD_COLUMN_MEANING
% setenv MPINSIDE_EVAL_SLT
% setenv MPINSIDE_EVAL_COLLECTIVE_WAIT
```

4. (Conditional) Set the MPINSIDE_LIB environment variable to your MPI implementation.

Complete this step if your MPI implementation is something other than HPE Performance MPI. The default setting is ${\tt MPINSIDE_LIB}$ ${\tt MPT}$, which assumes that HPE Performance MPI is your MPI implementation.

If you use an implementation that is not HPE Performance MPI, type the one command from the following list that pertains to your implementation:

Command MPI Implementation
% setenv MPINSIDE_LIB IMPI X86 Intel MPI

007–5780–005 55

3.024744

% setenv MPINSIDE_LIB OPENMPI

OpenMPI

Note: HPE supports the MPINSIDE_LIB environment variable as experimental technology. Use of this software can generate unexpected results.

5. Type the following command to run the program with MPInside:

```
% mpiexec mpt -np 4 MPInside ./example
```

6. Compare the mpinside_slt_stats report from this run to the mpinside stats report from the previous program run.

The preamble of the mpinside_slt_stats report contains information about the following additional statistics:

b_Bcast: b_MPI_Bcast: Barrier before MPI_bcast
b_Allreduce: b_MPI_Allreduce: Barrier before MPI_Allreduce
w_MPI_Recv: w_MPI-Recv: Send Late Time for MPI_Recv
unwind_overhead: unwind_overhead: Overhead Unwinding stack
mpinside_overhead: mpinside_overhead: Various MPInside overheads
Stiffness: Stiffness: Bytes sent=Stiffness=(Nb_Requests Att. Send)/(Nb_Request Att. Recv)

Note: The following output example is very wide. The rightmost columns are wrapped and shown below the main body of the output for inclusion in this documentation.

0.031092 0.000003

0.000000

0.000000

In this run, the Communication time totals area shows the new timings and is as follows:

```
>>>> Communication time totals (s) 0 1<<<<
                                                 Send
CPU Compute MPI Init w MPI Recv Recv
                                                               b Bcast
                                                                                       Bcast
---- General Send-late time Point-to-point Point-to-point Barrier before collective Collective
0000 5.004536 0.000181 0.000000 0.000000 0.000072 0.000002
                                                                                       0.000022
                                 0.000040 0.000000
0.000000 0.000102
0.000058 0.000000
0001 3.000160 0.000181 3.006710
                                                              2.001051
                                                                                       0.000021
0002 3.005915 0.000185 0.000000
                                                             2.018046
                                                                                       0.000018
0003 3.000141 0.000183 2.997876
                                                              2.015068
                                                                                       0.005942
                     ## The right-most columns of output are as follows:
                      b Allreduce
                                             Allreduce unwind overhead mpinside overhead Stiffness
                                                                     None
                      Barrier before collective Collective None
                                                                                        None
```

0.031649	0.024031	0.000004	0.00000	0.000000
3.023915	0.020045	0.000004	0.000000	0.000000
0.021838	0.021981	0.000003	0.00000	0.000000

In the preceding statistics, you can interpret all time in columns w_MPI_Recv, b_Bcast and b_Allreduce to be pure wait time. The pure, or real, physical transfer times are the timings in the Recv, Bcast, and Allreduce columns.

The real transfer times vary little with the example program. This is common in applications that show a load imbalance of this degree.

The output includes the Stiffness column. For information about communication stiffness, see "Communication Stiffness" on page 41.

The Bytes sent, Calls sending data, Bytes received, and Calls receiving data areas are identical to the baseline statistics.

Run 4 — Examining the Call Stack Branches

Call stack branches, or branches, show the paths in the program that led to various types of communication. In its output, MPInside organizes the call stack branch information by rank. The MPInside report includes information about the activity at the other end of the communication (the call stack partner) and how much of the total run time was consumed by each of these communication-generating program paths.

The following procedure shows how to generate and analyze information about call stack branches in MPInside reports.

Procedure 5-4 To generate and analyze call stack branch reports

- 1. Type the following command to load the MPInside module:
 - % module load MPInside
- 2. Type the following command to rename the MPInside report to mpinside_branches_stats:
 - % setenv MPINSIDE OUTPUT PREFIX mpinside branches

007–5780–005 57

3. Type the following commands to specify that you want to run MPInside in a way that generates call stack branch information:

```
% setenv MPINSIDE_ECHO_INPUT
% setenv MPINSIDE_PRINT_DIRTY
% setenv MPINSIDE_ADD_COLUMN_MEANING
% setenv MPINSIDE_CALLSTACK_DEPTH 6
% setenv MPINSIDE_CROSS_REFERENCE
```

4. (Conditional) Set the MPINSIDE_LIB environment variable to your MPI implementation.

Complete this step if your MPI implementation is something other than HPE Performance MPI. The default setting is MPINSIDE_LIB MPT, which assumes that HPE Performance MPI is your MPI implementation.

If you use an implementation that is not HPE Performance MPI, type the one command from the following list that pertains to your implementation:

Command	MPI Implementation
% setenv MPINSIDE_LIB IMPI	X86 Intel MPI
% setenv MPINSIDE_LIB OPENMPI	OpenMPI

Note: HPE supports the MPINSIDE_LIB environment variable as experimental technology. Use of this software can generate unexpected results.

5. Type the following command to run the program with MPInside:

```
% mpiexec mpt -np 4 MPInside ./example
```

6. Type the following command to process the additional files that contain information about the MPInside call stack branches:

```
% MPInside post - s0 - e3 -1 mpinside clstk
```

In addition to the expected MPInside report named mpinside_branches_stats, this MPInside run created the following call stack files:

```
mpinside_clstk.0
mpinside_clstk.1
mpinside_clstk.2
```

```
mpinside clstk.3
```

There are four call stack reports because there are four ranks in the example program.

The MPInside_post command processes the call stack files and creates the following reports:

```
mpinside_clstk_post.0
mpinside_clstk_post.1
mpinside_clstk_post.2
mpinside_clstk_post.3
```

7. Analyze the call stack branch reports.

The call stack branch reports show timing and partner information for each MPI function. For information about how to analyze these reports, see "Interpreting the Call Stack Branch Output" on page 35.

Note: The output in Example 1 and Example 2, which follows, is very wide. The rightmost columns are wrapped and shown below the main body of the output for inclusion in this documentation.

Example 1. The mpinside clstk post.0 report for this run is as follows:

007-5780-005 59

4096

```
MPI FUNCTION
             Branch ID Receive Time(s) Self% Self totals #Send reqs #Recv reqs Ave MBs sent
MPI Allreduce #769
                        1.008
                                         33.14 99.2
                                                            0
                                                                        1
Ancestors: level 2 /home/bryce6/dthomas/MPInside/TESTS/example.c:28
           level 1 /home/bryce6/dthomas/MPInside/TESTS/example.c:37
            main /home/bryce6/dthomas/MPInside/TESTS/example.c:56
             __libc_start_main ??:?
                                           ## The last column of output is as follows:
                                           Ave MBs received
                                           4096
MPI_FUNCTION Branch ID Receive Time(s) Self% Self totals #Send reqs #Recv reqs Ave MBs sent
                                         0.75 100.0
MPI Allreduce #1
                         0.023
                                                            1
                                                                                    2048
Ancestors: level 2 /home/bryce6/dthomas/MPInside/TESTS/example.c:16
           level 1 /home/bryce6/dthomas/MPInside/TESTS/example.c:37
            main /home/bryce6/dthomas/MPInside/TESTS/example.c:56
             __libc_start_main ??:?
                                           ## The last column of output is as follows:
                                           Ave MBs received
MPI_FUNCTION Branch ID Receive Time(s) Self% Self totals #Send reqs #Recv reqs Ave MBs sent
                         0.000
                                         0.00
                                                100.0
                                                                                    2048
MPI Allreduce #2
                                                            1
Ancestors: level_2 /home/bryce6/dthomas/MPInside/TESTS/example.c:16
           level 1 /home/bryce6/dthomas/MPInside/TESTS/example.c:38
            main /home/bryce6/dthomas/MPInside/TESTS/example.c:56
             libc start main ??:?
                                           ## The last column of output is as follows:
                                           Ave MBs received
MPI FUNCTION Branch ID Receive Time(s) Self% Self totals #Send reqs #Recv reqs Ave MBs sent
MPI Allreduce #770
                         0.000
                                         0.00
                                               100.0
                                                            0
Ancestors: level_2 /home/bryce6/dthomas/MPInside/TESTS/example.c:32
           level 1 /home/bryce6/dthomas/MPInside/TESTS/example.c:37
            main /home/bryce6/dthomas/MPInside/TESTS/example.c:56
             libc start main ??:?
```

```
## The last column of output is as follows:
                                           Ave MBs received
                                           1024
MPI_FUNCTION Branch ID Receive Time(s) Self% Self totals #Send reqs #Recv reqs Ave MBs sent
MPI Allreduce #772
                         0.000
                                         0.00
                                               100.0
                                                             0
Ancestors: level_2 /home/bryce6/dthomas/MPInside/TESTS/example.c:32
           level_1 /home/bryce6/dthomas/MPInside/TESTS/example.c:38
            main /home/bryce6/dthomas/MPInside/TESTS/example.c:56
             libc start main ??:?
                                            ## The last column of output is as follows:
                                           Ave MBs received
                                           1024
```

Example 2. In the following output, notice that some branches are followed with information about the branch partners:

```
MPInside report rank 1
Send Branches Ids : 1 - 255
RECV Branches Ids : 257 - 511
WAIT Branches Ids : 513 - 771
MPI FUNCTION Branch ID Receive Time(s) Self% Self totals #Send reqs #Recv reqs Ave MBs sent
    MPI Recv #258
                         2.003
                                         39.72 39.7
Ancestors: level_2 /home/bryce6/dthomas/MPInside/TESTS/example.c:20
           level_1 /home/bryce6/dthomas/MPInside/TESTS/example.c:38
            main /home/bryce6/dthomas/MPInside/TESTS/example.c:56
             __libc_start_main ??:?
Partners_1_0: 0:#2:100.00:100.00
                                           ## The last two columns of output are as follows:
                                           Ave MBs received Ave partner wait time(s)
                                                             2.003513
MPI FUNCTION Branch ID Receive Time(s) Self% Self totals #Send reqs #Recv reqs Ave MBs sent
    MPI Recv #257
                         1.026
                                         20.34 60.1
                                                            0
                                                                        1
Ancestors: level 2 /home/bryce6/dthomas/MPInside/TESTS/example.c:20
           level 1 /home/bryce6/dthomas/MPInside/TESTS/example.c:37
```

007–5780–005 61

```
main /home/bryce6/dthomas/MPInside/TESTS/example.c:56
             libc start main ??:?
Partners 1 0: 0:#1:100.00:99.88
                                           ## The last two columns of output are as follows:
                                           Ave MBs received Ave partner wait time(s)
                                                           1.027300
MPI_FUNCTION Branch ID Receive Time(s) Self% Self totals #Send reqs #Recv reqs Ave MBs sent
   MPI_Bcast #772
                        1.004
                                         19.91 80.0
                                                                        1
Ancestors: level 2 /home/bryce6/dthomas/MPInside/TESTS/example.c:32
           level_1 /home/bryce6/dthomas/MPInside/TESTS/example.c:38
            main /home/bryce6/dthomas/MPInside/TESTS/example.c:56
             __libc_start_main ??:?
                                           ## The last column of output is as follows:
                                           Ave MBs received
                                           1024
MPI_FUNCTION Branch ID Receive Time(s) Self% Self totals #Send reqs #Recv reqs Ave MBs sent
                   1.004
                                        19.91 99.9
                                                            0
   MPI_Bcast #770
Ancestors: level 2 /home/bryce6/dthomas/MPInside/TESTS/example.c:32
           level 1 /home/bryce6/dthomas/MPInside/TESTS/example.c:37
            main /home/bryce6/dthomas/MPInside/TESTS/example.c:56
             __libc_start_main ??:?
                                           ## The last column of output is as follows:
                                           Ave MBs received
                                           1024
MPI FUNCTION Branch ID Receive Time(s) Self% Self totals #Send regs #Recv regs Ave MBs sent
                        0.005
                                         0.10
MPI Allreduce #771
                                               100.0
Ancestors: level 2 /home/bryce6/dthomas/MPInside/TESTS/example.c:28
           level 1 /home/bryce6/dthomas/MPInside/TESTS/example.c:38
            main /home/bryce6/dthomas/MPInside/TESTS/example.c:56
             __libc_start_main ??:?
                                           ## The last column of output is as follows:
                                           Ave MBs received
                                           4096
```

```
MPI_FUNCTION Branch ID Receive Time(s) Self% Self totals #Send reqs #Recv reqs Ave MBs sent
MPI_Allreduce #769 0.001 0.02 100.0 0 1 0

Ancestors: level_2 /home/bryce6/dthomas/MPInside/TESTS/example.c:28
level_1 /home/bryce6/dthomas/MPInside/TESTS/example.c:37
main /home/bryce6/dthomas/MPInside/TESTS/example.c:56
__libc_start_main ??:?

## The last column of output is as follows:
Ave MBs received
4096
```

For Branch ID 258, for example, notice the following:

- The MPI_Recv call (with the level_2() call on line 38) was the partner (the matching send for this receive branch) with rank 0 branch ID 2. Function main calls level_1, which calls level_2, which calls MPI_Recv. The exact source files and line numbers that led to the call to MPI_Recv are .../TESTS/example.c.20 (where the 20 means line 20) and .../TESTS/example.c.38.
- The line Partners_1_0: 0:#2:100.00:100.00 shows that this branch spent 100% of its time partnering with rank 0, branch 2. The second 100.00 in this line reports that 100% of the time spent was waiting on a late send.

MPInside Calculations

This appendix section contains the following topics:

- "About MPInside and the Collective Functions" on page 65
- "Interpreting the Statistics for the MPI Bcast Collective Function" on page 65

About MPInside and the Collective Functions

The collective functions perform across the network. In its output, MPInside considers the number of individual point-to-point operations that were needed for each collective function. When MPInside generates a count for these collective functions, the way the count is created depends on where the count appears in the output.

Interpreting the Statistics for the MPI_Bcast Collective Function

The MPInside output contains statistics for the MPI_Bcast functions used in the program. These statistics appear in the five tables of output that MPInside generates by default every time it runs. The following list includes each table title and explains how to interpret the statistic for the MPI Bcast function in that table.

Table	MPI_Bcast Statistic's Meaning
Bytes sent	The number of times each rank acted as the root of an MPI_Bcast function.
Calls sending data	A count of the number of calls to the MPI_Bcast function multiplied by the number of ranks that participated in the function.
Bytes received	The number of bytes received by each rank as the result of an MPI_Bcast function.

007–5780–005 65

Calls receiving A count of the number of ranks that received data as the result of an MPI Bcast function.

Interpreting the Statistics for the MPI Allreduce Collective Function

The MPInside output contains statistics for the MPI_Allreduce functions used in the program. These statistics appear in the five tables of output that MPInside generates by default every time it runs. The following list includes each table title and explains how to interpret the statistic for the MPI_Allreduce function in that table.

Table	MPI_Allreduce Statistic's Meaning
Bytes sent	This field contains 0. For calls to the MPI_Allreduce, the BYTES SENT field is meaningless.
Calls sending data	The count of the number of calls to the MPI_Allreduce function multiplied by the number of ranks that participated in the function.
Bytes received	The number of bytes received by all ranks as the result of an MPI_Allreduce function.
Calls receiving data	The count of the number of times the rank called the MPI_Allreduce function.

Index

В	R
Branch, 7	Recv branches, 39
F	S
Function time, 6 Function waiting time, 6	Send branches, 40 Send late time (SLT), 7
M	Т
MPI communication terminology, 7	Transfer time, 6
N	w
non-synchronized send/receive pair definition and terminology, 7	wait branches, 39
0	
Ordinary branches, 39	