# Machine Learning Google Colab Tutorial

TA:許湛然(Chan-Jan Hsu) 2021.03.05

Colaboratory, or "Colab" for short, allows you to write and execute Python in your browser, with


- Zero configuration required
- Free access to GPUs
- Easy sharing

# Colab Demo: https://reurl.cc/ra63jE

In this demo, your will learn the following:

- Download files using colab
- Connect google colab with your google drive
- Pytorch examples and common errors

You can type python code in the code block, or use a leading exclamation mark! to change the code block to treating the input as a shell script




Exclamation mark (!) starts a new shell, does the operations, and then kills that shell, while percentage (%) affects the process associated with the notebook, and it is called a magic function.


Use % instead of! for cd (change directory) command

# **Changing Runtime**

To utilize the free GPU provided by google, click on "Runtime"(執行階段)
-> "Change Runtime Type"(變更執行階段類型). There are three options under "Hardware Accelerator"(硬體加速器), select "GPU".

\* Doing this will restart the session, so make sure you change to the desired runtime before executing any code.





## **Executing Code Block**

Click on the play button to execute the code block. This code downloads a file from google drive




## File Structure

Clicking on the folder icon will give you the visualization of the file structure

There should be a jpg file, if you do not see it, click the refresh button

The file is temporarily stored, and will be removed once you end your session. You can download the file to your local directory.



## **Mounting Google Drive**

Execute the code block with drive.mount('/content/drive')

or click on the Google Drive icon, a code block will appear



## **Mounting Google Drive**


Sign in to your google account to get the authorization code. Enter the authorization code in the box below.




# **Mounting Google Drive**

Execute the following three code blocks in order

This will download the image to your google drive, so you can access it later





# **Moving and Creating a New Code Block**

You can create a new code block by clicking on +Code(程式碼) on the top

```
Move cell up


Move cell down

Delete cell

from google.colab inport drive drive.nount(fcontent/drive)
```

# **Saving Colab**

You can download the ipynb file to your local device (File > Download .ipynb), or save the colab notebook to your google drive (File > Save a copy in Drive).



## **Recovering Files in Google Drive**

Right Click on File > Manage Versions (版本管理) to recover old files that have been accidentally overwritten.

#### Manage versions

Older versions of 'main.py' may be deleted after 30 days or after 100 versions are stored. To avoid deletion, select **Keep forever** in the file's context menu. **Learn more** 

Current version main.py	
Dec 18, 2020, 1:40 AM 許湛然	

CLOSE

## **Useful Linux Commands (in Colab)**

ls: List all files in the current directory

Is -l: List all files in the current directory with more detail

pwd: Output the working directory

mkdir <dirname> : Create a directory named <dirname>

cd <dirname> : Move to directory named <dirname>

gdown: Download files from google drive

wget: Download files from the internet

python <python\_file> : Executes a python file

# Machine Learning Pytorch Tutorial 2

### **Documentation and Common Errors**

TA:許湛然(Chan-Jan Hsu) 2021.03.05


## **PyTorch Documentation**

https://pytorch.org/docs/stable/

torch.nn -> neural network

torch.optim -> optimization algorithms

torch.utils.data -> dataset, dataloader



function inputs and outputs

data type and explanation of each input

#### TORCH.MAX

 $torch.max(input) \rightarrow Tensor$ 

Returns the maximum value of all elements in the input tensor.

#### WARNING

This function produces deterministic (sub)gradients unlike max(dim=0)

Parameters

input (Tensor) - the input tensor.

Some functions behave differently with different inputs

Parameters: You don't need to specify the name of the argument (Positional Arguments)

Keyword Arguments: You have to specify the name of the argument

They are separated by \*

torch.max(input, dim, keepdim=False \*, out=None) -> (Tensor, LongTensor)

Returns a namedtuple (values, indices) where values is the maximum value of each row of the input tensor in the given dimension dim. And indices is the index location of each maximum value found (argmax).

If keepdim is True, the output tensors are of the same size as input except in the dimension dim where they are of size 1. Otherwise, dim is squeezed (see torch.squeeze()), resulting in the output tensors having 1 fewer dimension than input.

#### NOTE

If there are multiple maximal values in a reduced row then the indices of the first maximal value are returned.

#### Parameters

- input (Tensor) the input tensor.
- dim (int) the dimension to reduce.
- keepdim (bool) whether the output tensor has dim retained or not. Default: False.

#### Keyword Arguments

out (tuple, optional) - the result tuple of two output tensors (max, max\_indices)

Some functions behave differently with different inputs

Arguments with default value:
Some arguments have a default value (keepdim=False), so passing a value of this argument is optional

torch.max(input, dim, keepdim=False \*, out=None) -> (Tensor, LongTensor)

Returns a namedtuple (values, indices) where values is the maximum value of each row of the input tensor in the given dimension dim. And indices is the index location of each maximum value found (argmax).

If keepdim is True, the output tensors are of the same size as input except in the dimension dim where they are of size 1. Otherwise, dim is squeezed (see torch.squeeze()), resulting in the output tensors having 1 fewer dimension than input.

#### NOTE

If there are multiple maximal values in a reduced row then the indices of the first maximal value are returned.

#### Parameters

- input (Tensor) the input tensor.
- . dim (int) the dimension to reduce.
- keepdim (bool) whether the output tensor has dim retained or not. Default: False.

#### Keyword Arguments

out (tuple, optional) - the result tuple of two output tensors (max, max\_indices)

### Three Kinds of torch.max

- 1. torch.max(input) → Tensor
- 2. torch.max(input, dim, keepdim=False, \*,
   out=None) → (Tensor, LongTensor)
- 3. torch.max(input, other, \*, out=None) →
  Tensor

```
input : Tensor, dim : int, keepdim : bool
other : Tensor
```

1.torch.max(input) → Tensor

Find the maximum value of a tensor, and return that value.

i	npu	t
[[1	2	3]
[5	6	4]]


2. torch.max(input, dim, keepdim=False, \*,
out=None) → (Tensor, LongTensor)

Find the maximum value of a tensor along a dimension, and return that value, along with the index corresponding to that value.

```
input
[[1 2 7] '
[5 6 4]]
```

3.torch.max(input) → Tensor

Perform element-wise comparison between two tensors of the same size, and select the maximum of the two to construct a tensor with the same size.



## **PyTorch Documentation Example (Colab)**

#### Three Kinds of torch.max

- torch.max(input) →
   Tensor
- 2. torch.max(input, dim,
   keepdim=False, \*,
   out=None) → (Tensor,
   LongTensor)
- 3. torch.max(input, other,
   \*, out=None) → Tensor

input : Tensor

dim : int

keepdim : bool
other : Tensor

#### Colab code

```
x = torch.randn(4,5)
y = torch.randn(4,5)
1. m = torch.max(x)
     m, idx = torch.max(x,0) \rightarrow 0
     m, idx = torch.max(input = x, dim=0) \rightarrow 0
     m, idx = torch.max(x, 0, False) \rightarrow 0
     m, idx = torch.max(x,0,keepdim=True)\rightarrow0
     m, idx = torch.max(x,0,False,out=p)\rightarrow0
     m, idx = torch.max(x,0,False,p)\rightarrowx
           *out is a keyword argument
     m, idx = torch.max(x,True) \rightarrow x
           *did not specify dim
     t = torch.max(x,y)
```

## **Common Errors -- Tensor on Different Device to Model**

```
model = torch.nn.Linear(5,1).to("cuda:0")
x = torch.Tensor([1,2,3,4,5]).to("cpu")
y = model(x)
```

Tensor for \* is on CPU, but expected them to be on GPU

=> send the tensor to GPU

```
x = torch.Tensor([1,2,3,4,5]).to("cuda:0")
y = model(x)
print(y.shape)
```

## **Common Errors -- Mismatched Dimensions**

```
x = torch.randn(4,5)

y = torch.randn(5,4)

z = x + y
```

The size of tensor a (5) must match the size of tensor b (4) at non-singleton dimension 1

=> the shape of a tensor is incorrect, use **transpose**, **squeeze**, **unsqueeze** to align the dimensions

```
y = y.transpose(0,1)
z = x + y
print(z.shape)
```

## **Common Errors -- Cuda Out of Memory**

```
import torch
import torchvision.models as models
resnet18 = models.resnet18().to("cuda:0") # Neural Networks for Image Recognition
data = torch.randn(512,3,244,244) # Create fake data (512 images)
out = resnet18(data.to("cuda:0")) # Use Data as Input and Feed to Model
print(out.shape)
```

CUDA out of memory. Tried to allocate 350.00 MiB (GPU 0; 14.76 GiB total capacity; 11.94 GiB already allocated; 123.75 MiB free; 13.71 GiB reserved in total by PyTorch)

=> The batch size of data is too large to fit in the GPU. Reduce the batch size.

## **Common Errors -- Cuda Out of Memory**

If the data is iterated (batch size = 1), the problem will be solved. You can also use DataLoader

```
for d in data:
  out = resnet18(d.to("cuda:0").unsqueeze(0))
print(out.shape)
```

## **Common Errors -- Mismatched Tensor Type**

```
import torch.nn as nn
L = nn.CrossEntropyLoss()
outs = torch.randn(5,5)
labels = torch.Tensor([1,2,3,4,0])
lossval = L(outs, labels) # Calculate CrossEntropyLoss between outs and labels
expected scalar type Long but found Float
=> labels must be long tensors, cast it to type "Long" to fix this issue
labels = labels.long()
lossval = L(outs, labels)
print(lossval)
```