
# Floating-Point Numbers

# **Floating Point**

Representation for non-integral numbers

Including very small and very large numbers

#### Like scientific notation



# Floating Point Standard


- Defined by IEEE Std 754-1985
- Developed in response to divergence of representations
  - Portability issues for scientific code
- Now almost universally adopted
- Two representations
  - Single precision (32-bit)
  - Double precision (64-bit)

Types **float** and **double** in C


## **IEEE Floating-Point Format**

single: 8 bits single: 23 bits double: 11 bits double: 52 bits

S Exponent Fraction



- S: sign bit (0  $\Rightarrow$  non-negative, 1  $\Rightarrow$  negative)
- Normalize significand: 1.0 ≤ |significand| < 2.0
  - Always has a leading pre-binary-point 1 bit, so no need to represent it explicitly (hidden bit)
  - Significand is Fraction with the "1." restored
- Exponent: excess representation: actual exponent + Bias
  - Ensures exponent is unsigned
  - Single: Bias = 127; Double: Bias = 1203



# Single-Precision Range

- Exponents 00000000 and 11111111 reserved
- Smallest value

Exponent: 0000001

 $\Rightarrow$  actual exponent = 1 – 127 = –126

Fraction:  $000...00 \Rightarrow significand = 1.0$ 

$$\pm 1.0 \times 2^{-126} \approx \pm 1.2 \times 10^{-38}$$

Largest value


exponent: 11111110

 $\Rightarrow$  actual exponent = 254 – 127 = +127

Fraction:  $111...11 \Rightarrow significand \approx 2.0$ 

$$\pm 2.0 \times 2^{+127} \approx \pm 3.4 \times 10^{+38}$$

CISC260, Liao



### **Double-Precision Range**

- Exponents 0000...00 and 1111...11 reserved
- Smallest value

Exponent: 0000000001

 $\Rightarrow$  actual exponent = 1 - 1023 = -1022

Fraction:  $000...00 \Rightarrow \text{significand} = 1.0$ 

$$\pm 1.0 \times 2^{-1022} \approx \pm 2.2 \times 10^{-308}$$

Largest value

Exponent: 1111111110

 $\Rightarrow$  actual exponent = 2046 – 1023 = +1023

Fraction:  $111...11 \Rightarrow \text{significand} \approx 2.0$ 

$$\pm 2.0 \times 2^{+1023} \approx \pm 1.8 \times 10^{+308}$$

# Floating-Point Precision

### Relative precision

- All fraction bits are significant
- Single: approximately 2<sup>-23</sup>
  - Equivalent to  $23 \times \log_{10} 2 \approx 23 \times 0.3 \approx 6$  decimal digits of precision

 $X = X \pm S$ 

- Double: approximately 2<sup>-52</sup>
  - Equivalent to  $52 \times \log_{10} 2 \approx 52 \times 0.3 \approx 16$  decimal digits of precision

CISC260, Liao

# Floating-Point Example

### Represent –0.75

• 
$$-0.75 = (-1)^1 \times 1.1_2 \times 2^{-1}$$

- S = 1
- Fraction =  $1000...00_2$
- Exponent = -1 + Bias
  - Single:  $-1 + 127 = 126 = 011111110_2$
  - Double:  $-1 + 1023 = 1022 = 0111111111110_2$

Single: 1011111101000...00

Double: 1011111111101000...00

$$0.\frac{1}{2} \frac{1}{2} \frac{1}{4} = 1.12 \times 2^{-1}$$

$$\frac{1}{2} \frac{1}{4} \frac{1}{8} = 1.12 \times 2^{-1}$$

# Floating-Point Example

What number is represented by the single-precision float

#### 11000000101000...00

$$S = 1$$
  
Fraction =  $01000...00_2$   
Exponent =  $10000001_2$  = 129

• 
$$x = (-1)^{1} \times (1 + 01_{2}) \times 2^{(129 - 127)}$$
  
=  $(-1) \times 1.25 \times 2^{2}$   
=  $-5.0$ 

### Infinities and NaNs

Exponent = 111...1, Fraction = 000...0

- ±Infinity
- Can be used in subsequent calculations, avoiding need for overflow check

Exponent = 111...1, Fraction  $\neq 000...0$ 

- Not-a-Number (NaN)
- Indicates illegal or undefined result
  - e.g., 0.0 / 0.0
- Can be used in subsequent calculations

Single precision		Double precision		Object represented	
Exponent	Fraction	Exponent	Fraction		
0	0	0	0	0	
0	Nonzero	0	Nonzero	± denormalized number	
1-254	Anything	1-2046	Anything	± floating-point number	
255	0	2047	0	± infinity	
255	Nonzero	2047	Nonzero	NaN (Not a Number)	

Let's multiply by 2 on both sides.

Remember multiplying a number in binary by 2 is achieved by shift left one bit.

RHS = 
$$b$$
.b b b b b ...

How do we know the b to the left of the binary point is 1 or 0?

It is 1 if the product is >= 1, and is 0 otherwise.

We can found it out by looking at the LHS:

**0.X** 
$$\times 2 = 1.X'$$
, or **0.X**  $\times 2 = 0.X'$ 

E.g., 
$$0.75 \times 2 = 1.5$$

$$X = "75"$$
, and  $X' = "5"$ 

E.g., 
$$0.45 \times 2 = 0.9$$

$$X = "45"$$
, and  $X' = "9"$ 

If  $0.X \times 2 = 1.X'$ , subtract 1 on both side.

Repeat the above process to determine all binary bits on the RHS.

00011001100110011  $0.1_{ten} = 0.bbbb..._{two}$ ? XZ 6.4 X2 1,240,2 XZ 0.4 1,100110011. XZ 100110011.

#### Converting a fraction number in decimal to binary

# Floating-Point Addition (decimal)

Consider a 4-digit decimal example

$$9.999 \times 10^{1} + 1.610 \times 10^{-1}$$

- 1. Align decimal points
  - Shift number with smaller exponent
  - $9.999 \times 10^{1} + 0.016 \times 10^{1}$
- 2. Add significands


$$9.999 \times 10^{1} + 0.016 \times 10^{1} = 10.015 \times 10^{1}$$

3. Normalize result & check for over/underflow

$$1.0015 \times 10^{2}$$

4. Round and renormalize if necessary

$$1.002 \times 10^{2}$$



CISC260, Liao

# Floating-Point Addition (binary)

- Now consider a 4-digit binary example  $1.000_2 \times 2^{-1} + (-1.110_2 \times 2^{-2})$ , which is (0.5 + -0.4375)
- 1. Align binary points
  - Shift number with smaller exponent
  - $1.000_2 \times 2^{-1} + (-0.111_2 \times 2^{-1})$
- 2. Add significands


$$1.000_2 \times 2^{-1} + (-0.111_2 \times 2^{-1}) = 0.001_2 \times 2^{-1}$$

- 3. Normalize result & check for over/underflow  $1.000_2 \times 2^{-4}$ , with no over/underflow
- 4. Round and renormalize if necessary
  - $1.000_2 \times 2^{-4}$  (no change) = 0.0625

### FP Adder Hardware

- Much more complex than integer adder
- Doing it in one clock cycle would take too long
  - Much longer than integer operations
  - Slower clock would penalize all instructions
- FP adder usually takes several cycles
  - Can be pipelined

### FP Adder Hardware



CISC260, Liao

# Floating-Point Multiplication (decimal)

Consider a 4-digit decimal example

$$1.110 \times 10^{10} \times 9.200 \times 10^{-5}$$

- 1. Add exponents
  - For biased exponents, subtract bias from sum
  - New exponent = 10 + -5 = 5
- 2. Multiply significands

$$1.110 \times 9.200 = 10.212 \implies 10.212 \times 10^{5}$$

3. Normalize result & check for over/underflow

$$1.0212 \times 10^6$$

4. Round and renormalize if necessary

$$1.021 \times 10^6$$

5. Determine sign of result from signs of operands

$$+1.021 \times 10^{6}$$

# Floating-Point Multiplication (binary)

Now consider a 4-digit binary example

$$1.000_2 \times 2^{-1} \times -1.110_2 \times 2^{-2} \ (0.5 \times -0.4375)$$

1. Add exponents

Unbiased: -1 + -2 = -3

Biased: 
$$(-1 + 127) + (-2 + 127) = -3 + 254 - 127 = -3 + 127$$

2. Multiply significands

$$1.000_2 \times 1.110_2 = 1.1102 \implies 1.110_2 \times 2^{-3}$$

- 3. Normalize result & check for over/underflow
  - $1.110_2 \times 2^{-3}$  (no change) with no over/underflow
- 4. Round and renormalize if necessary

$$1.110_2 \times 2^{-3}$$
 (no change)

5. Determine sign: +ve  $\times$  -ve  $\Rightarrow$  -ve

$$-1.110_2 \times 2^{-3} = -0.21875$$

### **FP Arithmetic Hardware**

- FP multiplier is of similar complexity to FP adder
  - But uses a multiplier for significands instead of an adder
- FP arithmetic hardware usually does
  - Addition, subtraction, multiplication, division, reciprocal, square-root
  - FP ↔ integer conversion
- Operations usually takes several cycles
  - Can be pipelined

### FP Instructions in ARM

#### FP hardware is coprocessor 1

- Adjunct processor that extends the ISA
- 32 Separate floating-point registers
  - s0, s1, ..., s31
  - Paired for double-precision:

$$d0 = (s0, s1); d1 = (s2, s3); ...; d15 = (s30, s31)$$

#### FP instructions operate only on FP registers

- Programs generally don't do integer ops on FP data, or vice versa
- More registers with minimal code-size impact

#### FP load and store instructions: FLDS and FSTS

```
• e.g., FLDS s4, [sp, #0]
FLDS s6, [sp, #4]
FADDS s2, s4, s6
FSTS s2, [sp, #8]
```

### FP Instructions in ARM

Single-precision arithmetic

- FADDS, FSUBS, FMULS, FDIVS
  - e.g., FADDS s2, s4, s6

Double-precision arithmetic

- FADDD, FSUBD, FMULD, FDIVD
  - e.g., FMULD d2, d4, d6

**Data Transfer** 

FLDS, FSTS, FLDD, FSTD

Single- and double-precision comparison

- FCMPS s2, s4
- FCMPD d2, d4
- FMSTAT

#### ARM floating-point operands

Name	Example	Comments		
32 floating-point registers	s0, s1, s2, , s31 or d0, d1, d2, , d15	ARM single-precision floating-point registers are used in pairs for double precision numbers.		
2 <sup>30</sup> memory words	Memory[0], Memory[4], , Memory[4294967292]	Accessed only by data transfer instructions. ARM uses byte addresses, sequential word addresses differ by 4. Memory holds data structures, so as arrays, and spilled registers, such as those saved on procedure calls.		

#### ARM floating-point assembly language

Category	instruction	Example	Meaning	Comments
Arithmetic	FP add single	FADDS 32,54,56	s2 - s4 + s6	FP add (single precision)
	FP subtract single	FSUBS 52,54,56	s2 - s4 - s6	FP sub (single precision)
	FP multiply single	FMULS s2,s4,s6	s2 - s4 × s6	FP multiply (single precision)
	FP divide single	FDIVS s2,s4,s6	s2 - s4 / s6	FP divide (single precision)
	FP add double	FADDD d2.d4.d6	d2 - d4 + d6	FP add (double precision)
	FP subtract double	FSUBD d2,d4,d6	d2 - d4 - d6	FP sub (double precision)
	FP multiply double	FMULD d2,d4,d6	d2 - d4 × d6	FP multiply (double precision)
	FP divide double	FDIVD d2.d4.d6	d2 - d4 / d6	FP divide (double precision)
Data transfer	FP load, single prec.	FLDS s1,[r1,#100]	s1 - Memory[r1 + 400]	32-bit data to FP register
	FP store, single prec.	FSTS s1,[r1,#100]	Memory[r1 + 400] = s1	32-bit data to memory
	FP load, double prec.	FLDD d1.[r1,#100]	dl - Memory[rl + 400]	64-bit data to FP register
	FP store, double prec.	FSTD d1.[r1.#100]	Memory[r1 + 400] = d1	64-bit data to memory
Compare	FP compare single	FCMPS s2.s4	if (s2 - s4)	FP compare less than single precision
	FP compare double	FCMPD d2.d4	if (d2 - d4)	FP compare less than double precision
	FP Move Status (for conditional branch)	FMSTAT	cond. flags = FP cond. flags	Copy FP condition flags to integer condition flags

CIOCZOU, LIAU

### FP Example: convert from °F to °C

C code:

```
float f2c (float fahr) {
  return ((5.0/9.0)*(fahr - 32.0));
}
```

- fahr is in s12, and the literals are in global memory space with offsets from the base address in r12.
- Put the result in s0,
- Compiled ARM code:

```
f2c: FLDS s16, [r12, const5]
FLDS s18, [r12, const9]
FDIVS s16, s16, s18
FLDS s18, [r12, const32]
FSUBS s18, s12, s18
FMULS s0, s16, s18
MOV pc, ]r
```

### Accurate Arithmetic

#### IEEE Std 754 specifies additional rounding control

- Extra bits of precision (guard, round, sticky)
- Choice of rounding modes
- Allows programmer to fine-tune numerical behavior of a computation

#### Not all FP units implement all options

Most programming languages and FP libraries just use defaults

Trade-off between hardware complexity, performance, and market requirements

#### **Rounding with Guard Digits**

Add  $2.56_{\rm ten} \times 10^0$  to  $2.34_{\rm ten} \times 10^2$ , assuming that we have three significant decimal digits. Round to the nearest decimal number with three significant decimal digits, first with guard and round digits, and then without them.

First we must shift the smaller number to the right to align the exponents, so  $2.56_{\rm ten} \times 10^0$  becomes  $0.0256_{\rm ten} \times 10^2$ . Since we have guard and round digits, we are able to represent the two least significant digits when we align exponents. The guard digit holds 5 and the round digit holds 6. The sum is

$$\begin{array}{r} 2.3400_{\rm ten} \\ + 0.0256_{\rm ten} \\ \hline 2.3656_{\rm ten} \end{array}$$

Thus the sum is  $2.3656_{\text{ten}} \times 10^2$ . Since we have two digits to round, we want values 0 to 49 to round down and 51 to 99 to round up, with 50 being the tiebreaker. Rounding the sum up with three significant digits yields  $2.37_{\text{ten}} \times 10^2$ .

Doing this *without* guard and round digits drops two digits from the calculation. The new sum is then

$$+ \frac{2.34_{\text{ten}}}{2.36_{\text{ten}}}$$

The answer is  $2.36_{\text{ten}} \times 10^2$ , off by 1 in the last digit from the sum above.

### **Clicker question**

What will be printed by the following java code?

```
double x1 = 0.3;
double x2 = 0.1 + 0.1 + 0.1;
StdOut.println(x1 == x2);
```

A.True B.False 


### **Clicker Question**

What will be printed by the following java code?

double 
$$x1 = 0.5$$
;  
double  $x2 = 0.1 + 0.1 + 0.1 + 0.1 + 0.1$ ;  
StdOut.println( $x1 == x2$ );

A.True B.False Newton's method to compute square root

```
#include <stdio.h>
int main(){
        double m;
        double xi;
        printf("type a positive number\n");
        scanf("%lf", &m);
        xi = m;
        while(1) {
                xi = (xi + m/xi)/2.0;
                if(xi*xi <= m) break;</pre>
        printf("sqrt of %lf = %lf\n", m, xi);
         return 1;
                                         CISC260, Liao
```



Try to calculate sqrt(20.0)

#### **Clicker question**

```
double q[8];
...
int x = 0;
while (x < 8) {
  if ( q[x] >= 0 ) return true;
  if ( q[x] < 0 ) ++x;
}
return false;</pre>
```

Which answer is wrong regarding the possible outcome of running the above code?

- A. Return true  $\sqrt{\phantom{a}}$
- B. Return false 1/
- C. Return either true or false (/
- D. Runs into infinite loop
- E. None of the above

CISC260, Liao

### Tips for floating-point number accuracy

- Use double instead of float for accuracy.
- Use float only if you really need to conserve memory, and are aware of the associated risks with accuracy. Usually it
  doesn't make things faster, and occasionally makes things slower.
- Be careful of calculating the difference of two very similar values and using the result in a subsequent calculation.
- Be careful about adding two quantities of very different magnitudes.
- Be careful about repeating a slightly inaccurate computation many many times. For example, calculating the change in position of planets over time.
- Designing stable floating point algorithms is highly nontrivial. Use libraries when available.