

STRIDE · USER GUIDE

Kiosk Setup & Operations Guide

KIOSK

Your front-desk self-service check-in station — always on, always ready, freeing your staff to focus on students instead of clipboards.

Stride Association Management Platform · Document version 1.0

Contents

1.	What is the Kiosk?
2.	Hardware requirements & setup
3.	Activating Kiosk mode
4.	Daily operation — what families see and do
5.	What each scan result means
6.	Exiting Kiosk mode
7.	Managing Kiosk terminals (Admin)
8.	Troubleshooting & FAQ

1. What Is the Kiosk?

The Kiosk is a dedicated tablet mode in Stride designed to sit permanently at your association's entrance and handle student check-in and check-out without any staff involvement. Families walk up, scan their child's QR code, and see an instant result — all without queuing at a front desk or waiting for an Operator to be available.

1.1 What the Kiosk does

- Scans student and guardian QR passes and shows an immediate allowed/denied result
- Verifies enrolment status, payment, and medical certificate validity in real time
- Logs every scan to the attendance record and audit trail automatically
- Alerts staff immediately if a denied scan occurs (rather than just showing an error to the family and moving on silently)

1.2 What the Kiosk does NOT do

- It does not replace an Operator at the door for situations requiring human judgment — it handles routine, expected check-ins
 - It cannot override a denied result — only an Admin can manually clear a block
 - It does not handle payments or enrolment — these are done in the main family app
-

2. Hardware Requirements & Setup

2.1 Recommended hardware

Item	Requirement
Tablet	Any modern iPad or Android tablet — 8" or larger recommended for readability at a reception desk. A tablet with a front-facing camera works well if families scan toward the screen.
Camera	The tablet's built-in camera is sufficient. A rear camera pointing outward (tablet in a stand) is the most common setup.
Mount/stand	A fixed, stable stand at counter height. The QR scanner works best when the camera is level with a held phone — typically 100–120 cm from the floor.
Network	Stable Wi-Fi or a data connection is required for real-time verification. A wired ethernet adapter (if your tablet supports it) is more reliable in busy venues.
Power	Keep the tablet permanently plugged in — Kiosk mode is designed to run all day without interruption.

2.2 App installation

Install the Stride app on the tablet from the App Store or Google Play — the same app used by Operators and Members. The Kiosk mode is activated from inside the app once the tablet has been registered by your Admin (see Section 3).

TIP

On iOS, enable Guided Access (Settings → Accessibility → Guided Access) after activating Kiosk mode — this prevents families from accidentally exiting the app or accessing other tablet functions.

3. Activating Kiosk Mode

Kiosk mode requires setup by the Admin first, then activation on the tablet itself.

3.1 Admin: register the terminal

- 1 In the Stride Admin app, go to `Operations hub → Check-in Terminals` .
- 2 Tap `Add Terminal` and give it a name (e.g. "Front Entrance", "Studio B Door").
- 3 The system generates a unique PIN for that terminal. Note it down — you'll need it on the tablet.

3.2 On the tablet: enter Kiosk mode

- 1 Open the Stride app on the tablet.
- 2 On the login screen, tap `Kiosk Mode` (or navigate to Settings and select it).
- 3 Enter the terminal PIN generated by the Admin in step 3.1.
- 4 The app switches to Kiosk mode — the scanner activates automatically and the screen displays the association's branding.

SECURITY NOTE

The terminal PIN is used to exit Kiosk mode as well as to activate it. Keep it confidential — it should be known only to Admin and trusted senior staff. Do not leave it written near the tablet where families could see it.

4. Daily Operation — What Families See and Do

Once Kiosk mode is active, the tablet requires no further staff interaction for routine check-ins. The screen stays on the scanner view at all times.

4.1 The family experience

- 1 Family member opens Stride on their phone and shows their child's QR pass to the tablet camera.
- 2 The tablet scans the QR automatically — no button to press, no waiting for staff.
- 3 A large, clear result appears on screen within one second: green (allowed), yellow (warning), or red (denied).
- 4 An audio tone also plays: a positive sound for allowed, a warning tone for yellow, and a distinct alert for denied.
- 5 The screen resets automatically after a few seconds, ready for the next scan.

4.2 Offline operation

If the tablet loses its network connection, Kiosk mode queues check-ins locally and syncs them automatically when the connection is restored. The tablet continues to function and scan — you will see a small network indicator on screen when offline. Real-time verification is limited during offline periods (the system cannot check payment or certificate status against the live database), so plan to have a staff member nearby when network outages are expected.

5. What Each Scan Result Means

Display	Sound	What it means	Action needed
✔ Green — Allowed	Pleasant tone	Student is enrolled, payment up to date, certificate valid.	None — student enters normally.
⚠ Yellow — Warning	Short double tone	Student can enter today but has an expiring document or upcoming payment due.	Let the student in. Flag the family to resolve the issue before the next class.
🛑 Red — Denied	Alert tone	Subscription lapsed, certificate expired, or student is flagged on the security list.	Do not allow entry. Direct the family to speak with the Admin or front desk. The Admin is automatically notified of the denied scan.
? Error — Cannot verify	Error tone	The QR could not be verified — expired pass, invalid format, or network issue.	Ask the family to refresh their QR in the Stride app and try again. If the error persists, direct them to the front desk. Do not allow entry on an unverified scan.

SAFETY RULE — RED AND ERROR RESULTS

The Kiosk is not designed to override a denied result. If the system says denied, a staff member must be involved before the student enters. Do not configure the Kiosk in a location where there is no staff member available to handle denied scans.

6. Exiting Kiosk Mode

Kiosk mode is designed to be difficult to exit accidentally — this is intentional, to prevent families or students from accessing other tablet functions.

6.1 How to exit

- 1 Tap the small, discreet exit icon (usually in a corner of the Kiosk screen — placement varies by association setup).
- 2 Enter the terminal PIN when prompted.
- 3 The app exits Kiosk mode and returns to the normal Stride login screen.

IMPORTANT

The exit PIN is loaded from the server when Kiosk mode starts. If the tablet has no network connection at the time of exit, it may display a "Cannot load PIN — check connection" message. Restore the network connection and try again — do not force-close the app as an alternative, as this may leave attendance records unsynced.

6.2 When to exit Kiosk mode

- At the end of the day when the tablet is being secured away
- If the tablet needs to be used for something else temporarily
- If there is a technical issue that requires restarting the app

There is no need to exit and re-enter Kiosk mode between classes during the day — the scanner resets automatically between scans and handles multiple classes sequentially without any intervention.

7. Managing Kiosk Terminals (Admin)

7.1 Viewing registered terminals

[Operations hub](#) → [Check-in Terminals](#) lists all registered Kiosk tablets for your organization, with their last-seen time and status.

7.2 Revoking a terminal

If a tablet is lost, stolen, or decommissioned, tap [Revoke](#) next to that terminal. The PIN becomes invalid immediately — even if someone has the old PIN, it will not work to exit or re-enter Kiosk mode on that device after revocation. You can register a replacement tablet at any time.

7.3 Rotating the PIN

To change the exit PIN for a terminal (recommended periodically as a security measure), revoke the existing terminal and register it again — a new PIN is generated automatically. The tablet will need to be re-activated with the new PIN the next time it is set up in Kiosk mode.

8. Troubleshooting & FAQ

The scanner isn't detecting QR codes.

Check that the tablet's camera has permission to be used by the Stride app (device Settings → Apps → Stride → Camera → Allow). Also check the lighting in the area — the scanner works best in good light. Clean the camera lens with a soft cloth if it appears smudged.

Every scan is showing an error — even ones that were working before.

Check the tablet's network connection. If the Wi-Fi has dropped, reconnect and wait a moment for the Kiosk to re-sync. If you are in an area with consistently poor signal, contact your Admin about a wired ethernet solution for the tablet.

I've forgotten the exit PIN.

The Admin can look up or regenerate the terminal PIN from [Operations hub → Check-in Terminals](#) . If you genuinely cannot access the Admin panel, force-closing the Stride app from the device's app switcher will exit Kiosk mode — but do this only as a last resort, and check with your Admin afterward to ensure attendance records are intact.

A family says their QR worked on the Kiosk but they were told to leave by a staff member — who is right?

A green scan means the system verified enrolment, payment, and certificate status at that moment. If a staff member had additional information (e.g. a very recent payment lapse not yet reflected in the system, or a safeguarding concern), their judgment takes precedence. The Kiosk is a first-line tool, not the final word in every situation.

Where do I go for help not covered here?

Contact your Admin, or reach Stride support through the Admin panel at [Operations hub → Help & Support](#) .