DATE: Aug 25th, 2017 (Friday)


FLUID STATICS Application of the Linear Momentum Principle

Stress Vector

When we apply the linear momentum principle we need to know the forces acting on the surface of the volume we select. So, first we need to understand stress vectors and related notation.

Stress vector is the force per unit area of the surface at a certain point on the surface. Since, it is a vector it has both magnitude and direction. The direction of stress vector will depend on the surface or – on the direction of normal to the surface.

Consider a solid bar subjected to a compressive force F. We want to calculate the force acting at point a. However, to define stress vector we need to define a plane on which this force is acting.



Now, consider the xz plane, the normal to this plane is along q direction. The force in this direction

is
$$F$$
.

So, $f_j = F$


Here, the subscript j refers to the normal to the plane (xz) on which the force is acting.

Next, we want stress vector at the same point but acting on xy plane. The normal to xy plane is so the stress vector for this plane is denoted by $\frac{1}{2}$

Question: For the given situation for the bar with compressive force, what is the stress vector for xy plane?

Normal Stress: In the above situation, t_j is known as normal stress, i.e. stress is acting normal to the plane.


In cases, where the forces are NOT normal to plane, we have two types of stress: Shear stress and Normal Stress. (Referred as Normal component of stress and shear component of stress).



Fluids differ from solid in that a shear force applied to the fluid results in motion of the fluid. This implies that "static fluid" cannot experience shear stress or in other words static fluid can only experience normal stress.

Notation for Shear and Normal Stresses in Fluid:


In the figure below, the stress is the stress. The first subscript refers to the normal to the plane on which stress is acting. The second subscript refers to the direction of the force. When the two subscripts are not the same, the stress is shear stress. On the other hand, when the two subscripts are the same, the stress is a normal stress. For example, the stress is a normal stress.



Application of Linear Momentum Principle on Static Fluid

For a static fluid, the momentum is zero. Therefore, the rate of change of linear momentum is also zero. So, the general principle of momentum balance reduces to:

Consider a tetrahedron that is shown below. The forces acting on different planes of tetrahedron are also shown. It is to be noted that all the forces are normal to the plane on which they are acting since shear stress0es are zero for a static fluid. ABCD is the tetrahedron. The four planes of the tetrahedron are ABC, BCD, ADC and ABD.



The area of these planes along with the direction of the normal and normal stress vector are:

Plane	Area	Normal	Stress Vector
ABC	SAh	₹)	3
BCD	AAV	J - L	T by
ADC	AAu		J by
ADB	DAZ	-K	RA
0 =	SS 3 dv	+ JZJA	

$$\Delta A_{x} = \Delta A_{n} \cos \theta$$

$$\Delta A_{x} = \overrightarrow{i}.\overrightarrow{m} \Delta A_{n} = m_{x} \Delta A_{n} \overrightarrow{i}$$

$$\Delta A_{y} = \overrightarrow{j}.\overrightarrow{m} \Delta A_{n} = m_{y} \Delta A_{n} \overrightarrow{k}$$

$$\Delta A_{z} = \overrightarrow{k}.\overrightarrow{m} \Delta A_{n} = m_{z} \Delta A_{n} \overrightarrow{k}$$

$$\Delta A_{z} = \overrightarrow{k}.\overrightarrow{m} \Delta A_{n} = \overrightarrow{m}_{z} \Delta A_{n} \overrightarrow{k}$$

$$\Delta A_{z} = \overrightarrow{k}.\overrightarrow{m} \Delta A_{n} = \overrightarrow{m}_{z} \Delta A_{n} \overrightarrow{k}$$

0 = gg DV - mph DAn + mx DAn pxi + my san þýj + mz san þzk Dividing by DAn Since $\Delta V \rightarrow 0$ farter than ΔA_n (cubicfunction vs. square fun) = mpn-[mxpxl+mypyj+mzpzk]