



GigaCloud

Troubleshooting Guide

July 2019

Table of Contents

<i>Introduction.....</i>	<i>2</i>
<i>GigaTrust Log Client</i>	<i>4</i>
<i>GigaTrust Issue List</i>	<i>7</i>

Introduction

This guide will assist you in troubleshooting your GTEP installation and configuration. If you are still unable to fix the problem, contact your GigaTrust Sales Engineer or go to our Help Desk at <http://helpdesk.gigatrust.com> for more assistance.




GigaTrust Log
Client

If you have already installed GTEP, make sure the [GTEP Log Client](#) is running to assist you in troubleshooting. Go to Programs and select **GigaTrust Log Client**.


There are three types of messages that may be displayed in GigaCloud Administration:

Success Message




This message is displayed to indicate successful updates/changes in the UI and automatically disappears after 5 seconds.

Warning Message



This message displays warnings in the UI and automatically disappears after 5 seconds.

Error Message



This message displays errors in the UI and will stay visible until you go to another page or close it out manually.

GigaCloud Administration Problems and Issues may fall into the following categories:

 [Prerequisites](#)

1. .NET Requirement

 [Installation](#)

1. Database Setup/Configuration

 [Access](#)

1. GTEP Access Issues

 [Performance](#)

1. Timing out
2. Reports

 [Miscellaneous Issues](#)

GigaCloud Log Client

All GTEP components send messages related to errors encountered and current status to the GigaTrust Log Server. The GigaTrust Log Server is a component of GTEP that is installed on the AD RMS Server as a service. The GTEP Log Client displays messages that are sent to the GigaTrust Log Server. You can install the GigaTrust Log Client component on its own server to isolate this component from the other GTEP components thereby allowing an administrator to delegate this process.



Access the GigaTrust Log Client via All Programs → GigaTrust Log Client. Click **Connect** to view messages from the GigaTrust Log Server that is specified in the Log Server field. The default is localhost, but the GTEP Log Client can view messages from any accessible GigaTrust Log Server running in the network.

Click **Suspend** button to pause log messages from loading so you can view the details more closely. Click **Resume** when you are finished and the log files will continue loading from where it left off.

Click **Clear Log** to clear the messages from the display.

Click **Save** to write the currently displayed log messages to a file. A destination path and filename will be required for saving.

Export allows for saving log messages for a specific date/time range to a file. From and To dates, and time values, must be specified for the export. A destination path and filename will be required for saving.



The **Filter** drop-down list contains the different levels of messages that are displayed by the GigaTrust Log Client: All, Debug, Info, Warn, Error, and Fatal. Selecting a filter will display incoming messages received by the GigaTrust Log Server that are that level and above. (Display of existing messages is not affected.) For example, if Warn is selected as the filter, only newly received messages with a status of Warn, Error, or Fatal will be displayed in the GTEP Log Client window.



To view the details of any message, double-click its row in the GTEP Log Client window.

The top of the details window displays all field information that displays in the GTEP Log Client window. Previous (<<) and Next (>>) buttons are available to move between messages.

For Error level messages, the trapped error message is displayed in the Exception field at the bottom of the Details window. This information is critical to troubleshooting and resolving issues with the GTEP application.




For additional features, click the menu icon at the upper right of the window.




Search

Enter either text or a regular expression to search for matching results. Optionally, only search for Exceptions. Results are displayed with an option to **Save**.



Export

Enter a date/time range for log messages to export. Specify the output filename and destination. The gray field shows progress as the export text file is created.




Archive

Use Archive to capture logging messages in real time. Enter a destination for what will be the archive file. Optionally define a maximum log file size.

Click **Start** when you want to start collecting log messages and **Stop** to cease collecting.

A text file labeled GTLogClient<date><start time> is created in the specified destination folder.



GigaCloud Issue List


PREREQUISITES

Issue: The installer stops because .NET 4.5.1 is not installed.

Solution: Download/Add Feature for .NET 4.5.1. It is suggested that all Windows Server updates be installed on the server as well.


INSTALLATION

Issue: During installation you receive the following error during GTEP database creation:




Solution: The SQL Server firewall is not allowing the installer to connect to it.


1. On the SQL Server(s) go to **Administrative Tools** ➤ **Windows Firewall with Advanced Security**.
2. Highlight **Inbound Rules** and select **New Rule** on the right-hand side.



3. The **New Inbound Rule Wizard** displays. Select **Port** and click **Next**.




4. Keep **TCP** checked and enter **1433** in the **Specific local ports** text box. Select **Next**.



5. Keep **Allow the connection** selected and click **Next**.
6. Keep all three rules checked on the next window and select **Next**.
7. On the next window name the rule **SQL Server** then click **Finish**.
8. Repeat Steps 1 – 7 with the same parameters except:
 - a. Select **UDP**, not **TCP**.
 - b. For **Specific local port** enter **1434**.
 - c. Name the rule **SQL Server Browser**.

ACCESS

Issue: You try to log in to GTEP and receive the following error:



Solution: GTEP cannot connect to SQL Server. Check the Server/Cluster instance and verify the service is running.

Issue: You try to log in to GTEP and receive the following error:



Solution: The **GTEP Service** is not running. On the server on which GTEP is installed, go to **Administrative Tools > Services**. Start/Restart the **GTEP Service**. This may also mean reinstalling GTEP to fix the problem.

PERFORMANCE

Issue: Receiving timeouts.

Tune the timeout setting in GTEP web.config:

1. Access c:\program files\gigatrust\gtep\web\adminclient
2. Find the key: OperationTimeout [Default value: 180 (seconds)]
3. Try setting it to 300 and see if that resolves the timeout issue. Tune as necessary.

Note: A value greater than 600 seconds will be ignored.

Issue: Some reports hang when being generated.

The GTEP service account language/locale must be set to English:

1. Log on to the GTEP server as the GTEP service account.
2. Change the language and locale to English.
3. Stop the GTEP services.
4. Restart IIS.
5. Start the GTEP services.

MISCELLANEOUS ISSUES

Issue: If IRM in Office for Mac 2011 is installed on RMS server after GTEP is installed, web.config file is deleted from under _wmcs and GTEP Modules are removed.

It is recommended that a backup be made of the c:\inetpub\wwwroot_wmcs\web.config file before installing IRM in Office for Mac 2011.

To fix the 500.23 error (%systemRoot%\system32\inetsrv\appcmd migrate config "Default Web Site/"), uninstall and then reinstall GTEP.