

Users Interface




Figure: Draft Users Interface – June 10, 2026

Users Overall:

1. Top of page: Navigation Path reads **Home / Users**.

Instead: **Home / Admin / Users**

Home text is **actionable**, as is Home button on Header, and Home button on Navigation Panel.

Inconsistent convention of actionable text (**color**) in these side-by-side controls.

2. Use Initial Caps on Headings and Labels. (as here when word is 4-letters or more)
3. Inconsistent Terminology: Users / Members (**Users** is always better)
4. Label ambiguous controls: **Filter by Role:** or **Filter (Funnel) Icon**.
5. **Select All Users checkbox** not working (known?)
6. **Status** column header is ambiguous. As this is a Boolean, propose: **Active / Inactive**.
7. The import of user **coin** color (initials) is unclear. Doesn't match role color.
8. Reduce User column width, to bring role data closer.
9. You have the real estate to show **Edit Profile** and **View Activity** buttons (why hide them?)
10. Does **Resend Invitation**, **Revoke Invitation**, and **Simulate Acceptance** send a notification to original Invitor? (They should.)
11. Invite User form fields are ALL CAPS. (Let's establish this as a convention.)
12. **Invite User** inline field text inconsistent and poorly worded (**See Corrections**.) Place task directions at the top of the dialog box, and sample data in the field (in disabled grey font).

13. Remove “**Personal**” from Invite User message form field.

Invite users

EMAIL ADDRESSES

name@company.com, press Enter to add

Separate multiple addresses with a comma or press Enter.

ROLE

Select a role...

PERSONAL MESSAGE (OPTIONAL)

Add a personal note to the invitation...

Cancel Send invitations

Corrections:

Set a color convention for actionable text and apply consistently. On this page: [Home](#)

Enter Initial Caps on Headings and Labels:

6 **A**ctive **M**embers – 2 **P**ending **I**nvitations (Make “Members” **U**sers)

Invite **U**sers

Search **U**sers

Active **U**sers

Pending **I**nvitations

Edit **P**rofile

View **A**ctivity

Last **A**ctive (Column Heading)

Resend Invitation

Revoke Invitation

Simulate Acceptance

On Invite Users dialog box:

Invite Users (Title)

Send Invitation(s) (Add parentheses)

Invite Users dialog box text corrections:

Invite Users

Enter e-mail addresses delimited with commas (,) or press Enter.

EMAIL ADDRESS(ES) (Add parentheses)

[name@company.com](#) (disabled grey)

ROLE

Select a role... (disabled grey)

MESSAGE (Optional)

Enter message... (disabled grey)

Roles and Permissions Interface

Role name	Description	Type	Users	Last modified
Administrator	All permissions across all subjects. Full system access.	System	1	System default
Estimator	Full access to Projects, Drawings, Rooms, Elevations, Pricing, and AI. No Drafting access.	System	1	System default
Draftsman	Project access (no delete), Drawings/Rooms/Elevations (no delete), full Drafting and AI access. No Pricing.	System	1	System default
Viewer	Read-only access to projects and estimates. Cannot create, edit, or export.	System	1	System default
Senior Estimator	Like Estimator with added access to manage pricing and product mappings.	Custom	2	Jun 2, 2026 - Rob Pryor
Outside Consultant	Limited access for external contractors — view projects and export to CAD only.	Custom	1	May 28, 2026 - Rob Pryor

Figure: Draft Roles and Permissions Interface – June 10, 2026

Overall:

Users Overall:

1. Top of page: Navigation Path reads **Home** / Roles & Permissions.

Instead: **Home** / Admin / Roles & Permissions

Home text is **actionable**, as is Home button on Header, and Home button on Navigation Panel. Inconsistent convention of actionable text (**color**) in these side-by-side controls.

Important: We must differentiate **Admin** (the task set) from **Administrator** (the user role) and use the term consistently. This would mean editing the Administrator label on the Navigation Panel.

2. Use Initial Caps on Headings and Labels. (**See Corrections** below.)
3. Use a colon (:) in the role count. (**See Corrections** below.)
4. "Custom" is ambiguous. Replace with "**User-defined**" or "**Company-defined**."
Documentation will explain that System roles cannot be edited or defined, but that an Administrator with the correct permissions can define an unlimited number of bespoke roles.
5. "Type" is also ambiguous. Amend with "**Role Type**" or "**Role Creator**."
6. The **Descriptions** column data seems too generic. I would have expected the definition to cite specific permissions. (**See Corrections** below.)
7. Add the following text at the top of the interface.
"**Clicking a Role Name navigates to the Role Definition interface.**"
8. Add a button to the Role Definition interface that returns to Roles & Permissions, next to **Edit Role**.

Corrections:

Set a color convention for actionable text and apply consistently. On this page: **Home**

6 **Roles**: 4 **System** · 2 **Custom** (**User-defined**)

Add:

Click a Role Name to view the role definition and corresponding permissions.

Enter Initial Caps on Headings and Labels:

6 **Roles**: 4 **System** · 2 **Custom** (**User-defined**)

Role **Name**

Last **M**odified

Create **R**ole

System **D**efault

Assigned **U**sers

Last **S**ign-in

System **R**ole

Save **R**ole

Grant **A**ll

Revoke **A**ll

Duplicate **E**xisting

Edit **R**ole

Edit these System Role Description strings:

Full System access. All possible permissions.
Full access to p rojects, d rawings, r ooms, e levations, p ricing, and AI. No d rafting access.
Project access (W ithout delete). Drawings/Rooms/Elevations (W ithout delete). Full d rafting and AI access. No p ricing.
Read-only access to p roject estimates. Cannot create, edit, or export.

Create role X

ROLE NAME *
e.g. Senior Estimator

DESCRIPTION
Describe what this role can do...

START FROM

Blank
No access to anything by default

Duplicate existing
Copy permissions from an existing role

Permissions

Projects
5 permissions v

Grant all Revoke all

☐ **Add**
Create a NEW project definition in your company

☐ **Update**
Change a project definition for your company

☐ **Delete**
Delete a project definition from your company

☐ **Import**
Import a project definition into your company

☐ **Export**
Export a project definition in WWIE format

Drawings
3 permissions v

Rooms
3 permissions v

Cancel Save role

Figure: Create Role Panel

The Cancel and Save Role buttons at the bottom truncate the panel (hiding the fact that there are more permissions. I wish there was a visible scroll bar to indicate there is more.

“START FROM” is ambiguous. Replace with “**CREATE FROM:**”

“Blank” is ambiguous. No one would want to create a role with “No access to anything by default.” The “by default” suggests this is a viable option imposed by the software. Replace with: “Blank: **Create an empty role, then add permissions below. Roles without permissions are assigned Viewer permissions by default.**” (or whatever the default really is...)