Chapter 1: IPv6 address Fundamental

1) Basics

An IPv6 address is a 128 bit binary number and expressed in hexadecimal form, e.g.

```
2001:1234:5678:0001:0000:0000:0000:0001/64 (32 hexadecimal numbers)
```

There is a colon between each 4 hexadecimal numbers. This is for easy reading, just like the "dot-decimal form" of IPv4 address. E.g. 202.175.3.3

/64 means the first 64 bit is the network prefix, it is similar to IPv4 CIDR (Classless Inter-Domain Routing) notation

2) Simplifying IPv6 addresses

Since it is too long to express the IPv6 address, we want to simply it.

```
e.g. 2001:1234:5678:0001:0000:0000:00001/64 can be simplified as 2001:1234:5678:1:0:0:0:1/64
```

This is called "Zero compression" – The leading zeros in each segment can be omitted. Continuous zeroes can be further compressed.

```
2001:1234:5678:<mark>000</mark>1:<mark>0000:0000:0000</mark>:<mark>000</mark>1/64
```

→ 2001:1234:5678:1:<mark>0:0:0</mark>:1/64

→ 2001:1234:5678:1<mark>::</mark>1/64

"::" – Double Colon, means a series of 0000 groups. Since the total length of an IPv6 address is 128 bit, the number of zeroes omitted can be calculated.

Another example:

- → 2001:<mark>0:0</mark>:1:0:0:0:1/64
- **→** 2001:0:0:1::1/64
- → But Note: 2001::1/64 is incorrect. It is because there is no way to identify the no. of zeroes omitted in the two double-colon areas.

3) IPv6 Prefix

Let's learn more about IPv6 Prefix.

In IPv4, we use subnet mask to denote the network portion.

e.g. 192.168.1.1 255.255.255.0 \rightarrow 192.168.1.0 is the network portion

It can be written as: 192.168.1.1/24 (CIDR notation)

In IPv6, we don't use subnet mask. We only use the latter CIDR notation e.g.

2001:1234:5678:0001:0000:0000:0000:0001/64

The network portion is: 2001:1234:5678:0001:: /64

The host portion is: 0000:0000:0000:0001.

That means there can be a tremendous number of hosts, 2⁶⁴.

In IPv6, the network portion of an IP address is basically fixed at /64 and the host portion is always 64 bits.

There is no need for subnetting. Since there are far too many bits in the IPv6 addresses that each organization can be assigned a network prefix of /48.

e.g. A company may be assigned range of IP addresses with a network prefix of 2001:1234:5678:: /48. Then, the company can use 16 bits for the local subnetting.

e.g.

2001:1234:5678:0000:: /64 is the first subnet

to

2001:1234:5678:FFFF:: /64 is the last subnet.

This results in 65536 subnets, which is far more than enough for each company or organization.

In each subnet, there can be 2^64 hosts.


So, the network prefix of a usable IPv6 address is basically fixed at /64 and no further subnetting is needed. This is an advantage over IPv4 because we need to

do quite a lot troublesome IP address subnetting in IPv4.

4) Demonstration

Let's use Packet Tracer to show a demonstration of using IPv6 addresses.

Topology:



PC setting:

```
IPv6 Configuration

○ DHCP ○ Auto Config ○ Static

IPv6 Address 2001:1234:5678:1::1 / 64

Router setting:
!
interface GigabitEthernet0/0
no ip address
duplex auto
speed auto
ipv6 address 2001:1234:5678:1::FFFF/64
```

Ping test:

```
PC>ping 2001:1234:5678:1::FFFF

Pinging 2001:1234:5678:1::FFFF with 32 bytes of data:

Reply from 2001:1234:5678:1::FFFF: bytes=32 time=1ms TTL=255


Reply from 2001:1234:5678:1::FFFF: bytes=32 time=0ms TTL=255
```

Chapter 2: Different kinds of IPv6 addresses

It is crucial to understand the different kinds of IPv6 addresses, their principle and usage. In this Chapter, we will introduce the various kinds of commonly used IPv6 addresses.

1) FIPv6 Global Unicast Address

IP addresses are allocated by IANA (Internet Assigned Numbers Authority), through 5 RIRs (Regional Internet Registries), which are responsible for 5 different areas on the Earth.



RIR	Responsible Regions
African Network Information Centre (AfriNIC)	Africa region
American Registry for Internet Numbers (ARIN)	The United States, Canada, several parts of the
	Caribbean region, and Antarctica regions.
Asia-Pacific Network Information Centre (APNIC)	Asia, Australia, New Zealand, and neighboring
	countries
Latin America and Caribbean Network	Latin America and parts of the Caribbean region
Information Centre (LACNIC)	
Réseaux IP Européens Network Coordination	Europe, Russia, the Middle East, and Central Asia
Centre (RIPE NCC)	

The current allocation of public IPv4 addresses is not sequential and continuous, meaning that a geographic region may acquire discontinuous ranges of public IPv4 address. This is due to the historical way of assignment and the insufficient public IPv4 addresses. E.g. For Macau region, it contains a large number of discontinuous, small address ranges, starting with 202.175.x, 27.x.y, 60.x.y, 113.x.y etc. This makes the aggregation of public IPv4 addresses very inefficient.

For IPv6, since it is a new deployment and there are huge numbers of IPv6 addresses. Huge enough to give each piece of sand on the Earth an IPv6 address. So, the assignment of public IPv6 addresses is more systematic.

Currently only 1/8 of the IPv6 addresses are publicly assigned, which is : 2000::/3. What does it means?

It means from 2000:: to 3FFF:FFFF:FFFF:FFFF:FFFF:FFFF


<mark>001</mark> 0	0000	0000	<u>0000</u> 0000 0000 0000 0000	(Binary)
2	0	0	0 :0000:0000:0000:0000:0000:0000	(Hexadecimal)
<u>001</u> 1	<u>1111</u>	<u>1111</u>	<u>1111</u> 1111 1111 1111 1111	(Binary)
3	F	F	F : FFFF:FFFF:FFFF:FFFF:FFFF	(Hexadecimal)

And, currently, most of the assigned public IPv6 addresses starts with 2001::/16.

0010	0000	0000	0001		(Binary)
2	0	0	1	:	(Hexadecimal)

The IANA assigns address blocks to the five RIRs. The following table shows only a small portion of them. Usually, the IANA assigns address block with /23 prefix.

2001:0200::/23	APNIC	2001:0400::/23	ARIN
2001:0600::/23	RIPE NCC	2001:1200::/23	LACNIC
2001:4200::/23	AFRINIC		



For APNIC, it has got 2001:0200::/23. What does 2001:0200::/23 include?

2	0	0	1 : 0	2	0	0	:0000:0000:0000:0000:0000:0000/23
0010	0000	0000	<u>0001</u> <u>00</u>	<u>001</u> 0	0000	0000	0000 00000000 0000/23
to							
2	0	0	1 : 0	3	F	F	:FFFF:FFFF:FFFF:FFFF/23
0010	0000	0000	<u>0001</u> <u>00</u>	<u>00</u> 0011	1111	1111	1111 1111 1111 1111/23

So, APNIC has got this block of IPv6 addresses:



Then, the APNIC assigns address blocks to ISPs.

e.g. APNIC may assign a block of addresses to ISPs like this:

2001:02 55::/32 to ISPa 2001:02 66::/32 to ISPb

So, ISPa gets a block of IP addresses as follows:

2001:02 55::/32	<u>2001:0255</u> :0000:0000:0000:0000:0000
	to
	2001:0255:FFFF:FFFF:FFFF:FFFF

2001 0255

Registry
$$\rightarrow \rightarrow /23$$

ISP $\rightarrow \rightarrow \rightarrow \rightarrow \rightarrow /32$

Then, ISPa assigns blocks of IP addresses to different organization, like this:

e.g.

<u>2001:0255</u>:8888::/48 to Organization A <u>2001:0255</u>:9999::/48 to Organization B

So, Organization A gets:

2001 0255 8888

Registry
$$\rightarrow \rightarrow /23$$

ISP Prefix $\rightarrow \rightarrow \rightarrow /32$

Site Prefix $\rightarrow \rightarrow \rightarrow \rightarrow \rightarrow \rightarrow /48$

In this point of view, Organization A is referred to as a Site.

Now, the organization can freely use the remaining bits for its own, but, keeping 16 bits for Subnet ID.

Then, for each subnet, there are 64 bits for hosts, all together, 2^64 hosts. This is called Interface ID and is used for identifying IPv6 host interface.

2001	0255	8888	4444	Interface ID
Registry-	>→/23 ×→→→/3	2		
Site Prefi	$x \rightarrow \rightarrow \rightarrow \dot{\gamma}$	>>> /4	8	
			<-Subnet->	←64bit Interface ID ->

As one organization can have 65536 subnets, with each subnet having 2^{64} hosts, this is far more than enough. So, no more subnetting is needed by the organization.

The above resultant IPv6 addresses is publicly reachable in the Internet and is called: **IPv6 Global Unicast Address**It is similar to the IPv4 public addresses.

2001	0255	8888	4444	Interface ID
Registry-	>→/23 ×→→→/3	2		
Site Prefi	$x \rightarrow \rightarrow$	>>> /4	8	
			<-Subnet->	←64bit host ID→


General format:

48bit	16bit	64bit
Global Routing Prefix	Subnet ID	Interface ID


2) FIPv6 Link local (Unicast) Address

In IPv6, a network host will try to discover if there is any neighbor nearby.

e.g. PC-A may send out a message like this:



And PC-B may reply:



You will notice that they are not using their Global Unicast address. Instead, they use a kind of IPv6 address called: "Link Local address". In IPv6, Link Local address is used to communicate with neighbors in the same link or Layer 2 segment.


How is the Link Local address formed?

1) All link local address starts with FE80::/10, in binary: 1111 1110 10.

It ranges from:

But commonly used Link Local Address starts with "FE80".

2) The MAC-address of the interface is used and converted as EUI-64 format.



3) Finally the two parts are combined to form the Link Local address.



The Link Local address is automatically generated, even though the interface has not been assigned with any IPv6 Global Unicast Address. IPv6 Link Local address is analogous to IPv4 Link Local address, in the range: 169.254.0.0/16. But, their usage is different. An IPv4 host will only get such an address when it is configured to use DHCP server to acquire IP address but no response from any DHCP server is got.

<u>Different ways of assigning IP address:</u>

Now, let's look more deeply into the actually usage of Link Local Address. To do so, we need to learn about how an IPv6 address can be assigned to an interface.


1) Static IPv6 address assignment

The most straight forward way is static assignment. E.g. On a PC:

IPv6 Configuration	IPv6 Configuration						
□ DHCP □ Auto Config							
IPv6 Address	2001:0255:8888:0000::1	/ 64					
Link Local Address	FE80::2D0:58FF:FE5B:98D6						

2) Stateless Auto-configuration

Another way, you can configure the PC to get an IPv6 address from its neighboring router. Let's see the following:




After a few seconds, the PC gets the following IPv6 address:

IPv6 Configuration	IPv6 Configuration					
○ DHCP ② Auto Config ○ Static						
IPv6 Address	2001:0:1234:8888:2E0:F9FF:FE0B:CC1 / 64					
Link Local Address	FE80::2E0:F9FF:FE0B:CC1					
IPv6 Gateway	FE80::260:3EFF:FE2A:A201					

How does the PC get this address?

a) The PC sends out a "Router Solicitation" Message, requesting for the network prefix.




b) When a nearby router receives this message, it replies with a "Router Advertisement" Message, including the "Network Prefix" and its "Link Local Address". In this case, the network prefix is 2001:0000:1234:8888::/64.

Hi, I am. My IPv6 address is FE80::260:3EFF:FE2A:A201.
Please use 2001:0000:1234:8888::/64 as the network prefix.

fa0/0
2001:0000:1234:8888::254 /64
FE80::260:3EFF:FE2A:A201

PC-A
00E0.F90B.0CC1

c) The PC then takes this network prefix and combines with its EUI-64 host ID to form its IPv6 address. → 2001:0000:1234:8888:2E0:F9FF:FE0B:CC1.



You may notice that the "IPv6 Gateway" is also automatically set. In the Router Advertisement message from the router, there is the link local address of that router interface. So, the PC set this link local address as its IPv6 gateway. PC:

IPv6 Gateway FE80::260:3EFF:FE2A:A201

Router: "show ipv6 interface brief"

FastEthernet0/0 [up/up] FE80::260:3EFF:FE2A:A201 2001:0:1234:8888::254

Now, you have learnt about one the usage of Link Local address. Remember that packets with destination IPv6 Link Local address will NOT be forwarded by router. So, The scope of Link Local address is only limited to the Layer 2 segment that it belongs to.

3) DHCPv6

This will be not be discussed here. But, it works similar to DHCP in IPv4.

3) 『Special IPv6 addresses that commonly used』

1) Unspecified address

When an IPv6 host has not yet got or assigned any IPv6 address. It will use 0:0:0:0:0:0:0:0 or :: as its source IP address. This is similar to 0.0.0.0 in IPv4.

2) Loopback address

In IPv4, the loopback address is in the range 127.0.0.0 / 8 and is typically 127.0.0.1. In IPv6, the loopback address is 0:0:0:0:0:0:0:0:1 or ::1. This address has a Node-scope, meaning that it is only destined for the Node itself.

3) Default Route address

::/0 is the default route address.

4) FIPv6 Multicast Addresses

1) Formation

In IPv4, multicast addresses are in the range of 224.0.0.0 – 239.255.255.255. What about IPv6? In IPv6, multicast addresses always starts with FF.



It ranges from:

In fact, the 3^{rd} and 4^{th} Octets have special usage/purpose, we will discuss later. That's why we mark them X here.


2) Typical usage

a) Router Discovery


An IPv6 host will try to discovery if there is any router on its local link, esp. when it is configured to get IP address using "Stateless Auto-Configuration".

Let's see the following example.


i) The PC-A sends out an ICMPv6 Router Solicitation Message (Type 133) with a source address of FE80::2E0:F9FF:FE0B:CC1, to a destination address of FF02::2, which is a multicast group including "All Routers in the Link Local scope".



ii) When the router receives this RS Message, it replies with an ICMPv6 Router Advertisement Message (Type 134), with a source address of its Link Local address and a destination address of FF02::1, which includes "All Nodes in the Link Local scope".



iii) When, PC-A receives this RA, it takes the G/W IP address and the N/W prefix. It uses EUI-64 to generate its Global Unicast IPv6 address.



Now let's examine the 2 IPv6 multicast addresses that we see above:

FF	Lifetime 0 R P T	Scope	Group ID
FF	0	2	2

It is a permanently assigned multicast adress With a link local scope Group ID = 2 means - All Routers

FF	Lifetime 0 R P T	Scope	Group ID
FF	0	2	1

It is a permanently assigned multicast adress With a link local scope Group ID = 1 means - All Nodes

All IPv6 enabled routers will join a multicast group of FF02::2 and all IPv6 hosts will join a multicast group of FF02::1.

Below, let's see the general form of IPv6 multicast addresses.

General form of an IPv6 multicast address

8 bits	4 bits	4 bits	112 bits
FF	Lifetime 0 R P T	Scope	Group ID

 $T = 0 \rightarrow Permanent multicast address assigned by IANA$ $T = 1 \rightarrow Transient multicast address$ R and P has other usages and is basically 0

Scope = 1	Node
Scope = 2	Link
Scope = 5	Site
Scope = E	Global

Notes:

- Basically T will be 0, Permanent assigned.
- Scope 1 is Node scope, meaning that this address is valid for this Node.
- Scope 2 is Link-Local scope, meaning that this address is valid for this Layer 2 link and will not be forwarded by routers.
- Scope 5 is Site-Local scope, meaning that this address is valid for this
 Site / Organization and will not be forwarded outside it.
- Scope E is Global scope. This kind of IPv6 address is Globally reachable.

3) Common IPv6 Multicast Addresses

FF02::1	All IPv6 nodes	
FF02::2	All IPv6 routers	
FF02::5	OSPF routers	
FF02::6	OSPF Designated Routers	Link Local Scope
FF02::9	RIP routers	
FF02::A	EIGRP Routers	
FF02::1:2	DHCP Srvs/Relay agents	


5) 『IPv6 Broadcast Address???』

1) No more broadcast in IPv6. Multicast is used instead.

In IPv6, to reduce the impact of broadcast traffic, there is no broadcast mechanism. So, what happen to those protocols that use broadcast in the past? Well, they uses multicast instead. So, let see 1 example.

Address Resolution Protocol ??


In IPv6, there is no ARP and it is replaced by a mechanism called **Neighbor Solicitation and Neighbor Advertisement.** It works like this. Let's use the Packet Tracer to see the details.




1) From PCO, we issue a ping command: ping 2001:0000:1234:8888::254 to ping RouterO. PCO drafts an ICMPv6 Echo Request packet, but cannot fill up the layer 2 information.

Layer7
Layer6
Layer5
Layer4
Layer 3: IPv6 Header Src. IP: 2001:0:1234:8888:2E0:F9FF:FE0B:CC1, Dest. IP: 2001:0:1234:8888::254 ICMPv6 Echo Message Type: 128
Layer 2:

2) PCO needs to resolve the MAC address of 2001:0000:1234:8888::254 first. So, it drafts an ICMPv6 packet called "Neighbor Solicitation", with an ICMPv6 type of 135 to resolve the target's MAC address. You will notice that the destination IP address is not a broadcast address as in ARP. It is a special multicast address: FF02::1:FF00:254. This is called the "Solicited Node Multicast address" of the target.




How is this "Solicited Node Multicast address" generated? Let's see the following.




Efficiency of "Solicited Node Multicast address":

Although this is a multicast packet, in fact, basically only Router0 will receive it in this local link. Only Router0 will join the multicast group: FF02::1:FF00:254 since it will be very rare that two hosts in this local link to have their IPv6 addresses with the lowest 24 bits equal. So, this multicast traffic effectively becomes unicast traffic. If the FF02::1 Link Local All Nodes multicast address is used as the destination, this packet will disturb all the IPv6 hosts in the local link. That is why a special "Solicited Node Multicast address" is used.

On the other hand, how does the MAC address: 3333.FF00.0254 obtained? The MAC address of an IPv6 multicast address is obtained as the following:



Now, let's look into the ICMP Neighbor Solicitation Message in more details. It is trying to look up the MAC address of 2001:0:1234:8888::254.



3) When Router0 receives this message, it finds that FF02::1:FF00:254 is destined to itself. Why? Every IPv6 interface will join a multicast group with an ID of "FF02::1:FF"+lowest 24bits of its IPv6 address. This is the "Solicited Node Multicast address". In this case the IPv6 address is 2001:0000:1234:8888::254. So, its "Solicited Node Multicast address" is FF02::1:FF00:254.

Let's see which multicast groups that fa0/0 of Router0 has joined.

```
FastEthernet0/0 is up, line protocol is up
   IPv6 is enabled, link-local address is FE80::260:3EFF:FE2A:A201
No Virtual link-local address(es):
   Global unicast address(es):
     2001:0:1234:8888::254, subnet is 2001:0:1234:8888::/64
   Joined group address(es):
     FF02::1
     FF02::2
     FF02::1:FF00:254
     FF02::1:FF2A:A201
```

Joined Multicast	Explanation	
Group		
FF02::1	Multicast group of all IPv6 nodes in link local	
	scope. Router0 is an IPv6 host.	
FF02::2	Multicast group of all IPv6 routers in link local	
	scope. Router0 is an IPv6 router.	
FF02::1:FF00:254	"Solicited Node Multicast address" of its Global	
	Unicast address:	
	2001:0:1234:8888::254	
FF02::1:FF2A:A201	"Solicited Node Multicast address" of its	
	Link Local address: FE80::260:3EFF:FE2A:A201	

4) Router0 replies with an ICMP Neighbor Advertisement, with an ICMPv6 type 136, to PC0, telling PC0 its MAC address. This is a unicast IPv6 packet destined to PC0.

Dut Layers

Layer7


Layer6

Layer4

Layer 3: IPv6 Header Src. IP:
2001:0:1234:8888::254, Dest. IP:
2001:0:1234:8888:2E0:F9FF:FE0B:CC1
ICMPv6 Neighbor Message Type: 136

Layer 2: Ethernet II Header
0060.3E2A.A201 >> 00E0.F90B.0CC1


Layer 1: Port(s): FastEthernet0/0




5) Now, PCO can issue the ICMPv6 Echo request Message, ICMPv6 Type 128, with this resolved MAC address. 0060.3E2A.A201.

In Layers
Layer7
Layer6
Layer5
Layer4
Layer 3: IPv6 Header Src. IP: 2001:0:1234:8888:2E0:F9FF:FE0B:CC1, Dest. IP: 2001:0:1234:8888::254 ICMPv6 Echo Message Type: 128
Layer 2: Ethernet II Header 00E0.F90B.0CC1 >> 0060.3E2A.A201
Layer 1: Port FastEthernet0/0

6) Finally, Router0 replies with a ICMPv6 Echo Reply Message, ICMPv6 Type 129 back to PC0.






<u>IC</u>	MPv6 Echo Mess	<u>age</u>		
0		8 1	.6	31 Bits
	TYPE: 0x81	CODE: 0x0	CHECKSUM	
	ID: 0x3		SEQ NUMBER: 2	

Since the "Solicited Node Multicast address" of the target rarely includes other hosts except the target, it becomes effectively unicast traffic. So, this process of Link Layer address resolution (Neighbor Solicitation and Advertisement) is more efficient that ARP in IPv4.

6) **IPv6** Anycast address **J**

Anycast address is a new concept. It is usually used for redundancy purpose.

Let's explain the IPv6 Anycast address with the following network topology:



There are two DNS servers, DNS server 1 and DNS server 2, which serves the same sets of DNS zones. They have different IPv6 Global Unicast Addresses - 2001:DDDD:EEEE:FFFF::100/64 and 2001:AAAA:BBBB:CCCC::100/64. But, they each have an extra IPv6 Global Unicast address which is the same: 2345::88/64.

DNS server 1 is connected to Fa0/0 of R2. Fa0/0 of R2 has two IPv6 addresses configured, which corresponds to the 2 different network IDs.

DNS server 2 is connected to Fa0/0 of R4. Fa0/0 of R4 has two IPv6 addresses configured, which corresponds to the 2 different network IDs.

This seems to have duplicated IPv6 addresses in this network. Yes, so, we need to turn off Duplicated Address Detection in R2 and R4 and then it is OK in IPv6.

All the routers run RIPng, so, R1 will receive 2 routes for the network 2345::/64 with different hop count. Of course, in normal situation, the route for 2345::/64 on R1 will direct to R2.

PC-A is configured to use a DNS server of 2345::88. In normal cases, the DNS requests will be forwarded via R1 – R2 and then to DNS server 1. It will process the request and then response.

But, if R2 has some problems and becomes unreachable. R1 will replace the route for 2345::/64 via R3. If now PC-A sends out DNS requests, they will be forwarded via R1 - R3 - R4 and then to DNS server 2.

By this means, redundancy on DNS server is achieved and the IPv6 address: 2345::88 is said to be an IPv6 Anycast address. This mechanism works only with the help of the routers and routing protocols.

IPv6 Anycast addresses share the same range of IPv6 Global Unicast addresses and there is no way to distinguish if an IPv6 address is Anycast or not by just looking at the IPv6 address.

7) Finally words ₁

Not all kinds of IPv6 addresses are covered here. Some of them are depreciated and some of them are not very common.

This tutorial helps students to understand IPv6 addressing in a easy-to-understand, step-by-step way.

Hoping this tutorial can help you.

Until next time... ...