# Operating System 실습 [Linux Module]



### **Background**

#### Monolithic kernel

- 커널 설정을 변경한 경우 커널 전체가 다시 컴파일 되어야함.
- 자주 사용되지 않는 파일 시스템이나 드라이버 코드가 메모리에 상 주하게 된다.
- 커널 코드를 변경하면 컴파일을 다시 해야 할 뿐만 아니라 매번 재 부팅이 필요하다.

#### Linux Module

- 파일 시스템이나 드라이버 같은 커널의 funnctional unit
- 시스템이 부팅된 후라 할지라도 언제든지 커널과 동적으로 링크됨.
- 동적으로 적재된 모듈도 커널의 일부로 취급됨.
- 더이상 필요하지 않으면 언제든지 제거하여 커널 메모리 낭비를 막을 수 있음.



### **Macros**

### MODULE\_LICENSE()

GPL	GNU Public License v2 or later
GPL v2	GNU Public License v2
GPL and additional rights	GNU Public License v2 rights and more
Dual BSD/GPL	GNU Public License v2 or BSD license choice
Dual MIT/GPL	GNU Public License v2 or MIT license choice
Dual MPL/GPL	GNU Public License v2 or Mozilla license choice

### MODULE\_DESCRIPTION()

- is used to describe what the module does
- MODULE\_AUTHOR()
  - declares the module's author
- MODULE\_SUPORTED\_DEVICE()
  - declares what types of devices the module supports



### **Modules Command**

### Modules Shell Command

명령어	설명
insmod	모듈 install
rmmod	실행중인 모듈 제거
Ismod	Load 된 모듈의 정보 표시
modinfo	Ko 파일의 관련 정보 표시
depmod	커널 내부에 적재된 모듈간의 의존성 검사
modeprobe	의존성을 검사하여 누락된 모듈을 적재



### 실습 (hello.c)

```
1 #include
 2 #include
 3 #include
 5 static int hello_init(void)
 6 {
       printk(KERN_ALERT "I bear a charmed life.\n");
       return 0;
 8
9 }
10
11 static void hello_exit(void)
12 {
       printk(KERN_ALERT "Out, out, brief candle!\n");
13
14 }
15
16 module_init(hello_init);
17 module_exit(hello_exit);
18
19 MODULE_LICENSE('
20 MODULE_DESCRIPTION(
21 MODULE_AUTHOR("Kihan
```



# 실습 (Makefile)

```
:= hello.o
 1 obj-m
 2
          := /lib/modules/$(shell uname -r)/build
 3 KDIR
          := $(shell pwd)
 4 PWD
 5
 6 default:
       $(MAKE) -C $(KDIR) SUBDIRS=$(PWD) modules
 8 clean:
      rm -rf *.ko
   rm -rf *.mod.*
   rm -rf .*.cmd
11
      rm -rf *.o
12
```



# 실습

- \$dmesg -c //clear dmesg
- \$ make
- \$modinfo hello.ko //module 정보 출력
- \$ insmod hello.ko
- \$ Ismod
- \$ rmmod hello.ko
- \$ dmesg



### **Function**

- hello\_init()
  - Registered as this module's entry point via module\_init()
  - The kernel invokes when the module is loaded
- module\_init()
  - Not actually a function call
  - A macro that assigns its sole parameter as the initialization function
  - All init functions must have the form
    - \* Int my\_init(void)
- module\_exit()
  - Registers a module's exit point
  - The kernel invokes when the module is removed from memory
  - Responsible for undoing whatever the init function and lifetime of the module did
  - Exit functions must have the form
    - \* Int my\_exit(void)



# **Debugging by printing**

- printk()
  - Happens to be a logging mechanism for the kernel, and is used to log information or give warnings
  - printk message is stored to ring buffer

## Loglevels

Declared in linux/kernel.h>

Loglevel	Description
KERN_EMERG	An emergency condition; the system is probably dead.
KERN_ALERT	A problem that requires immediate attention.
KERN_CRIT	A critical condition.
KERN_ERR	An error.
KERN_WARNING	A warning.
KERN_NOTICE	A normal, but perhaps noteworthy, condition.
KERN_INFO	An informational message.
KERN_DEBUG	A debug message—typically superfluous.



# 실습 (param\_mod.c)

```
1 #include
 6 static int age = 0;
 7 static char *name = NULL;
10 module_param(name,charp,0);
11 module_param(age,int,0);
12
13 static int hello_init(void)
14 {
15
       printk(KERN_ALERT "hello, My name is %s, my age is %d\n", name, age);
       return 0;
17 }
19 static void hello_exit(void)
20 {
21
       printk(KERN_ALERT "Bye bye!\n");
22 }
23
25 module_init(hello_init);
26 module exit(hello exit);
28 MODULE_LICENSE("GPL");
29 MODULE DESCRIPTION("
                                          ");
30 MODULE_AUTHOR('
```



### **Module Parameters**

- Creating and managing module parameters that can be specified in a myriad of convenient ways is trivial
- module\_param();
  - Define a module parameter module\_param(name, type, perm);
    - \* Name

The name of both the parameter exposed to the user and the variable holding the parameter inside your module

- \* Type
  - Holds the parameter's data type
  - Byte, short, ushort, int, uint, long, ulong, charp, bool, invbool
- \* Perm

The permissions of the corresponding file in sysfs



# 실습

- Modify Makefile
- \$dmesg-c
- \$ make
- \$modinfo param\_mod.ko
- \$ insmod param\_mod.ko name="Kihan" age=15
- \$ rmmod param\_mod.ko
- \$ dmesg



### 실습 결과

os@os-VirtualBox:~/practice\$ modinfo hello.ko

filename: hello.ko author: Kihan Choi

description: A hello, World Module

license: GPL

srcversion: D78D32956BF669CDE6E010D

depends:

vermagic: 3.11.0 SMP mod\_unload modversions 686

os@os-VirtualBox:~/practice\$ modinfo param\_mod.ko

filename: param\_mod.ko author: Kihan Choi

description: Module Parameters

license: GPL

srcversion: 7EE06BDF4C3486659C8C461

depends:

vermagic: 3.11.0 SMP mod\_unload modversions 686

os@os-VirtualBox:~/practice\$ dmesg

[147442.116355] hello, My name is Kihan, my age is 15

[148433.209435] Bye bye!

