



Trinity College Dublin  
Coláiste na Tríonóide, Baile Átha Cliath  
The University of Dublin

程序代写代做 CS编程辅导



WeChat: cstutorcs

## 3.1 Subroutines Assignment Project Exam Help

CSU11022 – Introduction to Computing II  
Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

Dr Jonathan Dukes / jdukes@scss.tcd.ie  
School of Computer Science and Statistics

# Subroutines

2

程序代写代做 CS编程辅导

Programs can be **decomposed** into blocks of instructions, each performing some well-defined task

compute  $x^y$



find the length of a NULL-terminated string

WeChat: cstutorcs

convert a string from UPPER CASE to lower case

play a sound

Assignment Project Exam Help

We would like to avoid repeating the same set of operations throughout our programs

QQ: 749389476

write the instructions to perform some specific task once

Email: tutorcs@163.com

invoke the set of instructions **many times** to perform the same task

QQ: 749389476

Methods in the Java world!

Functions or Procedures elsewhere

# Example - UPPER CASE

3

```
address = string1;
ch = byte[address];
while (ch != NULL) {
    if (ch >= 'a' && ch <= 'z')
        ch = char & 0xFFFFFFF;
    byte[address] = ch;
}
address = address + 1;
char = byte[address];
}
```

```
address = string2;
ch = byte[address];
while (ch != NULL) {
    if (ch >= 'a' && ch <= 'z') {
        ch = ch & 0xFFFFFD;
    }
    byte[address] = ch;
}
address = address + 1;
ch = byte[address];
}
```

程序代写代做 CS编程辅导



Repetition!

WeChat: cstutorcs

Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

# Example - UPPER CASE

4

```
// UPPER CASE
void upr (address)
{
    ch = byte[address];
    while (ch != NULL) {
        if (ch >= 'a' && ch <= 'z')
            ch = ch & 0xFFFFFD;
        byte[address] = ch;
    }
    address = address + 1;
    ch = byte[address];
}

address = string1;
upr(address);

address = string2;
upr(address);
```



程序代写代做 CS编程辅导

WeChat: cstutorcs

Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

Define upr(...)

Invoke upr(...) twice

# Example - UPPER CASE

5

```
// UPPER CASE
void upr (address)
{
    ch = byte[address];
    while (ch != NULL) {
        if (ch >= 'a' && ch <= 'z')
            ch = ch & 0xFFFFFD;
        byte[address] = ch;
    }
    address = address + 1;
    ch = byte[address];
}

upr(string1);

upr(string2);
```



程序代写代做 CS编程辅导

WeChat: cstutorcs

Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476


<https://tutorcs.com>

Define upr(...)

Invoke upr(...) twice

# Call / Return Example

6



Branching to a subroutine: branch to the address (or label) of the first instruction in the subroutine <https://tutorcs.com> ... easy!

Returning from a subroutine: must have remembered the address that we originally branched from (**return address**, A or B in the example above)

# Invoking the UPR subroutine

7

程序代写代做 CS编程辅导

Main:

```
@  
@ Program to convert two strings to UPPERCASE  
@ Assume the first string starts at the address in R1  
@ Assume the second string starts at the address in R2  
@
```



WeChat: cstutorcs

```
MOV    R0, R1      @ copy address of first string into R0  
BL     upr         @ invoke upr subroutine  
  
Email: tutorcs@163.com  
MOV    R0, R2      @ copy address of second string into R0  
BL     upr         @ invoke upr subroutine (again)  
QQ: 749389476
```

End\_Main:

```
BX    LR
```

<https://tutorcs.com>

# Implementing the UPRCASE subroutine

8

```
@  
@ upr subroutine  
@ Converts a NULL-terminated string to upper case  
@  
@ Parameters:  
@ R0: string start address  
@  
upr:  
.LwhUpr:  
    LDRB    R4, [R0], #1      @ char = byte[address++]  
    CMP     R4, #0            @ while (char != 0)  
    BEQ     .LeWhUpr        @ {  
    CMP     R4, #'a'          @ if (char >= 'a'  
    BLO     .LeIfLwr        @   &&  
    CMP     R4, #'z'          @   char <= 'z')  
    BHI     .LeIfLwr        @ {  
    BIC     R4, #0x00000020  @   char = char AND NOT 0x00000020  
    STRB    R4, [R0, #-1]    @   byte[address-1] = char  
.LeIfLwr:  
    B      .LwhUpr         @ }  
.LeWhUpr:  
    BX    LR
```

程序代写代做 CS编程辅导



WeChat: cstutorcs  
Assignment Project Exam Help  
Email: tutorcs@163.com  
QQ: 749389476  
<https://tutorcs.com>



Trinity College Dublin  
Coláiste na Tríonóide, Baile Átha Cliath  
The University of Dublin

程序代写代做 CS 编程辅导



WeChat: cstutorcs

## 3.2 Subroutines Assignment Project Exam Help - Unintended Side Effects

CSU11022 – Introduction to Computing II  
Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

Dr Jonathan Dukes / jdukes@scss.tcd.ie  
School of Computer Science and Statistics

# What's wrong with this program?

10

Main:

BL subroutine1

End\_Main:

BX LR

@ subroutine1

subroutine1:

ADD R0, R1, R2  
BL subroutine2  
ADD R3, R4, R5  
BX LR

@ subroutine2

subroutine2:

BX LR

程序代写代做CS编程辅导  
@ invoke subroutine1



WeChat: cstutorcs

@ do something  
Assignment Project Exam Help  
@ do something else

Email: tutorcs@163.com  
@ return from subroutine1

QQ: 749389476

<https://tutorcs.com>

@ just return from subroutine2

# Saving the Link Register

11

Save the contents of the link register on the system stack at the start of  
every subroutine



Restore the contents of the link register immediately before returning  
from every subroutine

```
@ subroutine1
subroutine1:
    PUSH    {LR}
    ADD     R0, R1, R2
    BL      subroutine2
    ADD     R3, R4, R5
    POP    {LR}
    BX     LR
```

WeChat: cstutorcs

Assignment Project Exam Help

@ do something

Email: tutorcs@163.com

@ call subroutine2

@ do something else

QQ: 749389476

@ return from subroutine1

<https://tutorcs.com>

Implement this fix now in the sideeffects1 example from the CSU1102x  
GitLab repository. Verify that the fix works.

# Saving the Link Register

12

More efficiently, we could ~~程序代写代做 CS 编程辅导~~ restore the saved LR to the PC, avoiding the need for the BX instruction (preferred)



```
@ subroutine1
subroutine1:
    PUSH    {LR}
    ADD     R0, R1, R2
    BL      subroutine2
    ADD     R3, R4, R5
    POP    {PC}
```

WeChat: cstutorcs

~~@ do something~~  
**Assignment Project Exam Help**

~~@ call subroutine2~~  
**Email: tutorcs@163.com**

**QQ: 749389476**

Implement this fix now in the ~~sideeffects1~~ example from the CSU1102x GitLab repository. Verify that the fix works.

# What's wrong with this program?

13

Imagine we are using our upr subroutine again ...

```
@  
@ upr subroutine  
@ Converts a NULL-terminated string to uppercase  
@  
@ Parameters:  
@ R0: string start address  
@  
upr:  
.LwhUpr:
```



case

WeChat: cstutorcs

```
LDRB    R4, [R0], #1      @ char = byte[address++]  
CMP     R4, #0          @ while (char != 0)  
BEQ     .LeWhUpr       @ {  
CMP     R4, #'a'        @   if (char >= 'a'  
BLO     .LeIfLwr        @     &&  
CMP     R4, #'z'        @     char <= 'z')  
BHI     .LeIfLwr       @ {  
BIC     R4, #0x00000020  @   char = char AND NOT 0x00000020  
STRB    R4, [R0, #-1]    @   byte[address - 1] = char  
.LeIfLwr:  
    B     .LwhUpr        @ }  
.LeWhUpr:  
    @
```

Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

BX

LR

# What's wrong with this program?

14

... and then use the upr subroutine to convert two strings to UPPER CASE but this time our second string starts at an address in R4 ...

Main:



```
@  
@ Program to convert two strings to UPPERCASE  
@ Assume the first string starts at the address in R1  
@ Assume the second string starts at the address in R4  
@
```

**Assignment Project Exam Help**

```
MOV    R0, R1      @ copy address of first string into R0  
BL     upr         @ invoke upr subroutine
```

```
MOV    R0, R4      @ copy address of second string into R0  
BL     upr         @ invoke upr subroutine (again)
```

**QQ: 749389476**

**<https://tutorcs.com>**

End\_Main:

```
BX    LR
```

# Unintended Side Effects

15

We want (need?) to be able to write subroutines independently from the rest of our program



When designing and writing subroutines, clearly and precisely define what effect the subroutine has

Effects outside this definition should be considered **unintended** and should be **hidden** by the subroutine

WeChat: cstutorcs

Assignment Project Exam Help

In general, subroutines should save the contents of the registers they use at the start of the subroutine and should restore the saved contents before returning

QQ: 749389476

<https://tutorcs.com>

**SOLUTION: PUSH register contents on the stack at the start of a subroutine, POP them off at the end**

# Hiding Unintended Side Effects

16

```
@  
@ upr subroutine  
@ Converts a NULL-terminated string to upper case  
@  
@ Parameters:  
@ R0: string start address  
@  
upr:  
    PUSH    {R0, R4, LR}  
  
.LwhUpr:  
    LDRB    R4, [R0], #1      @ char = byte[address++]  
    CMP     R4, #0            @ while( char != 0 )  
    BEQ     .LeWhUpr        @ {  
    CMP     R4, #'a'  
    BLO     .LeIfLwr         @ if (char >= 'a'  
    CMP     R4, #'z'          @     char <= 'z')  
    BHI     .LeIfLwr         @ [  
    BIC     R4, #0x00000020  @ char = char AND NOT 0x00000020  
    STRB    R4, [R0, #-1]    @ byte[address - 1] = char  
.LeIfLwr:  
    B       .LwhUpr         @ }  
.LeWhUpr:  
    POP    {R0, R4, PC}
```

程序代写代做 CS编程辅导



WeChat: cstutorcs

@ char = byte[address++]  
@ while( char != 0 )  
@ {  
@ if (char >= 'a'  
@ char <= 'z')  
@ [  
@ char = char AND NOT 0x00000020  
@ byte[address - 1] = char

QQ: 749389476

@ https://tutorcs.com



Trinity College Dublin  
Coláiste na Tríonóide, Baile Átha Cliath  
The University of Dublin



程序代写代做 CS编程辅导

WeChat: cstutorcs

### 3.3 Subroutines Assignment Project Exam Help Parameter Passing

CSU11022 – Introduction to Computing II  
Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

Dr Jonathan Dukes / jdukes@scss.tcd.ie  
School of Computer Science and Statistics

# Passing Parameters

18

Information must be passed to a subroutine using a fixed and well defined interface, known to both the subroutine and calling programs

upr subroutine had single parameter



```
address = string1;  
upr(address);
```

```
address = string2;  
upr(address);
```

... . . .

```
upr(address)  
{  
    . . .  
}
```

WeChat: cstutorcs

Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

Simplest way to pass parameters to a subroutine is to use well defined registers, e.g. for upr subroutine, use R0 for the address of the string

# Example - fill

19

Design and write an ARM Assembly Language subroutine that fills a sequence of words in memory with the same 32-bit value

Pseudo-code solution

```
fill (address, length, value)
{
    count = 0;
    while (count < length)
    {
        word[address] = value;
        address = address + 4;
        count = count + 1;
    }
}
```



3 parameters

**address** start address in memory <https://tutorcs.com>

**length** number of words to store

**value** value to store

WeChat: cstutorcs  
Assignment Project Exam Help  
Email: tutorcs@163.com  
QQ: 749389476

# Example - fill subroutine

20

程序代写代做 CS编程辅导

```
@ fill subroutine
@ Fills a contiguous sequence of words in memory with the same value
@
@ Parameters:
@     R0: address - address of first word to be filled
@     R1: length - number of words to be filled
@     R2: value - value to store in each word

fill:
    PUSH {R0-R2,R4,LR}
    MOV R4, #0
    @ count = 0;

.LwhFill:
    CMP R4, R1
    BHS .LeWhFill
    STR R2, [R0, R4, LSL #2]
    ADD R4, #1
    B .LwhFill
.LeWhFill:
    POP {R0-R2,R4,PC}
```

Assignment Project Exam Help

Email: tutorcs@163.com

@ write(count < length)

@ {

@ word[address+(count\*4)] = value;

@ count = count + 1;

@ }

<https://tutorcs.com>



WeChat: cstutorcs

QQ:749389476

程序代写代做 CS编程辅导

In high level languages, the interface is defined by the programmer and the compiler implements and enforces it



In assembly language, the interface must be defined, implemented and enforced by the programmer

WeChat: cstutorcs

Assignment Project Exam Help

**ARM Architecture Procedure Call Standard (AAPCS)** is a technical document that dictates how a high-level language interface should be implemented in ARM Assembly Language (or machine code!!)

QQ: 749389476

Enforcing the standard in <https://tutorcs.com> is your job!!

(based on AAPCS)

程序代写代做 CS编程辅导

Registers	
R0 ... R3	Parameters to subroutines – avoid using for other variables – <b>corruptible (not saved/restored on stack)</b>
R4 ... R12	Local variables within subroutines – <b>preserved (saved/restored on stack)</b> WeChat: cstutorcs
R13 (SP)	Stack Pointer – <b>preserved through proper use</b>
R14 (LR)	Email: <a href="mailto:tutorcs@163.com">tutorcs@163.com</a> Link Register – <b>corrupted through subroutine call</b>
R15 (PC)	QQ: 749389476 Program Counter <a href="https://tutorcs.com">https://tutorcs.com</a>

**Adhering to these guidelines will make it easier to write large programs with many subroutines**

# Example - fill revisited

23

Based on these guidelines, we could re-write fill (note that I was already adhering to the guidelines for passing parameters but I didn't need to save R0 or R1!!)

@ fill subroutine  
@ Fills a contiguous sequence in memory with the same value



@  
@ Parameters:  
@ R0: address - address of first word to be filled  
@ R1: length - number of words to be filled  
@ R2: value - value to store in each word

```
fill:  
    PUSH {R4,LR}  
    MOV R4, #0  
.LwhFill:  
    CMP R4, R1  
    BHS .LeWhFill  
    STR R2, [R0, R4, LSL #2]  
    ADD R4, #1  
    B .LwhFill  
.LeWhFill:  
    POP {R4,PC}
```

WeChat: cstutorcs  
Assignment Project Exam Help

Email: tutorcs@163.com  
@ count = 0;

QQ: 749389476  
@ while(count < length)

@ {  
 @ wordAddress + (count\*4) ] = value;  
 @ count = count + 1;  
 @ }  
@

<https://tutorcs.com>

# Example - calling fill

24

Recall the fill interface ... this is all we need to invoke fill  
程序代写代做 CS编程辅导

```
@ fill subroutine
@ Fills a contiguous sequence of memory with the same value
@
@ Parameters:
@     R0: address – address of memory to be filled
@     R1: length – number of words filled
@     R2: value – value to store in each word
```



Note that we only need to know the interface.

WeChat: cstutorcs

**We don't need to know how fill is implemented!**

Email: tutorcs@163.com

To invoke fill assuming R5 contains the start address, R9 the length to fill and R8 the value to fill memory with 749389476

MOV

R0, R5

MOV

R1, R9

MOV

R2, R8

BL

fill

@ address parameter  
@ length parameter  
@ value parameter

@ invoke fill

1

move parameters into place

2

Invoke subroutine

# Example - count1s

25

Design and write an ARM 程序代写 By Language subroutine that counts the number of set bits in a word



```
@ count1s subroutine
@ Counts the number of set bits in a word
@ Parameters:
@   R0: wordval - word in which 1s will be counted
@ Return:
@   R0: count of set bits (1s) in wordval
count1s:
    PUSH {R4, LR}          @ save registers
    MOV R4, R0              @ copy wordval parameter to local variable
    MOV R0, #0              @ count = 0;
.LwhCount1s:
    CMP R4, #0              @ while (wordval != 0)
    BEQ .LeWhCount1s       @ {
    MOVS R4, R4, LSR #1     @   wordval = wordval >> 1; (update carry)
    ADC R0, R0, #0          @   count = count + 0 + carry;
    B .LwhCount1s          @ }
.LeWhCount1s:
    POP {R4, PC}           @ restore registers
```

WeChat: cstutorcs  
Assignment Project Exam Help  
Email: tutorcs@163.com

QQ: 749389476  
https://tutorcs.com

# Interface Guidelines for Return Values

26

Use R0 for returning values from subroutines

程序代写代做 CS编程辅导

Registers	U  Parameters to subroutines or returning values from subroutines – avoid using for other variables – <b>corruptible</b>
R0 ... R3	Local variables within subroutines – <b>preserved (saved/</b> <b>WeChat:tutorcs</b> <b>restored on stack)</b>
R13 (SP)	Stack Pointer – <b>preserved through proper use</b> <b>Assignment Project Exam Help</b>
R14 (LR)	<b>Email: tutorcs@163.com</b> <b>Link Register – corrupted through subroutine call</b>
R15 (PC)	<b>QQ: 749389476</b> Program Counter

<https://tutorcs.com>

R0 used to pass wordval parameter **and** return result value from count1s subroutine (an implementation decision – real AAPCS compilers would also do this!)

# Example - count1s

27

Recall the count1s interface 程序代写代做 CS编程辅导

```
@ count1s subroutine  
@ Counts the number of set bits (1s) in a word  
@ Parameters:  
@   R0: wordval - word in which the bits will be counted  
@ Return:  
@   R0: count of set bits (1s) in wordval
```



WeChat: cstutorcs

Note again that we only need to know the interface ... we don't need to know how count1s is implemented Assignment Project Exam Help

Call count1s, assuming R7 contains the word value to be passed to count1s Email: tutorcs@163.com

```
...      ...  
MOV    R0, R7  
BL     count1s  
ADD    R5, R5, R0  
...      ...
```

QQ: 749389476

@ prepare the parameter

@ call count1s

https://tutorcs.com @ do something useful with the result

## Good practice to save ... 程序代写代做 CS 编程辅导

any registers used for local variables. R12)

the link register (LR / R14)

(and optionally, registers used for parameters)

but not registers used for return values



WeChat: cstutorcs

## ... on the system stack at the start of every subroutine

Restore exactly the same saved registers at the end of every subroutine

Email: tutorcs@163.com

QQ: 749389476

Avoids unintended side effects and simplifies subroutine interface design

<https://tutorcs.com>

**Remember: a subroutine must pop off everything that was pushed on to the stack before it returns**





Trinity College Dublin  
Coláiste na Tríonóide, Baile Átha Cliath  
The University of Dublin

程序代写代做 CS编程辅导



WeChat: cstutorcs

## 3.4 Subroutines Assignment Project Exam Help Recursion

CSU11022 – Introduction to Computing II  
Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

Dr Jonathan Dukes / jdukes@scss.tcd.ie  
School of Computer Science and Statistics

Subroutines can invoke themselves  
程序代码代做CS编程辅导

Example: Design, write a subroutine to compute  $x^n$



$$x^n = \begin{cases} 1 & \text{WeChat: cstutorcs if } n=0 \\ x & \text{Assignment Project Exam Help if } n=1 \\ (x^{n/2})^2 & \text{Email: tutorcs@163.com if } n \text{ is even} \\ x \cdot (x^2)^{(n-1)/2} & \text{QQ: 749389476} \\ \text{https://tutorcs.com} & \text{if } n \text{ is odd} \end{cases}$$

程序代写代做 CS编程辅导



WeChat: cstutorcs  
 $x^5 = x \times x \times x \times x \times x$   
Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

程序代写代做 CS编程辅导



WeChat: cstutorcs  
 $x^5 = x \times (x \times x) \times (x \times x)$   
Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

程序代写代做 CS编程辅导



$x^5 = x \times (x \times x)^2$   
WeChat: cstutorcs  
Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

程序代写代做 CS编程辅导



WeChat: cstutorcs  
 $x^5 = x \times (x^2)^2$   
Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

程序代写代做 CS编程辅导



WeChat: cstutorcs  
 $x^5 = x^{1+(2 \times 2)}$   
Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

Subroutines can invoke themselves  
程序代码代做CS编程辅导

Example: Design, write a subroutine to compute  $x^n$



$$x^n = \begin{cases} 1 & \text{WeChat: cstutorcs if } n=0 \\ x & \text{Assignment Project Exam Help if } n=1 \\ (x^{n/2})^2 & \text{Email: tutorcs@163.com if } n \text{ is even} \\ x \cdot (x^2)^{(n-1)/2} & \text{QQ: 749389476} \\ \text{https://tutorcs.com} & \text{if } n \text{ is odd} \end{cases}$$

程序代写代做 CS编程辅导



WeChat: cstutorcs  
 $x^9 = x \times (x^2)^{(9-1)/2}$   
Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

程序代写代做 CS编程辅导



WeChat: cstutorcs  
 $x^9 = x \times (x^2)^4$   
Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

程序代写代做 CS编程辅导



WeChat: cstutorcs  
 $x^9 = x \times ((x^2)^2)^{4/2}$   
Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

程序代写代做 CS编程辅导



WeChat: cstutorcs  
 $x^9 = x \times ((x^2)^2)^2$   
Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

# Example - power

41

程序代写代做 CS编程辅导

```
power (x, n)
{
    if (n == 0)
    {
        result = 1;
    }
    else if (n == 1)
    {
        result = x;
    }
    else if (n & 1 == 0) // n is even
    {
        result = power (x * x, n / 2);
    }
    else // n is odd
    {
        result = x * power (x * x, n / 2);
    }
}
```



WeChat: cstutorcs

Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

# Example - power (1)

42

```
@  
@ power subroutine  
@ Computes x^n  
@  
@ Parameters:  
@   R0:  x  
@   R1:  n  
@  
@ Return:  
@   R0:  x^n  
@  
power:
```

```
PUSH {R4-R6,LR}  
MOV R4, R0  
MOV R5, R1
```

程序代写代做 CS编程辅导



WeChat: cstutorcs

Assignment Project Exam Help

@ Email: [tutors@163.com](mailto:tutors@163.com)  
@ QQ: [749389476](#)  
@ Move parameters to local registers  
@ Doing this makes managing registers in subroutines  
@ \*much\* simpler. When we call a subroutine from the  
@ body of this subroutine, the parameter registers  
@ (R0-R3) will already be free for us to use because  
@ we have moved the original parameters to other  
@ registers.



# Example - power (2)

43

程序代写代做 CS编程辅导

```
CMP    R5, #0
BNE    .LpowerNe0

MOV    R0, #1

B      .LpowerEndIf
.LpowerNe0:
CMP    R5, #1
BNE    .LpowerNe1

MOV    R0, R4

B      .LpowerEndIf
.LpowerNe1:
```



== 0) {

lt = 1;

WeChat: cstutorcs

Assignment Project Exam Help

Email: tutorcs@163.com

@ result = x;

QQ: 749389476

@ }

<https://tutorcs.com>

# Example - power (3)

44

.LpowerNe1:

```
AND    R6, R5, #1  
CMP    R6, #0  
BNE    .LpowerNeEven
```

```
MUL    R0, R4, R4  
MOV    R1, R5, LSR #1  
BL     power
```

```
B      .LpowerEndIf
```

.LpowerNeEven:

```
MUL    R0, R4, R4  
MOV    R1, R5, LSR #1  
BL     power  
MUL    R0, R4, R0
```

.LpowerEndIf:

```
POP    {R4-R6, PC}
```

程序代写(代做CS编程辅导) n is even



```
t = power (x * x, n >> 1);  
using LSR by 1 bit to implement division by 2
```

WeChat: cstutorcs  
@ }

Assignment Project Exam Help

@else {  
Email: tutorcs@163.com  
@ result = x \* power (x \* x, n >> 1);

QQ: 749389476

<https://tutorcs.com>

@ }

@ return result;



Trinity College Dublin  
Coláiste na Tríonóide, Baile Átha Cliath  
The University of Dublin

程序代写代做 CS 编程辅导



WeChat: cstutorcs

## 3.5 Subroutines - Assignment Project Exam Help on the Stack

CSU11022 – Introduction to Computing II  
Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

Dr Jonathan Dukes / jdukes@scss.tcd.ie  
School of Computer Science and Statistics

程序代写代做 CS编程辅导

If there are insufficient registers to pass parameters to a subroutine, the system stack can be used



Commonly used by high-level languages

Number of parameters is limited only by the remaining space on the stack

General approach

Assignment Project Exam Help

Calling program pushes parameters onto the stack

Email: [tutorcs@163.com](mailto:tutorcs@163.com)

Subroutine accesses parameters on the stack, relative to the stack pointer

QQ: 749389476

Calling program pops parameters off the stack after the subroutine has returned

# Example - fill with Stack Parameters

47

程序代写代做 CS 编程辅导

Re-write the fill subroutine to pass parameters on the stack (instead of registers)

Pseudo-code reminder



```
fill (address, length, value)
{
    count = 0;
    while (count < length)
    {
        word[address] = value;
        address = address + 4;
        count = count + 1;
    }
}
```

WeChat: cstutorcs

Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

<https://tutorcs.com>

# Example - fill with Stack Parameters

48

```
@ fill subroutine          程序代写代做 CS编程辅导
@ Fills a contiguous sequence of words in memory with the same value
@ Parameters
@   [sp+0]: value - value in each word (1st Top Of Stack)
@   [sp+4]: length - number of words to be filled (2nd Top Of Stack)
@   [sp+8]: address - address of first word to be filled (3rd Top Of Stack)

fill:
    PUSH {R4-R7,lr}           @ save registers

    LDR R4, [SP, #28]         @ load address parameter (not popping)
    LDR R5, [SP, #24]         @ load length parameter (not popping)
    LDR R6, [SP, #20]         @ load value parameter (not popping)

    MOV R7, #0                @ count = 0;

.LwhFill:
    CMP R7, R5               @ while (count < length)
    BHS .LeWhFill:           @

    STR R6, [R4, R7, LSL #2]  @ word[address + count * 4] = value;
    ADD R7, #1                @ count = count + 1;
    B .LwhFill:               @ }

.LeWhFill:
    POP {R4-R7,pc}           @ restore registers
```



@ save registers

WeChat: cstutorcs

@ load address parameter (not popping)

@ load length parameter (not popping)

Assignment Project Exam Help

Email: tutorcs@163.com

QQ: 749389476

@ while (count < length)

@

https://tutorcs.com

@ count = count + 1;

@ }

@ restore registers

# Example - fill with Stack Parameters

49

Imagine we want to fill memory starting at the address in R5 with the value in R8 and filling the number of words in R9:



PUSH	{R5}	; Push address parameter on stack
PUSH	{R9}	; Push length parameter on stack
PUSH	{R8}	; Push value parameter on stack
BL	fill	Assignment Project Exam Help ; Call fillmem subroutine
ADD	SP, SP, #12	Email: <a href="mailto:tutorcs@163.com">tutorcs@163.com</a> , Efficiently pop parameters off stack

QQ: 749389476



The order of the parameters is important! If we want to control the order of the parameters on the stack, we can't push in one go!

<https://tutorcs.com>

# Example - fill with Stack Parameters

50

程序代写代做 CS 编程辅导



# Example - fill with Stack Parameters

51

Why not push the three parameters onto the stack using a single PUSH instruction?



Important that **calling program** restores the system stack to its original state

Pop off the three parameters

WeChat: cstutorcs

Quickly and simply done by adding 12 ( $3 \times 4$  word-size values) to SP

Subroutine doesn't pop parameters off the stack (why?)


Accesses them in-place, using offsets relative to the stack pointer

Subroutine saves some registers to the stack

compensate by adding additional offset (+20) to parameter offsets

# Example - fill with Stack Parameters

52



# Example - fill with Stack Parameters

53

What happens the fill example if we change the list of registers that we save?  
(Or worse, manipulate the stack during the execution of the subroutine)

```
@ fill subroutine
@ Fills a contiguous sequence of memory with the same value
@ Parameters
@ [sp+0]: value - value to fill word (1st Top Of Stack)
@ [sp+4]: length - number of words to be filled (2nd Top Of Stack)
@ [sp+8]: address - address of first word to be filled (3rd Top Of Stack)

fill
    PUSH {R4-R7,lr}
    @ save registers

    LDR R4, [SP, #8+20]
    LDR R5, [SP, #4+20]
    LDR R6, [SP, #0+20]
    @ Load address parameter (not popping)
    @ load length parameter (not popping)
    @ load value parameter (not popping)

.LwhFill:
    CMP R5, #0
    BEQ .LeWhFill:
    SUB R5, R5, #1
    STR R6, [R4, R7, LSL #2]
    B .LwhFill:
    @ while (count > 0)
    @ {
    @ count = count - 1;
    @ word[address + count * 4] = value;
    @ }

.LeWhFill:
    POP {R4-R6,pc}
    @ restore registers
```



WeChat: cstutorcs  
Email: tutorcs@163.com

Assignment Project Exam Help  
QQ: 749389476  
<https://tutorcs.com>

Offsets to parameters on the stack may change at design time or at runtime

# Example - fill with Stack Parameters

54

What happens the fill example if we change the list of registers that we save?  
(Or worse, manipulate the stack during the execution of the subroutine)

```
@ fill subroutine
@ Fills a contiguous sequence of memory with the same value
@ Parameters
@ [sp+0]: value - value to fill word (1st Top Of Stack)
@ [sp+4]: length - number of words to be filled (2nd Top Of Stack)
@ [sp+8]: address - address of first word to be filled (3rd Top Of Stack)

fill
    PUSH {R4-R6,lr}
    @ save registers

    LDR R4, [SP, #8+16]
    LDR R5, [SP, #4+16]
    LDR R6, [SP, #0+16]
    @ Load address parameter (not popping)
    @ load length parameter (not popping)
    @ load value parameter (not popping)

.LwhFill:
    CMP R5, #0
    BEQ .LeWhFill:
    SUB R5, R5, #1
    STR R6, [R4, R7, LSL #2]
    B .LwhFill:
    @ while (count > 0)
    @ {
    @ count = count - 1;
    @ word[address + count * 4] = value;
    @ }

.LeWhFill:
    POP {R4-R6,pc}
    @ restore registers
```



WeChat: cstutorcs  
Email: tutorcs@163.com

Assignment Project Exam Help  
QQ: 749389476  
<https://tutorcs.com>

Offsets to parameters on the stack may change at design time or at runtime

# Example - fill with Stack Parameters

55

Workaround – at start of subroutine

程序代写代做 CS编程辅导

Save contents of a “scratch” register (e.g. R12) and LR

Copy SP + 8 to “scratch” register

Continue to push data onto the stack as needed

Access parameters relative to “scratch” register



fill

```
PUSH {R12, LR}  
ADD r12, SP, #8  
PUSH {R4-R6}  
  
LDR R4, [r12, #8]  
LDR R5, [r12, #4]  
LDR R6, [r12, #0]
```

<remainder of subroutine as before>

```
POP {R4-R6}  
POP {R12, PC}
```

WeChat: cstutorcs

Assignment Project Exam Help

@ save R12, LR

@ scratch = SP + 8

@ save registers

Email: tutorcs@163.com

@ load address parameter

QQ: 749389476

@ load length parameter

@ load value parameter


<https://tutorcs.com>

@ restore registers

@ restore R12, PC

# Example - fill with Stack Parameters

56



程序代写代做 CS编程辅导

Use R0–R3 for parameters and return values

Avoid using R0–R3 for local va



No need to save/restore on sys

Use R4–R12 for local variables

WeChat: cstutorcs

Save and restore on system stack

Assignment Project Exam Help

Always save link register LR at start of subroutine

Email: tutorcs@163.com

Restore link register LR to ~~QQ: 749389476~~ from subroutine

When passing parameters on the stack, use a register (e.g. R12) as a pointer to the parameter block

<https://tutorcs.com>