

Ultra Fast Zip

User Manual · v1.0 · High-speed archive tool for massive file trees

Contents

1. Overview
2. Installation
3. Compress tab
4. Extract tab
5. Inspect tab
6. Settings tab
7. Command-line tool (ufz)
8. Supported formats
9. The .ufz format
10. Troubleshooting & FAQ

1. Overview

Ultra Fast Zip packs and unpacks folders containing very large numbers of small files — source trees, asset folders, datasets — much faster than ZIP. It uses its own `.ufz` format: files are grouped into blocks and compressed with **Zstandard**, verified by **xxHash64** checksums, and extracted through a parallel pipeline that uses every CPU core.

It also opens most common archive types: drop a `zip`, `7z`, `rar`, `tar(.gz/.bz2/.xz/.zst)`, `gz`, `cab`, or `iso` file on the Extract tab and the format is detected automatically from its content.

Benchmarked against 7-Zip and WinRAR at their normal presets, Ultra Fast Zip was the **fastest tool at both packing and extraction** on a mixed 4,412-file dataset and on 812 MB of real JPEG photos — extraction up to 5× faster than ZIP — while out-compressing ZIP. Both directions run block-parallel pipelines that scale with CPU cores. See `docs/format_comparison.md` for methodology and full results.

2. Installation

Portable distribution (Windows)

1. Unzip the release package anywhere.
2. Run `UltraFastZip\UltraFastZip.exe` for the GUI. Keep the folder intact — the exe does not run if copied out alone.
3. `ufz.exe` is the standalone CLI; copy it anywhere, or add it to `PATH`.


Requirements: Windows 10/11 64-bit. No installer or runtime needed.

From source (all platforms)

```
python -m venv .venv
# Windows: .venv\Scripts\activate      macOS/Linux: source .venv/bin/activate
pip install -r requirements.txt
python app/main.py      # GUI
python app/cli.py --help # CLI
```

Requires Python 3.11+. On Windows, `setup.bat` does the above in one step.

3. Compress tab



Compressing a folder to .ufz, 62% complete.

- 1. **Input Folders** — click *Select Folder*. Hold Ctrl/Shift in the dialog to pick several folders at once, or type paths separated by `;`. Each folder becomes its own archive.
- 2. **Output (.ufz)** — filled automatically (`<folder>.ufz` next to the source). With multiple inputs, this field holds the output *folder* instead.
- 3. **Compression Options**

Option	Effect
--------	--------

Block Size (1–32 MB)	Larger blocks compress slightly better; smaller blocks parallelize extraction more finely. The 8 MB default suits most data.
Compression Level	1 = fastest, 6 = balanced default, 9+ = smaller but slower.
Worker Threads	Parallel compression workers; 0 = one per CPU core. Output is identical regardless of the count.
Include hidden files / empty folders	Uncheck to skip them.

- Click **Start Compression**. The bar shows overall progress, the line beneath it the file currently being read, and the console a running log. **Cancel** stops the job and removes partial output.

4. Extract tab

Ultra Fast Zip

High-speed archive tool for massive file trees

Compress

Extract

Inspect

Settings

Archives (.ufz plus zip/7z/rar/tar etc. auto-detected; separate multiple with ;)

C:\Projects\my_project.ufz

Select Archives

Output Folder

C:\Projects\my_project_extracted

Browse

Extraction Options

Worker threads (.ufz only)

Auto (24 CPU cores)

Overwrite existing files

Open folder after extraction

45%

assets/images/logo.png

Cancel

Start Extraction

[13:07:55] Ultra Fast Zip ready.

[13:07:55] Compression started: C:\Projects\my_project

[13:07:55] Found 70,208 files, 1,053,105,443 bytes total

[13:07:55] Detected UFZ: my_project.ufz

[13:07:55] Extracting: 70,208 files, 121 blocks, 24 decompress + 24 write workers (pipeline)

Extracting an archive with automatic format detection.

- Archives** — select one or more files. Any supported format works (§8); the type is detected from the file's content, not its extension.
- Output Folder** — defaults to `<name>_extracted`. With multiple archives, each gets its own subfolder here.
- Options**

Option	Effect
Worker Threads (.ufz only)	0 = one per CPU core. The pipeline runs this many decompress <i>and</i> write workers.
Overwrite existing files	Off by default — extraction stops with an error rather than replacing files.
Open folder when done	Opens the output in Explorer.

4. Click **Start Extraction**. Every block and file checksum is verified during extraction; corruption aborts the job with an error.

Archive paths are always confined to the output folder. Malicious archives using `../` tricks (Zip Slip) are rejected before anything is written.

5. Inspect tab

Ultra Fast Zip

High-speed archive tool for massive file trees

Compress

Extract

Inspect

Settings

Archive (.ufz)

C:\Projects\my_project.ufz

Select Archive

Archive Summary

Format Version	Codec	Files	Blocks
3	zstd	4	1
Original Size	Compressed Size	Ratio	Created
10.4 KB	816 B	7.6%	2026-07-14 13:07:55
Block Size			
8.0 MB			

File List

Search file paths...

Path	Size	Block	Modified
README.md	480 B	0	2026-07-14 13:07:55

[13:07:55] Ultra Fast Zip ready.

[13:07:55] Compression started: C:\Projects\my_project

[13:07:55] Found 70,208 files, 1,053,105,443 bytes total

[13:07:55] Detected UFZ: my_project.ufz

[13:07:55] Extracting: 70,208 files, 121 blocks, 24 decompress + 24 write workers (pipeline)


[13:07:55] Inspection done: 4 files, ratio 7.6%

[13:07:55] Inspected archive: my_project.ufz

Archive summary and searchable file list — read instantly from the header.

Select a `.ufz` file to see its format version, codec, file/block counts, original and compressed sizes, ratio, and creation time, plus the full file list with a search filter. Because UFZ stores its metadata at the front of the archive, inspection is instant even for very large archives — nothing is decompressed.

6. Settings tab



Defaults applied to new jobs.

Set the default block size, compression level, and thread count, and optionally enable saving the log console to files (`logs/ufz_*.log`). All options — including those on the Compress/Extract tabs — are saved as you change them and restored on the next launch.

7. Command-line tool (ufz)

`ufz.exe` (or `python app/cli.py`) offers the same engine without the GUI:

```
# Pack a folder (default output: <folder>.ufz)
ufz pack my_folder
ufz pack my_folder -o backup.ufz --block-size 16 --level 9 --overwrite

# Extract any supported archive (format auto-detected)
ufz unpack backup.ufz
ufz unpack backup.ufz -o restore_dir --threads 8 --overwrite
ufz unpack photos.zip

# Show archive info / file list
```

```
ufz inspect backup.ufz
ufz inspect backup.ufz --list
```

Command	Option	Description
pack	<code>--block-size MB</code>	1/4/8/16/32, default 8
	<code>--level 1-22</code>	Zstandard level, default 6
	<code>-t, --threads N</code>	compress workers, 0 = CPU count
	<code>--no-hidden</code> / <code>--no-empty-dirs</code>	exclude hidden files / empty folders
	<code>--overwrite</code>	replace an existing output file
unpack	<code>-t, --threads N</code>	worker threads (.ufz only), 0 = CPU count
	<code>--overwrite</code>	replace existing files
inspect	<code>-l, --list</code>	print the file list
all	<code>-q, --quiet</code>	suppress progress and logs

Exit codes: `0` success · `1` error · `130` cancelled (Ctrl+C).

8. Supported formats

Format	Pack	Extract	Backend
<code>.ufz</code> (and legacy <code>.fpk</code>)	✓	✓ (parallel)	native pipeline
zip	—	✓	built-in (cp949 filename recovery)
tar, tar.gz, tar.bz2, tar.xz, tar.zst	—	✓	built-in, streaming
gz, bz2, xz, zst (single file)	—	✓	built-in (<code>foo.txt.gz</code> → <code>foo.txt</code>)
7z	—	✓	py7zr if installed, else bsdtar
rar, cab, iso	—	✓	bsdtar (bundled with Windows 10+/macOS)

Detection uses magic bytes, so files with wrong or missing extensions still extract correctly. Formats delegated to bsdtar show no percentage progress.

9. The .ufz format

Header			
MAGIC	8 bytes	UFZ1\0\0\0\1	(legacy FPK1\0\0\0\1 readable)
VERSION	uint16	little-endian	
METADATA_LENGTH	uint64		
Metadata	JSON (UTF-8)	– file table, block map, sizes, mtimes	
Block Header #1	RAW_SIZE u64	COMPRESSED_SIZE u64	XXH64 u64
Compressed Block #1 (zstd)			
Block Header #2 ...			

- Files are packed into fixed-size blocks before compression, so thousands of small files cost one compression context, and blocks decompress independently — the basis of parallel extraction and block-level random access.
- Two checksum layers: each block (compressed bytes) and each file (original bytes).
- Version history: v1 zlib+CRC32 · v2 zstd+CRC32 · v3 (current) zstd+xxHash64. All older versions remain extractable.

10. Troubleshooting & FAQ

Symptom	Cause / fix
"File already exists (overwrite disabled)"	The output already contains that file. Enable <i>Overwrite existing files</i> (GUI) or pass <code>--overwrite</code> (CLI).
"Block checksum mismatch"	The archive is damaged (truncated download, disk error). Re-obtain the archive; extraction never writes unverified data.
"Unsupported or unrecognized archive format"	The file is not an archive Ultra Fast Zip can read — or is encrypted. Encrypted zip/7z/rar archives are not supported.
"Extracting RAR requires bsdtar"	rar/cab/iso (and 7z without py7zr) use the system's <code>tar.exe</code> . It ships with Windows 10+ and macOS; on Linux, install <code>libarchive-tools</code> (bsdtar).
First run on a folder is slow, later runs fast	Cold-cache small-file reads are limited by the disk and antivirus, not the tool. Subsequent (warm-cache) runs show the true speed.
UltraFastZip.exe does nothing when double-clicked	It was copied out of its folder. Copy the whole <code>UltraFastZip</code> folder; only <code>ufz.exe</code> is standalone.

FAQ

Can it create zip/7z archives? No — packing is `.ufz` only. Extraction covers the common formats.

Does it encrypt archives? Not yet; use OS or container encryption for sensitive data.

Are my old .fpk archives still usable? Yes. UFZ is the same format renamed; every legacy version (v1–v3, FPK magic) extracts as-is.

Does the worker-thread count change the archive? No. Both packing and extraction are block-parallel, and blocks are always written in order, so the archive is byte-identical whatever the thread count.