# TWL-System NITRO-Composer

# Sequence Data Manual

2008/05/30

The content of this document is highly confidential and should be handled accordingly.

### Confidential

These coded instructions, statements, and computer programs contain proprietary information of Nintendo and/or its licensed developers and are protected by national and international copyright laws. They may not be disclosed to third parties or copied or duplicated in any form, in whole or in part, without the prior written consent of Nintendo.

# **Table of Contents**

1	Ove	erview	
	1.1	Sequence Files	9
	1.2	Sequence Archives	9
2	Bas	sics	10
	2.1	Time Base	10
	2.2	Comments	10
	2.3	Labels	10
	2.3.		
	2.3.		
3	Seq	quence Files	11
	3.1	Overview	11
	3.2	Standard MIDI Files	11
	3.2.		
	3.2.	.2 Tracks	11
	3.2.	.3 Specifying Loops	11
	3.2.	.4 Blank Space at the Start of the SMF	11
	3.2.	.5 MIDI Events	12
	3.2.	.6 Compatibility with MusicPlayer2000	12
	3.3	Text Sequences	12
	3.3.	.1 Overview	12
	3.3.	.2 Track Opening Process	13
	3.3.	.3 Track Process	14
	3.4	Embedding Text Commands in SMF	14
	3.4.	.1 Overview	14
	3.4.	.2 How to Embed	15
	3.4.	•	
	3.4.	r	
	3.4.	.5 Cautions Regarding the Real-Time MIDI Playback	15
4	Seq	quence Archives	16
	4.1	Overview	16
	4.2	Using the Sound Archive Label File	17
	4.3	Structure	17
	4.3.	.1 Sequence Table	18
	4.3.	.2 Sequence Data	18
	4.4	Sequence Tables	19
	4.4.	.1 Sequence Label Name	20
	4.4.	.2 Data Label Name	20

	4.4.3	3 Bank	20
	4.4.4	4 Volume	20
	4.4.5	5 Voice Priority	20
	4.4.6		
	4.4.7	•	
	4.5	Numeric Value Notation	
	4.5.1	•	
	4.5.2		
	4.5.3	3 Mathematical Expressions	21
5	Seq	uence Commands	23
	5.1	Note Command	24
	5.2	Rest Command	25
	5.3	End Sequence	25
	5.4	Change Program	25
	5.5	Change Tempo	25
	5.6	Track Volume	25
	5.7	Main Volume	26
	5.8	Pitch Bend	26
	5.9	Transpose	26
	5.10	Track Pan	26
	5.11	Voice Priority	27
	5.12	Tie Mode	27
	5.13	Note Wait Mode	27
	5.14	Mute	27
	5.15	Portamento	28
	5.16	Sweep	28
	5.17	Allocate Tracks	29
	5.18	Start a Track	29
	5.19	Sequence Jump	29
	5.20	Sequence Call	30
	5.21	Loop	30
	5.22	Envelope	30
	5.23	Modulation	31
3	Exte	ended Sequence Commands	33
	6.1	Overview	
	6.2	Random Command	
	6.2.		
	6.2.2	2 Random Commands	33

	6.2.3	3 Random Note Length Command	34
	6.3	Variable Commands	34
	6.3.	1 What Is a Variable?	34
	6.3.2	.2 Variable Calculation Command	35
	6.3.3	.3 Variable Commands	35
	6.3.4	4 Format	35
	6.3.	5 List of Variable Commands	35
	6.3.6	.6 Variable Note Length Command	36
	6.3.	.7 Calculation Between Variable Commands	36
	6.4	Conditional Commands	36
	6.4.	.1 Comparison Command	36
	6.4.2	2 Conditional Command	37
	6.5	Communication with the Program	37
	6.5.	.1 Communication with the MIDI Sequence	37
	6.5.2	2 Combination with Conditional Commands	38
	6.6	Debugging Variables	38
7			
	App	Denaix	39
	7.1	pendix  Complete List of Sequence Commands	
			39
	7.1	Complete List of Sequence Commands	39 41
	7.1 7.2	Complete List of Sequence Commands	41 43
	7.1 7.2 7.2.	Complete List of Sequence Commands  MIDI Control Code Table  1 RPN Support Chart  Compatibility with SMF Created for MusicPlayer2000	41 43 44
	7.1 7.2 7.2.7	Complete List of Sequence Commands  MIDI Control Code Table	41 43 44
	7.1 7.2 7.2.7 7.3	Complete List of Sequence Commands  MIDI Control Code Table  1 RPN Support Chart  Compatibility with SMF Created for MusicPlayer2000  1 Track Number  2 Modulation	41 43 44 44
	7.1 7.2 7.2.7 7.3 7.3.7	Complete List of Sequence Commands  MIDI Control Code Table  1 RPN Support Chart  Compatibility with SMF Created for MusicPlayer2000  1 Track Number  2 Modulation  3 Tuning	41 43 44 44
	7.1 7.2 7.3 7.3. 7.3.2 7.3.3	Complete List of Sequence Commands  MIDI Control Code Table  1 RPN Support Chart  Compatibility with SMF Created for MusicPlayer2000  1 Track Number  2 Modulation  3 Tuning  4 Simulated Echo	
	7.1 7.2 7.2.7 7.3 7.3.2 7.3.2 7.3.2	Complete List of Sequence Commands  MIDI Control Code Table  1 RPN Support Chart  Compatibility with SMF Created for MusicPlayer2000  1 Track Number  2 Modulation  3 Tuning  4 Simulated Echo  5 Priority	
	7.1 7.2 7.2.7 7.3 7.3.2 7.3.3 7.3.4 7.3.5	Complete List of Sequence Commands  MIDI Control Code Table  1 RPN Support Chart  Compatibility with SMF Created for MusicPlayer2000  1 Track Number  2 Modulation  3 Tuning  4 Simulated Echo  5 Priority  6 Loops on Individual Tracks	
	7.1 7.2 7.3.7 7.3.2 7.3.2 7.3.4 7.3.6 7.3.6	Complete List of Sequence Commands  MIDI Control Code Table  1 RPN Support Chart  Compatibility with SMF Created for MusicPlayer2000  1 Track Number  2 Modulation  3 Tuning  4 Simulated Echo  5 Priority  6 Loops on Individual Tracks  7 Volume Calculation	

# Code

	12
Code 3-2 Track Opening Process	13
Code 3-3 Track Process	14
Code 4-1 Text Sequence Archive	16
Code 4-2 Sequence Table	18
Code 4-3 Sequence Data	18
Code 4-4 Sequence Table	19
Code 5-1 Example of Note Command	25
Code 6-1 Example of Calculation Between Variab	oles36
Code 6-2 Example of Conditions Command	37
Code 6-3 Example of Combination with Condition	al Command38
Tables	
Table 4-1 Sequence Table Elements	19
Table 4-2 Operators	22
Table 5-1 List of Sequence Commands	23
Table 5-2 Degrees of Modulation Change	31
Table 5-3 List of Modulation Types	32
Table 6-1 List of Random Commands	33
Table 6-2 List of Variable Calculation Commands	35
Table 6-3 List of Variable Commands	36
Table 6-4 List of Comparison Commands	37
Table 6-5 List of Variable Debug Commands	38
Table 7-1 Complete List of Sequence Commands	39
Table 7-2 MIDI Control Code Table	41
Table 7-3 RPN Support Chart	43
Figures	
Figure 6-1 Local and Global Variables	34

# **Revision History**

Revision Date	Description
2008/05/30	Made revisions in line with the NITRO-System name change (from NITRO-System to TWL-System).
2008/04/08	Changed the format of the Revision History. Changed page headers.
2007/11/26	Added explanation for disabling the envelope command.  Support for MIDI RPN.  Added notes specific to the call/ret and loop_start/loop_end commands.
2006/05/29	Added explanation of mute command.  Added explanation of extended feature for expansion of label names embedded in SMF text commands.  Fixed errors.
2005/03/28	Added a description of numeric value notations.
2005/01/31	Added a description of the printvar command.  Changed "NITRO" to "Nintendo DS".
2004/11/10	Explained difference between volume and volume2 commands in detail.  Explained randvar command in detail.  Fixed typos.
2004/10/12	Added an explanation of the method for specifying a player with a label in the @SEQ_TABLE sequence archive.
2004/09/16	Made it possible to use a value of 0 for the argument of the loop_start command so that it is handled as an infinite loop.  Made it possible to use loop_start and loop_end from an SMF.  Made it possible to use loop_start and loop_end for loop markers in an SMF.  Revised the description of Blank Space at Start of SMF.  Made the correction in "Compatibility with SMF created for MusicPlayer2000" because of the addition of the loop feature for individual tracks in an SMF.  Added the description on how to specify banks by using labels with @SEQ_TABLE of sequence archive.
2004/09/02	Added the description about embedding text commands in SMF.
2004/08/10	Revisions reflecting changes in the smfconv output format.
2004/07/20	Style adjustments.
2004/06/01	Added expansion sequence command.  Added list of all sequence commands.  Added table for MIDI control codes.  Added a description of how to specify an index number for the sequence label name of the sequence archive.

Revision Date	Description
	In conjunction with the change of being able to play back multiple sequences with one Player, revised the description of Player Numbers in the sequence table of the sequence archive.  Revised the description of the Player priority.
	Made MIDI control change (29) to increase the value by 24 time and convert to sweep_pitch command.
	Changed the maximum value of the prg and mod_delay commands from 65535 to 32767.  Added volume 2 command.
	Clearly stated the range of the bendrange command value.
2004/04/12	Placed the explanation about Sequence Tables in a separate section.  Made distinction for sequence label and data label names.  Added a warning about multiple definition of sequence labels.
2004/04/01	Assignment of porta of MIDI Control Change #84.  Added Envelope command.  Added section about compatibility of SMF and MusicPlayer2000.  Added loop_start / loop_end commands.  Added description that only single sounds can be played in tie mode.  Added a warning about infinite loops with the jump command.  Deleted the incorrect statement that mod_range worked only for pitch change.  Corrected errors about Voice Priority comparisons.
2004/03/18	Changed the overall composition.  Made corrections in step with changes to text format specifications.  Added section relating to special specification for when Note command length is 0.  Added section relating to expanded specifications for portamento and sweep.
2004/03/01	Initial version.

# 1 Overview

Sequences are a data format that corresponds to sheet music data, such as a standard MIDI file. Commands that process sound generation and volume change over time are described in this document. Sequence data is a collection of commands, and sounds are generated using bank data that corresponds to the sound source data.

Sequences have two formats: sequence files and sequence archive files.

This section provides simple explanations of both types of files.

# 1.1 Sequence Files

Sequence files contain one set of sequence data per file. Sequence files can be handled the same way as standard MIDI files.

By using the SMF converter smfconv, a standard MIDI file can be converted into sequence files.

# 1.2 Sequence Archives

A sequence archive is a single file that contains a collection of sequence data. You cannot use smfconv to convert data to this format; therefore, you must use a text editor to create a sequence archive. Sequence archives can reduce the data size. Because many sequences are handled in a single file, simple sequence data can be created in a short time.

9

# 2 Basics

### 2.1 Time Base

The quarter-note resolution is 48. When the tempo is 240, the length of one produced sound is equal to the length of one tick. Variations in sound generation can be minimized by setting the tempo to a divisor of 240. The default tempo is 120.

## 2.2 Comments

Comments in sequence files and sequence archives start with a semicolon (;) for each line of code written in text format as shown below.

```
;;; comment
Track_0: ; comment
```

## 2.3 Labels

A colon (:) at the end of the string defines a label definition. Once a label is defined, that label can be called from any other file.

#### 2.3.1 Characters Used for Labels

All global label names must start with a letter. Subsequent characters can be letters, numbers, or an underscore (\_).

```
LoopStart:
test_seq:
Track_01
```

#### 2.3.2 Local Labels

Label names that *begin* with an underscore (\_) are treated as local labels.

A local label is valid only in the label section. Therefore, the same local label name can be used in another section.

```
label_1:
          ;; The "_local" from line 3 can be used here
_local:
          ;; The "_local" from line 3 can be used here

label_2:
          ;; The "_local" from line 7 can be used here
_local:
          ;; The "_local" from line 7 can be used here

label3:
          ;; The "_local" cannot be used here
```

# 3 Sequence Files

#### 3.1 Overview

A sequence file is a file that stores a single sequence. Normally, the sequence file is created by converting a standard MIDI file.

The standard MIDI file is first converted into a text format sequence file. The text format sequence file is implemented using the same sequence commands as a sequence archive, which is explained in the following sections.

The text sequence file is then converted to the binary data that has the file extension .sseq by the sequence converter sequency and played on the Nintendo DS.

## 3.2 Standard MIDI Files

A standard MIDI file (SMF) is created using commercially available sequencers.

The following sections describe precautions to take when creating SMFs.

#### 3.2.1 SMF Format

Use only SMF format 0 or 1. There is no support for SMF format 2.

#### 3.2.2 Tracks

A maximum of 16 tracks can be used. However, the entire NITRO-Composer can use only up to 32 tracks.

Channel numbers 1 to 16 correspond to track numbers 0 to 15. MIDI events like tempo changes that affect the overall sequence get mixed into track 0 for output.

# 3.2.3 Specifying Loops

To loop all of the tracks in SMF using the same timing, write square brackets as markers on the MIDI sequencer. The file is converted by taking the opening bracket ([) as the start of the loop, and the closing bracket (]) as the end of the loop. The opening bracket and closing bracket can be replaced with the loop\_start and loop\_end strings, respectively.

To loop each track, enter a value of 0 for Control Change 89 for the loop starting point; enter an arbitrary value for Control Change 90 (with an arbitrary value) for the loop ending point.

# 3.2.4 Blank Space at the Start of the SMF

When the SMF is converted, all empty notes are truncated automatically until the first Note On. To keep the empty notes from being truncated, add a low-volume dummy note to start the sequence.

However, if the start of a loop is placed before the first Note On, only the empty notes before the starting position of the marked loop are truncated.

#### 3.2.5 MIDI Events

To learn about the MIDI events that are converted, see the list of sequence commands in Chapter 5 Sequence Commands.

## 3.2.6 Compatibility with MusicPlayer2000

An SMF that is created for MusicPlayer2000 (the sound driver for AGB) can be converted without modification. However, some of the specifications have changed, and adjustments are needed to reproduce the file correctly. For details, see section 7.3 Compatibility with SMF Created for MusicPlayer2000.

# 3.3 Text Sequences

#### 3.3.1 Overview

When the SMF is converted using smfconv, the text sequence file shown in Code 3-1 is generated.

#### **Code 3-1 Text Sequence File**

```
; mid/kart64_title.smft
    generated by smfconv
SMF_kart64_title_Begin:
     alloctrack 0x0eff
SMF_kart64_title_Start:
     opentrack 1, SMF_kart64_title_Track_1
     opentrack 2, SMF_kart64_title_Track_2
     opentrack 3, SMF_kart64_title_Track_3
     opentrack 4, SMF_kart64_title_Track_4
     opentrack 5, SMF_kart64_title_Track_5
     opentrack 6, SMF_kart64_title_Track_6
     opentrack 7, SMF_kart64_title_Track_7
     opentrack 9, SMF_kart64_title_Track_9
     opentrack 10, SMF_kart64_title_Track_10
     opentrack 11, SMF_kart64_title_Track_11
; Track 0
```

```
SMF_kart64_title_Track_0:
  notewait_off
Measure 1 -----
  tempo
           140
            0
  prq
SMF_kart64_title_Track_0_LoopStart:
           1
  wait
  volume
           127
  pan
  bendrange
  pitchbend
           0
  mod_speed 16
  mod_depth 0
  wait
           767
; Measure 2 -----
```

This text sequence file is written as a series of sequence commands. Generally, these commands are processed from top to bottom. For explanations of each command, see Chapter 5 Sequence Commands.

# 3.3.2 Track Opening Process

The process to open tracks follows the first comment.

#### **Code 3-2 Track Opening Process**

```
SMF_kart64_title_Begin:
    alloctrack 0x0eff

SMF_kart64_title_Start:
    opentrack 1, SMF_kart64_title_Track_1
    opentrack 2, SMF_kart64_title_Track_2
    opentrack 3, SMF_kart64_title_Track_3
    opentrack 4, SMF_kart64_title_Track_4
    opentrack 5, SMF_kart64_title_Track_5
    opentrack 6, SMF_kart64_title_Track_6
    opentrack 7, SMF_kart64_title_Track_7
    opentrack 9, SMF_kart64_title_Track_9
    opentrack 10, SMF_kart64_title_Track_10
    opentrack 11, SMF_kart64_title_Track_11
```

Note that the first set of sequence data is processed on track 0. When the sequence starts, track 0 is already allocated, and the process to open sequences begins at that point. When using multiple tracks, another track needs to be allocated and started from track 0.

alloctrack on line 2 allocates tracks. This command can only be used immediately after the start of the sequence. The argument is a bitmask expressing the tracks starting at track 0 from the LSB to allocate the bit-enabled track.

opentrack from lines 4 and on starts the tracks. The first argument is the track number. The second argument is the label for the beginning of the sequence on that track.

From the position of this label, the process on the specified track begins. The processes for track 0 execute the lines that follow after the last opentrack command.

#### 3.3.3 Track Process

The process for each track is described after the label, as seen in Code 3-1, for kart64\_title\_Track\_0.

#### **Code 3-3 Track Process**

```
SMF_kart64_title_Track_0:
   notewait_off
; Measure 1 -----
               140
   tempo
               0
   prg
SMF_kart64_title_Track_0_LoopStart:
   wait
                1
   volume
               127
                64
   bendrange
                2
   pitchbend
   mod_speed
   mod depth
   wait
                767
; Measure 2 --
```

For more information about the each sequence command, see Chapter 5 Sequence Commands.

# 3.4 Embedding Text Commands in SMF

#### 3.4.1 Overview

Creating sequence data on a sequencer is convenient because you can check the sound immediately. There are many restrictions with SMF; most commands used with text sequences cannot be used with SMF. You can edit converted SMFT files directly with a text editor to use these commands, but the file will be overwritten the next time you edit it with the sequencer.

For this reason, a feature is provided to embed text commands in SMF and output text commands and MIDI events in a SMFT file. With this feature, any text command can be used and the command will not be overwritten when the file is edited with the sequencer.

#### 3.4.2 How to Embed

Embed the following string in the SMF data as either a marker or a text event.

```
text_03: pan_r 30, 90
```

This string outputs the command "pan\_r 30, 90" at the specified location on Track 03 (MIDI channel).

## 3.4.3 Output All Tracks

The statement shown below is specified for all tracks.

```
text_all: pan_r 30, 90
```

However, this statement does not output information for unused tracks.

## 3.4.4 Expansion of the Label Name

As shown below, defining the label in the same place on all tracks using text\_all causes an error.

```
text_all:BLOCK_A:
```

This statement defines label BLOCK\_A at multiple locations and causes a multiple definition error. In this case, use the following statement.

```
text all: $BLOCK A:
```

By adding the \$ character, the label name is given a unique prefix and passed into each track as shown below.

```
SMF_filename_Track_0_BLOCK_A:
```

filename indicates the SMF file name, 0 indicates the track number, and the edition of this information prevents the multiple definition error.

## 3.4.5 Cautions Regarding the Real-Time MIDI Playback

Real-time MIDI playback does not process the embedded text sequence. For this reason, the result is different from the playback of the converted file.

By replacing \$ with \$\$ as shown below:

```
text_all:$$BLOCK_A:
```

The SMF filename part is no longer expanded.

Track\_0\_BLOCK\_A:

# **4 Sequence Archives**

### 4.1 Overview

A sequence archive is a single file that comprises multiple sets of sequence data. The example shown in Code 4-1 helps explain sequence archives.

#### **Code 4-1 Text Sequence Archive**

```
SeqArc for Sample SE
#include "../sound_data.sbdl"
@SEQ_TABLE
SE_YOSHI:
                         BANK_SE, 127, 96, 64, PLAYER_VOICE
             yoshi,
SE_WIHAHO:
                     wihaho, BANK_SE, 127, 96, 64, PLAYER_VOICE
SE_COIN:
                       BANK_SE, 65, 96, 64, PLAYER_SE
             note_only,
                                BANK_SE, 55, 96, 64, PLAYER_SE
SE_AMBULANCE:
                     jump_seq,
                                BANK_SE, 55, 96, 64, PLAYER_SE
SE PATTERN:
                    loop_seq,
                                BANK_SE, 55, 96, 64, PLAYER_SE
SE_PATTERN:
                    call_seq,
                    porta_seq, BANK_SE, 65, 96, 64, PLAYER_SE
SE_PORTAMENT:
                    porta_time_seq, BANK_SE, 65, 96, 64, PLAYER_SE
SE_PORTAMENT2:
         sweep_seq,
SE_SWEEP:
                         BANK_SE, 65, 96, 64, PLAYER_SE
                   mod_seq, BANK_SE, 65, 96, 64, PLAYER_SE
SE_VIBRATE:
SE_VIBRATE2:
                     tie_seq,
                                BANK_SE, 65, 96, 64, PLAYER_SE
                    waitoff_seq, BANK_SE, 65, 96, 64, PLAYER_SE
SE_SUPER_MARIO:
SE_SUPER_MARIO2: opentrack_seq, BANK_SE, 65, 96, 64, PLAYER_SE
@SEQ_DATA
yoshi:
  prg 0
  cn4 127, 0
  fin
wihaho:
  prg 1
  cn4 127, 0
  fin
```

```
; Note commands only
; Coin sound
note_only:
    prg 2
    as5 127, 6
    ds6 127, 48
    fin

; loop by jump (repeated endlessly)
; Ambulance
jump_seq:
    prg 3
_loop_start:
    bn4 127, 48
    gn4 127, 48
    jump _loop_start
```

# 4.2 Using the Sound Archive Label File

This section explains the first statement in the file.

```
#include "../sound.data.sbdl"
```

This statement shows that the sound archive label file named <code>sound\_data.sbdl</code> is included in the directory a level above the current directory. The sound archive label file is generated automatically during sound data conversion. By including this file, the labels defined in the sound archive definition file can be used in this sequence archive.

By including this statement at the beginning of the file, the bank label can be used for specifying banks in subsequent lines. Including this file with #include is unnecessary if you specify banks with numbers instead of labels.

### 4.3 Structure

The structure of the code is divided into two parts.

- · Sequence table
- Sequence data

## 4.3.1 Sequence Table

Code 4-2 show a sequence table.

#### Code 4-2 Sequence Table

```
@SEQ_TABLE
SE_YOSHI:
                               BANK_SE, 127, 96, 64, PLAYER_VOICE
                yoshi,
SE_WIHAHO:
                        wihaho,
                                     BANK_SE, 127, 96, 64, PLAYER_VOICE
SE_COIN:
               note_only, BANK_SE, 65, 96, 64, PLAYER_SE
SE_AMBULANCE:
                        jump_seq,
                                    BANK_SE, 55, 96, 64, PLAYER_SE
SE_REPEAT:
                       loop_seq,
                                     BANK_SE, 55, 96, 64, PLAYER_SE
SE_PATTERN:
                                     BANK_SE, 55, 96, 64, PLAYER_SE
                       call_seq,
SE_PORTAMENT:
                      porta_seq,
                                    BANK_SE, 65, 96, 64, PLAYER_SE
SE_PORTAMENT2:
                       porta_time_seq, BANK_SE, 65, 96, 64, PLAYER_SE
                              BANK_SE, 65, 96, 64, PLAYER_SE
SE_SWEEP:
                sweep_seq,
SE_VIBRATE:
                                  BANK_SE, 65, 96, 64, PLAYER_SE
                       mod_seq,
SE_VIBRATE2:
                                    BANK_SE, 65, 96, 64, PLAYER_SE
                        tie_seq,
                        waitoff_seq, BANK_SE, 65, 96, 64, PLAYER_SE
SE_SUPER_MARIO:
SE_SUPER_MARIO2: opentrack_seq, BANK_SE, 65, 96, 64, PLAYER_SE
```

Calling @SEQ\_TABLE on line 1 indicates the start of the sequence table. The sequence table data begins on line 3. Each line defines a single sequence. Sequence data details are explained in the next section.

## 4.3.2 Sequence Data

Code 4-3 shows sequence data.

#### Code 4-3 Sequence Data

```
; Note commands only
; Coin sound
note_only:
    prg 0
    as5 127, 6
    ds6 127, 48
    fin

; loop by jump (repeated endlessly)
; Ambulance
loop_seq:
    prg 1
_loop_start:
    bn4 127, 48
    gn4 127, 48
    jump _loop_start
```

Each sequence begins with a label name definition and the sequence associated with that label. The label name definition is followed by sequence commands used to create a single set of sequence data. For further details about each sequence command, see Chapter 5 Sequence Commands.

# 4.4 Sequence Tables

This section describes the contents of a sequence table.

#### Code 4-4 Sequence Table

```
@SEQ_TABLE
SE_YOSHI:
                         yoshi,
                                        BANK_SE, 127, 96, 64, PLAYER_VOICE
SE_WIHAHO:
                         wihaho,
                                        BANK_SE, 127, 96, 64, PLAYER_VOICE
SE_COIN:
                         note_only,
                                       BANK_SE, 65, 96, 64, PLAYER_SE
SE_AMBULANCE:
                         jump_seq,
                                       BANK_SE, 55, 96, 64, PLAYER_SE
SE_REPEAT:
                                        BANK_SE, 55, 96, 64, PLAYER_SE
                         loop_seq,
                                        BANK_SE, 55, 96, 64, PLAYER_SE
SE_PATTERN:
                         call_seq,
SE_PORTAMENT:
                                        BANK_SE, 65, 96, 64, PLAYER_SE
                         porta_seq,
                         porta_time_seq, BANK_SE, 65, 96, 64, PLAYER_SE
SE PORTAMENT2:
SE_SWEEP:
                                        BANK_SE, 65, 96, 64, PLAYER_SE
                         sweep_seq,
                                        BANK_SE, 65, 96, 64, PLAYER_SE
SE_VIBRATE:
                         mod_seq,
                                        BANK_SE, 65, 96, 64, PLAYER_SE
SE_VIBRATE2:
                         tie_seq,
                                        BANK_SE, 65, 96, 64, PLAYER_SE
SE_SUPER_MARIO:
                         waitoff_seq,
                         opentrack_seq, BANK_SE, 65, 96, 64, PLAYER_SE
SE_SUPER_MARIO2:
```

The format of each statement is shown below.

```
seqName: dataLabel, bankNo, volume, channelPrio, playerPrio, playerNo
```

The description of the statement elements is shown in Table 4-1.

**Table 4-1 Sequence Table Elements** 

Element	Description
seqName	Sequence label name.
dataLabel	Data label name.
bankNo	Bank label or bank number.
Volume	Volume.
channelPrio	Voice priority.
playerPrio	Player priority.
playerNo	Player label or player number.

The following sections discuss each element.

## 4.4.1 Sequence Label Name

The sequence label name identifies a specific sequence. The name must begin with an uppercase Roman letter, but subsequent characters can be uppercase Roman letters, underscores, or numbers. The same label name cannot be defined more than once because label names are global. Note that the same label name should not be defined even in other sequence archives.

The label name specified here is used in the program to play back the sequence. Instead of the label name, the index number can be used to specify a sequence.

```
      SE_COIN = 2:
      note_only,
      BANK_SE, 65, 96, 64, PLAYER_SE

      SE_AMBULANCE:
      loop_seq,
      BANK_SE, 55, 96, 64, PLAYER_SE

      10:
      call_seq,
      BANK_SE, 55, 96, 64, PLAYER_SE
```

In the example above, statement 1 specifies both the label and index number. Here, the label is SE COIN and the index number is 2.

If only a label name is specified, the index number for this statement will be determined by incrementing the index number of the previous statement by one. Therefore, in the second statement in the example above, the index number is 3.

The third statement is assigned an index number only and the label name is undefined. Because this sequence archive is assigned only an index number, the sequence archive must be referred to using the index number.

#### 4.4.2 Data Label Name

The data label name specifies the label name of the sequence data described after @SEQ\_DATA.

#### 4.4.3 Bank

Using the label name or number specifies the bank to use for sequence playback. However, if a sound archive label file (.sbdl) is not included, a bank cannot be specified with a bank label.

#### **4.4.4 Volume**

Volume is specified to adjust the overall sequence volume; it is a value from 0 to 127.

#### 4.4.5 Voice Priority

This specifies priority for sound generation of all sequences. The voice priority determines which sound to generate from the 16 channels. The value ranges from 0 to 127, and the higher the value, the higher the priority. For details on voice priority, see the *NITRO-Composer Sound System Manual*.

## 4.4.6 Player Priority

This specifies the player priority. The player priority determines which sequence will play from the maximum number of sequences that can play. The value ranges from 0 to 127, and the higher the value, the higher the priority.

For details on Player Priority, see the NITRO-Composer Sound System Manual.

## 4.4.7 Player Number

Using the player label or player number specifies which of the 32 players to use for playback. However, you can specify the player label only if the sound archive label file (.sbdl) is loaded.

The number of sequences that can play back on a single player is limited; therefore, the player must be specified if this limitation is taken into consideration.

# 4.5 Numeric Value Notation

The numeric value notations in the following sections can be used in place of decimal values to specify numeric parameters in the text sequence file.

# 4.5.1 Binary and Hexadecimal Notation

Numeric values are frequently expressed as decimals, but can also be expressed in binary and hexadecimal notations.

When describing binary or hexadecimal numbers, attach the prefix 0b or 0x, respectively, to begin the notation. For example, the decimal number 12 is expressed as:

```
0b1100
0xc
```

#### 4.5.2 Bit Notation

Bit notation is helpful when writing a value that specifies whether a bit is 1 or 0, such as with a bit flag.

Bit notation expresses which bits are set to 1. For example, when setting bits 1, 3, and 6 to 8 to the value of 1, it should be written as:

```
{ 1,3,6-8 }
```

This corresponds to 0b111001010. Note that the LSB is 0.

## 4.5.3 Mathematical Expressions

Numeric values may also be written as mathematical expressions. Binary, hexadecimal, and bit notations may be used in the terms of the mathematical expression.

For example, the following notations are possible.

```
2 * 4 + 0x10
( 1 << 4 ) + 3
{ 0, 2 } | { 4-6 }
```

Table 4-2 shows the operators that can be used in an expression, as well as the priority of the operators.

**Table 4-2 Operators** 

Priority	Operator	Meaning
1	*	Multiplication
'	/	Division
2	+	Addition
	-	Subtraction
3	>>	Right Shift
	<<	Left Shift
	<	Left side is Less Than the right side
<= Left side is Les		Left side is Less Than or Equal To the right side
	>	Left side is Greater Than the right side
	>=	Left side is Greater Than or Equal To the right side
5	==	Left side is equal to the right side
6	&	Bitwise AND
7		Bitwise OR

# **5 Sequence Commands**

Sequence commands are the group of commands used in the sequence data.

**Table 5-1 List of Sequence Commands** 

Command Name	Explanation	Default	MIDI	Ref.(pg)
cn4 velocity, length	Note command.		\$9x, \$8x	24
wait length	Rest command.			25
fin	End sequence.			25
prg x	Change program.	0	\$Cx	25
tempo x	Change tempo.	120		25
volume x	Change track volume.	127	\$Bx, 7	25
volume 2x	Change track volume.	127	\$Bx, 11	25
main_volume x	Change Player's volume.	127	\$Bx, 12	26
pitchbend x	Change pitch bend.	0	\$Ex	26
bendrange x	Change pitch bend range.	2	\$Bx, 20	26
transpose x	Transpose.	0	\$Bx, 13 <sup>i</sup>	26
pan x	Change track pan.	64	\$Bx, 10	26
prio x	Change voice priority of track.	64	\$Bx, 14	27
tieon / tieoff	Tie mode start/end.	off		27
notewait_on / notewait_off	Note wait on/off.	on		27
mute	Changes the mute flag.	0		27
porta x	Set portamento's start key and start.	cn4(60)	\$Bx, 84 <sup>ii</sup>	27
porta_time x	Set portamento time.	0	\$Bx, 5	27
porta_on / porta_off	Portamento start/end.	off	\$Bx, 65 <sup>iii</sup>	27
sweep_pitch x	Set the amount-of-change in sweep pitch.	0	\$Bx, 28 <sup>iv</sup> \$Bx, 29 <sup>v</sup>	28
alloctrack mask	Secure tracks.			29
opentrack no, label	Start a track.			29
jump label	Sequence jump.			29
call label	Sequence call.			30

<sup>&</sup>lt;sup>i</sup> 0 to 127 for transpose (#13) becomes -64 to +63.

For portamento control (#84), specify the note number that takes 60 as cn4 (middle C).

<sup>0</sup> to 63 for portamento (#65) becomes porta\_off, while 64 to 127 become porta\_on.

o to 127 for sweep pitch (#28) becomes -64 to +63.

With 0 to 127 for sweep pitch (#29), the values are multiplied by 24 and range from -1536 to +1512.

Command Name	Explanation	Default	MIDI	Ref.(pg)
ret	Sequence return.			30
loop_start count	Loop starting point.		\$Bx, 89	30
loop_end	Loop ending point.		\$Bx, 90	30
attack x	Set attack value.		\$Bx, 85	30
decay x	Set decay value.		\$Bx, 86	30
sustain x	Set sustain value.		\$Bx, 87	30
release x	Set release value.		\$Bx, 88	30
envelope a,d,s,r	Set envelope values.			30
mod_depth x	Set modulation depth.	0	\$Bx, 1	31
mod_range x	Set modulation range.	1	\$Bx, 23	31
mod_speed x	Set modulation speed.	16	\$Bx, 21	31
mod_delay x	Set modulation delay.	0	\$Bx, 26 \$Bx, 27 <sup>vi</sup>	31
mod_type x	Set modulation type.	0	\$Bx, 22	31

## 5.1 Note Command

This command generates sounds using the current program number.

```
cn4 velocity, length
```

Keys are written in the format cn4, cs4, dn4, ds4, en4, fn4, fs4, gn4, gs4, an4, as4, bn4, and cn5. The middle C is cn4. The value ranges from cnm1 to gn9 can be specified. (m1 indicates "minus 1.")

velocity specifies a value that ranges from 0 to 127, and the value is based on a squared value scale interpreted. In other words, by taking 127 as 100 percent:

```
( ( velocity / 127 ) ^ 2 ) * 100 [%]
```

length indicates the length of a note in which 48 corresponds to the length of a quarter note. The actual length depends on the tempo. The value ranges from 0 to 268435455. The value 0 represents infinity. In other words, the waveform data plays to the end. If the waveform data loops, the sound plays back indefinitely (the playback can be stopped by the program).

In the note-wait ON state (default), the sequence stops for the same length of time as the length of a note. When length is 0, the sequence waits for playback to end in the channel. In other words, the next sequence process starts after the waveform data has played back to the end. If the waveform data loops, the sequence stops indefinitely (can be stopped in the program). Even if the note has low voice priority, the process shifts to the next sequence, and the playback is forcibly stopped.

vi Modulation delay (27) multiples the value by 10 for output.

#### Code 5-1 Example of Note Command

```
cn4 110, 48
dn4 110, 48
en4 127, 96
```

#### 5.2 Rest Command

This command stops the sequence for a specified length of time.

```
wait length
```

length matches the length of a note, where 48 corresponds to the length of a quarter note. The actual length depends on the tempo. The value ranges from 0 to 268435455.

# 5.3 End Sequence

This command ends the sequence process of the track.

fin

When the sequence processes for all tracks end, the player processes also stop. If you forget to write the fin command, the following sequence data will execute without a break. This oversight can cause unexpected sounds to play and the system to hang.

# 5.4 Change Program

This command executes a program change.

```
prg x
```

A program number ranges from 0 to 32767. However, only values from 0 to 127 can be specified with MIDI. The default value is 0.

# 5.5 Change Tempo

This command changes the tempo.

```
tempo x
```

A tempo value ranges between 0 and 1023. The tempo scale that can be set in the program determines the ultimate tempo value. The default value is 120.

## 5.6 Track Volume

This command changes the track volume.

```
\begin{array}{c} \text{volume } x \\ \text{volume2} \ x \end{array}
```

A volume value i ranges from 0 to 127. The default value is 127.

Like velocity, the volume value is based on a squared value scale. In other words, if 127 is taken as 100 percent:

```
( ( volume / 127 ) ^ 2 ) * 100 [%]
```

There is no functional difference between volume2 and volume. When both are specified at the same time, both values are reflected in the results. For example, if volume is set to 80 percent and volume2 is set to 50 percent, the volume will be 40 percent (0.8 x 0.5 = 0.4).

### 5.7 Main Volume

This command changes the volume of the player.

```
main\_volume x
```

The volume value ranges from 0 to 127. The default value is 127.

Like velocity, the volume value is based on a squared value scale. In other words, if 127 is taken as 100 percent:

```
( ( volume / 127 ) ** 2 ) * 100 [%]
```

## 5.8 Pitch Bend

These commands change the pitch bend and the pitch bend range.

```
pitchbend x bendrange x
```

The pitch bend value ranges from -128 to 127. The default value is 0.

The units of bendrange are semitones. The default value is 2 and the value ranges from 0 to 127.

When the maximum pitchbend value is specified, the pitch of the note changes by the value specified by bendrange. For example, if the value assigned to bendrange is 2, a pitchbend value of 127 changes by +2 semitones, a value of 64 changes by +1 semitone, and the value of -64 changes by -1 semitone.

# 5.9 Transpose

This command transposes the sequence.

```
transpose x
```

The transpose value specified in units of semitones ranges from -64 to +63. The default value is 0.

## 5.10 Track Pan

This command changes the pan for the track.

```
pan x
```

The pan value ranges from 0 and 127, with 0 being left, 127 being right, and 64 being center. The default value is 64.

# **5.11 Voice Priority**

This command sets the voice priority for the track.

```
prio x
```

The priority value ranges from 0 to 127. The default value is 64. In actuality, the final voice priority value comprises the player and voice priority. A larger value indicates higher priority. When both values match, player priority has priority to generate sound.

## 5.12 Tie Mode

These commands change the tie mode.

tieon tieoff

The default is tie mode off.

When Note On is generated while tie mode is on, regardless of the note length specified by the Note command, the sound will play continuously. When the next Note On is generated, sound will continue to generate, but only the pitch and velocity will change. To discontinue generating sound, set the tie mode to OFF or stop the sequence.

When tie mode is set to ON, sounds being generated are forcibly released. Even if note-wait mode is set to OFF, only single notes can be played.

### 5.13 Note Wait Mode

These commands change the note-wait mode.

notewait\_on
notewait\_off

By default, note-wait is ON.

When Note On is generated and note wait is ON, the sequence stops for the same length of time as the note length specified by the Note command. When note wait is OFF, the next command is processed without a break.

In the ON state, the sequence stops while notes are playing and not needing to insert a Rest command is convenient. However, nothing can be processed while the notes are playing. In the OFF state, there is no wait after a Note command, so two or more notes can play at once and move the pan while notes are playing.

### 5.14 Mute

This command changes the mute flag.

mute x

The argument can be set to any value between 0 and 3. The meanings of the different values are shown below. The default value is 0.

**Table 5-1 Mute Command Arguments** 

Argument	Explanation
0	Cancels mute.
1	Mutes without stopping the sound that is playing.
2	Mutes after releasing the sound that is playing.
3	Mutes by immediately stopping the sound that is playing.

Note: The mute command can be used only with NITRO-SDK version 3.1 and later.

#### 5.15 Portamento

These commands set the portamento.

```
porta key
porta_time time
porta_on
porta_off
```

Enter portamento mode with the porta command. When a Note command is executed in portamento mode, the pitch specified with key changes to a pitch specified by the Note command during playback. With the following calls to the Note command, the previous Note command pitch changes to the current Note command pitch.

The porta\_time command specifies the speed of the pitch change. (Following the MIDI convention, this command is called porta\_time instead of porta\_speed.) The value ranges from 0 to 255, and the default value is 0. The larger the value, the longer change takes. When set to 0, the speed of the pitch change is the same length as the note length. In other words, the pitch changes during the time set to generate sound using the note command.

porta\_on like porta, enters portamento mode, but does not specify a starting key. With the next note command, the pitch is changed from the pitch specified in the note command executed before porta\_on. When the next note command is executed, the pitch changes from the previous note command to the pitch of the current note command.

The porta\_off command cancels portamento mode.

If portamento is used while in the tieon state, commands such as repeatedly changing the pitch with pitchbend are possible.

# 5.16 Sweep

This command configures the sweep settings.

sweep\_pitch pitch

When the sweep\_pitch command is used, play the sound with a sweeping effect. When Note is executed while the sweep is set, the sound begins offset by the value pitch from the pitch specified by Note. The pitch is then gradually changed to the correct pitch. The pitch value ranges from -32768 to 32767, and the default value is 0. A value of 64 shifts the pitch by exactly one semitone.

The speed it takes to return to the correct pitch is the same speed set in the porta\_time command.

## 5.17 Allocate Tracks

This command allocates the tracks.

alloctrack mask

Note: This command must be used at the very start of a sequence.

mask is the bitmask of the tracks that are going to be secured. Starting from the LSB, the bitmasks represent track0, track1, track2, and so on. The tracks with enabled bits are allocated. (Track0 is already allocated, so the LSB is ignored.) Using the macro, this command can be written as:

```
alloctrack TRACK_1 | TRACK_2 | TRACK_3
```

Using the above statement allocates track1, track2, and track3.

## 5.18 Start a Track

This command starts a different track.

```
opentrack no, label
```

**Note:** This command can be executed only on tracks that have already been allocated using allocated.

no is the track number and the value ranges from 0 to 15, but the current track cannot be specified. The track being executed will run once all of the notes are released.

label indicates the start of the sequence.

If a track with a larger number than the current track is opened, the first process is executed in the same frame. However, if the track with a smaller number is opened, the process is executed one frame later.

# 5.19 Sequence Jump

This command jumps from one location in the sequence to another.

jump *label* 

label indicates the jump destination.

By using <code>jump</code>, a loop sequence can be created. However, if commands that stop sequences are not included in the loop, such as the wait or note command with the note wait on, the sequence loops indefinitely and causes an unexpected error.

# 5.20 Sequence Call

These commands jump from one location in the sequence to another and then return to the original location.

```
call label
ret
```

label indicates the jump destination.

By using the ret command at the jump destination, the sequence will return to the original location of the call. can be executed again at the jump destination, but call can be called only up to three levels.

Note that these three levels include the nested levels explained in section 5.21 Loop.

The call/ret commands and the loop\_start/loop\_end commands must be called in nested pairs. For example, once you have used the call command and then used the loop\_start command at the jump destination, you must call the loop\_end command before calling the ret command. Note that the ret command cannot be called in between the loop\_start and loop\_end commands.

# **5.21 Loop**

This command specifies the number of times to execute a certain section of a sequence repeatedly.

```
loop_start count
loop_end
```

loop\_start sets the starting point of the loop. count sets the number of loops and the values ranges from 0 to 255. When the value is 0, the loop is infinite. loop\_end sets the ending point of the loop. The process returns to the starting point of the loop until it reaches the number of loops specified by count.

Embedded loops can be set within other loops, but only up to three levels. Note that three levels include the nested levels explained in section 5.20 Sequence Call.

The call/ret commands and the <code>loop\_start/loop\_end</code> commands must be called in nested pairs. For example, once you have used the <code>call</code> command and then used the <code>loop\_start</code> command at the jump destination, you must call the <code>loop\_end</code> command before calling the <code>ret</code> command. Note that the <code>ret</code> command cannot be called in between the <code>loop\_start</code> and <code>loop\_end</code> commands.

Note: If this command is used with MIDI during the real-time MIDI playback, loops are ignored.

# 5.22 Envelope

These commands configure the envelope settings.

```
attack x decay x sustain x release x envelope a, d, s, r
```

The bank's envelope values are used by default, but the envelope values can be overwritten by using these commands. If the value for each individual command is specified, the unspecified values are set with the bank's envelope values. Using the <code>envelope</code> command, all values can be set at once.

If these values are set to -1, you can return to using the bank's envelope values.

## 5.23 Modulation

These commands configure the modulation settings.

```
mod_depth depth
mod_range range
mod_speed speed
mod_delay delay
mod_type type
```

Set the depth of the modulation with  $mod_{depth}$ . The value ranges from 0 to 127, and the default value is 0.

Table 5-2 shows the maximum values for the degrees of change. (If mod\_range, described later is set to 1.)

Table 5-2 Degrees of Modulation Change

Туре	Degrees of Change
Change in pitch	±1 semitone.
Change in volume	±6.0 dB.
Change in location	Left MAX to Right MAX.

mod\_range sets the maximum variation width of change. The value ranges from 0 to 127, and the default value is 1. For example, if the pitch changes with the default setting, the change occurs in the range of ±1 semitone at the maximum mod\_depth and a mod\_range of 12; the modulation occurs in the range of ± 12 semitones, or one octave.

mod\_speed sets modulation speed. The value ranges from 0 to 127, and the default value is 16. When the value is set to 1, the modulation speed linearly changes at approximately 0.4Hz, and the value that can be set ranges from approximately 0.0Hz to 50Hz.

mod\_delay sets the delay time of the modulation. The value ranges from 0 to 32767, and the default value is 0. The delay time is measured in units of sound frames (approximately 5 ms) and is independent from the tempo. Use Control Change 26 or 27 with MIDI. Control Change 26 outputs a value as is, and the Control Change 27 outputs a value multiplied by 10. Consequently, the value that can be set ranges from 0 to 1270.

 $mod\_type$  sets modulation type. The possible settings are shown in Table 5-3. The default value is 0 = vibrato (pitch change).

**Table 5-3 List of Modulation Types** 

Numerical Value	Label	Explanation
0	MOD_TYPE_PITCH	Vibrato (pitch change).
1	MOD_TYPE_VOLUME	Tremolo (volume change).
2	MOD_TYPE_PAN	Pan (location change).

**Note:** Amplitudes do not change beyond the threshold. For example, if the volume is already at the maximum when trying to change it, the volume will not become louder. Instead, it will only become softer.

# 6 Extended Sequence Commands

## 6.1 Overview

The extended sequence commands allow you to configure settings with a higher degree of freedom than the sequence commands described in previous chapters.

For normal sequence playback, normal sequence commands are sufficient. But the use of extended sequence commands allow for more elaborate sequences and interactive sequence playback among other enhancements.

# 6.2 Random Command

With some sequence commands, random numbers can be set for the values.

```
pitchbend_r -12 , 12
```

In the example above, pitchbend is given a random value range of -12 to +12. This command allows for subtle changes to the pitch each time a sound plays.

#### **6.2.1** Format

The basic format of the random command is shown below.

```
(command)_r min, max
```

The random numbers are generated between the minimum value of min, and the maximum value of max. These values are executed as the arguments of the command.

#### 6.2.2 Random Commands

#### **Table 6-1 List of Random Commands**

wait_r	prg_r	volume_r	volume2_r
main_volume_r	pitchbend_r	pan_r	transpose_r
mute_r	porta_time_r	sweep_pitch_r	mod_depth_r
mod_speed_r	attack_r	decay_r	sustain_r
release_r	mod_delay_r	loop_start_r	setvar_r
addvar_r	subvar_r	mulvar_r	divvar_r
shiftvar_r	randvar_r	cmp_eq_r	cmp_ge_r
cmp_gt_r	cmp_le_r	cmp_lt_r	cmp_ne_r

The setvar\_r command and subsequent commands in Table 6-1 are explained later.

For a table that shows the correspondence with the normal sequence commands, see section 7.1 Complete List of Sequence Commands.

## 6.2.3 Random Note Length Command

Adding \_r to a note command makes it a random command. This command sets the note length to a random range of values.

```
cn4_r velocity min, max
```

To change the pitch randomly, use transpose\_r. To change the velocity randomly, use volume\_r or volume2\_r.

# 6.3 Variable Commands

Variables can be handled in a sequence.

#### 6.3.1 What Is a Variable?

Variables are locations in memory that allow the storage of numeric values. In one, variable values ranging from -32768 to 32767 can be stored.

Sixteen variables can be used in one sequence, and 16 variables can be shared by the entire system. A variable handled only in one sequence is called a local variable, and a variable shared by the entire system is called a global variable.

Variables that can be used in one sequence Local Variables Global Variables Variable 16 variables 0 Variable 0 Local Variables 16 variables Variable Variable Local Variables 16 variables 16 variables Variable Variable Variable 0 2

Figure 6-1 Local and Global Variables

Each variable is specified by numbers in the sequence. Specifying a value from 0 to 15 declares one of the 16 local variables. Specifying a value from 16 to 31 declares one of the 16 global variables. In other words, 16 to 31 express the global variables 0 to 15.

The initial value of the variable is -1. The global variables are initialized during the startup of the system, and local variables are initialized when a sequence starts.

### 6.3.2 Variable Calculation Command

Values can be set, and four arithmetic operations can be performed for each variable.

**Table 6-2 List of Variable Calculation Commands** 

Command Name	Description
setvar varNo, x	Sets x in the variable.
addvar varNo, x	Adds x to the variable.
subvar varNo, x	Subtracts x from the variable.
mulvar varNo, x	Multiplies x times the variable.
divvar varNo, x	Divides the variable by x.
shiftvar <i>varNo</i> , x	Left shifts the variable by x bits (right shift for a negative value).
randvar varNo, x	Sets the random value between 0 and x in the variable (or in the range of x to 0 if the value is negative).

#### 6.3.3 Variable Commands

Sequence commands can be executed using set variables with the variable calculation commands listed in Table 6-2.

pitchbend\_v 0

As shown in the above example, the pitchbend command is executed using the local variable 0.

### **6.3.4 Format**

The basic format of the variable command is shown below.

(command)\_v varNo

Use the variable specified with varNo to execute the command.

The range values are set in the arguments of each sequence command. Note that if values exceed the range set in the variables, proper operation of variable commands cannot be guaranteed.

#### 6.3.5 List of Variable Commands

Sequence commands that can be used as random commands can also be used as variable commands.

Table	6-3 I	ist of	Variable	Commands
Iable	U-3 I	LISL UI	variable	Communication

wait_v	prg_v	volume_v	volume2_v
main_volume_v	pitchbend_v	pan_v	transpose_v
mute_v	porta_time_v	sweep_pitch_v	mod_depth_v
mod_speed_v	attack_v	decay_v	sustain_v
release_v	mod_delay_v	loop_start_v	setvar_v
addvar_v	subvar_v	mulvar_v	divvar_v
shiftvar_v	randvar_v	cmp_eq_v	cmp_ge_v
cmp_gt_v	cmp_le_v	cmp_lt_v	cmp_ne_v

Commands that begin with <code>cmp\_</code> in Table 6-3 are comparison commands and are described in section 6.4.1 Comparison Command.

For a table that shows the correspondence with the normal sequence commands, see section 7.1 Complete List of Sequence Commands.

## 6.3.6 Variable Note Length Command

Adding \_v to a note command makes it into a variable command. In doing so, the note length is specified with a variable.

```
cn4_v velocity varNo
```

To specify pitch with a variable, use transpose\_v. To specify the velocity with a variable, use volume\_v or volume2\_v.

#### 6.3.7 Calculation Between Variable Commands

The variable calculation commands described above add or subtract a certain value to or from a particular variable. By using variable commands such as setvar\_v, variables can be assigned to other variables or add the value of a variable to another variable.

#### Code 6-1 Example of Calculation Between Variables

```
setvar_v 0, 1 ; Assign a value from variable 1 to variable 0
addvar_v 2, 3 ; Add value of variable 3 to variable 2
```

### 6.4 Conditional Commands

Executing a sequence command can be determined by conditional statements using variables.

#### 6.4.1 Comparison Command

Before using conditional commands, execute comparison commands. Conditional commands execute based on the results of comparison commands. Comparison commands compare two values to determine if the conditional command is executed.

Table 6-4 lists the available comparison commands.

**Table 6-4 List of Comparison Commands** 

Command Name	Formula	Description
cmp_eq varNo, x	(variable) == x	If the value of the variable and x are equal, true (abbreviation for equal).
cmp_ge varNo, x	(variable) >= x	If the value of the variable is greater than or equal to x, true (abbreviation for greater than or equal).
cmp_gt varNo, x	(variable) > x	If the value of the variable is greater than x, true (abbreviation for greater than).
cmp_le varNo, x	(variable) <= x	If the value of the variable is less than or equal to x, true (abbreviation for less than or equal).
cmp_lt varNo, x	(variable) < x	If the value of the variable is less than x, true (abbreviation for less than).
cmp_ne varNo, x	(variable) != x	If the value of the variable and x are not equal, true (abbreviation for not equal).

If the result of the comparison is true, the following conditional commands are executed. If the result of the comparison is false, the conditional commands are not executed.

#### 6.4.2 Conditional Command

There are corresponding conditional commands for all sequence commands. The conditional command has \_if attached to the end of the original command name.

```
pitchbend_if +48
```

In the following example, a random number determines if a sound is played.

#### Code 6-2 Example of Conditions Command

```
randvar 0, 100 ; Set random number value from 0 to 100
cmp_le 0, 80 ; True if random number value is 80 or lower
cn4 96, 12
dn4_if 96, 12 ; Plays sound only when true
en4 96, 12
fin
```

# 6.5 Communication with the Program

Communication with the program can be conducted using a variable. The variable can read and write from the program, which uses this feature to exchange information.

## 6.5.1 Communication with the MIDI Sequence

Using a variable, information from the MIDI sequence notifies the program. The four control changes 16 to 19 are converted to the setvar command. Control change 16 is set in the local variable 0. The following control changes, 17, 18, and 19, are set in local variables 1, 2, and 3, respectively.

For example, if a variable is set at each break in the blocks that make up a song, the block that is currently playing back in the program can be found.

#### 6.5.2 Combination with Conditional Commands

Combining the conditional commands and variables from the program allows you to change a sequence with the program timing.

#### Code 6-3 Example of Combination with Conditional Command

```
_loop:
    cmp_eq 0, 1
    jump_if _loop2 ; Jumps only when variable 0 is 1
    cn4 96, 12
    dn4 96, 12
    jump _loop
_loop2:
    cn4 96, 12
    en4 96, 12
    jump _loop2
```

In Code 6-3, the notes C/D/C/D will continue to play if the program does nothing; but if 1 is assigned to local variable 0 in the program, the notes will change and play C/E/C/E.

# 6.6 Debugging Variables

Operations may not always proceed as expected to perform complex variable operations because of mistakes in the process. The sequence command is provided to check that the intended value is assigned to the used variable.

**Table 6-5 List of Variable Debug Commands** 

Command Name	Description
printvar varNo	Outputs the value of the variable for debugging.

If this command is processed, an output for debugging the following statement will result.

```
#0[1]: printvar No.0 = 1
```

What follows printvar indicates that the value of variable number 0 is 1. #0[1] indicates that the player identification number is 0 and the track number is 1. With the player identification number, the numeric value itself does not have significance. It simply shows that the output is from a different sequence if the player identification number differs. The track number shows which track from the sequence was output.

This sequence command is valid only when playing back a sequence on the NITRO-Player or SoundPlayer. This sequence command is ignored when playback is performed using any other method.

The print statement is output to the MCS server or the IS-NITRO-DEBUGGER output window.

# 7 Appendix

# 7.1 Complete List of Sequence Commands

**Table 7-1 Complete List of Sequence Commands** 

Command Name	Description	Specified Value	Range	Variable <sup>vii</sup>	Ref.
cn4 velocity, length	Note command.			0	24
wait x	Wait command.			0	25
fin	End sequence.				25
prg x	Change program.	0	0-32767	0	25
tempo $x$	Change tempo.	120	1-1023		25
volume x	Track volume.	127	0-127	0	25
volume2 x	Track volume (expression).	127	0-127	0	26
main_volume x	Main volume.	127	0-127	0	26
pitchbend x	Pitch bend.	0	-128-127	0	26
bendrange x	Pitch bend range.	2	0-127		26
transpose x	Transpose.	0	-64-63	0	26
pan x	Track pan.	64	0-127	0	26
prio x	Track voice priority.	64	0-127		27
tieon / tieoff	Tie mode on/off.	off			27
notewait_on / notewait_off	Note wait on/off.	on			27
mute x	Mute.	0	0-3	yes	27
porta x	Set portamento start key and portamento on.	cn4(60)	0-127		27
porta_time x	Portamento time.	0	0-255	0	27
porta_on / porta_off	Portamento on/off.	off			28
sweep_pitch x	Sweep pitch.	0	-32768- 32767	0	29
alloctrack mask	Allocate a track.				29

vii Shows whether it can also be used as a variable and random command.

© 2004-2009 Nintendo 39 TWL-06-0093-001-A CONFIDENTIAL Released: February 27, 2009

Command Name	Description	Specified Value	Range	Variable <sup>vii</sup>	Ref.
opentrack no, label	Start a track.				29
jump label	Sequence jump.				30
call label	Sequence call.				30
ret	Sequence return.				30
loop_start x	Loop start.		0–255	0	30
loop_end	Loop end.				30
attack x	Envelope attack.		-1–127	0	30
decay x	Envelope decay.		-1–127	0	30
sustain x	Envelope sustain.		-1–127	0	30
release x	Envelope release.		-1–127	0	30
envelope a,d,s,r	Envelope ADSR.		-1–127		31
mod_depth x	Modulation depth.	0	0-127	0	31
mod_range x	Modulation range.	1	0-127		31
mod_speed x	Modulation speed.	16	0-127	0	31
mod_delay x	Modulation delay.	0	0-32767	0	31
mod_type x	Modulation type.	0	0-2		
setvar no, x	Assign variable.			0	
addvar no, x	Add variable.			0	
subvar no, x	Subtract variable.			0	
mulvar no, x	Multiple variable.			0	
divvar no, x	Divide variable.			0	
shiftvar no, x	Shift variable.			0	
randvar no, x	Assign random number.			0	
printvar no	Debug Output Variable.			0	
cmp_eq no, x	Comparison (==).			0	
cmp_ge no, x	Comparison (>=).			0	
cmp_gt no, x	Comparison (>).			0	
cmp_le no, x	Comparison (<=).			0	
	•	•	•	•	

Command Name	Description	Specified Value	Range	Variable <sup>vii</sup>	Ref.
cmp_lt no, x	Comparison (<).			0	
cmp_ne no, x	Comparison (!=).			0	

# 7.2 MIDI Control Code Table

**Table 7-2 MIDI Control Code Table** 

Decimal	Hexadecimal	Command	Ref.	Decimal	Hexadecimal	Command	Ref.
0	00h			64	40h		
1	01h	mod_depth	31	65	41h	porta_on / porta_off	28
2	02h			66	42h		
3	03h			67	43h		
4	04h			68	44h		
5	05h	porta_time	28	69	45h		
6	06h	(data entry)	39	70	46h		
7	07h	volume	26	71	47h		
8	08h			72	48h		
9	09h			73	49h		
10	0Ah	pan	26	74	4Ah		
11	0Bh	volume2	26	75	4Bh		
12	0Ch	main_volume	26	76	4Ch		
13	0Dh	transpose	26	77	4Dh		
14	0Eh	prio	27	78	4Eh		
15	0Fh			79	4Fh		
16	10h	setvar 0	39	80	50h		
17	11h	setvar 1	39	81	51h		
18	12h	setvar 2	39	82	52h		
19	13h	setvar 3	39	83	53h		
20	14h	bendrange	26	84	54h	porta	28
21	15h	mod_speed	31	85	55h	attack	30

Decimal	Hexadecimal	Command	Ref.	Decimal	Hexadecimal	Command	Ref.
22	16h	mod_type	31	86	56h	decay	30
23	17h	mod_range	31	87	57h	sustain	30
24	18h			88	58h	release	30
25	19h			89	59h	loop_start	30
26	1Ah	mod_delay	31	90	5Ah	loop end	30
27	1Bh	mod_delay ( x	31	91	5Bh		
28	1Ch	sweep_pitch	29	92	5Ch		
29	1Dh	sweep_pitch ( x 24 )	29	93	5Dh		
30	1Eh			94	5Eh		
31	1Fh			95	5Fh		
32	20h			96	60h		
33	21h			97	61h		
34	22h			98	62h		
35	23h			99	63h		
36	24h			100	64h	(RPN LSB)	39
37	25h			101	65h	(RPN MSB)	39
38	26			102	66h		
39	27h			103	67h		
40	28h			104	68h		
41	29h			105	69h		
42	2Ah			106	6Ah		
43	2Bh			107	6Bh		
44	2Ch			108	6Ch		
45	2Dh			109	6Dh		
46	2Eh			110	6Eh		
47	2Fh			111	6Fh		
48	30h			112	70h		

Decimal	Hexadecimal	Command	Ref.	Decimal	Hexadecimal	Command	Ref.
49	31h			113	71h		
50	32h			114	72h		
51	33h			115	73h		
52	34h			116	74h		
53	35h			117	75h		
54	36h			118	76h		
55	37h			119	77h		
56	38h			120	78h		
57	39h			121	79h		
58	3Ah			122	7Ah		
59	3Bh			123	7Bh		
60	3Ch			124	7Ch		
61	3Dh			125	7Dh		
62	3Eh			126	7Eh		
63	3Fh			127	7Fh		

- For #13 transpose, subtract 64 from the value.
- For #16 19, set values in the local variable 0 3, respectively.
- For #28 and 29 sweep\_pitch, subtract 64 from the value (#29 sweep\_pitch is multiplied by 24 after this).
- For #65 porta\_on / porta\_off, porta\_on when the value is greater than 64 and porta\_off when less than 64.
- #120 127 are channel mode messages and not control changes.

## 7.2.1 RPN Support Chart

**Table 7-3 RPN Support Chart** 

MSB	LSB	Commands	Ref.
00h	00h	bendrange	24
7Fh	7Fh		

# 7.3 Compatibility with SMF Created for MusicPlayer2000

This section lists some differences with SMF created for an AGB sound development tool, MusicPlayer2000 (or MP2000). Note that this list is incomplete.

#### 7.3.1 Track Number

With MP2000, track numbers are assigned in order, starting from the lowest track number. With NITRO-Composer, tracks are numbered using the numbers in the sequence data. Missing numbers are not automatically filled.

#### 7.3.2 Modulation

The modulation value is interpreted differently from MP2000, so adjustments in the value are necessary.

## **7.3.3 Tuning**

MIDI Control Change 24 no longer has the tuning feature.

#### 7.3.4 Simulated Echo

MIDI Control Change 30 and 31 no longer have the simulated echo feature.

# 7.3.5 Priority

The MIDI control code for priority has been changed from 33 to 14.

# 7.3.6 Loops on Individual Tracks

With MP2000, the loop starting point is MIDI control code 30 and the value is 100. The loop ending point is MIDI control code 30, and the value is 101.

With NITRO-Composer, the loop starting point is MIDI control code 89, and the value is 0. The loop ending point is MIDI control code 90 (arbitrary value).

#### 7.3.7 Volume Calculation

The method to calculate volume with NITRO-Composer is slightly different than the method used with MP2000, so volume adjustments may be needed.

### 7.3.8 Tempo When Creating Sound Effects

With MP2000, a tempo of 150 synchronizes perfectly with process base time, whereas with NITRO-Composer a tempo of 240 or 120 synchronizes with process base time.

#### 7.3.9 Quarter Note Resolution

With MP2000, the resolution for quarter notes is 24, whereas with NITRO-Composer it is 48.

All company and product names in this document are the trademarks or registered trademarks of the respective companies.

### © 2004-2009 Nintendo

The contents of this document cannot be duplicated, copied, reprinted, transferred, distributed, or loaned in whole or in part without the prior approval of Nintendo.