Thread synchronization pt. 2





Agenda

Producer-Consumer


Thread synchronization

AutoResetEvent

ManualResetEvent


Queues and BlockingCollection

Tyre Pressure Monitor System





TPMS design



TyrePressureMonitor has many responsibilities:


- Read the pressure using the TyrePressureSensor.
- Determine if the pressure is too low.
- Turn on/off the PressureLowIndicator

Design principle: Single Responsibility

THERE SHOULD NEVER BE MORE THAN ONE REASON FOR A CLASS TO CHANGE




TPMS design




TyrePressureMonitor has many responsibilities:

- Read the pressure using the TyrePressureSensor.
- Determine if the pressure is too low.
- Turn on/off the PressureLowIndicator




Now, reading the pressure is separated out.

Wouldn't it be nice, if the pressure monitor did not have to control when the pressure was read?




Let's put the TyrePressureReader on a separate thread.

How does the TyrePressureMonitor know, when a new reading has taken place?



The Monitor consumes data, which the Reader provides.


Producer - Consumer



The Monitor consumes data, which the Reader provides.

This is a very common design: Producer – Consumer.

Producer - Consumer




The Consumer consumes data, which the Provider provides.

Let's put that data into another object, so the Consumer thread does not have to know the Producer thread.



Producer - Consumer



The Consumer would like to know when new data is available.

The Producer would like to know, if the data has been consumed, so it can provide a new value.

Thread synchronization



AutoResetEvent and ManualResetEvent

Event handles can be used to signal from one thread to another.

AutoResetEvent changes from signaled to unsignaled automatically any time it activates a thread.

ManualResetEvent allows any number of threads to be activated by its signaled state, and will only revert to an unsignaled state when its Reset method is called.

DataContainer

```
class DataContainer
    private int tyrePressure;
    public int GetTyrePressure()
        return tyrePressure;
    public void SetTyrePressure(int value)
        tyrePressure = value;
```

Objects of the DataContainer class is used to pass data from producer to consumer.

Producer

```
class Producer
   private readonly DataContainer dataContainer;
    private readonly AutoResetEvent dataConsumedEvent;
   private readonly AutoResetEvent dataReadyEvent;
    private readonly Random random = new Random();
   public Producer(DataContainer dataContainer,
                    AutoResetEvent dataConsumedEvent,
                    AutoResetEvent dataReadyEvent)
        _dataContainer = dataContainer;
        dataConsumedEvent = dataConsumedEvent;
        dataReadyEvent = dataReadyEvent;
   public void Run()
        while (true)
            dataConsumedEvent.WaitOne();
            int pressure = _random.Next(0, 50);
            dataContainer.SetTyrePressure(pressure);
            dataReadyEvent.Set();
            Thread.Sleep(1000);
```

The Consumer would like to know when new data is available.

The Producer would like to know, if the data has been consumed, so it can provide a new value.

Consumer

```
class Consumer
   private readonly DataContainer dataContainer;
   private readonly AutoResetEvent dataReadyEvent;
    private readonly AutoResetEvent dataConsumedEvent;
   public Consumer(DataContainer dataContainer,
                    AutoResetEvent dataReadyEvent,
                    AutoResetEvent dataConsumedEvent)
        _dataContainer = dataContainer;
        dataReadyEvent = dataReadyEvent;
        dataConsumedEvent = dataConsumedEvent;
   public void Run()
        while (true)
            dataReadyEvent.WaitOne();
            int pressure = _dataContainer.GetTyrePressure();
            System.Console.WriteLine("Tyre pressure: {0}", pressure);
           dataConsumedEvent.Set();
```

The Consumer would like to know when new data is available.


The Producer would like to know, if the data has been consumed, so it can provide a new value.

Producer – Consumer creation

```
class Program
    static void Main(string[] args)
        AutoResetEvent dataConsumedEvent = new AutoResetEvent(true);
        AutoResetEvent dataReadyEvent = new AutoResetEvent(false);
        DataContainer dataContainer = new DataContainer();
        Producer producer = new Producer(dataContainer,
                                         dataConsumedEvent,
                                         dataReadyEvent);
        Consumer consumer = new Consumer(dataContainer,
                                         dataReadyEvent,
                                         dataConsumedEvent);
        Thread producerThread = new Thread(producer.Run);
        Thread consumerThread = new Thread(consumer.Run);
        producerThread.Start();
        consumerThread.Start();
```


The AutoResetEvent can be initialized to be set (true) or not set (false).

The AutoResetEvent objects are injected into the constructor of both the producer and consumer.




Queues and BlockingCollection

Queues



Right now, the producer and consumer runs in lock-step.

Queues



Right now, the producer and consumer runs in lock-step.

To overcome this we can introduce a queue.

.Net System.Collections.Concurrent

Access to the queue must be thread safe.

We can do this with **locks**, but...

.Net has built in thread safe collections:

ConcurrentQueue<T>

ConcurrentStack<T>

ConcurrentBag<T>

And BlockingCollection<T> which implements the Producer-Consumer pattern.



BlockingCollection<T>

A thread-safe collection class that provides the following features:

An implementation of the Producer-Consumer pattern.

Concurrent adding and taking of items from multiple threads.

Optional maximum capacity.

Insertion and removal operations that block when collection is empty or full. Insertion and removal "try" operations that do not block or that block up to a specified period of time.

Encapsulates any collection type that implements <a href="mailto:IProducerConsumerCollection<T>">IProducerConsumerCollection<T>

BlockingCollection<T> - Producer

```
class Producer
    private readonly BlockingCollection<DataContainer> dataQueue;
    private readonly Random random = new Random();
    public Producer(BlockingCollection<DataContainer> dataQueue)
       dataQueue = dataQueue;
    public void Run()
       int cnt = 50;
       while (cnt > 0)
           int pressure = random.Next(0, 50);
           DataContainer reading = new DataContainer();
            reading.SetTyrePressure(pressure);
            _dataQueue.Add(reading);
           Thread.Sleep(10);
            cnt--;
        _dataQueue.CompleteAdding();
```

We'll use a BlockingCollection as the queue.

The BlockingCollection handles all synchronization.

Calling CompleteAdding() signals to the receiver, that it shall expect no more data.



BlockingCollection<T> - Consumer

```
class Consumer
    private readonly BlockingCollection<DataContainer> dataQueue;
    public Consumer(BlockingCollection<DataContainer> dataQueue)
        _dataQueue = dataQueue;
    public void Run()
        while (!_dataQueue.IsCompleted)
            try
                var container = dataQueue.Take();
                int pressure = container.GetTyrePressure();
                System.Console.WriteLine("Tyre pressure: {0}", pressure);
            catch (InvalidOperationException)
                // IOE means that Take() was called on a completed collection.
            Thread.Sleep(10);
        System.Console.WriteLine("No more data expected");
```

The consumer takes data from the queue, until IsCompleted is set to true (by CompleteAdding() by the producer).

Remember try-catch around the Take() invocation. The queue might be marked as completed.

BlockingCollection<T> - Creation

```
static void Main(string[] args)
    BlockingCollection<DataContainer> dataQueue = new
                         BlockingCollection<DataContainer>();
    Producer producer = new Producer(dataQueue);
    Consumer consumer = new Consumer(dataQueue);
    Thread producerThread = new Thread(producer.Run);
    Thread consumerThread = new Thread(consumer.Run);
    producerThread.Start();
    consumerThread.Start();
    Console.ReadKey();
```

BlockingCollection – Add/Take with timeouts

```
public bool TryAdd (T item, int millisecondsTimeout);
```

```
public bool TryTake (out T item, TimeSpan timeout);
```

If you have something else for the thread to do, you can use timeouts on the Add and Take method.

See code examples on:

https://docs.microsoft.com/en-us/dotnet/standard/collections/thread-safe/how-to-add-and-take-items

Your turn Solve exercises 1, 2, 3 and 4 (and 5, 6 and 7 if you like or continue with the exercise from last week)

References and image sources

Images:

Printer: https://i5.walmartimages.com/asr/5bf8c70c-c0f4-46c8-8de2-d14417c3dcdb_2.a974142a063bb1f235f672f9a68eeb10.jpeg

TPMS: http://www.rematiptop.com/tpms/img/TPMS-warning-light.jpg

Computer keyboard: http://stockmedia.cc/computing_technology/slides/DSD_8790.jpg

Bonus: http://wjreviews.com/reviews-cta/bonus.png

