
# **PP-Module for Client Virtualization Systems**



**National Information Assurance Partnership** 

## **Revision History**

Version	Date	Comment	
1.0	2016-11-17	Initial Publication	
1.1	2020-11-17	Converted to PP-Module and applied all active TDs	

## **Contents**

1 Introduction
1.1 Overview
1.2 Terms
1.2.1 Common Criteria Terms
1.2.2 Technical Terms
1.3 Compliant Targets of Evaluation
1.3.1 TOE Boundary
1.4 Use Cases
2 Conformance Claims
3 Security Problem Description
2.1 Threate
<ul><li>3.1 Threats</li><li>3.2 Assumptions</li><li>3.3 Organizational Security Policies</li></ul>
3.2 Organizational Cognity Policies
4. Convity Objectives
4 Security Objectives
4.1 Security Objectives for the TOE
4.2 Security Objectives for the Operational Environment
4.3 Security Objectives Rationale
5 Security Requirements
5.1 PP Security Functional Requirements Direction
5.1.1 Modified SFRs
5.2 TOE Security Functional Requirements
<ul><li>5.2.1 Auditable Events for Mandatory SFRs</li><li>5.2.2 Security Management (FMT)</li></ul>
5.3 TOE Security Functional Requirements Rationale
6 Consistency Rationale
6.1 Protection Profile for
<ul> <li>6.1.1 Consistency of TOE Type</li> <li>6.1.2 Consistency of Security Problem Definition</li> <li>6.1.3 Consistency of Objectives</li> </ul>
6.1.2 Consistency of Security Problem Definition
6.1.3 Consistency of Objectives
6.1.4 Consistency of Requirements
Appendix A - Optional SFRs
A.1 Strictly Optional Requirements A.2 Objective Requirements A.3 Implementation-based Requirements
A.2 Objective Requirements
A.3 Implementation-based Requirements
Appendix B - Selection-based Requirements
Appendix C - Extended Component Definitions
C.1 Extended Components Table
<ul><li>C.1 Extended Components Table</li><li>C.2 Extended Component Definitions</li></ul>
Appendix D - Entropy
Appendix E - Acronyms
Appendix F - Bibliography

## 1 Introduction

### 1.1 Overview

The scope of this PP-Module is to define the security functionality of a Client Virtualization product in terms of [CC] and to define functional and assurance requirements for such products. This PP-Module is not complete in itself, but rather is intended for use with the following base PP:

• Protection Profile for Virtualization, Version 1.1.

This base PP is valid because Client Virtualization is a specific type of Virtualization System and is expected to implement security functionality that is not common to all Virtualization Systems. One additional SFR has been defined in this PP-Module to define security functionality that is unique to this particular type of Virtualization System.

## 1.2 Terms

The following sections list Common Criteria and technology terms used in this document.

### 1.2.1 Common Criteria Terms

Assurance	Grounds for confidence that a TOE meets the SFRs [CC].
Base Protection Profile (Base- PP)	Protection Profile used as a basis to build a PP-Configuration.
Common Criteria (CC)	Common Criteria for Information Technology Security Evaluation (International Standard ISO/IEC 15408).
Common Criteria Testing Laboratory	Within the context of the Common Criteria Evaluation and Validation Scheme (CCEVS), an IT security evaluation facility, accredited by the National Voluntary Laboratory Accreditation Program (NVLAP) and approved by the NIAP Validation Body to conduct Common Criteria-based evaluations.
Common Evaluation Methodology (CEM)	Common Evaluation Methodology for Information Technology Security Evaluation.
Distributed TOE	A TOE composed of multiple components operating as a logical whole.
Operational Environment (OE)	Hardware and software that are outside the TOE boundary that support the TOE functionality and security policy.
Protection Profile (PP)	An implementation-independent set of security requirements for a category of products.
Protection Profile Configuration (PP- Configuration)	A comprehensive set of security requirements for a product type that consists of at least one Base-PP and at least one PP-Module.
Protection Profile Module (PP-Module)	An implementation-independent statement of security needs for a TOE type complementary to one or more Base Protection Profiles.
Security Assurance Requirement (SAR)	A requirement to assure the security of the TOE.
Security Functional Requirement (SFR)	A requirement for security enforcement by the TOE.
Security Target (ST)	A set of implementation-dependent security requirements for a specific product.
TOE Security Functionality (TSF)	The security functionality of the product under evaluation.
TOE Summary Specification (TSS)	A description of how a TOE satisfies the SFRs in an ST.
Target of Evaluation (TOE)	The product under evaluation.

## 1.2.2 Technical Terms

Administrator Administrators perform management activities on the VS. These management functions do not include administration of software running within Guest VMs, such as the Guest OS.

Administrators need not be human as in the case of embedded or headless VMs.

Administrators are often nothing more than software entities that operate within the VM.

Domain	A Domain or Information Domain is a policy construct that groups together execution environments and networks by sensitivity of information and access control policy. For example, classification levels represent information domains. Within classification levels, there might be other domains representing communities of interest or coalitions. In the context of a VS, information domains are generally implemented as collections of VMs connected by virtual networks. The VS itself can be considered an Information Domain, as can its Management Subsystem.
Guest Operating System (OS)	An operating system that runs within a Guest VM.
Guest VM	A Guest VM is a VM that contains a virtual environment for the execution of an independent computing system. Virtual environments execute mission workloads and implement customer-specific client or server functionality in Guest VMs, such as a web server or desktop productivity applications.
Host Operating System (OS)	An operating system onto which a VS is installed. Relative to the VS, the Host OS is part of the Platform.
Hypercall	An API function that allows VM-aware software running within a VM to invoke VMM functionality.
Hypervisor	The Hypervisor is part of the VMM. It is the software executive of the physical platform of a VS. A Hypervisor's primary function is to mediate access to all CPU and memory resources, but it is also responsible for either the direct management or the delegation of the management of all other hardware devices on the hardware platform.
Management Subsystem	Components of the VS that allow VS Administrators to configure and manage the VMM, as well as configure Guest VMs. VMM management functions include VM configuration, virtualized network configuration, and allocation of physical resources.
Platform	The hardware, firmware, and software environment into which a VS is installed and executes.
User	Users operate Guest VMs and are subject to configuration policies applied to the VS by Administrators. Users need not be human as in the case of embedded or headless VMs, users are often nothing more than software entities that operate within the VM.
Virtual Machine (VM)	A Virtual Machine is a virtualized hardware environment in which an operating system may execute.
Virtual Machine Manager (VMM)	A VMM is a collection of software components responsible for enabling VMs to function as expected by the software executing within them. Generally, the VMM consists of a Hypervisor, Service VMs, and other components of the VS, such as virtual devices, binary translation systems, and physical device drivers. It manages concurrent execution of all VMs and virtualizes platform resources as needed.
Virtualization System (VS)	A software product that enables multiple independent computing systems to execute on the same physical hardware platform without interference from one other. For the purposes of this document, the VS consists of a Virtual Machine Manager (VMM), Virtual Machine abstractions, a management subsystem, and other components.

## 1.3 Compliant Targets of Evaluation

Client Virtualization, for the purposes of this PP-Module, refers to a Virtualization System that implements virtualized hardware components locally on an endpoint machine. Endpoints are typically client hardware such as desktop or laptop computers that a user interacts with directly, but may also include headless embedded systems without direct human interaction. A Virtualization System creates a virtualized hardware environment for each instance of a guest operating system (a virtual machine) permitting these environments to execute concurrently while maintaining isolation and the appearance of exclusive control over assigned computing resources. Client virtualization is generally used on endpoint systems, making use of the local machine's resources (memory, CPU, etc.) to provide isolated user environments.

This document does not address virtualization on mobile devices (typically devices that use a baseband processor or connect to a cellular network), nor does it address application virtualization or containers.

### 1.3.1 TOE Boundary

The TOE boundary is the same as that which is defined for a Virtualization System in general. Refer to the base Virtualization PP for an outline of the TOE boundary.

### 1.4 Use Cases

Requirements in this PP-Module are designed to address the security problem in the following use cases. The

description of these use cases provides examples for how the TOE and its Operational Environment could support the functionality required by this PP-Module.

## [USE CASE 1] Locally Managed Client

A local administrator creates and runs one or more VMs locally. This client could be stand-alone or connected to a network.

## [USE CASE 2] Enterprise Managed Client

An enterprise administrator for the VS centrally manages one or more client hypervisors, creating and configuring VMs which are then pushed to the clients. These VMs are then available for users on that client to run using the computing resources of that client. (Note that this is not Virtual Desktop Infrastructure where the hypervisors and the VMs run on remote servers. While both can be centrally managed and accessed from clients, for client virtualization, the VMs are local to the endpoint machine.)

## [USE CASE 3] Headless Client

A VM is used by a program without direct human interaction.

### 2 Conformance Claims

### **Conformance Statement**

This PP-Module inherits exact conformance as required from the Virtualization PP and as defined in the CC and CEM addenda for Exact Conformance, Selection-Based SFRs, and Optional SFRs (dated May 2017).

There are no other PP-Modules that are allowed to be specified in a PP-Configuration with this PP-Module.

### **CC Conformance Claims**

This PP Module is conformant to Parts 2 (extended) and 3 (conformant) of Common Criteria Version 3.1, Release 5 [CC].

## **3 Security Problem Description**

The security problem is described in terms of the threats that the TOE is expected to address, assumptions about its operational environment, and any organizational security policies that the TOE is expected to enforce.

### 3.1 Threats

This PP-Module defines no additional threats beyond those defined in the base Virtualization PP. Note however that the SFRs defined in this PP-Module will assist in the mitigation of the following threats defined in the base PP:

### T.UNAUTHORIZED UPDATE

See Virtualization PP, Section 3.1.

### T.UNAUTHORIZED ACCESS

See Virtualization PP, Section 3.1.

### 3.2 Assumptions

This document does not define any additional assumptions.

### 3.3 Organizational Security Policies

An organization deploying the TOE is expected to satisfy the organizational security policy listed below in addition to all organizational security policies defined by the claimed base PP.

This document does not define any additional OSPs.

## **4 Security Objectives**

### 4.1 Security Objectives for the TOE

This PP-Module defines no additional TOE security objectives beyond those defined in the base Virtualization PP. Note however that the SFR defined in this PP-Module will assist in the achievement of the following objectives defined in the base PP:

### O.VMM\_INTEGRITY

See Virtualization PP, Section 4.1.

### **O.MANAGEMENT ACCESS**

See Virtualization PP, Section 4.1.

### 4.2 Security Objectives for the Operational Environment

This PP-Module does not define any objectives for the Operational Environment. Because this Module does

 $not \ define \ any \ additional \ assumptions \ or \ organizational \ security \ policies, \ there \ are \ no \ additional \ security \ objectives \ for \ the \ Operational \ Environment \ to \ satisfy.$ 

## 4.3 Security Objectives Rationale

This section describes how the assumptions, threats, and organization security policies map to the security objectives.

Threat, Assumption, or OSP	Security Objectives	Rationale
T.UNAUTHORIZED_UPDATE	O.VMM_INTEGRITY	Integrity of a Virtualization System can be maintained by ensuring that the only way to modify the VS is through a trusted update process initiated by an authorized Administrator as required by FMT_MOF_EXT.
T.UNAUTHORIZED_ACCESS	O.MANAGEMENT_ACCESS	Access to management functions must be limited to authorized Administrators as managed through controls required by FMT_MOF_EXT.1.

## **5 Security Requirements**

This chapter describes the security requirements which have to be fulfilled by the product under evaluation. Those requirements comprise functional components from Part 2 and assurance components from Part 3 of [CC]. The following conventions are used for the completion of operations:

- **Refinement** operation (denoted by **bold text** or <del>strikethrough text</del>): is used to add details to a requirement (including replacing an assignment with a more restrictive selection) or to remove part of the requirement that is made irrelevant through the completion of another operation, and thus further restricts a requirement.
- **Selection** (denoted by *italicized text*): is used to select one or more options provided by the [CC] in stating a requirement.
- **Assignment** operation (denoted by *italicized text*): is used to assign a specific value to an unspecified parameter, such as the length of a password. Showing the value in square brackets indicates assignment.
- **Iteration** operation: is indicated by appending the SFR name with a slash and unique identifier suggesting the purpose of the operation, e.g. "/EXAMPLE1."

## 5.1 PP Security Functional Requirements Direction

In a PP-Configuration that includes the Virtualization PP, the TOE is expected to rely on some of the security functions implemented by the Virtualization System as a whole and evaluated against the Base-PP. This section describes any modifications that the ST author must make to Base-PP SFRs to satisfy the required VS functionality.

### 5.1.1 Modified SFRs

This PP-Module does not modify any SFRs defined by the PP.

## **5.2 TOE Security Functional Requirements**

The following section describes the SFRs that must be satisfied by any TOE that claims conformance to this PP-Module. These SFRs must be claimed regardless of which PP-Configuration is used to define the TOE.

### 5.2.1 Auditable Events for Mandatory SFRs

**Table 2: Auditable Events for Mandatory Requirements** 

Requirement	Auditable Events	Additional Audit Record Contents
FMT_MOF_EXT.1	Attempts to invoke any of the management functions listed in Table $\boldsymbol{3}$	Success or failure of attempt Identity of actor

### 5.2.2 Security Management (FMT)

### FMT\_MOF\_EXT.1 Management of Security Functions Behavior

FMT\_MOF\_EXT.1.1

The TSF shall be capable of supporting [**selection**: *local*, *remote*] administration.

**Application Note:** Selection of "remote" requires the selection-based requirement FTP\_TRP.1 defined in the base PP to be included in the ST.

FMT\_MOF\_EXT.1.2

The TSF shall be capable of performing the following management functions, controlled by an Administrator or User as shown in Table 3, based on the following key:

### **Table 3: Client Virtualization Management Functions**

X = Mandatory (TOE must provide that function to that role)

O = Optional (TOE may or may not provide that function to that role)

N = Not Permitted (TOE must not provide that function to that role)

S = Selection-Based (TOE must provide that function to that role if the TOE claims a particular selection-based SFR)

See also, the Functional Packages for Transport Layer	Number	Function	Administrator	User	references are from the base Virtualization PP
and instrator password policy as defined in FIA_PMG_EXT.1. Not applicable.]  3 Ability to create, configure and delete VMs  4 Ability to set default initial VM configurations  5 Ability to configure virtual networks including VM  6 Ability to configure X N  6 Ability to configure X N  6 Ability to configure X N  7 Ability to configure VM access to physical devices  8 Ability to configure inter-VM data sharing  9 Ability to configure X N  9 Ability to configure inter-VM data sharing  10 Ability to configure removable media policy  11 Ability to configure the cryptographic functionally packages for Transport Layer Security (TLS) and FCS_CVM.2, and FCS_CVM.3, and FCS_CVM.4, a	1		X	N	
configure and delete VMs  Ability to set default initial VM configure virtual networks including VM  Ability to configure and manage the audit system and audit data virtual networks including VM  Ability to configure and manage the audit system and audit data virtual networks including VM  Ability to configure VM access to physical devices  Ability to configure vM access to physical devices  Ability to configure inter-VM data sharing virtual networks included virtual networks inter-VM data sharing virtual networks including virtual ne	2	configure Administrator password policy as defined in FIA_PMG_EXT.1, Not	S	N	if ST includes
initial VM configurations  Ability to configure and manage the audit system and audit data  Ability to configure and manage the audit system and audit data  Ability to configure VM access to physical devices  Ability to configure Inter-VM data sharing  Ability to configure inter-VM data sharing  Ability to configure conductors and provided inter-VM data sharing  Ability to configure to enable/disable VM access to Hypercall functions  Ability to configure Typercall Typercall functions  Ability to configure Typercall functionality  Ability to change default authorization factors  Ability to change feed authorization factors  Ability to configure Screen fock inactivity	3	configure and delete	X	0	
virtual networks including VM  6 Ability to configure and manage the audit system and audit data  7 Ability to configure VM access to physical devices  8 Ability to configure inter-VM data sharing  9 Ability to enable/disable VM access to Hypercall functions  10 Ability to configure removable media policy functionality  11 Ability to configure the cryptographic functionality  12 Ability to change default authorization factors  13 Ability to enable/disable screen lock inactivity  14 Ability to configure o O O O O O O O O O O O O O O O O O O	4	initial VM	X	О	
and manage the audit system and audit data  7	5	virtual networks	X	0	
VM access to physical devices  8	6	and manage the audit	X	N	
inter-VM data sharing  FDP_VMS_EXT.1 and FMT_MSA_EXT.1  9	7	VM access to physical	X	0	
enable/disable VM access to Hypercall functions  10 Ability to configure removable media policy  11 Ability to configure the cryptographic functionality  12 Ability to change default authorization factors  13 Ability to enable/disable screen lock  14 Ability to configure screen lock inactivity  15 See FPT_RDM_EXT.1  16 See FPT_RDM_EXT.1  17 See FPT_RDM_EXT.1  18 See FPT_RDM_EXT.1  18 See FPT_RDM_EXT.1  19 See FPT_RDM_EXT.1  10 See FPT_RDM_EXT.1  10 See FPT_RDM_EXT.1  11 See FIA_PAG_EXT.1  12 Ability to change default authorization factors  13 Ability to enable/disable screen lock  14 Ability to configure screen lock inactivity	8		X	0	FDP_VMS_EXT.1 and
removable media policy  11 Ability to configure the cryptographic functionality  12 Ability to change default authorization factors  13 Ability to configure Socuent lock  14 Ability to configure Socuent lock  Tremovable media policy  O See FCS_CKM.1, FCS_CKM.2, and FCS_COP.1/HASH. See also, the Functional Packages for Transport Layer Security (TLS) and for Secure Shell (SSH) if claimed for methods to configure their respective cryptographic functionality.  N See FIA_PMG_EXT.1	9	enable/disable VM access to Hypercall	0	0	function 9 is no
the cryptographic functionality  FCS_CKM.2, and FCS_COP.1/HASH. See also, the Functional Packages for Transport Layer Security (TLS) and for Secure Shell (SSH) if claimed for methods to configure their respective cryptographic functionality.  Ability to change default authorization factors  Ability to enable/disable screen lock  Ability to configure O O O O O O Screen lock inactivity	10	removable media	X	О	
default authorization factors  FIA_PMG_EXT.1  Ability to enable/disable screen lock  Ability to configure O O Screen lock inactivity  FIA_PMG_EXT.1	11	the cryptographic	O	O	FCS_CKM.2, and FCS_COP.1/HASH. See also, the Functional Packages for Transport Layer Security (TLS) and for Secure Shell (SSH) if claimed for methods to configure their respective cryptographic
enable/disable screen lock  Ability to configure O O Screen lock inactivity	12	default authorization	X	N	
screen lock inactivity	13	enable/disable screen	0	0	
	14	screen lock inactivity	0	О	

15	Ability to configure remote connection inactivity timeout	X	N	
16	Ability to configure lockout policy for unsuccessful authentication attempts through [selection: timeouts between attempts, limiting number of attempts during a time period]	X	N	See FIA_AFL_EXT.1
17	[selection: Ability to configure name/address of directory server to bind with, Not applicable]	S	O	Must be selected if "directory-based" is selected anywhere in FIA_UAU.5.1 in the base Virtualization PP.
18	Ability to configure name/address of audit/logging server to which to send audit/logging records	X	N	See FAU_STG_EXT.1.
19	Ability to configure name/address of network time server	X	0	
20	Ability to configure banner	X	N	See FTA_TAB.1
21	Ability to connect/disconnect removable devices to/from a VM	0	0	See FPT_RDM_EXT.1
22	Ability to start a VM	О	О	
23	Ability to stop/halt a VM	O	О	
24	Ability to checkpoint a VM	O	О	
25	Ability to suspend a VM	0	О	
26	Ability to resume a VM	О	O	
27	[selection: Ability to configure action taken if unable to determine the validity of a certificate, Not applicable]	S	N	This function must be selected if "allow the administrator to choose whether to accept the certificate in these cases" in FIA_X509_EXT.2.2 in the base PP.

**Application Note:** The ST author is expected to update Table 3 with an indication as to whether any of the 'optional' or 'selection-based' functions are included as part of the TOE. The ST author may also omit the 'Notes' column as it is provided in this PP-Module as an aid to the ST author in constructing the table.

This SFR addresses the roles of the CC Part 2 SFRs FMT\_MOF.1, FMT\_SMF.1, and FMT\_SMR.2.

Administration is considered "local" if the Administrator is physically present at the machine on which the VS is installed.

Administration is considered "remote" if communications between the Administrator and the Management Subsystem travel on a network.

There is no requirement to authenticate Users of the Virtualization System. Users that have access to VMs but not to the Management Subsystem need not authenticate to the Virtualization System in order to use Guest VMs. Requirements for authentication of VM users is determined by the policies of the domains running within the Guest VMs.

For a VS where the OS is part of the platform and not part of the TOE, it is acceptable for the VS to invoke the Host OS screen lock.

## **Evaluation Activities**



### FMT MOF EXT.1:

#### **TSS**

The evaluator shall examine the TSS and Operational Guidance to ensure that it describes which security management functions require Administrator privilege and the actions associated with each management function. The evaluator shall verify that for each management function and role specified in Table 3, the defined role is able to perform all mandatory functions as well as all optional or selection-based functions claimed in the ST.

#### Guidance

The evaluator shall examine the Operational Guidance to ensure that it describes how the Administrator and/or User are able to perform each management function that the ST claims the TOE supports.

The evaluator shall verify for each claimed management function that the Operational Guidance is sufficiently detailed to allow the function to be performed and that the function can be performed.

#### Tosts

The evaluator shall test each management function for each role listed in the FMT MOF EXT.1.1 Table 3 in the ST to demonstrate that the function can be performed by the role(s) that are authorized to do so and the result of the function is demonstrated. The evaluator shall also verify for each claimed management function in Table 3, that if the TOE claims not to provide a particular role with access to the function, then it is not possible to access the TOE as that role and perform that function.

## 5.3 TOE Security Functional Requirements Rationale

The following rationale provides justification for each security objective for the TOE, showing that the SFRs are suitable to meet and achieve the security objectives:

Table 4: SFR Rationale

OBJECTIVE	ADDRESSED BY	RATIONALE
O.VMM_INTEGRITY	FMT_MOF_EXT.1	Integrity of a Virtualization System can be maintained by ensuring that the only way to modify the VS is through a trusted update process initiated by an authorized Administrator as required by FMT_MOF_EXT.1.
O.MANAGEMENT_ACCESS	FMT_MOF_EXT.1	Access to management functions must be limited to authorized Administrators as managed through controls required by FMT_MOF_EXT.1.

## **6 Consistency Rationale**

### 6.1 Protection Profile for

### 6.1.1 Consistency of TOE Type

When this PP-Module is used to extend the Virtualization PP, the TOE type for the overall TOE is still a Virtualization System. The TOE boundary does not change.

## 6.1.2 Consistency of Security Problem Definition

### PP-Module Threat, **Assumption, OSP**

### **Consistency Rationale**

<u>-</u>	
T.UNAUTHORIZED_UPDATE	This threat applies to functionality that is described in the base PP, but is managed through functionality described in this PP-module.
T.UNAUTHORIZED_ACCESS	This threat applies to functionality that is described in the base PP, but is managed through functionality described in this PP-module.

## 6.1.3 Consistency of Objectives

The objectives for the TOEs are consistent with the PP based on the following rationale:

PP-Module TOE Objective	Consistency Rationale
O.VMM_INTEGRITY	This objective comes directly from the PP.
O.MANAGEMENT ACCESS	This objective comes directly from the PP.

### 6.1.4 Consistency of Requirements

This PP-Module identifies several SFRs from the PP that are needed to support Client Virtualization Systems functionality. This is considered to be consistent because the functionality provided by the PP is being used for its intended purpose. The rationale for why this does not conflict with the claims defined by the PP are as follows:

## **PP-Module** Requirement

### **Consistency Rationale**

### **Modified SFRs**

This PP-Module does not modify any requirements when the PP is the base.

### **Mandatory SFRs**

FMT MOF EXT.1 This SFR requires the Client Virtualization product to manage security functionality defined in the Virtualization PP in FPT TUD EXT.1, FIA PMG EXT.1, FDP VNC EXT.1, FDP PPR EXT.1, FDP VMS EXT.1, FMT MSA EXT.1, FPT RDM EXT.1, FCS CKM.1, FCS CKM.2, FCS COP.1/HASH, FIA AFL EXT.1, FAU STG EXT.1, FIA X509 EXT.2.2, and FTA TAB.1.

### **Optional SFRs**

This PP-Module does not define any Optional requirements.

### **Selection-based SFRs**

This PP-Module does not define any Selection-based requirements.

### **Objective SFRs**

This PP-Module does not define any Objective requirements.

### **Implementation-Dependent SFRs**

This PP-Module does not define any Implementation-Dependent requirements.

# **Appendix A - Optional SFRs**

## **A.1 Strictly Optional Requirements**

This PP-Module does not define any Strictly Optional SFRs.

## **A.2 Objective Requirements**

This PP-Module does not define any Objective SFRs.

## **A.3 Implementation-based Requirements**

This PP-Module does not define any Implementation-based SFRs.

# **Appendix B - Selection-based Requirements**

This PP-Module does not define any Selection-based SFRs.

## **Appendix C - Extended Component Definitions**

This appendix contains the definitions for all extended requirements specified in the PP-Module.

## **C.1 Extended Components Table**

All extended components specified in the PP are listed in this table:

### **Table 5: Extended Component Definitions**

**Functional Class** 

**Functional Components** 

Security Management (FMT) FMT\_MOF\_EXT Management of Security Functions Behavior

## **C.2 Extended Component Definitions**

## FMT\_MOF\_EXT Management of Security Functions Behavior

This family is defined in the Virtualization PP. This Module augments the extended family by adding one additional component, FMT MOF EXT.1.

## **Component Leveling**

FMT\_MOF\_EXT.1, Management of Security Functions Behavior, defines required management functions and responsibilities.

### Management: FMT\_MOF\_EXT.1

There are no additional management functions beyond those already described in FMT MOF EXT.1.

## **Audit: FMT MOF EXT.1**

There are no auditable events defined for this SFR.

## FMT\_MOF\_EXT.1 Management of Security Functions Behavior

Hierarchical to: No other components.

Dependencies to: No other dependencies.

## FMT\_MOF\_EXT.1.1

The TSF shall be capable of supporting [assignment: a type of administration] administration.

### **FMT MOF EXT.1.2**

The TSF shall be capable of performing the following management functions [assignment: description of management functions].

## **Appendix D - Entropy**

The TOE does not require any additional supplementary information to describe its entropy source(s) beyond the requirements outlined in the 'Entropy Documentation and Assessment' section of the Base Virtualization PP. As with other base PP requirements, the only additional requirement is that the entropy documentation also applies to the specific Client Virtualization capabilities of the TOE in addition to the functionality required by the base PP.

# **Appendix E - Acronyms**

Acronym	Meaning
Base-PP	Base Protection Profile
CC	Common Criteria
CEM	Common Evaluation Methodology
OE	Operational Environment
OS	Operating System
PP	Protection Profile
PP-Configuration	Protection Profile Configuration
PP-Module	Protection Profile Module
SAR	Security Assurance Requirement
SFR	Security Functional Requirement
ST	Security Target
TOE	Target of Evaluation
TSF	TOE Security Functionality
TSFI	TSF Interface
TSS	TOE Summary Specification
VM	Virtual Machine
VMM	Virtual Machine Manager
VS	Virtualization System

# **Appendix F - Bibliography**

## **Identifier Title**

[CC]

Common Criteria for Information Technology Security Evaluation -

- Part 1: Introduction and General Model, CCMB-2017-04-001, Version 3.1 Revision 5, April 2017
- Part 2: Security Functional Components, CCMB-2017-04-002, Version 3.1 Revision 5, April 2017.
- Part 3: Security Assurance Components, CCMB-2017-04-003, Version 3.1 Revision 5, April 2017.

[VirtPP]

Protection Profile for Virtualization, Version: 1.1, 2020-11-17