Introduction to Portfolio Theory

Yuming Liu and Eric Zivot

4/12/2021

Consider investing in two risky assets (Amazon and Boeing)

 $R_A = \text{ simple return on asset A}$

 $R_B = \text{ simple return on asset B}$

 $W_0 = \text{ initial wealth}$

Assumptions

 \bullet R_A and R_B are described by the GWN model

$$R_i \sim \text{iid } N(\mu_i, \sigma_i^2), i = A, B$$

 $\text{cov}(R_A, R_B) = \sigma_{AB}, \text{cor}(R_A, R_B) = \rho_{AB}$

- Traditionally in portfolio theory, returns are simple and not continuously compounded because the simple return on a portfolio is a share weighted average of the individual asset returns
- Assume that GWN model for continuously compounded returns can also be used for simple returns

Investor Preferences:

- Investors like high $E[R_i] = \mu_i$
- Investors dislike high $var(R_i) = \sigma_i^2$
- Investment horizon is one period (e.g., one month or one year)

Portfolios

$$x_A = \text{share of wealth in asset A} = \frac{\$ \text{ in A}}{W_0}$$

 $x_B = \text{share of wealth in asset B} = \frac{\$ \text{ in B}}{W_0}$

Long position

$$x_A, x_B > 0$$

Short position

$$x_A < 0 \text{ or } x_B < 0$$

Allocate all wealth between assets A and B

$$x_A + x_B = 1$$

Portfolio Return

$$R_p = x_A R_A + x_B R_B$$

Portfolio Distribution

$$\mu_{p} = E[R_{p}] = x_{A}\mu_{A} + x_{B}\mu_{B}$$

$$\sigma_{p}^{2} = var(R_{p}) = x_{A}^{2}\sigma_{A}^{2} + x_{B}^{2}\sigma_{B}^{2} + 2x_{A}x_{B}\sigma_{AB}$$

$$= x_{A}^{2}\sigma_{A}^{2} + x_{B}^{2}\sigma_{B}^{2} + 2x_{A}x_{B}\rho_{AB}\sigma_{A}\sigma_{B}$$

$$R_{p} \sim iid N(\mu_{p}, \sigma_{p}^{2})$$

End of Period Wealth

$$W_1 = W_0(1 + R_p) = W_0(1 + x_A R_A + x_B R_B)$$

 $W_1 \sim N(W_0(1 + \mu_p), \sigma_p^2 W_0^2)$

Result: Portfolio SD is not a weighted average of asset SD unless $\rho_{AB}=1$:

$$\sigma_p = \left(x_A^2 \sigma_A^2 + x_B^2 \sigma_B^2 + 2x_A x_B \rho_{AB} \sigma_A \sigma_B\right)^{1/2}$$

$$\neq x_A \sigma_A + x_B \sigma_B \text{ for } \rho_{AB} \neq 1$$

If $\rho_{AB} = 1$ then

$$\sigma_{AB} = \rho_{AB}\sigma_{A}\sigma_{B} = \sigma_{A}\sigma_{B}$$

and

$$\sigma_p^2 = x_A^2 \sigma_A^2 + x_B^2 \sigma_B^2 + 2x_A x_B \sigma_A \sigma_B$$
$$= (x_A \sigma_A + x_B \sigma_B)^2$$
$$\Rightarrow \sigma_B = x_A \sigma_A + x_B \sigma_B$$

Example Data (calibrated for annual investment horizon and to create nice graphs)

$$\mu_A = 0.175, \ \mu_B = 0.055$$
 $\sigma_A^2 = 0.067, \ \sigma_B^2 = 0.013$
 $\sigma_A = 0.258, \ \sigma_B = 0.115$
 $\sigma_{AB} = -0.004875,$
 $\rho_{AB} = \frac{\sigma_{AB}}{\sigma_A \sigma_B} = -0.164$

Note: Asset A has higher expected return and risk than asset B

```
mu.A = 0.175

sig.A = 0.258

sig2.A = sig.A^2

mu.B = 0.055

sig.B = 0.115

sig2.B = sig.B^2

rho.AB = -0.164

sig.AB = rho.AB*sig.A*sig.B
```

Example: Long only two asset portfolio

Consider an equally weighted portfolio with $x_A = x_B = 0.5$. The expected return, variance and volatility are

$$\mu_p = (0.5) \cdot (0.175) + (0.5) \cdot (0.055) = 0.115$$

$$\sigma_p^2 = (0.5)^2 \cdot (0.067) + (0.5)^2 \cdot (0.013)$$

$$+ 2 \cdot (0.5)(0.5)(-0.004875) = 0.01751$$

$$\sigma_p = \sqrt{0.01751} = 0.1323$$

This portfolio has expected return half-way between the expected returns on assets A and B, but the portfolio standard deviation is less than half-way between the asset standard deviations. This reflects risk reduction via diversification.

Long-Only Portfolio

```
x.A.p1 = 0.5
x.B.p1 = 0.5
mu.p1 = x.A.p1*mu.A + x.B.p1*mu.B
sig2.p1 = x.A.p1^2 * sig2.A + x.B.p1^2 * sig2.B +
    2*x.A.p1*x.B.p1*sig.AB
sig.p1 = sqrt(sig2.p1)
```

```
## Expected Return Std Dev Variance

## Asset A 0.1750 0.2580 0.0666

## Asset B 0.0550 0.1150 0.0132

## Long-Only Portfolio 0.1150 0.1323 0.0175
```

Example: Long-Short two asset portfolio

Next, consider a long-short portfolio with $x_A=1.5$ and $x_B=-0.5$. In this portfolio, asset B is sold short and the proceeds of the short sale are used to leverage the investment in asset A. The portfolio characteristics are

$$\mu_p = (1.5) \cdot (0.175) + (-0.5) \cdot (0.055) = 0.235$$

$$\sigma_p^2 = (1.5)^2 \cdot (0.067) + (-0.5)^2 \cdot (0.013)$$

$$+ 2 \cdot (1.5)(-0.5)(-0.004875) = 0.1604$$

$$\sigma_p = \sqrt{0.01751} = 0.4005$$

This portfolio has both a higher expected return and standard deviation than asset A

Long-Short two asset portfolio

```
x.A.p2 = 1.5
x.B.p2 = -0.5
mu.p2 = x.A.p2*mu.A + x.B.p2*mu.B
sig2.p2 = x.A.p2^2 * sig2.A + x.B.p2^2 * sig2.B +
    2*x.A.p2*x.B.p2*sig.AB
sig.p2 = sqrt(sig2.p2)
```

```
## Expected Return Std Dev Variance

## Asset A 0.1750 0.2580 0.0666

## Asset B 0.0550 0.1150 0.0132

## Long-Short Portfolio 0.2350 0.4005 0.1604
```

Portfolio Value-at-Risk

- Given an initial investment of W_0 in the portfolio of assets A and B.
- Given that the simple return $R_p \sim N(\mu_p, \sigma_p^2)$. For $\alpha \in (0, 1)$, the $\alpha \times 100\%$ portfolio value-at-risk is

$$\begin{aligned} \operatorname{VaR}_{p,\alpha} &= q_{p,\alpha}^R W_0 \\ &= \left(\mu_p + \sigma_p q_\alpha^z \right) W_0 \end{aligned}$$

where $q_{p,\alpha}^R$ is the α quantile of the distribution of R_p and $q_{\alpha}^z=\alpha$ quantile of $Z\sim N(0,1)$.

Relationship between Portfolio VaR and Individual Asset VaR

Result: Portfolio VaR is not a weighted average of asset VaR:

$$VaR_{p,\alpha} \neq x_A VaR_{A,\alpha} + x_B VaR_{B,\alpha}$$

unless $\rho_{AB} = 1$.

Asset VaRs for A and B are:

$$VaR_{A,\alpha} = q_{\alpha}^{R_A} W_0 = (\mu_A + \sigma_A q_{\alpha}^z) W_0$$
$$VaR_{B,\alpha} = q_{\alpha}^{R_B} W_0 = (\mu_B + \sigma_B q_{\alpha}^z) W_0$$

Portfolio VaR is:

$$\begin{aligned} \operatorname{VaR}_{\boldsymbol{p},\alpha} &= \left(\mu_{\boldsymbol{p}} + \sigma_{\boldsymbol{p}} q_{\alpha}^{\boldsymbol{z}}\right) W_{0} \\ &= \left[\left(x_{A} \mu_{A} + x_{B} \mu_{B}\right) + \left(x_{A}^{2} \sigma_{A}^{2} + x_{B}^{2} \sigma_{B}^{2} + 2x_{A} x_{B} \sigma_{AB}\right)^{1/2} q_{\alpha}^{\boldsymbol{z}} \right] W_{0} \end{aligned}$$

Relationship between Portfolio VaR and Individual Asset VaR Cont.

If $\rho_{AB} \neq 1$, weighted Average of the asset VaR is:

$$\begin{aligned} x_A \mathrm{VaR}_{A,\alpha} + x_B \mathrm{VaR}_{B,\alpha} &= x_A (\mu_A + \sigma_A q_\alpha^z) W_0 + x_B (\mu_B + \sigma_B q_\alpha^z) W_0 \\ &= \left[(x_A \mu_A + x_B \mu_B) + (x_A \sigma_A + x_B \sigma_B) q_\alpha^z \right] W_0 \\ &\neq \left[(x_A \mu_A + x_B \mu_B) + \left(x_A^2 \sigma_A^2 + x_B^2 \sigma_B^2 + 2 x_A x_B \sigma_{AB} \right)^{1/2} q_\alpha^z \right] W_0 \\ &= (\mu_p + \sigma_p q_\alpha^z) W_0 = \mathrm{VaR}_{p,\alpha} \end{aligned}$$

If $\rho_{AB}=1$, then $\sigma_{AB}=\rho_{AB}\sigma_{A}\sigma_{B}=\sigma_{A}\sigma_{B}$ and:

$$\sigma_p^2 = x_A^2 \sigma_A^2 + x_B^2 \sigma_B^2 + 2x_A x_B \sigma_A \sigma_B = (x_A \sigma_A + x_B \sigma_B)^2$$

$$\Rightarrow \sigma_p = x_A \sigma_A + x_B \sigma_B$$

and so,

$$x_A VaR_{A,\alpha} + x_B VaR_{B,\alpha} = VaR_{p,\alpha}$$

Example: Two Risky Asset VaR

For an initial investment of $W_0 = 100,000$:

The 5% VaRs on assets A and B are:

$$\begin{aligned} \operatorname{VaR}_{A,0.05} &= q_{0.05}^{R_A} W_0 = (0.175 + 0.258(-1.645)) \cdot 100,000 = -24,937, \\ \operatorname{VaR}_{B,0.05} &= q_{0.05}^{R_B} W_0 = (0.055 + 0.115(-1.645)) \cdot 100,000 = -13,416. \end{aligned}$$

The 5% VaR on the equal weighted portfolio with $x_A = x_B = 0.5$ is:

$$\operatorname{VaR}_{p,0.05} = q_{0.05}^{R_p} W_0 = (0.115 + 0.1323(-1.645)) \cdot 100,000 = -10,268,$$

The weighted average of the asset VaRs is:


$$x_A \text{VaR}_{A,0.05} + x_B \text{VaR}_{B,0.05} = 0.5(-24,937) + 0.5(-13,416) = -19,177.$$

Portfolio Frontier

Vary investment shares x_A and x_B and compute resulting values of μ_p and σ_p^2 . Plot μ_p against σ_p as functions of x_A and x_B

- Portfolios with only asset A or only asset B will be on the frontier.
- Shape of portfolio frontier depends on correlation between assets A and B
- If $\rho_{AB}=-1$ then there exists portfolio shares x_A and x_B such that $\sigma_p^2=0$
- If $ho_{AB}=1$ then there is no benefit from diversification
- ullet Diversification is beneficial even if 0 < ho_{AB} < 1


Risk return characteristics of portfolios




Create portfolio frontier

```
# create portfolios for frontier plot
x.A = seq(from=-0.4, to=1.4, by=0.1)
x.B = 1 - x.A
mu.p = x.A*mu.A + x.B*mu.B
sig2.p = x.A^2 * sig2.A + x.B^2 * sig2.B + 2*x.A*x.B*sig.AB
sig.p = sqrt(sig2.p)
```


Plot portfolio frontier



Portfolio frontier as a function of ρ_{AB}



Portfolio Frontier when $\rho_{AB} = +/-1$




Efficient Portfolios

Definition: Portfolios with the highest expected return for a given level of risk, as measured by portfolio standard deviation, are efficient portfolios.

- If investors like portfolios with high expected returns and dislike portfolios with high return standard deviations then they will want to hold efficient portfolios.
- Which efficient portfolio an investor will hold depends on their risk preferences.
 - Very risk averse investors dislike volatility and will hold portfolios near the global minimum variance portfolio. They sacrifice expected return for the safety of low volatility.
 - Risk tolerant investors (tolerate risk) and will hold portfolios that have high expected returns-high risk trade-offs. They gain expected return by taking on more volatility.

Efficient Portfolios



Globabl Minimum Variance Portfolio

- The efficient portfolio with the smallest possible variance is called the global minimum variance portfolio.
- This portfolio is chosen by the most risk averse individuals.
- To find this portfolio, one has to solve the following constrained minimization problem

$$\min_{x_A, x_B} \sigma_p^2 = x_A^2 \sigma_A^2 + x_B^2 \sigma_B^2 + 2x_A x_B \sigma_{AB}$$

$$s.t. \ x_A + x_B = 1$$

Review of Optimization Techniques: Constrained Optimization

Example: Find the minimum of a bivariate function subject to a linear constraint

$$y = f(x, z) = x^{2} + z^{2}$$

$$\min_{x,z} y = f(x, z)$$

$$s.t. x + z = 1$$

Solution methods:

- Substitution
- Lagrange multipliers

Method of Substitution

Substitute z = 1 - x in f(x, z) and solve univariate minimization:

$$y = f(x, 1 - x) = x^{2} + (1 - x)^{2}$$

 $\min_{x} f(x, 1 - x)$

First order conditions:

$$0 = \frac{d}{dx}(x^2 + (1 - x)) = 2x + 2(1 - x)(-1)$$

= 4x - 2
\Rightarrow x = 0.5

Solving for z:

$$z = 1 - 0.5 = 0.5$$

Method of Lagrange Multipliers

Augment function to be minimized with extra terms to impose constraints.

1 Put constraints in homogeneous form:

$$x + z = 1 \Rightarrow x + z - 1 = 0$$

2 Form Lagrangian function:

$$L(x, z, \lambda) = x^2 + z^2 + \lambda(x + z - 1)$$

$$\lambda = \text{Lagrange multiplier(Shadow Price)}$$

Minimize Lagrangian function:

$$\min_{x,z,\lambda} L(x,z,\lambda)$$

Method of Lagrange Multipliers Cont.

First order conditions:

$$0 = \frac{\partial L(x, z, \lambda)}{\partial x} = 2 \cdot x + \lambda \to 2x = -\lambda$$
$$0 = \frac{\partial L(x, z, \lambda)}{\partial z} = 2 \cdot z + \lambda \to 2z = -\lambda$$
$$0 = \frac{\partial L(x, z, \lambda)}{\partial \lambda} = x + z - 1$$

We have three linear equations in three unknowns. Solving gives:

$$2x = 2z = -\lambda \Rightarrow x = z$$
$$2z - 1 = 0 \Rightarrow z = 0.5, \ x = 0.5$$

Example: Finding the Global Minimum Variance Portfolio

Two methods for solution:

- Analytic solution using Calculus
- Numerical solution
 - use the Solver in Excel
 - use R function solve.QP() in package **quadprog* for quadratic optimization problems with equality and inequality constraints

Calculus Solution

Minimization problem:

$$\min_{x_A, x_B} \sigma_p^2 = x_A^2 \sigma_A^2 + x_B^2 \sigma_B^2 + 2x_A x_B \sigma_{AB}$$

$$s.t. \ x_A + x_B = 1$$

Use substitution method with:

$$x_B = 1 - x_A$$

to give the univariate minimization,

$$\min_{x_A} \ \sigma_p^2 = x_A^2 \sigma_A^2 + (1 - x_A)^2 \sigma_B^2 + 2x_A (1 - x_A) \sigma_{AB}$$

Calculus Solution Cont.

First order conditions:

$$0 = \frac{d}{dx_A} \sigma_p^2 = \frac{d}{dx_A} \left(x_A^2 \sigma_A^2 + (1 - x_A)^2 \sigma_B^2 + 2x_A (1 - x_A) \sigma_{AB} \right)$$

$$= 2x_A \sigma_A^2 - 2(1 - x_A) \sigma_B^2 + 2\sigma_{AB} (1 - 2x_A)$$

$$\Rightarrow x_A^{\min} = \frac{\sigma_B^2 - \sigma_{AB}}{\sigma_A^2 + \sigma_B^2 - 2\sigma_{AB}}, \ x_B^{\min} = 1 - x_A^{\min}$$

Excel Solver Solution

The Solver is an Excel add-in, that can be used to numerically solve general linear and nonlinear optimization problems subject to equality or inequality constraints.


- The solver is made by FrontLine Systems and is provided with Excel
- The solver add-in may not be installed in a "default installation" of Excel
 - Tools/Add-Ins and check the Solver Add-In box
 - If Solver Add-In box is not available, the Solver Add-In must be installed from original Excel installation CD

Computing the Minimum Variance Portfolio

```
# compute mininimum variance portfolio weights
xA.min = (sig2.B - sig.AB)/(sig2.A + sig2.B - 2*sig.AB)
xB.min = 1 - xA.min
xA.min
## [1] 0.202
xB.min
## [1] 0.798
# compute expected return and volatility
mu.p.min = xA.min*mu.A + xB.min*mu.B
sig2.p.min = xA.min^2 * sig2.A + xB.min^2 * sig2.B + 2*xA.min^2
sig.p.min = sqrt(sig2.p.min)
mu.p.min
```

[1] 0.0793

Minimum Variance Portfolio



Portfolios with a Risk Free Asset

Risk Free Asset (The Risk Free Rate):

- Asset with fixed and known rate of return over investment horizon
- \bullet Usually U.S. government T-Bill rate (horizons <1 year) or T-Note rate (horizon >1 year)
- T-Bill or T-Note rate is only nominally risk free.

Properties of Risk-Free Asset

$$R_f = \text{return on risk-free asset}$$
 $E[R_f] = r_f = \text{constant}$
 $\text{var}(R_f) = 0$
 $\text{cov}(R_f, R_i) = 0, \ R_i = \text{return on any asset}$

Portfolios of Risky Asset and Risk Free Asset:

$$x_f = \text{ share of wealth in T-Bills}$$

 $x_B = \text{ share of wealth in asset B}$
 $x_f + x_B = 1$
 $\Rightarrow x_f = 1 - x_B$

Properties of Risk-Free Asset Cont.

Portfolio return:

$$R_p = x_f r_f + x_B R_B$$

= $(1 - x_B) r_f + x_B R_B$
= $r_f + x_B (R_B - r_f)$

Portfolio excess return:

$$R_p - r_f = x_B (R_B - r_f)$$

Portfolio Distribution:

$$\mu_p = E[R_p] = r_f + x_B(\mu_B - r_f)$$

$$\sigma_p^2 = \text{var}(R_p) = x_B^2 \sigma_B^2$$

$$\sigma_p = x_B \sigma_B$$

$$R_p \sim N(\mu_p, \sigma_p^2)$$

Risk Premium

$$\mu_B - r_f = \text{excess expected return on asset B}$$

$$= \text{expected return on risky asset over return on safe asset}$$

Portfolio of T-Bills and asset B:

$$\mu_p - r_f = x_B(\mu_B - r_f)$$
= expected portfolio return over T-Bill
= excess expected return on portfolio

The risk premia is an increasing function of the amount invested in asset B. (willingness to take on more risk)

Leveraged Investment

Leverage - to multiply gains and losses.

Short the Risk-free asset and Long the Risky asset

$$x_f < 0, x_B > 1$$

Borrow at T-Bill rate to buy more of asset B.

Result: Leverage increases portfolio expected return and risk.

$$\mu_{p} = r_{f} + x_{B}(\mu_{B} - r_{f})$$

$$\sigma_{p} = x_{B}\sigma_{B}$$

$$x_{B} \uparrow \Rightarrow \mu_{p} \& \sigma_{p} \uparrow$$

Determining Portfolio Frontier

Goal: Plot μ_p vs. σ_p .

$$\sigma_{p} = x_{B}\sigma_{B} \Rightarrow x_{B} = \frac{\sigma_{p}}{\sigma_{B}}$$

$$\mu_{p} = r_{f} + x_{B}(\mu_{B} - r_{f})$$

$$= r_{f} + \frac{\sigma_{p}}{\sigma_{B}}(\mu_{B} - r_{f})$$

$$= r_{f} + \left(\frac{\mu_{B} - r_{f}}{\sigma_{B}}\right)\sigma_{p}$$

where,

$$\left(\frac{\mu_B - r_f}{\sigma_B}\right) = SR_B = Asset B Sharpe Ratio$$

= excess expected return per unit risk (linear slope)

Sharpe Ratio (SR)

The Sharpe Ratio:

$$SR_{\mathcal{B}} = \left(\frac{\mu_{\mathcal{B}} - r_{\mathcal{f}}}{\sigma_{\mathcal{B}}}\right)$$

Remarks:

- William Sharpe developed while at UW Foster
- The Sharpe Ratio (SR) is commonly used to rank assets.
- Assets with high Sharpe Ratios (steep slope) are preferred to assets with low Sharpe Ratios.

Portfoliols of T-Bills and 1 risky asset

```
mu.p.A = r.f + x.A*(mu.A - r.f)
sig.p.A = x.A*sig.A
sharpe.A = (mu.A - r.f)/sig.A
sharpe.A
## [1] 0.562
# T-bills + asset B
x.B = seq(from=0, to=1.4, by=0.1)
mu.p.B = r.f + x.B*(mu.B - r.f)
sig.p.B = x.B*sig.B
sharpe.B = (mu.B - r.f)/sig.B
sharpe.B
```


x.A = seq(from=0, to=1.4, by=0.1)

Risk-free rate

T-bills + asset A

r.f = 0.03

Portfoliols of T-Bills and 1 risky asset



Efficient Portfolios with 2 Risky Assets and a Risk Free Asset

Investment in 2 Risky Assets and T-Bill:

$$R_A = \text{simple return on asset A}$$

 $R_B = \text{simple return on asset B}$
 $R_f = r_f = \text{return on T-Bill}$


Assumptions:

• R_A and R_B are described by the GWN model:

$$R_i \sim iid \ N(\mu_i, \sigma_i^2), \ i = A, B$$

 $cov(R_A, R_B) = \sigma_{AB}, \ corr(R_A, R_B) = \rho_{AB}$

Portfolios of T-Bills and 2 risky assets




Efficient Portfolios with 2 Risky Assets and a Risk Free Asset Cont.


Results:

- The "best portfolio" of two risky assets and T-Bills is the one with the highest Sharpe Ratio.
- Graphically, this portfolio occurs at the tangency point of a line drawn from R_f to the risky asset only frontier.
 - $E[R_p^e] = \mu_p^e$ with standard deviation σ_p^e
- The maximum Sharpe Ratio portfolio is called the "tangency portfolio"

Portfolios of T-Bills and 2 risky assets



Efficient portfolios and risk preferences



Mutual Fund Separation Theorem

Efficient portfolios are combinations of two portfolios (mutual funds):

- T-Bill portfolio
- Tangency portfolio portfolio of assets A and B that has the maximum Shape ratio

Implication: All investors hold assets A and B according to their proportions in the tangency portfolio regardless of their risk preferences.

Finding the Tangency Portfolio

The Tangency Portfolio is the portfolio with the maximum Sharpe Ratio.

$$\max_{x_A, x_B} SR_p = \frac{\mu_p - r_f}{\sigma_p}$$
subject to $\mu_p = x_A \mu_A + x_B \mu_B$

$$\sigma_p^2 = x_A^2 \sigma_A^2 + x_B^2 \sigma_B^2 + 2x_A x_B \sigma_{AB}$$

$$1 = x_A + x_B$$

Solution can be found analytically or numerically (e.g. using solver in Excel).

Finding the Tangency Portfolio Cont.

Using the substitution method it can be shown that:

$$x_A^{tan} = \frac{(\mu_A - r_f)\sigma_B^2 - (\mu_B - r_f)\sigma_{AB}}{(\mu_A - r_f)\sigma_B^2 + (\mu_B - r_f)\sigma_A^2 - (\mu_A - r_f + \mu_B - r_f)\sigma_{AB}}$$
$$x_B^{tan} = 1 - x_A^{tan}$$

Portfolio characteristics:

$$\begin{split} \mu_{p}^{\mathrm{tan}} &= x_{A}^{\mathrm{tan}} \mu_{A} + x_{B}^{\mathrm{tan}} \mu_{B} \\ \left(\sigma_{p}^{\mathrm{tan}}\right)^{2} &= \left(x_{A}^{\mathrm{tan}}\right)^{2} \sigma_{A}^{2} + \left(x_{B}^{\mathrm{tan}}\right)^{2} \sigma_{B}^{2} + 2 x_{A}^{\mathrm{tan}} x_{B}^{\mathrm{tan}} \sigma_{AB} \end{split}$$

Efficient Portfolios: Tangency Portfolio plus T-Bills

Portfolio with the Risk-Free Asset + Tangency Portfolio

Result: The weights x_{tan} and x_f are determined by an investor's risk preferences

- Risk averse investors hold mostly T-Bills
- Risk tolerant investors hold mostly tangency portfolio

Example: Tangent Portfolio and Efficient Portfolio Distribution

For the two asset example, the tangency portfolio is:

$$\begin{aligned} x_A^{\mathsf{tan}} &= .46, \ x_B^{\mathsf{tan}} &= 0.54 \\ \mu_p^{\mathsf{tan}} &= (.46)(.175) + (.54)(.055) = 0.11 \\ \left(\sigma_p^{\mathsf{tan}}\right)^2 &= (.46)^2(.067) + (.54)^2(.013) + 2(.46)(.54)(-.005) \\ &= 0.015 \\ \sigma_p^{\mathsf{tan}} &= \sqrt{.015} = 0.124 \end{aligned}$$

Efficient portfolios have the following characteristics:

$$\mu_p^e = r_f + x_{tan}(\mu_p^{tan} - r_f)$$

$$= 0.03 + x_{tan}(0.11 - 0.03)$$
 $\sigma_p^e = x_{tan}\sigma_p^{tan}$

$$= x_{tan}(0.124)$$

Example: Efficient Portfolio with Targeted Risk

What is the efficient portfolio that has the same risk (σ_p^e) as asset B? That is, determine x_{tan} and x_f such that

$$\sigma_p^e = \sigma_B = 0.114 = {\rm target~risk}.$$

Note: The efficient portfolio will have a higher expected return than asset B.

Solution: Efficient Portfolio with Targeted Risk

Since the portfolio variance is: $\sigma_p^{2,e} = x_{tan}^2 \sigma_p^{2,tan}$

$$.114 = \sigma_p^e = x_{tan} \sigma_p^{tan}$$

$$= x_{tan}(.124)$$

$$\Rightarrow x_{tan} = \frac{.114}{.124} = .92$$

$$x_f = 1 - x_{tan} = .08$$

Efficient portfolio with same risk as asset B has:

$$(.92)(.46) = .42$$
 in asset A
 $(.92)(.54) = .50$ in asset B
 $.08$ in T-Bills

If $r_f = 0.03$, then expected Return on efficient portfolio is:

$$\mu_p^e = .03 + (.92)(.11 - 0.03) = .104.$$

Example: Efficient Portfolio with Targeted Expected Return

For $r_f = 0.03$, find the efficient portfolio that has the same expected return as asset B. That is, determine x_{tan} and x_f such that:

$$\mu_p^e = \mu_B = 0.055 = {\rm target~expected~return.}$$

Note: The efficient portfolio will have a lower SD than asset B.

Solution: Efficient Portfolio with Targeted Expected Return

Since the expected portfolio return:

$$\mu_p^e = r_f + x_{tan}(\mu_p^{tan} - r_f)$$

$$0.055 = \mu_p^e = 0.03 + x_{tan}(.11 - .03)$$

$$x_{tan} = \frac{0.055 - 0.03}{.11 - .03} = .31$$

$$x_f = 1 - x_{tan} = .69$$

Efficient portfolio with same expected return as asset B has:

$$(.31)(.46) = .14$$
 in asset A
 $(.31)(.54) = .17$ in asset B
 $.69$ in T-Bills

The standard deviation of the efficient portfolio is:

$$\sigma_p^e = .31(.124) = .038$$
.
Introduction to Portfolio Theory

Interpreting efficient portfolios

