
TTEST and ANOVA the theory



Probability and Statistics

COMS10011


Dr. Anne Roudaut csxar@bristol.ac.uk




today::

look more into the math behind t-test and anova


lets go back to our memorization experience




no evidences for chocolate vs. baseline (p>0.05)




no evidences for chocolate vs. baseline (p>0.05) (let's just assume these are normally distributed)




if the mean where further apart, it would increase our chances to have a p<0.05



<without changing the means, what else can we do to these data to make some more different?>



if the distributions where less spread out, it would increase our chances to have a p<0.05




the goal of a study is to find a signal in a lot of noise

any statistical tests ::


signal noise

T-tests ::



difference between group means variability of groups

T-tests ::



difference between group means variability of groups

T-tests ::

Paired
$$t = \frac{\overline{x1} - \overline{x2}}{s/\sqrt{n}}$$

Unpaired
$$t=rac{x1-x2}{s\sqrt{\left(rac{1}{n1}+rac{1}{n2}
ight)}}$$

paired t-test

different between group means

(to maximize)

$$t=rac{x_1-x_2}{s_1\sqrt{n}}$$

(to minimize)

of the differences


different between group means

(to maximize)

$$t = \frac{\boxed{x1 - x2}}{\boxed{s/\sqrt{n}}}$$

standard error of the mean (to minimize)

but why do we need to divide by \sqrt{n} (n = sample size)?



this comes from the central limit theorem you have seen before with Conor

by dividing by \sqrt{n} , we add a "penalty" for using a sample instead of the entire population

penalty is large when sample is very small

as sample size increases, penalty diminishes ...

... infinitely approaching point where sample = the population itself

$$t = \frac{x1 - x2}{s/\sqrt{n}}$$

we get a t-value

(to maximize)

both signal and noise are in the units of your data


If signal = 6 and noise = 2, your t-value = 3, so the difference is 3 times the size of the standard error

If signal = 6 and noise = 6, your t-value = 1, the signal is at the same scale as the noise


t-values = how distinguishable signal from noise

how do we know our t-value is any good, and how does this related to p-value?

this is where t-distributions come in



now let's take all these possible values and ...



... plot a distribution of them


this type of distribution is a sampling distribution

fortunately, the properties of t-distributions are well understood in statistics, so we can plot them without having to collect many samples!


a specific t-distribution is defined by its degrees of freedom (DF), a value closely related to sample size (here n-1)

different t-distributions exist for every sample size


Comparison of t Distributions



t-distributions assume that you draw repeated random samples from a population where the null hypothesis is true. You place the t-value from your study in the t-distribution to determine how consistent your results are with the null hypothesis.




e.g. here a t-distribution (DF =20 which means a sample size of 21). It plots the probability density function (PDF), which describes the likelihood of each t-value.



shade the area of the curve with t-values >2 and <-2

each regions has a probability of 0.02963, which sums to a total probability of 0.05926 ... this is our pvalue!



it also does explain one-tail vs. two tails ttests: one-tail only case about t=2 (not -2 or oppositely), so multiply pvalue by two. at this point you understand more the three reasons of a low p_value (or t_value)

difference not large enough
 (what you are searching for, your signal is weak)

$$t = \frac{\boxed{x1 - x2}}{\boxed{s}/\sqrt{n}}$$


2. too much noise

(could your experimental design introduce noise?


Check it)

3. not enough data(run more participants, gather more trials)

how much data is enough?



the larger the sample size, the more t-distributions become a z-distribution (at around n=30), the less the area under the curve to reach a low pvalue.




mean that more sample = back to using a Z-score (i.e. number of standard deviations from the mean on normal distribution)

so why using a t-test then?

well there are cases when we want to use less sample to speed up the evaluation

this was the case of William Sealy Gosset ...



Employee of Guiness, Gosset developed a small sample method to select the best yielding varieties of barley.

Biometricians like Pearson typically had hundreds of observations.

Guinness allowed him to publish his method under the name "Student" to prevent disclosure of confidential information.

Where do t-distrubitions came from? https://www.youtube.com/watch?v=N vUDvmrd6fo&feature=youtu.be

now it does not mean that 2 sample is enough ... a rule of thumb for a simple within experiment is 12-16 participants for example (and twice more for between experiment).

... we will actually look at how to know if you sample size is good in the last week


unpaired t-test

T-tests ::

Paired
$$t = \frac{\overline{x1} - \overline{x2}}{s/\sqrt{n}}$$

Unpaired
$$t = \frac{x1-x2}{s\sqrt{\left(\frac{1}{n1}+\frac{1}{n2}\right)}}$$

similar than paired ttest except this




paired t-test :: divide by \sqrt{n} because data point paired


unpaired t-test :: by
$$\sqrt{\left(\frac{1}{n1} + \frac{1}{n2}\right)}$$

you can do the math: unpaired t-test the denominator (noise) is larger because we add n1 + n2

... thus why harder to reach low pvalue with unpaired t-test

anovas






(let's assume again these are normally distributed)

any statistical tests ::

signal noise

ANOVA ::



difference between group means variability of groups

ANOVA ::

$$F = \frac{MS_{between}}{MS_{within}}$$

$$MS_{between} = \frac{SS_{between}}{df_{between}}$$
 $MS_{within} = \frac{SS_{within}}{df_{within}}$

$$SS_{between} = \sum_{j=1}^{p} n_j (\overline{x}_j - \overline{x})^2$$
 $SS_{within} = \sum_{j=1}^{p} \sum_{i=1}^{n_j} (x_{ij} - \overline{x}_j)^2$

don't be afraid by these equations, these are just simple math

if you like that kind of calculation you can even do it by hand ...

	Group 1	Group 2	Group 3	Anova by hand (step by step)		
n (sample size)	70	70	70			
M (mean)	4	3.7	3.4	1. compute th combined sample size N	210	
s^2 (variance)	4.4	5.2	6.1	2. compute the degress of freedom between (dfbetween)	2	(number of groups - 1)
				3. compute the degress of freedom within (dfwithin)	207	(n1-1)+(n2-1)+(n3-1)
				the nominator		(C)
				4. compute the average mean	3.7	
				5. compute the SSbetween 12.6 6. compute the MSbetween (divide by dfbetween) 6.3	$\nabla (\mathbf{V} - \overline{\mathbf{V}})^2$	
					6.3	Sample Variance = $s^2 = \frac{\Sigma(X - \overline{X})^2}{n-1}$
						$\begin{array}{cccccccccccccccccccccccccccccccccccc$
				the denominator		<u> </u>
				7. compute the SSwithin	1083.3	(I multiply by ni here as the variance formula has a dividor which we don't need her
				8. Compute Mswithing (divide by dfwithin)	5.233333	
				9. compute F	1.203822	
				10. find p_value	0.302137	(p value NOT < alpha so DO NOT reject Ho)
	1			I and the second		

(excel file in the git hub repository)

В	С	D	Е	F	G
<u>IDs</u>	Before	<u>After</u>	1. difference	Paired T-test example	
1	312	300	12	(In green the initial data, in blue the computation)	
2	242	201	41		
3	340	232	108	steps by steps	
4	388	312	76		
5	296	220	76	1. add new colum to compute the differences between conditions for each participants	
6	254	256	-2	compute the mean of the differences (use excel formula =AVERAGE(new column))	56.1111111
7	391	328	63	3. compute the standard deviation of the differences (use formula =STDEV(new column))	34.173983
8	402	330	72	4. compute de standard error of the mean difference (difive 3. by SQRT(n))	11.3913277
9	290	231	59	5. compute t_value, i.e. step 2. divided by step. 4	4.92577449

(excel file in the git hub repository)



ANOVA ::


$$F = \frac{MS_{between}}{MS_{within}}$$

$$MS_{between} = \frac{SS_{between}}{df_{between}}$$
 $MS_{within} = \frac{SS_{within}}{df_{within}}$

$$egin{aligned} SS_{between} &= \sum_{j=1}^p n_j (\overline{x}_j - \overline{x})^2 \ SS_{within} &= \sum_{j=1}^p \sum_{i=1}^{n_j} (x_{ij} - \overline{x}_j)^2 \end{aligned}$$

how do we know if the Fvalue is anygood?

... this is where F-distributions come in



they take two degrees of freedom rather than just one like with t-distributions

```
Denominator (the within df - also called the error)
    Numerator DF (the between df)
DF
                                                                                                 1000
    161.45 199.50 215.71 224.58 230.16 236.77 241.88 245.95 248.01 250.10 252.20 253.25 254.06 254.19
     18.513 19.000 19.164 19.247 19.296 19.353 19.396 19.429 19.446 19.462 19.479 19.487 19.494 19.495
     10.128 9.5522 9.2766 9.1172 9.0135 8.8867 8.7855 8.7028 8.6602 8.6165 8.5720 8.5493 8.5320 8.5292
    7.7086 6.9443 6.5915 6.3882 6.2560 6.0942 5.9644 5.8579 5.8026 5.7458 5.6877 5.6580 5.6352 5.6317
    6.6078 5.7862 5.4095 5.1922 5.0504 4.8759 4.7351 4.6187 4.5582 4.4958 4.4314 4.3985 4.3731 4.3691
    5.5914 4.7375 4.3469 4.1202 3.9715 3.7871 3.6366 3.5108 3.4445 3.3758 3.3043 3.2675 3.2388 3.2344
    4.9645 4.1028 3.7082 3.4780 3.3259 3.1354 2.9782 2.8450 2.7741 2.6996 2.6210 2.5801 2.5482 2.5430
    4.5431 3.6823 3.2874 3.0556 2.9013 2.7066 2.5437 2.4035 2.3275 2.2467 2.1601 2.1141 2.0776 2.0718
    4.3512 3.4928 3.0983 2.8660 2.7109 2.5140 2.3479 2.2032 2.1241 2.0391 1.9463 1.8962 1.8563 1.8498
    4.1709 3.3159 2.9223 2.6896 2.5336 2.3343 2.1646 2.0149 1.9317 1.8408 1.7396 1.6835 1.6376 1.6300
    4.0012 3.1505 2.7581 2.5252 2.3683 2.1666 1.9927 1.8365 1.7480 1.6492 1.5343 1.4672 1.4093 1.3994
     3.9201 3.0718 2.6802 2.4473 2.2898 2.0868 1.9104 1.7505 1.6587 1.5544 1.4289 1.3519 1.2804 1.2674
    3.8601 3.0137 2.6227 2.3898 2.2320 2.0278 1.8496 1.6864 1.5917 1.4820 1.3455 1.2552 1.1586 1.1378
1000 3.8508 3.0047 2.6137 2.3808 2.2230 2.0187 1.8402 1.6765 1.5811 1.4705 1.3318 1.2385 1.1342 1.1096
```

Example: , F for df = 2,207 is 3.0718

also in form of table (here for the dfwithin and dfbetween of our excel example)



```
# first we run the one-way anova
library(ez)
ezANOVA(dat,id,between=group,dv=score)
```

```
Effect DFn DFd F p p<.05 ges
1 group 2 57 154.8886 9.056612e-24 * 0.8445923
```

second, run the pairwise comparison

ok something is going to be interesting here

```
pairwise.t.test(dat$score,dat$group, paired=FALSE,
p.adjust.method="bonferroni")
```

A B
B 0.16 C <2e-16 <2e-16

here are significant differences

and we don't need to do the Bonferroni

this was from last week, Regives us all this numbers

degrees of freedom

degrees of freedom::

the number of values in the final calculation of a statistic that are free to vary

a complex notion but here is the intuition ...

you have 7 hats, you want to wear one different every day for a week

Monday: 7 choices

Tuesday: 6 choices

Wednesday: 5 choices

Thursday: 4 choices

Friday: 3 choices

Saturday: 2 choices

Sunday: NO choice




degrees of freedom is 7-1

if we have 7 observations and the mean of these observation (that you need to do t-test or Anova) your degree of freedom is 7-1

because if you know 6 observations you automatically know the 7th one (thanks to the mean)

remember the lecture on regression?

standard error of the estimate



also called degree of freedom

a simple (approximate) way to understand this is that we have two variables, the slope and the intercept of the regression line

that give us extra information, thus the minus 2

statistic tests on multiple ID variables

until now, we did statistical test on one independent variable (with multiple conditions or groups) and one dependant variable

e.g. effect of chocolate, baseline, punishment (IV) on memorization score (DV)

now it is possible to do tests for multiple IVs and multiple DVs

however doing so decrease the power of your experiment (because you run more tests)


so it only works with powerful tests based on ANOVA (i.e. continuous variable and assumption of normality and homogeneity assumed)

e.g. two-ways ANOVA, MANOVA, ANVOVA

one-way ANOVA::

compare the effect of one discrete independent variables, having 2 or more levels on one dependant variable


e.g. effect of alcohol consumption (none, 2-pints, 4-pints) on attractiveness ratings



two-way ANOVA::

compare the effect of two discrete independent variables, each of them having 2 or more levels on one dependant variable


e.g. effect of gender (female, male) and alcohol consumption (none, 2-pints, 4-pints) on attractiveness ratings



one-way MANOVA::

(multivariate analysis of variance) compare the effect of one independent variable, having 2 or more levels on two dependant variables

e.g. effect of different memorization enhancing drugs (placebo, drug A, drug B) on memorization skills and emotional ratings (to find the sweet spot for a drug that enhance skills without depressing people!)



one-way ANCOVA::

(analysis of **co**variance) compare the effect of **one independent variable**, having 2 or more levels and **one continuous covariate** on **one dependant variable**

e.g. effect of phone sizes (iphone 4, iphone 5, iphone 6, iphone 7) on the amplitude of phone movements made when texting given the measure of the participants hand width (covariate)



one-way MANCOVA::

(multivariate analysis of covariance) compare the effect of one independent variable, having 2 or more levels and one continuous covariate on two dependant variable

... you can even two a two-way MANCOVA (but your experience might not have much statistical power because there are too many tests to perform)

although these tests exist, my advice is to keep the experimental design as simple as possible as you can, analysis will be easier and more powerful

... will look at power with

guest lecturer: Luluah Al-Barrack

summary

- 1. Explain the general equation of a statistical test (signal/noise)
- 2. Explain how a t-test is computed but I will not ask you to do it by hand
- 3. Explain the 3 reasons why a t-value can be low (signal too low, noise too high, small sample)
- 4. Explain how an Anova is computed but I will not ask you to do it by hand
- 5. Explain what are t-distributions and f-distributions

take away

try this with a friend during reading weeks

https://tinyurl.com/statsBristol




tea milk water





don't tell them how you made the cup



tea water milk





extra