

Section Cheat Sheet (PPT)


Model Binding

Model Binding is a feature of asp.net core that reads values from http requests and pass them as arguments to the action method.




QueryString vs RouteData






[FromQuery] and [FromRoute]



[FromQuery]


[FromRoute]



Models

Model is a class that represents structure of data (as properties) that you would like to receive from the request and/or send to the response.


Also known as POCO (Plain Old CLR Objects).



Model

```
class ClassName
{
   public type PropertyName { get; set; }
}
```

form-urlencoded and form-data



form-urlencoded (default)

Request Headers

Content-Type: application/x-www-form-urlencoded


Request Body

param1=value1¶m2=value2

form-data

Request Headers

Content-Type: multipart/form-data




Content-Disposition: form-data; name="param2"

value2

Model Validation

```
class ClassName
{
    [Attribute] //applies validation rule on this property
    public type PropertyName { get; set; }
}
```



ModelState

IsValid

Specifies whether there is at least one validation error or not (true or false).

Values

Contains each model property value with corresponding "Errors" property that contains list of validation errors of that model property.

ErrorCount

Returns number of errors.

Model Validation

[Required(ErrorMessage = "value")]

Specifies that the property value is required (can't be blank or empty).

[StringLength(int maximumLength, MinimumLength = value, ErrorMessage = "value")]

Specifies minimum and maximum length (number of characters) allowed in the string.

[Range(int minimum, int maximum, ErrorMessage = "value")]

Specifies minimum and maximum numerical value allowed.

[RegularExpression(string pattern, ErrorMessage = "value")]

Specifies the valid pattern (regular expression).

[EmailAddress(ErrorMessage = "value")]

Specifies that the value should be a valid email address.

[Phone(ErrorMessage = "value")]

Specifies that the value should be a valid phone number).

Eg: (999)-999-9999 or 9876543210

[Compare(string otherProperty, ErrorMessage = "value")]

Specifies that the values of current property and other property should be same.

[Url(ErrorMessage = "value")]

Specifies that the value should be a valid url (website address).

Eg: http://www.example.com

[ValidateNever]

Specifies that the property should not be validated (excludes the property from model validation).

Custom Validations

```
class ClassName : ValidationAttribute
{
   public override ValidationResult? IsValid(object?
       value, ValidationContext validationContext)
   {
       //return ValidationResult.Success;
      //[or] return new ValidationResult("error message");
   }
}
```

Validation Attribute

- Base class for all validation attributes such as RequiredAttribute, RegularExpressionAttribute, RangeAttribute, StringLengthAttribute, CompareAttribute etc.
- Provides properties such as ErrorMessage & methods such as Validate(), IsValid() etc.

ValidationContext

- Acts as a parameter for "IsValid()" method of custom validation attribute classes.
- Provides properties such as ObjectType, ObjectInstance.

Custom Validations with Multiple Properties

Field1: Field2: Field3: Field4: Field5: Field6:	Model Validation
---	------------------

IValidatableObject

```
class ClassName : IValidatableObject
{
    //model properties here

public IEnumerable<ValidationResult>
        Validate(ValidationContext validationContext)
    {
        if (condition)
        {
            yield return new ValidationResult("error message");
        }
    }
}
```

Base class for model classes with validation.

- Provides a method called Validate() to define class level validation logic.
- The Validate() method executes after validating all property-level validations are executed; but doesn't execute if at least one property-level validations result error.

ValidationContext

- Acts as a parameter for "Validate()" method of model classes with IValidatableObject.
- Provides properties such as ObjectType, ObjectInstance.

[Bind] and [BindNever] [Bind]

• [Bind] attribute specifies that only the specified properties should be included in

model binding.


• Prevents over-posting (post values into unexpected properties) especially in 'Create' scenarios.

[BindNever]


```
class ModelClassName
{
    [BindNever]
    public type PropertyName { get; set; }
}
```

- [BindNever] attribute specifies that the specified property should NOT be included in model binding.
- Useful when you have fewer properties to eliminate from model binding.

[FromBody]



Input Formatters



Custom Model Binders

Custom Model Binder

```
class ClassName : IModelBinder
{
   public Task BindModelAsync(ModelBindingContext
        bindingContext)
   {
      //gets value from request
      bindingContext.ValueProvider.GetValue("FirstName");
      //returns model object after reading data from the request
      bindingContext.Result =
            ModelBindingResult.Success(your_object);
   }
}
```

IModelBinder

- Base interface for all custom model binders.
- Provides a method called BindModelAsync, to define logic for binding (reading) data from the request and creating a model object that has be received as parameter in the action method.

ModelBindingContext

• Acts as a parameter for "BindModelAsync()" method of custom model binder classes.

 Provides properties such as HttpContext, ModelState, ValueProvider, Result etc..

Custom Model Binder Providers

```
class ClassName : IModelBinderProvider
{
   public IModelBinder
        GetBinder(ModelBinderProviderContext
        providerContext)
   {
        //returns type of custom model binder class to be invoked
        return new
        BinderTypeModelBinder(typeof(YourModelBinderClassName));
   }
}
```

IModelBinderProvider

- Base interface for all custom model binder providers.
- Provides a method called GetBinder, to return the type of custom model binder class.

ModelBinderProviderContext

• Acts as a parameter for "GetBinder()" method of custom model binder provider classes.

• Provides properties such as BindingInfo, Services etc.